

PsdToUIToolKit

Quick Start and Configuration Guide | Unity 2022.3.62f3

PsdToUIToolKit is a Unity Editor tool that reads Photoshop PSD and PSB layer structures and exports them as Unity UI Toolkit assets:

- PNG sprites for raster layers
- One UXML document for the UI hierarchy
- One USS stylesheet referenced by the UXML document

The project currently targets Unity 2022.3.62f3. Export runs in the Unity Editor only; no runtime PSD conversion code is included.

Quick start

- 1 Open the project in Unity 2022.3.62f3 and wait for scripts to compile.
- 2 Choose Tools > PSD > UI Toolkit Editor.
- 3 Click Open PSD and select a .psd or .psb file.
- 4 Select layers in the tree or canvas. Use the Inspector to choose which layers are exported, how raster images are handled, and how children are arranged.
- 5 Check the export settings:
 - Image Root defaults to `Assets/PsdToUIToolKit/Generated/Images`.
 - UXML Root defaults to `Assets/PsdToUIToolKit/Generated/Uxml`.
 - Auto image naming is enabled by default.
- 6 If needed, configure nine-slice detection, image deduplication, common image directories, or font mapping from Tools > PSD > UI Toolkit.
- 7 Click Export.
- 8 If the target UXML or USS already exists, review the replacement warning and choose Replace All only when those files can be overwritten.
- 9 Unity selects and opens the exported UXML. Open it in UI Builder to inspect the result and make final spacing or styling adjustments.

For a PSD named `login.psd`, the default outputs are:

```
Assets/PsdToUIToolKit/Generated/Images/login/*.png
Assets/PsdToUIToolKit/Generated/Uxml/login.uxml
Assets/PsdToUIToolKit/Generated/Uxml/login.uss
```

The UXML references the USS file. Re-exporting replaces both UI Builder files after confirmation. It also removes top-level PNG files in the matching image folder that are no longer used by the current export. Do not keep manually maintained PNG files in that folder.

Editor overview

The main window has three working areas:

- Layer Tree: displays the PSD hierarchy and supports single or multi-selection.
- Canvas Preview: switches between Layout, PSD, and Split views. The layout preview can be used to select and arrange nodes.
- Inspector: edits the selected layer or virtual layout group and contains the export settings.

The toolbar provides Open PSD, Reload, Undo, Redo, and Export. Undo and Redo apply to layout edits in the current window session.

Layer export parameters

The following fields are stored per PSD layer.

Inspector field	Default	Applies to	Effect and related configuration
Name	PSD layer name	All layers	Becomes the UXML element name. Raster image names are derived from it after invalid filename characters and spaces are replaced.
Export	On	All layers	Off excludes the layer and its export contribution. An excluded non-clipped layer also breaks the current clipping sequence.
Visible	PSD visibility	All layers	Off keeps the element in UXML but writes <code>display: none</code> . It also updates the editor preview.
Merge export	Off	PSD groups	Exports the group as one composited raster image and stops exporting its children as separate layout nodes. Child layout fields are disabled while this is on.
Slice / nine-slice	On	Non-text raster output	Attempts to detect a stretchable center, builds a compact sliced PNG, sets the imported Sprite border, and writes <code>-unity-slice-*</code> styles. Detection may legitimately return no slice.
Participate local dedup	On	Non-text raster output	Allows identical raster content in the current PSD export to share one generated image. Comparison uses the global MAE threshold and fingerprint size.
Participate common dedup	On	Non-text raster output	Searches configured common directories for a matching PNG. A match is referenced instead of writing another PNG.
Override nine-slice params	Off	Non-text layers with nine-slice on	Uses this layer's five nine-slice values instead of the global <code>PSD_NineSliceConfig.json</code> values.

Text layers are written as `ui:Label` elements. Other exported nodes are written as `ui:VisualElement` elements; raster nodes receive a `background-image`. Text export includes the parsed text, effective font size, fill color, supported outline and shadow effects, and an optional mapped font.

Per-layer nine-slice overrides

These fields appear only when Slice / nine-slice and Override nine-slice params are both enabled.

Inspector field	Default	Sanitized range	Meaning
Border inset	2	0 or greater	Keeps candidate cut lines away from visible color boundaries.
Pixel threshold	10	0 to 255	Maximum per-channel RGBA difference for adjacent rows or columns to remain cuttable. Lower values are stricter.
Min center cols	10	1 or greater during export	Caps the width of the rebuilt center block. The underlying JSON name is <code>nineSliceMinCenterCols</code> .
Min center rows	10	1 or greater during export	Caps the height of the rebuilt center block. The underlying JSON name is <code>nineSliceMinCenterRows</code> .

Inspector field	Default	Sanitized range	Meaning
Min same-zone	15	1 or greater during export	Minimum contiguous region that must be considered consistently cuttable.

If locally deduplicated layers have identical raster content but conflicting enabled nine-slice parameters, export stops and reports the conflicting layers. Keep their slice settings identical, disable nine-slice for at least one cluster policy, or disable local dedup for the layers that require different output.


Layout intent parameters

Layout is explicitly configured. There is no automatic layout-analysis mode. Absolute positioning is the default.

Inspector field	Choices	Availability	Effect
In parent	Follow parent layout; Keep original position	Every selected layer	Follow parent layout participates in a Row or Column parent. Keep original position remains absolutely positioned relative to the container.
Arrange children	Keep absolute; Row; Column	Unmerged PSD groups	Selects absolute child placement or a UI Toolkit flex direction. Leaf layers have no editable children.
Main axis	Preserve PSD spacing; Start; Center; End; Space between; Space around	Group uses Row or Column	Controls distribution along the flow direction. Non-preserve choices map to <code>justify-content</code> .
Cross axis	Preserve PSD offset; Start; Center; End	Group uses Row or Column	Controls perpendicular alignment and maps to <code>align-items</code> .
Wrap	No wrap; Wrap	Group uses Row or Column	Enables <code>flex-wrap: wrap</code> and PSD-derived line grouping.
Multiple lines	Preserve PSD lines; Start; Center; End	Wrap is enabled	Controls wrapped-line distribution and maps to <code>align-content</code> .

Preserve PSD spacing, Preserve PSD offset, and Preserve PSD lines use positions inferred from the original PSD instead of forcing a standard CSS-style distribution.

Layout dependencies



Virtual layout groups

Virtual groups arrange selected sibling nodes without requiring a matching Photoshop group:

- 1 Hold Ctrl on Windows or Cmd on macOS and select two or more sibling layers in the tree or canvas.
- 2 Choose Create Row Group or Create Column Group in the multi-selection Inspector.

- 3 Select the virtual group to edit its name, Row or Column layout, main axis, cross axis, wrap, and multi-line settings.
- 4 Use the member controls to remove nodes, add sibling nodes, nest groups, wrap a group in another Row or Column, move it into a compatible group, or dissolve it.

Virtual groups may contain layer references and other virtual-group references. They are stored in the PSD-specific config and do not modify the original PSD.

Export settings

These settings are stored in Unity `EditorPrefs`, so they are local to the current editor user rather than committed in a project JSON file.

Inspector field	Default	Effect
Image Root	<code>Assets/PsdToUIToolKit/Generated/Images</code>	The exporter creates <code><Image Root>/<PSD file name>/</code> and writes generated PNGs there. A value without the <code>Assets</code> prefix is normalized under <code>Assets/</code> .
UXML Root	<code>Assets/PsdToUIToolKit/Generated/Uxml</code>	Receives <code><PSD file name>.uxml</code> and <code><PSD file name>.uss</code> . A value without the <code>Assets</code> prefix is normalized under <code>Assets/</code> .
Auto image naming	On	Appends the PSD layer ID to the sanitized layer name, for example <code>button_178.png</code> . When off, repeated names receive numeric suffixes as needed.

The export button performs these operations:

- 1 Saves and synchronizes the PSD-specific config.
- 2 Warns before replacing an existing UXML or USS file.
- 3 Exports raster layers and imports generated PNGs as Sprites.
- 4 Builds the manually configured layout tree.
- 5 Writes the UXML and USS.
- 6 Deletes only stale top-level PNGs from the current PSD image folder.
- 7 Refreshes the Asset Database and opens the exported UXML.

Global image settings

Global settings are stored under:

```
Assets/PsdToUIToolKit/EditorConfig
```

If a JSON file does not exist or cannot be read, the defaults compiled into the tool are used.

Nine-slice settings

Open Tools > PSD > UI Toolkit > Nine-slice settings.... Changes are saved immediately to `PSD_NineSliceConfig.json` and apply on the next export.

UI field	JSON field	Default	Accepted range
Border inset	<code>borderInset</code>	2	0 or greater
Adjacent pixel threshold	<code>pixelThreshold</code>	10	0 to 255
Minimum contiguous cut zone	<code>minSameZone</code>	15	1 to 4096

UI field	JSON field	Default	Accepted range
Maximum center columns	<code>minCenterCols</code>	10	1 to 4096
Maximum center rows	<code>minCenterRows</code>	10	1 to 4096

```
{
  "borderInset": 2,
  "pixelThreshold": 10,
  "minCenterCols": 10,
  "minCenterRows": 10,
  "minSameZone": 15
}
```

The historical JSON names `minCenterCols` and `minCenterRows` are retained even though the current settings window describes them as maximum center dimensions.

Deduplication settings

Open Tools > PSD > UI Toolkit > Dedup settings.... Changes are saved immediately to `PSD_DedupConfig.json` and apply on the next export.

UI field	JSON field	Default	Accepted range	Effect
MAE threshold	<code>maeThreshold</code>	0.04	0.001 to 0.5	Maximum mean absolute error between premultiplied RGBA fingerprints. Lower values require a closer match.
Fingerprint size (N x N)	<code>fingerprintSize</code>	8	4 to 32	Resamples trimmed image content into an N by N fingerprint. Larger values preserve more detail but require more comparison work.

```
{
  "maeThreshold": 0.04,
  "fingerprintSize": 8
}
```

Local and common deduplication use the same threshold and fingerprint size. Local dedup compares exported layers with each other. Common dedup compares the post-nine-slice image, if any, against the cached common-directory PNGs.

Common image directories

Select a folder in Unity's Project window and choose Assets > PsdToUIToolKit > Add to Common Dir. The folder is appended to `PSD_CommonDirectories.json`. Reopen the PsdToUIToolKit window if it was already open.

```
{
  "paths": [
    "Assets/PsdToUIToolKit/Generated/Images/common"
  ]
}
```

Each configured directory is scanned recursively for PNG files. Paths may be Unity `Assets` paths, project-relative paths, or absolute paths. However, a matched PNG is usable only when it can be converted to a Unity asset path under the current project's `Assets` directory. Keep reusable common assets inside `Assets`.

There is no removal window for common directories. Remove obsolete entries by editing `PSD_CommonDirectories.json`.


Font mapping

Open Tools > PSD > UI Toolkit > Font mapping... to map each Photoshop font name to a Unity `Font` or `TextCore FontAsset`.

```
{
  "entries": [
    {
      "psdFontName": "ExamplePSFontName",
      "fontAssetPath": "Assets/Fonts/ExampleFont.asset"
    }
  ]
}
```

At export time, previously unseen PSD font names are automatically added to `PSD_FontMapping.json` with a blank asset path. Blank or invalid mappings use the UI Toolkit default font and produce a warning. Valid mappings are written as `-unity-font-definition` references.

Configuration precedence and storage



PSD-specific export config

Opening a PSD creates or updates:

```
Assets/PsdToUIToolKit/PSDConfig/<PSD file name>_uitoolkit_export_config.json
```

The current schema is config version 4. It stores:

- Per-layer export, visibility, merge, nine-slice, dedup, and layout settings keyed by PSD layer ID
- Virtual layout group names, host PSD parent IDs, member references, nesting, and layout settings

When the PSD is reopened, the tool synchronizes the current layer list while preserving settings for layer IDs that still exist. Config versions 1 through 3 are migrated in memory and saved as version 4.

The config filename uses only the PSD basename. Two PSD files in different folders with the same basename share one config file. Use unique PSD filenames to avoid unintended configuration overlap.

Storage summary

Setting category	Storage	Shared through version control?
Layer and virtual-group settings	PSDConfig/<PSD name>_uitoolkit_export_config.json	Yes, when the file is committed
Nine-slice defaults	EditorConfig/PSD_NineSliceConfig.json	Yes, when the file is committed
Deduplication defaults	EditorConfig/PSD_DedupConfig.json	Yes, when the file is committed
Common image directories	EditorConfig/PSD_CommonDirectories.json	Yes, when the file is committed
Font mappings	EditorConfig/PSD_FontMapping.json	Yes, when the file is committed
Export roots and auto naming	Unity EditorPrefs	No; local to the editor user

Output details

- The UXML root is a relative-positioned `ui:VisualElement` named after the PSD, with the original canvas width and height and `overflow: hidden`.
- Text layers become `ui:Label`; raster and container nodes become `ui:VisualElement`.
- Absolute nodes retain PSD-derived left, top, width, and height.
- Row and Column containers use UI Toolkit flex styles plus PSD-derived padding, gaps, and margins.
- Nine-slice output sets both the imported Sprite border and the corresponding UXML slice styles.
- Common-directory matches are referenced directly and are not copied into the generated image folder.

Generated UXML and USS are drafts owned by the exporter. Make durable manual changes in a separate copy or be prepared to reapply them after export.

Troubleshooting

Layout controls are disabled

- Arrange children requires a PSD group.
- A merged group is a single raster node; turn off Merge export to arrange its children.
- Main axis, cross axis, and wrap require Row or Column.
- Multiple lines requires Wrap.

Export reports conflicting nine-slice parameters

Identical layers participating in local dedup must resolve to a compatible export policy. Give them the same enabled nine-slice parameters or turn off local dedup for layers that need different slicing.

Exported text uses the wrong font

Open Font mapping..., find the exact Photoshop font name, and assign a Unity `Font` or TextCore `FontAsset`. A blank or invalid asset path intentionally falls back to the UI Toolkit default font.

A manually added PNG disappeared

After export, top-level PNGs in `Images/<PSD name>/` that are not referenced by the new result are treated as stale and deleted. Keep hand-authored images elsewhere, such as a configured common directory.

Two PSD files appear to share settings

PSD config filenames use only the source basename. Rename one PSD so both files have unique basenames, then reopen it to create a separate config.

Common-directory dedup does not find a match

Check that the layer has Participate common dedup enabled, the directory is listed in `PSD_CommonDirectories.json`, the candidate is a PNG under the current project's `Assets` directory, and the fingerprint difference is within the configured MAE threshold.

The exported UXML or USS lost manual edits

Both files are replaced on re-export after a confirmation dialog. Keep long-lived customization in a separate copy or source-controlled patch workflow.