## **CIAB Remote Desktop System Installation Guide**

by Brian Mullan (bmullan.mail@gmail.com)
March 2022

IMPORTANT – If you already have LXD installed on your "server" be aware CIAB installation can install/re-install LXD and re-init LXD!

If you do NOT have LXD installed then please utilize a CIAB pre-install script and yaml config file to insure LXD is properly installed on your Server/VM/Cloud-Instance:

Open a Terminal and run:

\$ ciab-pre-install.sh

So consider only Installing CIAB on a "fresh" Ubuntu 20.04 Server, VM or Cloud Server!

Major changes:

- 1. CIAB now utilizes a Dockerized Guacamole container running on the Server in an "nesting enabled" LXD container which then allows the Guacamole Docker container to run inside (ie "nested") the LXD ciab-guac container.
- 2. The CIAB Remote Desktop is still installed in an LXD container. As part of the Installation you will be asked to enter a "name" for the LXD Container into which a selectable Desktop Environment (*DE*) will be installed. Note: suggest naming the LXD container with the name of the DE you intend to install as part of the container name

Example: If you intend to create a an MATE Desktop Container then you might call the container "mate-desktop"

Enter a name for your new LXD Desktop Container:
Hint: if you want to create a MATE LXD Desktop then maybe name the new LXD Desktop Container "Mate-Desktop" and the other LXD Desktop Containers might be "KDE-Desktop" "Gnome-Desktop" etc.
Enter the name for your new LXD Desktop Container: mate-desktop
Creating the LXD Desktop Container using the name "mate-desktop" provided above.
Creating mate-desktop Starting mate-desktop

**NOTE:** a User Account for the Installer will be created in the new LXD container and you will be prompted for the Password for that User Account.

Next, you (the CIAB Installer) will be prompted to choose which Desktop Environment (DE) to install into the Desktop Container (example: entering 4 would install the MATE DE).

The Installation of the CIAB Remote Desktop System is mostly automatic except when you will be prompted to enter your Sudo password for specific configuration/installation steps.

Instructions are provided in several CIAB Installation Mind Maps which will be shown on the following pages.

Please substitute the *UserName* you intend to utilize anywhere in *Part 1 and Part 2* where ever you see "*UserID*".

Create a "work" directory:

\$ sudo mkdir /opt/ciab \$ sudo chown \$USER:\$USER /opt/ciab \$ sudo chmod 766 /op/tciab

The copy all of the CIAB files from Github to that directory and make the scripts executable.

Executing the CIAB Script "mk-ciab-desktop-container.sh" will begins installing CIAB.

Each time you run the above command you can install a new LXD Desktop Container and choose which Desktop Environment you want to install.

When the script completes it will have created a "launcher" script in your Home directory and copied that same script to /usr/bin/. To access the Container Desktop just execute that DE's launcher script.

Example for "mate-desktop": \$ ~/.mate-desktop.sh

CIAB Installation will also prompt you as to whether you want to install CIAB's Guacamole into a separate LXD container called "ciab-gtwy".


If you choose to to do this (you only have to do it once) then a CIAB Dockerized Guacamole/Tomcat/NGINX/PostgreSQL/Tomcat wil be installed in a "nesting" enabled LXD container named "ciab-gtwy".

Following Installation of "ciab-gtwy" you can point a Web Browser at the IP Address of the Server you installed CIAB on.


https://A.B.C.D

Default Admin login and password are both: guacadmin


## **CIAB Remote Desktop System Installation – PART 1**



## **CIAB Remote Desktop System Installation – PART 2**



## **CIAB Remote Desktop System Installation – PART 3**



## **Basic CIAB Guacamole Configuration Steps**

Point your web browser to the IP address of your CIAB Server:


https://X.X.X.X

and you will see the Guacamole Login Menu:




Default initial Login & Password are:

guacadmin guacadmin In the upper right corner of the next screen you will see:



Click on "guacadmin" and choose "Settings" and the next screen you will see is:



For basic configuration of CIAB we will show configuring a "new" Connection (ie to ciab-cn1) and a "new User.


## **Configure a new Connection**

Click on "Connections" and you will see the following screens. I will fill in the forms and take a screen shot of each so you can see what you will need to do. *The only difference will be the IP address of your LXD Desktop Container.* 

**Note:** you can find LXD Desktop Container IP address by starting a Terminal on the Server/Host/VM and executing:

### \$ lxc ls

**Example:** The following shows the "mate-desktop" container IPv4 address is 10.157.85.104



EDIT CON	NECTION
Name:	mate-desktop
Location:	ROOT
Protocol:	RDP
CONCURR	RENCY LIMITS
Maximum	number of connections:
Maximum	number of connections per user:
LOAD BAL	ANCING
Connection	weight:
Use for fail	
GUACAM	OLE PROXY PARAMETERS (GUACD)
	OLE PROXY PARAMETERS (GUACD)
GUACAM Hostname:	OLE PROXY PARAMETERS (GUACD)
GUACAM Hostname: Port:	OLE PROXY PARAMETERS (GUACD)
GUACAMe Hostname: Port: Encryption	OLE PROXY PARAMETERS (GUACD)
Hostname: Port: Encryption PARAMET Network	OLE PROXY PARAMETERS (GUACD)  ERS
Hostname: Port: Encryption PARAMET Network Hostname	OLE PROXY PARAMETERS (GUACD)  ERS  E: 10.157.85.104
Hostname: Port: Encryption PARAMET Network	OLE PROXY PARAMETERS (GUACD)  ERS
Hostname: Port: Encryption PARAMET Network Hostname	OLE PROXY PARAMETERS (GUACD)  TERS  E: 10.157.85.104  3389
Hostname: Port: Encryption PARAMET Network Hostname Port:	OLE PROXY PARAMETERS (GUACD)  ERS  E: 10.157.85.104  3389
Hostname: Port: Encryption  PARAMET  Network  Hostname Port: Authentic	DLE PROXY PARAMETERS (GUACD)  FERS  E: 10.157.85.104  3389  Cation  E: \${GUAC_USERNAME}
Hostname: Port: Encryption  PARAMET  Network  Hostname Port: Authentic	DLE PROXY PARAMETERS (GUACD)  ERS  E: 10.157.85.104  3389  Cation  E: \${GUAC_USERNAME}
Hostname: Port: Encryption  PARAMET  Network  Hostname Port:  Authentic  Username Password	DLE PROXY PARAMETERS (GUACD)  EERS  E: 10.157.85.104  3389  Cation  E: S{GUAC_USERNAME}  E: S{GUAC_PASSWORD}
Hostname: Port: Encryption  PARAMET  Network  Hostname Port:  Authentic  Username Password Domain: Security recommended	DLE PROXY PARAMETERS (GUACD)  ERS  E: 10.157.85.104  3389  Cation  E: \${GUAC_USERNAME}  E: \${GUAC_PASSWORD}

## Remote Desktop Gateway

Hostname:	
Port:	^
Username:	
Password:	
Domain:	
Domain.	
Basic Settings	
Initial program:	
Client name:	
Keyboard layout:	US English (Qwerty)
Time zone:	America V New York V
Enable multi-touch:	
Administrator console:	
Display	
Width:	•
Height:	\$
Resolution (DPI):	\$
Color depth:	True color (32-bit)
Force lossless compressi	ion:
Resize method:	~
Read-only:	
Clipboard	
Line endings:	V
Disable copying from rer	mote desktop:
Disable pasting from clie	

# Device Redirection

Support audio in console:	
Disable audio:	
Enable audio input (microphone):	
Enable printing:	
Redirected printer name:	
Enable drive:	<b>☑</b>
Drive name:	thinclient_drives
Disable file download:	
Disable file upload:	
Drive path:	drives/
Automatically create drive:	
Static channel names:	rdpdr
Performance	
Enable wallpaper:	
Enable theming:	
Enable font smoothing (ClearType):	
Enable full-window drag:	
Enable desktop composition (Aero):	
Enable menu animations:	
Disable bitmap caching:	
Disable off-screen caching:	
Disable glyph caching:	
RemoteApp	
Program:	
Working directory:	
Parameters:	
Preconnection PDU / Hyper-V	
RDP source ID:	<b>\$</b>
Preconnection BLOB (VM ID):	

## **Screen Recording**


Recording path:	
Recording name:	
Exclude graphics/streams:	
Exclude mouse:	
Exclude touch events:	
Include key events:	
Automatically create recording	path:
SFTP	
Enable SFTP:	
Hostname:	
Port:	•
Public host key (Base64):	
Username:	
Password:	
Private key:	
	lis.
Passphrase:	-
File browser root directory:	
Default upload directory:	
SFTP keepalive interval:	\$
Disable file download:	
Disable file upload:	
Wake-on-LAN (WoL)	
Send WoL packet:	
MAC address of the remote hos	st:
Broadcast address for WoL pack	ket:
UDP port for WoL packet:	\$
Host hoot wait time:	^

Then at the bottom of the screen Click on SAVE:



### **Configure a New Guacamole User**

NOTE: you will need to create a User Account in the CIAB Desktop Containers for each Guacamole User you create that you want to have access to that Desktop!



Click on "Users" then click on "New User".

### **IMPORTANT NOTE:**

Enter the **Username** and **Password** for the New User to <u>exactly match</u> the User Account created for that Username in the LXD Desktop Container.

### For yourself as the CIAB Installer give your Guacamole Account ALL Permissions

Make sure you check all the boxes for each Container Desktop Connection you want to access.

Finally, Click SAVE.

Username:	YourUsername
Password:	
Re-enter Password:	•••••
PROFILE	
Full name:	
Email address:	
Organization:	
Role:	
ACCOUNT RESTRI	CTIONS
Login disabled:	
Password expired:	
Allow access after:	:
Do not allow access a	after::
Enable account after	mm / dd / yyyy
Disable account after	
User time zone:	America V New York V
PERMISSIONS	
Administer system:	
Create new users:	
Create new user gro	ups:
•	
Create new connecti	on groups:
Create new connection Create new connection	_
	orofiles:
Create new connecti	
Create new connecti Create new sharing p Change own passwo	
Create new connecti Create new sharing p	rd:
Create new connections Create new sharing processes Change own passwo CONNECTIONS Current Connections	All Connections
Create new connections Create new sharing processes Change own passwo  CONNECTIONS  Current Connections  budgie-december 1985	All Connections  Jesktop
Create new connections Create new sharing processes Change own passwo  CONNECTIONS  Current Connections  Dudgie-d Duggnome-c	All Connections  Jesktop Jesktop
Create new connections Create new sharing processes Change own passwo  CONNECTIONS  Current Connections  budgie-december 1985	All Connections  Jesktop Jesktop

Back on the next Screen Click in the upper right corner on guacadmin again and Select Logout.


	<b>≜</b> guacadmin →
	<b>☆</b> Home
	Settings
	- Logout
Last active	
2022-01-10 09:29:14	

### Next...

Login to Guacamole with your own UserID and Password and you will see something like the following. Clicking on either the Icon or the connection name "mate-desktop" will log you into that CIAB Desktop Container.

#### RECENT CONNECTIONS





### ALL CONNECTIONS

- budgie-desktop
- kde-desktop
- mate-desktop