

ThreeDViewport Keyboard Reference

Primary Keyboard Commands

Available in the main viewport (no modifier unless noted).

Key	Action
B	Nudge selected keyframe 1 frame backward
C	Camera mode
D	Director mode — navigate the Director's POV (Scene mode only)
Delete / Backspace	Delete selected keyframe(s) (forwarded to Timeline Editor)
E / End	Jump playhead to end
F	Nudge selected keyframe 1 frame forward
G	Cycle render mode: Greyscale → Color → Black + White
H / Home	Jump playhead to start
I / Insert	Stamp keyframe for active mode
L	Light mode (press again to cycle to next light)
M	Model mode (move/rotate whole group as one unit)
O	Object mode (press again to cycle to next object)
P	Play / Pause
R	Reset current object, light, or camera orientation
⌘R	Re-auto-fit Director (only in Scene mode)
S	Toggle Scene mode (Director's POV — see camera, lights, models from above and behind); auto-engages Director mode
W	Wireframe toggle
1–6	Snap Director to a standard view of the selection — Front/Left/Rear/Right/Top/Bottom (Scene mode only)
7	Solo: hide everything except the selected object's group (Scene mode only)
8	Solo: make the hidden others still occlude (Scene mode only; pairs with 7)
⌘+ / ⌘–	Dolly Director in / out (only in Scene mode)
Escape	Cancel keyframe edit
Return	Commit keyframe edit
Shift+Tab	Previous keyframe across visible Timeline rows
Tab	Next keyframe across visible Timeline rows

Menu Shortcuts

Shortcut	Menu	Action
⌘E	File	Export ProRes Video...
⌘F	Window	Feedback panel
⌘G	View	Render Mode (cycles Greyscale → Color → Black + White)
⌘⇧G	Window	Color Grade panel
⌘⇧A	Window	Atmosphere panel (Fog + Weather: rain/snow/sleet)
⌘J	Window	Timeline Editor
⌘K	Window	Camera panel (follow-target picker + stamp button)
⌘L	Window	Lights & Background panel
⌘M	Window	Minimize
⌘N	File	New Project
⌘O	File	Open Model... (adds to scene)
⌘Q	ThreeDViewport	Quit
⌘S	File	Save Project
⌘⇧S	File	Save Project As...

Movement and Directional Keys

Hold for smooth repeat. Numpad equivalents: 4/6/8/2/+/-

Key	Camera	Object / Model	Lights
←	Truck left	Move left (screen-relative)	Move left (positional) / Pan left (directional)
→	Truck right	Move right (screen-relative)	Move right (positional) / Pan right (directional)
↑	Pedestal up	Move up (screen-relative)	Move up (positional) / Tilt up (directional)
↓	Pedestal down	Move down (screen-relative)	Move down (positional) / Tilt down (directional)
Shift+←	Free-look yaw left	Rotate around world Y-	Pan left (directional/spot/laser)
Shift+→	Free-look yaw right	Rotate around world Y+	Pan right (directional/spot/laser)
Shift+↑	Free-look tilt up	Rotate around world X+	Tilt up (directional/spot/laser)
Shift+↓	Free-look tilt down	Rotate around world X-	Tilt down (directional/spot/laser)
+ / KP+	Focal length increase (FOV narrow)	Move forward (camera depth)	Dolly in (positional only)
- / KP-	Focal length decrease (FOV wide)	Move backward (camera depth)	Dolly out (positional only)
Option++	—	Scale up 5%	—
Option+-	—	Scale down 5%	—
[	Orbit yaw left	Roll left (Z-)	Azimuth left
]	Orbit yaw right	Roll right (Z+)	Azimuth right
R	Reset to defaults	Reset rotation to loaded orientation	Reset to default direction

Mouse

Button	Camera	Object / Model	Lights
Left drag	Axis-locked Truck + Pedestal	Axis-locked translate (screen-relative)	Axis-locked Move (positional) / Pan + Tilt (directional)
Right drag	Free Pan + Tilt	Free rotate (both axes)	Free Pan + Tilt (directional/spot/laser only)
Space + Left drag	Free orbit (orbits Director in Scene mode, scene camera otherwise)	Free orbit	Free orbit
Scroll wheel	Dolly in / out	Move forward / backward (camera depth)	Dolly in / out (positional only)
Option + Scroll wheel	—	Uniform scale around object/group centre	—

Director Mode (Scene Mode Only)

Press **D** in Scene mode — or just press **S**, which auto-engages Director mode — to fly the Director's POV (the free editing viewpoint) without disturbing the keyframed scene camera. This makes it easy to frame individual parts (hands, feet, arms, legs) for posing. Controls mirror Camera mode but drive the Director:

Input	Director action
← → ↑ ↓	Pan
+ / -	FOV narrow / wide
⌘+ / ⌘-	Dolly in / out
Left drag	Truck + Pedestal (pan)
Right drag	Free-look (aim)
⌘R	Re-auto-fit the Director to the scene
Scroll wheel	Dolly in / out (move toward / away from a part)
Space + Left drag	Orbit
Shift + arrows	Free-look (aim)

The Director is never keyframed or saved. Typical flow: **S** to enter Scene mode, frame the part, **O** to select and pose it, **D** to reframe. Leaving Scene mode (**S**) returns to Camera mode.

Note: **D** means *Director mode* in the viewport, but *delete keyframe* in the Timeline Editor window — two separate views. The viewport always consumes **D**, so it can never delete a keyframe by accident.

Snap to a standard view (number row 1–6)

In Scene mode, the number keys snap the Director to an axis-aligned view of the **selected object's group**, centered and framed to fit. Views are **object-relative** — they follow the object's own orientation, so "Front" always shows the object's front no matter how it's flown or turned. (The orbit Director can't roll, so a banked object appears tilted in frame but is seen from the correct side.)

Key	View
1	Front
2	Left
3	Rear
4	Right
5	Top
6	Bottom

The snap uses the object's pose at the **current playhead** — if you scrub to a frame where the object has turned, press the key again to re-frame. Works in any control mode while Scene mode is active, so the flow is: **S** → select via **O** (or click a Timeline lane) → press **1–6** → pose the part.

Solo while posing (7 / 8)

In Scene mode, two keys declutter the view around what you're posing. They are **non-destructive** — your real Visible / Holdout settings are never changed, and leaving Scene mode restores the normal view instantly.

Key	Action
7	Hide everything except the selected object's group (e.g. just the robot stays). Press again to restore.
8	Make those hidden others still occlude (holdout) — so you can judge how the part sits behind / in front of them. Only has effect while 7 is on.

Solo tracks the selection live (cycle with **O** and the kept group follows). The HUD shows **[Solo]** / **[Solo+Occlude]** while active. Both reset when you leave Scene mode.

Timeline Editor

The Timeline Editor is a floating window (⌘J) that shows every keyframe on every track. Most viewport shortcuts also work when the Timeline Editor has focus — unrecognised keys are forwarded back to the viewport.

Keyboard

Command	Operation
A	Align multi-selected keyframes to the earliest selected (one per lane; aborts if a lane has 2+ selected)
B	Nudge selected keyframe(s) 1 frame backward (whole multi-selection moves together)
⌘C	Copy selected keyframe(s) to internal clipboard
D / Delete / Backspace	Delete selected keyframe(s)
F	Nudge selected keyframe(s) 1 frame forward (whole multi-selection moves together)
I / Insert	Stamp a keyframe on the selected lane at the playhead (replaces the nearest existing one within 1.5 frames)
⌘V	Paste clipboard at current playhead on selected lane(s)
End	Seek playhead to end
Escape	Cancel keyframe edit
Home	Seek playhead to start
Return	Enter edit mode on the selected diamond (or commit while editing)
Shift+Tab	Previous keyframe across all rows currently visible on screen
Tab	Next keyframe across all rows currently visible on screen

Mouse

Action	Operation
Click diamond	Select that keyframe and seek to its time
Click lane label	Select the lane (selects its track for ⌘V paste)
Click group disclosure triangle	Expand / collapse the group's lanes

Action	Operation
Click ruler	Scrub the playhead
Control + Left drag	Rubber-band select keyframes in a region
Double-click diamond	Enter edit mode (live-adjust pose, then Return to commit)
Drag diamond	Move it in time (multi-selection drags together)
Option-click diamond	Toggle keyframe in/out of multi-selection