

AWS Systems Manager Automation runbook reference: User Guide

Copyright © Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Table of Contents

	n runbook reference
	runbook content
API (Gateway
	AWSConfigRemediation-DeleteAPIGatewayStage
	AWSConfigRemediation-EnableAPIGatewayTracing
	AWSConfigRemediation-UpdateAPIGatewayMethodCaching
AWS	CloudFormation
	AWS-DeleteCloudFormationStack
	AWS-RunCfnLint
	AWS-UpdateCloudFormationStack
Cloud	dFront
	AWSConfigRemediation-EnableCloudFrontDefaultRootObject
	AWSConfigRemediation-EnableCloudFrontAccessLogs
	AWSConfigRemediation-EnableCloudFrontOriginAccessIdentity
	AWSConfigRemediation-EnableCloudFrontOriginFailover
	AWSConfigRemediation-EnableCloudFrontViewerPolicyHTTPS
Cloud	dTrail
	AWSConfigRemediation-CreateCloudTrailMultiRegionTrail
	AWS-EnableCloudTrail
	AWSConfigRemediation-EnableCloudTrailEncryptionWithKMS
	AWSConfigRemediation-EnableCloudTrailLogFileValidation
Cloud	dWatch
Cioui	AWS-ConfigureCloudWatchOnEC2Instance
Code	Build
Couc	AWSConfigRemediation-ConfigureCodeBuildProjectWithKMSCMK
	AWSConfigRemediation-DeleteAccessKeysFromCodeBuildProject
۸۱۸/۲	CodeDeploy
AVV	AWSSupport-TroubleshootCodeDeploy
۸۱۸/۲	
AWS	Config
۸۱۸۱۲	AWSSupport-SetupConfig
AWS	Directory Service
	AWS-CreateDSManagementInstance
D	AWSSupport-TroubleshootDirectoryTrust
Dyna	moDB
	AWS-CreateDynamoDBBackup
	AWS-DeleteDynamoDbBackup
	AWSConfigRemediation-DeleteDynamoDbTable
	AWS-DeleteDynamoDbTableBackups
	AWSConfigRemediation-EnableEncryptionOnDynamoDBTable
	AWSConfigRemediation-EnablePITRForDynamoDbTable
Amaz	zon EBS
	AWS-AttachEBSVolume
	AWSSupport-CalculateEBSPerformanceMetrics
	AWS-CopySnapshot
	AWS-CreateSnapshot
	AWS-DeleteEbsVolumeSnapshots
	AWS-DeleteSnapshot
	AWSConfigRemediation-DeleteUnusedEBSVolume
	AWS-DetachEBSVolume
	AWSConfigRemediation-EnableEbsEncryptionByDefault
	AWSSupport-ModifyEBSSnapshotPermission
	AWSConfigRemediation-ModifyEBSVolumeType
Amaz	zon EC2
	AWSSupport-ActivateWindowsWithAmazonLicense

AWS-ASGEnterStandby	53
AWS-ASGExitStandby	54
AWSSupport-CheckXenToNitroMigrationRequirements	54
AWSEC2-CloneInstanceAndUpgradeWindows	56
AWSEC2-CloneInstanceAndUpgradeSQLServer	
AWSSupport-ConfigureEC2Metadata	
AWSEC2-ConfigureSTIG	
AWSSupport-CopyEC2Instance	
AWS-CreateImage	
AWS-DeleteImage	
AWSConfigRemediation-EnableAutoScalingGroupELBHealthCheck	
AWSConfigRemediation-EnforceEC2InstanceIMDSv2	
AWSSupport-ExecuteEC2Rescue	79
AWSSupport-ListEC2Resources	
AWSSupport-ManageRDPSettings	
AWSSupport-ManageWindowsService	
AWSSupport-MigrateEC2ClassicToVPC	
AWS-PatchAsgInstance	
AWS-PatchInstanceWithRollback	
AWSEC2-PatchLoadBalancerInstance	
AWSSupport-ResetAccess	
AWSSupport-ResetAccess	
AWS-RestartEC2Instance	
AWSSupport-RestoreEC2InstanceFromSnapshot	
AWSSupport-SendLogBundleToS3Bucket	
AWSEC2-SQLServerDBRestore	
AWS-StartEC2Instance	
AWS-StopEC2Instance	
AWSSupport-StartEC2RescueWorkflow	
AWS-TerminateEC2Instance	
AWSPremiumSupport-TroubleshootEC2DiskUsage	
AWSSupport-TroubleshootRDP	
AWSSupport-TroubleshootSSH	
AWSSupport-TroubleshootSUSERegistration	
AWS-UpdateLinuxAmi	
AWS-UpdateWindowsAmi	
AWSSupport-UpgradeWindowsAWSDrivers	
Amazon ECS	
AWSSupport-CollectECSInstanceLogs	
AWS-InstallECSContainerAgent	131
AWSSupport-TroubleshootECSContainerInstance	
AWS-UpdateECSContainerAgent	133
Amazon EFS	134
AWSSupport-CheckAndMountEFS	134
Amazon EKS	
AWSSupport-CollectEKSInstanceLogs	137
AWS-DeleteEKSCluster	138
AWSPremiumSupport-TroubleshootEKSCluster	140
AWSSupport-TroubleshootEKSWorkerNode	
AWS-UpdateEKSManagedNodegroupVersion	
Elastic Beanstalk	
AWSSupport-CollectElasticBeanstalkLogs	
AWSConfigRemediation-EnableElasticBeanstalkEnvironmentLogStreaming	
AWSConfigRemediation-EnableBeanstalkEnvironmentNotifications	
Elastic Load Balancing	
AWSConfigRemediation-DropInvalidHeadersForALB	
AWSConfigRemediation-EnableCLBCrossZoneLoadBalancing	

AWSConfigRemediation-EnableELBDeletionProtection			
AWSConfigRemediation-EnableLoggingForALBAndCLB	154		
AWSConfigRemediation-EnableNLBCrossZoneLoadBalancing	155		
Amazon EMR	156		
AWSSupport-AnalyzeEMRLogs	156		
Amazon OpenSearch Service			
AWSConfigRemediation-DeleteOpenSearchDomain	160		
AWSConfigRemediation-EnforceHTTPSOnOpenSearchDomain	161		
AWSConfigRemediation-UpdateOpenSearchDomainSecurityGroups			
EventBridge			
AWS-AddOpsItemDedupStringToEventBridgeRule			
AWS-DisableEventBridgeRule			
GuardDuty			
AWSConfigRemediation-CreateGuardDutyDetector			
IAM			
AWS-AttachIAMToInstance	167		
AWSConfigRemediation-DeleteIAMRole			
AWSConfigRemediation-DeleteIAMUser			
AWSConfigRemediation-DeleteUnusedIAMGroup			
AWSConfigRemediation-DeleteUnusedIAMPolicy			
AWSConfigRemediation-DetachIAMPolicy			
AWSConfigRemediation-EnableAccountAccessAnalyzer			
AWSSupport-GrantPermissionsToIAMUser			
AWSConfigRemediation-RemoveUserPolicies			
AWSConfigRemediation-ReplaceIAMInlinePolicy			
AWSConfigRemediation-RevokeUnusedIAMUserCredentials			
AWSConfigRemediation-SetIAMPasswordPolicy			
AWS KMS			
AWSConfigRemediation-CancelKeyDeletion			
AWSConfigRemediation-EnableKeyRotation			
Lambda			
AWSConfigRemediation-ConfigureLambdaFunctionXRayTracing			
AWSConfigRemediation-ConfigureDambdaFunction			
AWSConfigRemediation-EncryptLambdaEnvironmentVariablesWithCMK			
AWSConfigRemediation-MoveLambdaToVPC	101		
AWSSupport-RemediateLambdaS3Event			
AWSSupport-TroubleshootLambdaInternetAccess			
AWSSupport-TroubleshootLambdaS3Event	106		
Amazon RDS			
AWS-CreateRdsSnapshot			
AWSConfigRemediation-DeleteRDSCluster			
AWSConfigRemediation-DeleteRDSClusterSnapshot			
AWSConfigRemediation-DeleteRDSInstance			
AWSConfigRemediation-DeleteRDSInstanceSnapshot			
AWSConfigRemediation-DisablePublicAccessToRDSInstance			
AWSConfigRemediation-EnableCopyTagsToSnapshotOnRDSCluster			
AWSConfigRemediation-EnableCopyTagsToSnapshotOnRDSDBInstance			
AWSConfigRemediation-EnableEnhancedMonitoringOnRDSInstance			
AWSConfigRemediation-EnableMinorVersionUpgradeOnRDS			
AWSConfigRemediation-EnableMultiAZOnRDSInstance			
AWSConfigRemediation-EnablePerformanceInsightsOnRDSInstance			
AWSConfigRemediation-EnableRDSClusterDeletionProtection			
AWSConfigRemediation-EnableRDSInstanceBackup			
AWSConfigRemediation-EnableRDSInstanceDeletionProtection			
AWSConfigRemediation-ModifyRDSInstancePortNumber			
AWSSupport-ModifyRDSSnapshotPermission			
AWS-RebootRdsInstance	219		

AWSSupport-ShareRDSSnapshot	
AWS-StartRdsInstance	222
AWSSupport-TroubleshootConnectivityToRDS	222
Amazon Redshift	224
AWSConfigRemediation-DeleteRedshiftCluster	
AWSConfigRemediation-DisablePublicAccessToRedshiftCluster	
AWSConfigRemediation-EnableRedshiftClusterAuditLogging	
AWSConfigRemediation-EnableRedshiftClusterAutomatedSnapshot	
AWSConfigRemediation-EnableRedshiftClusterEncryption	
AWSConfigRemediation-EnableRedshiftClusterEnhancedVPCRouting	
AWSConfigRemediation-EnforceSSLOnlyConnectionsToRedshiftCluster	
AWSConfigRemediation-ModifyRedshiftClusterMaintenanceSettings	
AWSConfigRemediation-ModifyRedshiftClusterNodeType	
Amazon S3	
AWS-ConfigureS3BucketLogging	
AWS-ConfigureS3BucketVersioning	
AWSConfigRemediation-ConfigureS3BucketPublicAccessBlock	
AWSConfigRemediation-ConfigureS3PublicAccessBlock	
AWS-DisableS3BucketPublicReadWrite	
AWS-EnableS3BucketEncryption	
AWSConfigRemediation-RemovePrincipalStarFromS3BucketPolicy	
AWSConfigRemediation-RestrictBucketSSLRequestsOnly	
AWSSupport-TroubleshootS3PublicRead	
Secrets Manager	
AWSConfigRemediation-DeleteSecret	
AWSConfigRemediation-RotateSecret	
Security Hub	
AWSConfigRemediation-EnableSecurityHub	
Amazon SNS	252
AWSConfigRemediation-EncryptSNSTopic	252
AWS-PublishSNSNotification	253
Systems Manager	254
AWS-BulkEditOpsItems	
AWS-BulkResolveOpsItems	
AWS-CreateManagedLinuxInstance	
AWS-CreateManagedWindowsInstance	
AWSConfigRemediation-EnableCWLoggingForSessionManager	
AWS-ExportOpsDataToS3	
AWS-ExportPatchReportToS3	
AWS-SetupInventory	
AWS-SetupManagedInstance	
AWS-SetupManagedRoleOnEC2Instance	
AWSSupport-TroubleshootManagedInstance	
Third-party	
AWS-CreateJiraIssue	
AWS-CreateServiceNowIncident	
AWS-CreateserviceNowIncident AWS-RunPacker	
Amazon VPC	
AWSSupport-ConfigureDNSQueryLogging	
AWSSupport-ConnectivityTroubleshooter	
AWSConfigRemediation-DeleteEgressOnlyInternetGateway	
AWSConfigRemediation-DeleteUnusedENI	
AWSConfigRemediation-DeleteUnusedSecurityGroup	
AWSConfigRemediation-DeleteUnusedVPCNetworkACL	
AWSConfigRemediation-DeleteVPCFlowLog	
AWSConfigRemediation-DetachAndDeleteInternetGateway	
AWSConfigRemediation-DetachAndDeleteVirtualPrivateGateway	287

	AWS-DisablePublicAccessForSecurityGroup	288 289
	AWSSupport-EnableVPCFlowLogs	
	AWSConfigRemediation-EnableVPCFlowLogsToCloudWatch	292
	AWSConfigRemediation-EnableVPCFlowLogsToS3Bucket	294
	AWS-ReleaseElasticIP	295
	AWSConfigRemediation-RemoveUnrestrictedSourceIngressRules	296
	AWSConfigRemediation-RemoveVPCDefaultSecurityGroupRules	297
	AWSSupport-SetupIPMonitoringFromVPC	
	AWSSupport-TerminateIPMonitoringFromVPC	
AWS	WAF	307
	AWSConfigRemediation-EnableWAFClassicLogging	307
	AWSConfigRemediation-EnableWAFClassicRegionalLogging	
	AWSConfigRemediation-EnableWAFV2Logging	
Amaz	zon WorkSpaces	
	AWSSupport-RecoverWorkSpace	311
X-Ra		314
	AWSConfigRemediation-UndateVRayKMSKey	31 <i>I</i>

Systems Manager Automation runbook reference

To help you get started quickly, AWS Systems Manager provides predefined runbooks. These runbooks are maintained by Amazon Web Services, AWS Support, and AWS Config. The runbook reference describes each of the predefined runbooks provided by Systems Manager, AWS Support, and AWS Config.

Important

If you run an automation workflow that invokes other services by using an AWS Identity and Access Management (IAM) service role, be aware that the service role must be configured with permission to invoke those services. This requirement applies to all AWS Automation runbooks (AWS-* runbooks) such as the AWS-ConfigureS3BucketLogging, AWS-CreateDynamoDBBackup, and AWS-RestartEC2Instance runbooks, to name a few. This requirement also applies to any custom Automation runbooks you create that invoke other AWS services by using actions that call other services. For example, if you use the aws:executeAwsApi, aws:createStack, or aws:copyImage actions, then you must configure the service role with permission to invoke those services. You can enable permissions to other AWS services by adding an IAM inline policy to the role. For more information, see Add an Automation inline policy to invoke other AWS services.

This reference includes topics that describe each of the Systems Manager runbooks that are owned by AWS, AWS Support, and AWS Config. Runbooks are organized by the relevant AWS service. Each page provides an explanation of the required and optional parameters you can specify when using the runbook. Each page also lists the steps in the runbook and the output of the automation, if any.

This section does *not* include a separate page for runbooks that require approval such as the AWS-CreateManagedLinuxInstanceWithApproval or AWS-StopEC2InstanceWithApproval runbook. Any runbook name that includes *WithApproval*, means the runbook includes the aws:approve action. This action temporarily pauses an automation until designated principals either approve or reject the action. After the required number of approvals is reached, the automation resumes.

For information about running automations, see Running a simple automation. For information about running automations on multiple targets, see Running automations that use targets and rate controls.

Topics

- View runbook content (p. 2)
- API Gateway (p. 2)
- AWS CloudFormation (p. 6)
- CloudFront (p. 9)
- CloudTrail (p. 15)
- CloudWatch (p. 20)
- CodeBuild (p. 21)
- AWS CodeDeploy (p. 23)
- AWS Config (p. 25)
- AWS Directory Service (p. 27)
- DynamoDB (p. 33)
- Amazon EBS (p. 38)

AWS Systems Manager Automation runbook reference User Guide View runbook content

- Amazon EC2 (p. 50)
- Amazon ECS (p. 129)
- Amazon EFS (p. 134)
- Amazon EKS (p. 137)
- Elastic Beanstalk (p. 146)
- Elastic Load Balancing (p. 150)
- Amazon EMR (p. 156)
- Amazon OpenSearch Service (p. 160)
- EventBridge (p. 163)
- GuardDuty (p. 166)
- IAM (p. 167)
- AWS KMS (p. 185)
- Lambda (p. 187)
- Amazon RDS (p. 197)
- Amazon Redshift (p. 224)
- Amazon S3 (p. 235)
- Secrets Manager (p. 248)
- Security Hub (p. 250)
- Amazon SNS (p. 252)
- Systems Manager (p. 254)
- Third-party (p. 271)
- Amazon VPC (p. 275)
- AWS WAF (p. 307)
- Amazon WorkSpaces (p. 311)
- X-Ray (p. 314)

View runbook content

You can view the content for runbooks in the Systems Manager console.

To view runbook content

- 1. Open the AWS Systems Manager console at https://console.aws.amazon.com/systems-manager/.
- 2.
- 3. Choose a runbook, and then choose View details.
- 4. Choose the Content tab.

API Gateway

AWS Systems Manager Automation provides predefined runbooks for Amazon API Gateway. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

• AWSConfigRemediation-DeleteAPIGatewayStage (p. 3)

- AWSConfigRemediation-EnableAPIGatewayTracing (p. 4)
- AWSConfigRemediation-UpdateAPIGatewayMethodCaching (p. 5)

AWSConfigRemediation-DeleteAPIGatewayStage

Description

The AWSConfigRemediation-DeleteAPIGatewayStage runbook deletes an Amazon API Gateway (API Gateway) stage. AWS Config must be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

StageArn

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the API Gateway stage you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- config:GetResourceConfigHistory
- apigateway:GET
- apigateway: DELETE

Document Steps

AWSConfigRemediation-EnableAPIGatewayTracing

• aws:executeScript - Deletes the API Gateway stage specified in the StageArn parameter.

AWSConfigRemediation-EnableAPIGatewayTracing

Description

The AWSConfigRemediation-EnableAPIGatewayTracing runbook enables tracing on an Amazon API Gateway (API Gateway) stage. AWS Config must be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

· AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

StageArn

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the API Gateway stage you want to enable tracing on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:GetAutomationExecution
- ssm:StartAutomationExecution
- config:GetResourceConfigHistory
- apigateway:GET
- apigateway:PATCH

Document Steps

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

UpdateAPIGatewayMethodCaching

 aws:executeScript - Enables tracing on the API Gateway stage specified in the StageArn parameter.

AWSConfigRemediation-UpdateAPIGatewayMethodCaching

Description

The AWSConfigRemediation-UpdateAPIGatewayMethodCaching runbook updates the cache method setting for an Amazon API Gateway stage resource.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $\arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· CachingAuthorizedMethods

Type: StringList

Description: (Required) The methods authorized to have caching enabled. The list must be some combination of DELETE, GET, HEAD, OPTIONS, PATCH, POST, and PUT. Caching is enabled for selected methods and disabled for non-selected methods. Caching is enabled for all methods if ANY is selected and is disabled for all methods if NONE is selected.

StageArn

Type: String

Description: (Required) The API Gateway stage ARN for the REST API.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

AWS Systems Manager Automation runbook reference User Guide AWS CloudFormation

apigateway:PATCHapigateway:GET

Document Steps

 aws:executeScript - Accepts the stage resource ID as input, updates the cache method setting for an API Gateway stage using the UpdateStage API action, and verifies the update.

AWS CloudFormation

AWS Systems Manager Automation provides predefined runbooks for AWS CloudFormation. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWS-DeleteCloudFormationStack (p. 6)
- AWS-RunCfnLint (p. 7)
- AWS-UpdateCloudFormationStack (p. 8)

AWS-DeleteCloudFormationStack

Description

Delete an AWS CloudFormation stack.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

StackNameOrId

Type: String

Description: (Required) Name or Unique ID of the CloudFormation stack to be deleted

AWS-RunCfnLint

Description

This runbook uses an AWS CloudFormation Linter (cfn-python-lint) to validate YAML and JSON templates against the AWS CloudFormation resource specification. The AWS-RunCfnLint runbook performs additional checks, such as ensuring that valid values have been entered for resource properties. If validation is not successful, the RunCfnLintAgainstTemplate step fails and the linter tool's output is provided in an error message. This runbook is using cfn-lint v0.24.4.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ConfigureRuleFlag

Type: String

Description: (Optional) Configuration options for a rule to pass to the --configure-rule parameter.

Example: E2001:strict=false,E3012:strict=false.

FormatFlag

Type: String

Description: (Optional) Value to pass to the --format parameter to specify the output format.

Valid values: Default | quiet | parseable | json

Default: Default
• IgnoreChecksFlag

Type: String

Description: (Optional) IDs of rules to pass to the --ignore-checks parameter. These rules are not checked.

Example: E1001,E1003,W7001

IncludeChecksFlag

AWS Systems Manager Automation runbook reference User Guide AWS-UpdateCloudFormationStack

Type: String

Description: (Optional) IDs of rules to pass to the --include-checks parameter. These rules are

checked.

Example: E1001,E1003,W7001

InfoFlag

Type: String

Description: (Optional) Option for the --info parameter. Include the option to enable additional logging information about the template processing.

Default: false

TemplateFileName

Type: String

Description: The name, or key, of the template file in the S3 bucket.

• TemplateS3BucketName

Type: String

Description: The name of the S3 bucket containing the packer template.

RegionsFlag

Type: String

Description: (Optional) Values to pass to the for --regions parameter to test the template against

specified AWS Regions.

Example: us-east-1,us-west-1

Document Steps

RunCfnLintAgainstTemplate – Runs the cfn-python-lint tool against the specified AWS CloudFormation template.

Outputs

RunCfnLintAgainstTemplate.output - The stdout from the cfn-python-lint tool.

AWS-UpdateCloudFormationStack

Description

Update an AWS CloudFormation stack by using an AWS CloudFormation template stored in an Amazon S3 bucket.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

LambdaAssumeRole

Type: String

Description: (Required) The ARN of the role assumed by Lambda

StackNameOrld

Type: String

Description: (Required) Name or Unique ID of the AWS CloudFormation stack to be updated

TemplateUrl

Type: String

Description: (Required) S3 bucket location that contains the updated CloudFormation template (e.g. https://s3.amazonaws.com/doc-example-bucket/updated.template)

CloudFront

AWS Systems Manager Automation provides predefined runbooks for Amazon CloudFront. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-EnableCloudFrontDefaultRootObject (p. 9)
- AWSConfigRemediation-EnableCloudFrontAccessLogs (p. 10)
- AWSConfigRemediation-EnableCloudFrontOriginAccessIdentity (p. 12)
- AWSConfigRemediation-EnableCloudFrontOriginFailover (p. 13)
- AWSConfigRemediation-EnableCloudFrontViewerPolicyHTTPS (p. 14)

AWSConfigRemediation-EnableCloudFrontDefaultRootObject

Description

The AWSConfigRemediation-EnableCloudFrontDefaultRootObject runbook configures the default root object for the Amazon CloudFront (CloudFront) distribution that you specify.

Run this Automation (console)

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnableCloudFrontAccessLogs

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

CloudFrontDistributionId

Type: String

Description: (Required) The ID of the CloudFront distribution that you want to configure the default root object for.

DefaultRootObject

Type: String

Description: (Required) The object that you want CloudFront to return when a viewer request points to your root URL.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- cloudfront:GetDistributionConfig
- cloudfront:UpdateDistribution

Document Steps

 aws:executeScript - Configures the default root object for the CloudFront distribution that you specify in the CloudFrontDistributionId parameter.

AWSConfigRemediation-EnableCloudFrontAccessLogs

Description

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnableCloudFrontAccessLogs

The AWSConfigRemediation-EnableCloudFrontAccessLogs runbook enables access logging for the Amazon CloudFront (CloudFront) distribution you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

BucketName

Type: String

Description: (Required) The name of the Amazon Simple Storage Service (Amazon S3) bucket you want to store access logs in. Buckets in the af-south-1, ap-east-1, eu-south-1, and me-south-1 AWS Region are not supported.

CloudFrontId

Type: String

Description: (Required) The ID of the CloudFront distribution you want to enable access logging on.

IncludeCookies

Type: Boolean

Valid values: true | false

Description: (Optional) Set this parameter to true, if you want cookies to be included in the access logs.

Prefix

Type: String

Description: (Optional) An optional string that you want CloudFront to prefix to the access log filenames for your distribution, for example, myprefix/.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

• ssm:StartAutomationExecution

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableCloudFrontOriginAccessIdentity

- ssm:GetAutomationExecution
- cloudfront:GetDistributionConfig
- cloudfront:UpdateDistribution

Document Steps

 aws:executeScript - Enables access logging for the CloudFront distribution you specify in the CloudFrontDistributionId parameter.

AWSConfigRemediation-EnableCloudFrontOriginAccessIdentity

Description

The AWSConfigRemediation-EnableCloudFrontOriginAccessIdentity runbook enables origin access identity for the Amazon CloudFront (CloudFront) distribution you specify. This automation assigns the same CloudFront Origin Access Identity for all Origins of the Amazon Simple Storage Service (Amazon S3) Origin type without origin access identity for the CloudFront distribution you specify. This automation does not grant read permission to the origin access identity for CloudFront to access objects in your Amazon S3 bucket. You must update your Amazon S3 bucket permissions to allow access.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· CloudFrontDistributionId

Type: String

Description: (Required) The ID of the CloudFront distribution you want to enable origin failover on.

· OriginAccessIdentityId

Type: String

Description: (Required) The ID of the CloudFront origin access identity to associate with the origin.

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableCloudFrontOriginFailover

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- cloudfront:GetDistributionConfig
- cloudfront:UpdateDistribution

Document Steps

• aws:executeScript - Enables origin access identity for the CloudFront distribution you specify in the CloudFrontDistributionId parameter, and verifies the origin access identity was assigned.

AWSConfigRemediation-EnableCloudFrontOriginFailover

Description

The AWSConfigRemediation-EnableCloudFrontOriginFailover runbook enables origin failover for the Amazon CloudFront (CloudFront) distribution you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

CloudFrontDistributionId

Type: String

Description: (Required) The ID of the CloudFront distribution you want to enable origin failover on.

OriginGroupId

Type: String

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableCloudFrontViewerPolicyHTTPS

Description: (Required) The ID of the origin group.

· PrimaryOriginId

Type: String

Description: (Required) The ID of the primary origin in the origin group.

· SecondaryOriginId

Type: String

Description: (Required) The ID of the secondary origin in the origin group.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- cloudfront:GetDistributionConfig
- cloudfront:UpdateDistribution

Document Steps

• aws:executeScript - Enables origin failover for the CloudFront distribution you specify in the CloudFrontDistributionId parameter, and verifies that failover has been enabled.

AWSConfigRemediation-EnableCloudFrontViewerPolicyHTTPS

Description

The AWSConfigRemediation-EnableCloudFrontViewerPolicyHTTPS runbook enables the viewer protocol policy for the Amazon CloudFront (CloudFront) distribution you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· CloudFrontDistributionId

Type: String

Description: (Required) The ID of the CloudFront distribution you want to enable the viewer protocol policy on.

ViewerProtocolPolicy

Type: String

Valid values: https-only, redirect-to-https

Description: (Required) The protocol that viewers can use to access the files in the origin.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- cloudfront:GetDistributionConfig
- cloudfront:UpdateDistribution

Document Steps

• aws:executeScript - Enables the viewer protocol policy for the CloudFront distribution you specify in the CloudFrontDistributionId parameter, and verifies the policy was assigned.

CloudTrail

AWS Systems Manager Automation provides predefined runbooks for AWS CloudTrail. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-CreateCloudTrailMultiRegionTrail (p. 15)
- AWS-EnableCloudTrail (p. 17)
- AWSConfigRemediation-EnableCloudTrailEncryptionWithKMS (p. 18)
- AWSConfigRemediation-EnableCloudTrailLogFileValidation (p. 19)

AWSConfigRemediation-CreateCloudTrailMultiRegionTrail

Description

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

CreateCloudTrailMultiRegionTrail

The AWSConfigRemediation-CreateCloudTrailMultiRegionTrail runbook creates an AWS CloudTrail (CloudTrail) trail that delivers log files from multiple AWS Regions to the Amazon Simple Storage Service (Amazon S3) bucket of your choice.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

BucketName

Type: String

Description: (Required) The name of the Amazon S3 bucket you want to upload logs to.

KeyPrefix

Type: String

Description: (Optional) The Amazon S3 key prefix that comes after the name of the bucket you designated for log file delivery.

• TrailName

Type: String

Description: (Required) The name of the CloudTrail trail to be created.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- cloudtrail:CreateTrail
- cloudtrail:StartLogging
- cloudtrail:GetTrail
- s3:PutObject

AWS Systems Manager Automation runbook reference User Guide AWS-EnableCloudTrail

- s3:GetBucketAcl
- s3:PutBucketLogging
- s3:ListBucket

Document Steps

- aws:executeAwsApi Accepts the trail name and the Amazon S3 bucket name as input and creates a CloudTrail trail.
- aws:executeAwsApi Enables logging on the created trail and starts log delivery to the Amazon S3 bucket you specified.
- aws:assertAwsResourceProperty Verifies that the CloudTrail trail has been created.

AWS-EnableCloudTrail

Description

Create an AWS CloudTrail trail and configure logging to an S3 bucket.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

S3BucketName

Type: String

Description: (Required) Name of the S3 bucket designated for publishing log files.

Note

The S3 bucket must exist and the bucket policy must grant CloudTrail permission to write to it. For information, see Amazon S3 Bucket Policy for CloudTrail.

TrailName

Type: String

Description: (Required) The name of the new trail.

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableCloudTrailEncryptionWithKMS

AWSConfigRemediation-EnableCloudTrailEncryptionWithKMS

Description

The AWSConfigRemediation-EnableCloudTrailEncryptionWithKMS runbook encrypts an AWS CloudTrail (CloudTrail) trail using the AWS Key Management Service (AWS KMS) customer managed key you specify. This runbook should only be used as a baseline to ensure that your CloudTrail trails are encrypted according to minimum recommended security best practices. We recommend encrypting multiple trails with different KMS keys. CloudTrail digest files are not encrypted. If you have previously set the EnableLogFileValidation parameter to true for the trail, see the "Use server-side encryption with AWS KMS managed keys" section of the CloudTrail Preventative Security Best Practices topic in the AWS CloudTrail User Guide for more information.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

KMSKeyId

Type: String

Description: (Required) The ARN, key ID, or the key alias of the of the customer managed key you want to use to encrypt the trail you specify in the TrailName parameter.

TrailName

Type: String

Description: (Required) The ARN or name of the trail you want to update to be encrypted.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableCloudTrailLogFileValidation

- cloudtrail:GetTrail
- cloudtrail:UpdateTrail

Document Steps

- aws:executeAwsApi Enables encryption on the trail you specify in the TrailName parameter.
- aws:executeAwsApi Gathers the ARN for the customer managed key you specify in the KMSKeyId parameter.
- aws:assertAwsResourceProperty Verifies that encryption has been enabled on the CloudTrail trail.

AWSConfigRemediation-EnableCloudTrailLogFileValidation

Description

The AWSConfigRemediation-EnableCloudTrailLogFileValidation runbook enables log file validation for your AWS CloudTrail trail.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

TrailName

Type: String

Description: (Required) The name or Amazon Resource Name (ARN) of the trail you want to enable log validation for.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

• ssm:StartAutomationExecution

- ssm:GetAutomationExecution
- cloudtrail:DescribeTrails
- cloudtrail:UpdateTrail

Document Steps

- aws:executeAwsApi Enables log validation for the AWS CloudTrail trail you specify in the TrailName parameter.
- aws:assertAwsResourceProperty Verifies log validation is enabled for your trail.

CloudWatch

AWS Systems Manager Automation provides predefined runbooks for Amazon CloudWatch. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

• AWS-ConfigureCloudWatchOnEC2Instance (p. 20)

AWS-ConfigureCloudWatchOnEC2Instance

Description

Enable or disable Amazon CloudWatch detailed monitoring on managed instances.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

InstanceId

Type: String

Description: (Required) The ID of the Amazon EC2 instance on which you want to enable CloudWatch monitoring.

properties

Type: String

Description: (Optional) This parameter is not supported. It is listed here for backwards compatibility.

status

Valid values: Enabled | Disabled

Description: (Optional) Specifies whether to enable or disable CloudWatch.

Default: Enabled

Document Steps

configureCloudWatch - Configures CloudWatch on the Amazon EC2 instance with the given status.

Outputs

This automation has no output.

CodeBuild

AWS Systems Manager Automation provides predefined runbooks for AWS CodeBuild. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-ConfigureCodeBuildProjectWithKMSCMK (p. 21)
- AWSConfigRemediation-DeleteAccessKeysFromCodeBuildProject (p. 22)

AWSConfigRemediation-ConfigureCodeBuildProjectWithKMSCMK

Description

The AWSConfigRemediation-ConfigureCodeBuildProjectWithKMSCMK runbook encrypts an AWS CodeBuild (CodeBuild) project's build artifacts using the AWS Key Management Service (AWS KMS) customer managed key you specify. AWS Config must be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

DeleteAccessKeysFromCodeBuildProject

Parameters

• AutomationAssumeRole

Type: String

Allowed values: $\arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

KMSKeyId

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the AWS KMS customer managed key you want to use to encrypt the CodeBuild project you specify in the ProjectId parameter.

ProjectId

Type: String

Description: (Required) The ID of the CodeBuild project whose build artifacts you want to encrypt.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- codebuild:BatchGetProjects
- codebuild:UpdateProject
- config:GetResourceConfigHistory

Document Steps

- aws:executeAwsApi Gathers the CodeBuild project name from the project ID.
- aws:executeAwsApi Enables encryption on the CodeBuild project you specify in the ProjectId parameter.
- aws:assertAwsResourceProperty Verifies that encryption has been enabled on the CodeBuild project.

Outputs

UpdateLambdaConfig.UpdateFunctionConfigurationResponse - Response from the UpdateFunctionConfiguration API call.

AWSConfigRemediation-DeleteAccessKeysFromCodeBuildProject

Description

The AWSConfigRemediation-DeleteAccessKeysFromCodeBuildProject runbook deletes the AWS_ACCESS_KEY_ID and AWS_SECRET_ACCESS_KEY environment variables from the AWS CodeBuild

AWS Systems Manager Automation runbook reference User Guide AWS CodeDeploy

(CodeBuild) project you specify. AWS Config must be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Resourceld

Type: String

Description: (Required) The ID of the CodeBuild project whose access key environment variables you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- config:GetResourceConfigHistory
- codebuild:BatchGetProjects
- codebuild:UpdateProject

Document Steps

 aws:executeScript - Deletes the access key environment variables for the CodeBuild project specified in the ResourceId parameter.

AWS CodeDeploy

AWS Systems Manager Automation provides predefined runbooks for AWS CodeDeploy. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootCodeDeploy

Topics

AWSSupport-TroubleshootCodeDeploy (p. 24)

AWSSupport-TroubleshootCodeDeploy

Description

The AWSSupport-TroubleshootCodeDeploy runbook helps diagnose why an AWS CodeDeploy deployment failed on an Amazon Elastic Compute Cloud (Amazon EC2) instance. The runbook outputs steps to help you resolve the issue or troubleshoot further. Best practices for CodeDeploy are also provided to help you avoid similar issues in the future.

This runbook can help you to resolve the following issues:

- The CodeDeploy agent is not installed or not running on the Amazon EC2 instance
- The Amazon EC2 instance does not have an AWS Identity and Access Management (IAM) instance profile attached
- The IAM instance profile attached to the Amazon EC2 instance does not have the required Amazon Simple Storage Service (Amazon S3) permissions
- A revision stored in Amazon S3 is missing, or the Amazon S3 bucket used is in an AWS Region that is different than the Amazon EC2 instance
- Application specification (AppSpec) file issues
- "File already exists at location" errors
- Failed CodeDeploy managed lifecycle event hooks
- · Failed customer managed lifecycle event hooks
- · Scale-in events during the deployment

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

· DeploymentId

Type: String

Description: (Required) The ID of the deployment which failed.

Instanceld

Type: String

Description: (Required) The ID of the Amazon EC2 instance where the deployment failed.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- codedeploy:GetDeployment
- codedeploy:GetDeploymentTarget
- ec2:DescribeInstances

Document Steps

- aws:executeAwsApi Verifies the values provided for the DeploymentId and InstanceId parameters.
- aws:executeScript Collects information from the Amazon EC2 instance such as the state of the instance and IAM instance profile details.
- aws:executeScript Reviews the specified deployment, and returns an analysis regarding why the
 deployment failed.

AWS Config

AWS Systems Manager Automation provides predefined runbooks for AWS Config. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

AWSSupport-SetupConfig (p. 25)

AWSSupport-SetupConfig

Description

The AWSSupport-SetupConfig runbook creates an AWS Identity and Access Management (IAM) service-linked role, a configuration recorder powered by AWS Config, and a delivery channel with an Amazon Simple Storage Service (Amazon S3) bucket where AWS Config sends configuration snapshots and configuration history files. If you specify values for the AggregatorAccountId and AggregatorAccountRegion parameters, the runbook also creates authorizations for data aggregation to collect AWS Config configuration and compliance data from multiple AWS accounts and multiple AWS Regions. To learn more about aggregating data from multiple accounts and Regions, see Multi-Account Multi-Region Data Aggregation in the AWS Config Developer Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide AWSSupport-SetupConfig

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

· AggregatorAccountId

Type: String

Description: (Optional) The ID of the AWS account where an aggregator will be added to aggregate AWS Config configuration and compliance data from multiple accounts and AWS Regions. This account is also used by the aggregator to authorize the source accounts.

· AggregatorAccountRegion

Type: String

Description: (Optional) The Region where an aggregator will be added to aggregate AWS Config configuration and compliance data from multiple accounts and Regions.

· IncludeGlobalResourcesRegion

Type: String

Default: us-east-1

Description: (Required) To avoid recording global resource data in each Region, specify one Region to record global resource data from.

Partition

Type: String

Default: aws

Description: (Required) The partition you want to collect AWS Config configuration and compliance data from.

S3BucketName

Type: String

Default: aws-config-delivery-channel

Description: (Optional) The name you want to apply to the Amazon S3 bucket created for the delivery channel. The account ID is appended to the end of the name.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

AWS Systems Manager Automation runbook reference User Guide AWS Directory Service

- config:DescribeConfigurationRecorders
- config:DescribeDeliveryChannels
- config:PutAggregationAuthorization
- config:PutConfigurationRecorder
- config:PutDeliveryChannel
- config:StartConfigurationRecorder
- iam:CreateServiceLinkedRole
- iam:PassRole
- s3:CreateBucket
- s3:ListAllMyBuckets
- s3:PutBucketPolicy

Document Steps

- aws:executeScript Creates a service-linked IAM role for AWS Config if one does not already exist.
- aws:executeScript Creates a configuration recorder if one does not already exist.
- aws:executeScript Creates an Amazon S3 bucket to be used by the delivery channel if one does not already exist.
- aws:executeScript Creates a delivery channel using the resources created by the runbook.
- aws:executeAwsApi Starts the configuration recorder.
- aws:executeScript If you specified values for the AggregatorAccountId and AggregatorAccountRegion parameters, authorizations for multi-account and multi-Region data aggregation are configured.

AWS Directory Service

AWS Systems Manager Automation provides predefined runbooks for AWS Directory Service. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWS-CreateDSManagementInstance (p. 27)
- AWSSupport-TroubleshootDirectoryTrust (p. 30)

AWS-CreateDSManagementInstance

Description

The AWS-CreateDSManagementInstance runbook creates an Amazon Elastic Compute Cloud (Amazon EC2) Windows instance that you can use to manage your AWS Directory Service directory. The management instance can't be used to manage AD Connector directories.

Run this Automation (console)

Document type

Automation

Owner

AWS Systems Manager Automation runbook reference User Guide AWS-CreateDSManagementInstance

Platforms

Windows

Parameters

• AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

AmilD

Type: String

```
Default: {{    ssm:/aws/service/ami-windows-latest/Windows_Server-2019-English-
Full-Base }}
```

Description: (Required) The ID of the Amazon Machine Image (AMI) you want to use to launch the management instance.

DirectoryId

Type: String

Description: (Required) The ID of the AWS Directory Service directory you want to manage. The instance is joined to the directory you specify.

IamInstanceProfileName

Type: String

Description: (Required) The name you specify is applied to the IAM instance profile that is created by the automation and attached to the management instance.

InstanceType

Type: String

Default: t3.medium

Allowed values:

- t2.nano
- · t2.micro
- t2.small
- t2.medium
- t2.large
- t2.xlarge
- t2.2xlarge
- t3.nano
- t3.micro
- t3.small
- t3.medium
- t3.large

AWS-CreateDSManagementInstance

- t3.xlarge
- t3.2xlarge

Description: (Required) The type of instance you want to launch.

KeyPairName

Type: String

Description: (Optional) The key pair to use when creating the instance. If you do not specify a value, no key pair is associated with the instance.

RemoteAccessCidr

Type: String

Description: (Required) The CIDR block you want to allow RDP traffic (port 3389) from. The CIDR block you specify is applied to an inbound rule that's added to the security group created by the automation.

• SecurityGroupName

Type: String

Description: (Required) The name you specify is applied to the security group that is created by the automation and associated with the management instance.

Tags

Type: MapList

Description: (Optional) A key-value pair you want to apply to the resources created by the automation.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ds:DescribeDirectories
- ec2:AuthorizeSecurityGroupIngress
- ec2:CreateSecurityGroup
- ec2:CreateTags
- ec2:DeleteSecurityGroup
- ec2:DescribeInstances
- ec2:DescribeInstanceStatus
- ec2:DescribeKeyPairs
- ec2:DescribeSecurityGroups
- ec2:DescribeVpcs
- ec2:RunInstances
- ec2:TerminateInstances
- iam:AddRoleToInstanceProfile
- iam:AttachRolePolicy
- iam:CreateInstanceProfile
- iam:CreateRole
- iam:DeleteInstanceProfile
- iam:DeleteRole
- iam:DetachRolePolicy
- iam:GetInstanceProfile

AWS Systems Manager Automation runbook reference User Guide

AWSSupport-TroubleshootDirectoryTrust

- iam:GetRole
- iam:ListAttachedRolePolicies
- iam:ListInstanceProfiles
- iam:ListInstanceProfilesForRole
- iam:PassRole
- iam:RemoveRoleFromInstanceProfile
- iam:TagInstanceProfile
- iam:TagRole
- ssm:CreateDocument
- ssm:DeleteDocument
- ssm:DescribeInstanceInformation
- ssm:GetAutomationExecution
- ssm:GetParameters
- ssm:ListCommandInvocations
- ssm:ListCommands
- ssm:ListDocuments
- ssm:SendCommand
- ssm:StartAutomationExecution

Document Steps

- aws:executeAwsApi Gathers details about the directory you specify in the DirectoryId parameter.
- aws:executeAwsApi Gets the CIDR block of the virtual private cloud (VPC) where the directory was launched.
- aws:executeAwsApi Creates a security group using the value you specify in the SecurityGroupName parameter.
- aws:executeAwsApi Creates an inbound rule for the newly created security group that allows RDP traffic from the CIDR you specify in the RemoteAccessCidr parameter.
- aws:executeAwsApi Creates an IAM role and instance profile using the value you specify in the IamInstanceProfileName parameter.
- aws:executeAwsApi Launches an Amazon EC2 instance based on the values you specify in the runbook parameters.
- aws:executeAwsApi Creates an AWS Systems Manager document to join the newly launched instance to your directory.
- aws:runCommand Joins the new instance to your directory.
- aws:runCommand Installs remote server administration tools on the new instance.

AWSSupport-TroubleshootDirectoryTrust

Description

The AWSSupport-TroubleshootDirectoryTrust runbook diagnoses trust creation issues between an AWS Managed Microsoft AD and a Microsoft Active Directory. The automation ensures the directory type supports trusts, and then checks the associated security group rules, network access control lists (network ACLs), and route tables for potential connectivity issues.

Run this Automation (console)

Document type

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootDirectoryTrust

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

DirectoryId

Type: String

Allowed pattern: ^d-[a-z0-9]{10}\$

Description: (Required) The ID of the AWS Managed Microsoft AD to troubleshoot.

· RemoteDomainCidrs

Type: StringList

Allowed pattern: $(([0-9][1-9][0-9][1[0-9][2][0-4][0-9][25[0-5])).){3}([0-9][1-9][0-9][1[0-9][2][0-4][0-9][25[0-5]))$

Description: (Required) The CIDR(s) of the remote domain you are attempting to establish a trust relationship with. You can add multiple CIDRs using comma-separated values. For example, 172.31.48.0/20, 192.168.1.10/32.

RemoteDomainName

Type: String

Description: (Required) The fully qualified domain name of the remote domain you are establishing a trust relationship with.

RequiredTrafficACL

Type: String

Description: (Required) The default port requirements for AWS Managed Microsoft AD. In most cases, you should not modify the default value.

 $\label{lem:prop:state} Default: {"inbound":{"tcp":[[53,53],[88,88],[135,135],[389,389],[445,445],[464,464],[636,636], [1024,65535]],"udp":[[53,53],[88,88],[123.123],[138,138],[389,389],[445,445],[464,464]],"icmp": [[-1,-1]]},"outbound":{"-1":[[0,65535]]}}\\$

RequiredTrafficSG

Type: String

Description: (Required) The default port requirements for AWS Managed Microsoft AD. In most cases, you should not modify the default value.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootDirectoryTrust

Default: {"inbound":{"tcp":[[53,53],[88,88],[135,135],[389,389],[445,445],[464,464],[636,636], [1024,65535]],"udp":[[53,53],[88,88],[123.123],[138,138],[389,389],[445,445],[464,464]],"icmp": [[-1,-1]]},"outbound":{"-1":[[0,65535]]}}

TrustId

Type: String

Description: (Optional) The ID of the trust relationship to troubleshoot.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ds:DescribeConditionalForwarders
- ds:DescribeDirectories
- ds:DescribeTrusts
- ds:ListIpRoutes
- ec2:DescribeNetworkAcls
- ec2:DescribeSecurityGroups
- ec2:DescribeSubnets

Document Steps

- aws:assertAwsResourceProperty Confirms the directory type is AWS Managed Microsoft AD.
- aws:executeAwsApi Gets information about the AWS Managed Microsoft AD.
- aws:branch Branches automation if a value is provided for the TrustId input parameter.
- aws:executeAwsApi Gets information about the trust relationship.
- $\bullet \ \ \text{aws:executeAwsApi-Gets the conditional forwarder DNS IP addresses for the $\tt RemoteDomainName.}\\$
- aws:executeAwsApi Gets information about IP routes that have been added to the AWS Managed Microsoft AD.
- aws:executeAwsApi Gets the CIDRs of the AWS Managed Microsoft AD subnets.
- aws:executeAwsApi Gets information about the security groups associated with the AWS Managed Microsoft AD.
- aws:executeAwsApi Gets information about the network ACLs associated with the AWS Managed Microsoft AD.
- aws:executeScript Confirms the RemoteDomainCidrs are valid values. Confirms that the AWS Managed Microsoft AD has conditional forwarders for the RemoteDomainCidrs, and that the requisite IP routes have been added to the AWS Managed Microsoft AD if the RemoteDomainCidrs are non-RFC 1918 IP addresses.
- aws:executeScript Evaluates security group rules.
- aws:executeScript Evaluates network ACLs.

Outputs

evalDirectorySecurityGroup.output - Results from evaluating whether the security group rules associated with the AWS Managed Microsoft AD allow the requisite traffic for trust creation.

evalAclEntries.output - Results from evaluating whether the network ACLs associated with the AWS Managed Microsoft AD allow the requisite traffic for trust creation.

AWS Systems Manager Automation runbook reference User Guide DynamoDB

evaluateRemoteDomainCidr.output - Results from evaluating whether the RemoteDomainCidrs are valid values. Confirms that the AWS Managed Microsoft AD has conditional forwarders for the RemoteDomainCidrs, and that the requisite IP routes have been added to the AWS Managed Microsoft AD if the RemoteDomainCidrs are non-RFC 1918 IP addresses.

DynamoDB

AWS Systems Manager Automation provides predefined runbooks for Amazon DynamoDB. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWS-CreateDynamoDBBackup (p. 33)
- AWS-DeleteDynamoDbBackup (p. 34)
- AWSConfigRemediation-DeleteDynamoDbTable (p. 34)
- AWS-DeleteDynamoDbTableBackups (p. 35)
- AWSConfigRemediation-EnableEncryptionOnDynamoDBTable (p. 36)
- AWSConfigRemediation-EnablePITRForDynamoDbTable (p. 37)

AWS-CreateDynamoDBBackup

Description

Create a backup of an Amazon DynamoDB table.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

BackupName

Type: String

Description: (Required) Name of the backup to create.

LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

TableName

Type: String

Description: (Required) Name of the DynamoDB table.

AWS-DeleteDynamoDbBackup

Description

Delete the backup of an Amazon DynamoDB table.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

BackupArn

Type: String

Description: (Required) ARN of the DynamoDB table backup to delete.

AWSConfigRemediation-DeleteDynamoDbTable

Description

The AWSConfigRemediation-DeleteDynamoDbTable runbook deletes the Amazon DynamoDB (DynamoDB) table you specify.

Run this Automation (console)

Document type

AWS Systems Manager Automation runbook reference User Guide AWS-DeleteDynamoDbTableBackups

Owner

Automation

Amazon

Platforms

Databases

Parameters

• AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

TableName

Type: String

Description: (Required) The name of the DynamoDB table you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- dynamodb:DeleteTable
- dynamodb:DescribeTable

Document Steps

- aws:executeScript Deletes the DynamoDB table specified in the TableName parameter.
- aws:executeScript Verifies the DynamoDB table has been deleted.

AWS-DeleteDynamoDbTableBackups

Description

Delete DynamoDB table backups based on retention days or count.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableEncryptionOnDynamoDBTable

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

RetentionCount

Type: String
Default: 10

Description: (Optional) The number of backups to retain for the table. If more than the specified number of backup exist, the oldest backups beyond that number are deleted. Either RetentionCount or RetentionDays can be used, not both.

RetentionDays

Type: String

Description: (Optional) The number of days to retain backups for the table. Backups older than the specified number of days are deleted. Either RetentionCount or RetentionDays can be used, not both.

TableName

Type: String

Description: (Required) Name of the DynamoDB table.

AWSConfigRemediation-EnableEncryptionOnDynamoDBTable

Description

The AWSConfigRemediation-EnableEncryptionOnDynamoDBTable runbook encrypts an Amazon DynamoDB (DynamoDB) table using the AWS Key Management Service (AWS KMS) customer managed key you specify for the KMSKeyId parameter.

Run this Automation (console)

Document type

Automation

Owner

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnablePITRForDynamoDbTable

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

KMSKeyId

Type: String

Description: (Required) The ARN of the customer managed key you want to use to encrypt the DynamoDB table you specify in the TableName parameter.

TableName

Type: String

Description: (Required) The name of the DynamoDB table you want to encrypt.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- dynamodb:DescribeTable
- dynamodb:UpdateTable

Document Steps

- aws:executeAwsApi Encrypts the DynamoDB table you specify in the TableName parameter.
- aws:waitForAwsResourceProperty Verifies the Enabled property for the DynamoDB table's SSESpecification is set to true.
- aws:assertAwsResourceProperty Verifies the DynamoDB table is encrypted with the customer managed key specified in the KMSKeyId parameter.

AWSConfigRemediation-EnablePITRForDynamoDbTable

Description

The AWSConfigRemediation-EnablePITRForDynamoDbTable runbook enables point-in-time recovery (PITR) on the Amazon DynamoDB table you specify.

Run this Automation (console)

AWS Systems Manager Automation runbook reference User Guide Amazon EBS

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

TableName

Type: String

Description: (Required) The name of the DynamoDB table to enable point-in-time recovery on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- dynamodb:DescribeContinuousBackups
- dynamodb: UpdateContinuousBackups

Document Steps

- aws:executeAwsApi Enables point-in-time recovery on the DynamoDB table you specify in the TableName parameter.
- aws:assertAwsResourceProperty Confirms point-in-time recovery is enabled on the DynamoDB table.

Amazon EBS

AWS Systems Manager Automation provides predefined runbooks for Amazon Elastic Block Store. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWS-AttachEBSVolume (p. 39)
- AWSSupport-CalculateEBSPerformanceMetrics (p. 40)
- AWS-CopySnapshot (p. 41)

AWS Systems Manager Automation runbook reference User Guide AWS-AttachEBSVolume

- AWS-CreateSnapshot (p. 42)
- AWS-DeleteEbsVolumeSnapshots (p. 43)
- AWS-DeleteSnapshot (p. 44)
- AWSConfigRemediation-DeleteUnusedEBSVolume (p. 44)
- AWS-DetachEBSVolume (p. 46)
- AWSConfigRemediation-EnableEbsEncryptionByDefault (p. 46)
- AWSSupport-ModifyEBSSnapshotPermission (p. 47)
- AWSConfigRemediation-ModifyEBSVolumeType (p. 49)

AWS-AttachEBSVolume

Description

Attach an Amazon Elastic Block Store (Amazon EBS) volume to an Amazon Elastic Compute Cloud (Amazon EC2) instance.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Device

Type: String

Description: (Required) The device name (for example, /dev/sdh or xvdh).

InstanceId

Type: String

Description: (Required) The ID of the instance where you want to attach the volume.

VolumeId

Type: String

Description: (Required) The ID of the Amazon EBS volume. The volume and instance must be in the same Availability Zone.

AWSSupport-CalculateEBSPerformanceMetrics

Description

The AWSSupport-CalculateEBSPerformanceMetrics runbook helps diagnose Amazon Elastic Block Store (Amazon EBS) performance issues by calculating metrics published to Amazon CloudWatch and creating CloudWatch dashboards that display the average I/O size and total aggregate throughput and IOPS of individual Amazon EBS volumes, or the total aggregate throughput and IOPS across all Amazon EBS volumes attached to an Amazon Elastic Compute Cloud (Amazon EC2) instance by utilizing CloudWatch metric math. The runbook outputs the link to the newly created CloudWatch dashboard that displays the relevant calculated CloudWatch metrics.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

EndTime

Type: String

Description: (Required) The end of the time range to use for each widget on the CloudWatch dashboard when the dashboard loads. For the value of this parameter, specify an absolute time in the ISO 8601 format. To learn more about creating ISO 8601 formatted strings, see Creating formatted date and time strings for Systems Manager.

Resourceld

Type: String

Description: (Required) The ID of the Amazon EBS volume or Amazon EC2 instance whose attached Amazon EBS volumes performance metrics you want to calculate and view.

StartTime

Type: String

Description: (Required) The start of the time range to use for each widget on the CloudWatch dashboard. For the value of this parameter, specify an absolute time in the ISO 8601 format.

Period

AWS Systems Manager Automation runbook reference User Guide AWS-CopySnapshot

Type: String

Description: (Required) The default period, in seconds, for all metrics in this widget. The period is the length of time represented by one data point on the graph.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeVolumes
- ec2:DescribeInstances
- ec2:DescribeInstanceTypes
- cloudwatch:PutDashboard
- cloudwatch:ListMetrics

Document Steps

- aws:executeScript Validates the values provided for StartTime and EndTime parameters.
- aws:branch Checks whether the value provided in the parameter ResourceId is an Amazon EBS volume ID, or an Amazon EC2 instance ID.
- aws:executeScript If an Amazon EBS volume ID is provided for the parameter ResourceId, creates a CloudWatch dashboard with calculated aggregate throughput, aggregate IOPS, and average IO size for the Amazon EBS volume.
- aws:executeScript If an Amazon EC2 instance ID is provided for the parameter ResourceId, creates a CloudWatch dashboard with calculated aggregate throughput and aggregate IOPS for the Amazon EC2 instance and the calculated aggregate throughput, aggregate IOPS, and average IO size for each of the Amazon EBS volumes attached to the Amazon EC2 instance.

AWS-CopySnapshot

Description

Copies a point-in-time snapshot of an Amazon Elastic Block Store (Amazon EBS) volume. You can copy the snapshot within the same AWS Region or from one Region to another. Copies of encrypted Amazon EBS snapshots remain encrypted. Copies of unencrypted snapshots remain unencrypted. To copy an encrypted snapshot that was shared from another account, you must have permissions for the KMS key used to encrypt the snapshot. Snapshots created by copying another snapshot have an arbitrary volume ID that should not be used for any purpose.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

AWS Systems Manager Automation runbook reference User Guide AWS-CreateSnapshot

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

• Description

Type: String

Description: (Optional) A description for the Amazon EBS snapshot.

SnapshotId

Type: String

Description: (Required) The ID of the Amazon EBS snapshot to copy.

SourceRegion

Type: String

Description: (Required) The Region where the source snapshot currently exists.

Document Steps

copySnapshot - Copies a snapshot of an Amazon EBS volume.

Outputs

copySnapshot.SnapshotId - The ID of the new snapshot.

AWS-CreateSnapshot

Description

Create a snapshot of an Amazon EBS volume.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

AWS Systems Manager Automation runbook reference User Guide AWS-DeleteEbsVolumeSnapshots

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Description

Type: String

Description: (Optional) A description for the snapshot

VolumeId

Type: String

Description: (Required) The ID of the volume.

AWS-DeleteEbsVolumeSnapshots

Description

Delete a snapshot of an Amazon Elastic Block Store (Amazon EBS) volume.

Note

The AWS Lambda function that runs during this operation has a maximum run time (timeout) of 60 seconds. If you have a large number of Amazon EBS volume snapshots to delete, the operation might fail with an error message.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

• LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

RetentionCount

Type: String

AWS Systems Manager Automation runbook reference User Guide AWS-DeleteSnapshot

Default: 10

Description: (Optional) Number of snapshots to keep for the volume. Either RetentionCount or RetentionDays should be mentioned, not both.

RetentionDays

Type: String

Description: (Optional) Number of days to keep snapshots for the volume. Either RetentionCount or RetentionDays should be mentioned, not both

VolumeId

Type: String

Description: (Required) The volume identifier to delete snapshots for.

AWS-DeleteSnapshot

Description

Delete a snapshot of an Amazon EBS volume.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

SnapshotId

Type: String

Description: (Required) The ID of the EBS snapshot.

AWSConfigRemediation-DeleteUnusedEBSVolume

Description

AWS Systems Manager Automation runbook reference User Guide

AWSConfigRemediation-DeleteUnusedEBSVolume

The AWSConfigRemediation-DeleteUnusedEBSVolume runbook deletes an unused Amazon Elastic Block Store (Amazon EBS) volume.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

CreateSnapshot

Type: Boolean

Description: (Optional) If set to true, the automation creates a snapshot of the Amazon EBS volume before it is deleted.

VolumeId

Type: String

Description: (Required) The ID of the Amazon EBS volume that you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:CreateSnapshot
- ec2:DeleteVolume
- ec2:DescribeSnapshots
- ec2:DescribeVolumes

Document Steps

- aws:executeScript Verifies the Amazon EBS volume you specify in the VolumeId parameter is not in use, and creates a snapshot depending on the value you choose for the CreateSnapshot parameter.
- aws:branch Branches based on the value you chose for the CreateSnapshot parameter.
- aws:waitForAwsResourceProperty Waits for the snapshot to complete.

AWS Systems Manager Automation runbook reference User Guide AWS-DetachEBSVolume

- aws:executeAwsApi Deletes the snapshot if the snapshot creation failed.
- aws:executeAwsApi Deletes the Amazon EBS volume you specify in the VolumeId parameter.
- aws:executeScript Verifies the Amazon EBS volume has been deleted.

AWS-DetachEBSVolume

Description

Detach an Amazon EBS volume from an Amazon Elastic Compute Cloud (Amazon EC2) instance.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

• LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role assumed by Lambda

VolumeId

Type: String

Description: (Required) The ID of the EBS volume. The volume and instance must be within the same Availability Zone

AWSConfigRemediation-EnableEbsEncryptionByDefault

Description

The AWSConfigRemediation-EnableEbsEncryptionByDefault runbook enables encryption on all new Amazon Elastic Block Store (Amazon EBS) volumes in the AWS account and AWS Region where you run the automation. Volumes that were created before you run the automation are not encrypted.

Run this Automation (console)

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ModifyEBSSnapshotPermission

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ec2:EnableEbsEncryptionByDefault
- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

Document Steps

- aws:executeAwsApi Enables the default Amazon EBS encryption setting in the current account and Region.
- aws:assertAwsResourceProperty Verifies that the default Amazon EBS encryption setting has been enabled.

AWSSupport-ModifyEBSSnapshotPermission

Description

The AWSSupport-ModifyEBSSnapshotPermission runbook helps you to modify permissions for multiple Amazon Elastic Block Store (Amazon EBS) snapshots. Using this runbook, you can make snapshots Public or Private and share them with other AWS accounts. Snapshots encrypted with a default KMS key can't be shared with other accounts using this runbook.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ModifyEBSSnapshotPermission

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Accountlds

Type: StringList

Default: none

Description: (Optional) The IDs of the accounts you want to share snapshots with. This parameter is required if you enter No for the value of the Private parameter.

• AccountPermissionOperation

Type: String

Valid values: add | remove

Default: none

Description: (Optional) The type of operation to perform.

Private

Type: String

Valid values: Yes | No

Description: (Required) Enter No for the value if you want to share snapshots with specific accounts.

SnapshotIds

Type: StringList

Description: (Required) The IDs of Amazon EBS snapshots whose permission you want to modify.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeSnapshots
- ec2:ModifySnapshotAttribute

Document Steps

1. aws:executeScript - Verifies the IDs of the snapshots provided in the SnapshotIds parameter. After verifying the IDs, the script checks for encrypted snapshots and outputs a list if any are found.

AWS Systems Manager Automation runbook reference User Guide

AWSConfigRemediation-ModifyEBSVolumeType

- 2. aws:branch Branches the automation based on the value you enter for the Private parameter.
- aws:executeScript Modifies permissions of the snapshots specified to share it with the accounts specified.
- aws:executeScript Modifies permissions of the snapshots to change them from Public to Private.

Outputs

ValidateSnapshots.EncryptedSnapshots

SharewithOtherAccounts.Result

MakePrivate.Result

MakePrivate.Commands

AWSConfigRemediation-ModifyEBSVolumeType

Description

The AWSConfigRemediation-ModifyEBSVolumeType runbook modifies the volume type of an Amazon Elastic Block Store (Amazon EBS) volume. After the volume type is modified, the volume enters an optimizing state. For information about monitoring the progress of volume modifications, see Monitor the progress of volume modifications in the Amazon EC2 User Guide for Linux Instances.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

EbsVolumeId

Type: String

Description: (Required) The ID of the Amazon EBS volume that you want to modify.

EbsVolumeType

Type: String

AWS Systems Manager Automation runbook reference User Guide Amazon EC2

Valid values: standard | io1 | io2 | gp2 | sc1 | st1

Description: The volume type you want to change the Amazon EBS volume to. For information about Amazon EBS volume types, see Amazon EBS volume types in the Amazon EC2 User Guide for Linux Instances.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeVolumes
- ec2:ModifyVolume

Document Steps

- aws:waitForAwsResourceProperty Verifies the state of the volume is available or in-use.
- aws:executeAwsApi Modifies the Amazon EBS volume you specify in the EbsVolumeId parameter.
- aws:waitForAwsResourceProperty Verifies the type of the volume has been changed to the value you specified in the EbsVolumeType parameter.

Amazon EC2

AWS Systems Manager Automation provides predefined runbooks for Amazon Elastic Compute Cloud. Runbooks for Amazon Elastic Block Store are located in the Amazon EBS (p. 38) section of the runbook reference. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSSupport-ActivateWindowsWithAmazonLicense (p. 51)
- AWS-ASGEnterStandby (p. 53)
- AWS-ASGExitStandby (p. 54)
- AWSSupport-CheckXenToNitroMigrationRequirements (p. 54)
- AWSEC2-CloneInstanceAndUpgradeWindows (p. 56)
- AWSEC2-CloneInstanceAndUpgradeSQLServer (p. 59)
- AWSSupport-ConfigureEC2Metadata (p. 61)
- AWSEC2-ConfigureSTIG (p. 64)
- AWSSupport-CopyEC2Instance (p. 71)
- AWS-CreateImage (p. 75)
- AWS-DeleteImage (p. 76)
- AWSConfigRemediation-EnableAutoScalingGroupELBHealthCheck (p. 77)
- AWSConfigRemediation-EnforceEC2InstanceIMDSv2 (p. 78)
- AWSSupport-ExecuteEC2Rescue (p. 79)
- AWSSupport-ListEC2Resources (p. 80)
- AWSSupport-ManageRDPSettings (p. 82)
- AWSSupport-ManageWindowsService (p. 84)
- AWSSupport-MigrateEC2ClassicToVPC (p. 85)

AWS Systems Manager Automation runbook reference User Guide

AWSSupport-ActivateWindowsWithAmazonLicense

- AWS-PatchAsgInstance (p. 89)
- AWS-PatchInstanceWithRollback (p. 90)
- AWSEC2-PatchLoadBalancerInstance (p. 92)
- AWSSupport-ResetAccess (p. 92)
- AWS-ResizeInstance (p. 94)
- AWS-RestartEC2Instance (p. 95)
- AWSSupport-RestoreEC2InstanceFromSnapshot (p. 96)
- AWSSupport-SendLogBundleToS3Bucket (p. 99)
- AWSEC2-SQLServerDBRestore (p. 100)
- AWS-StartEC2Instance (p. 103)
- AWS-StopEC2Instance (p. 104)
- AWSSupport-StartEC2RescueWorkflow (p. 105)
- AWS-TerminateEC2Instance (p. 111)
- AWSPremiumSupport-TroubleshootEC2DiskUsage (p. 112)
- AWSSupport-TroubleshootRDP (p. 115)
- AWSSupport-TroubleshootSSH (p. 119)
- AWSSupport-TroubleshootSUSERegistration (p. 121)
- AWS-UpdateLinuxAmi (p. 122)
- AWS-UpdateWindowsAmi (p. 124)
- AWSSupport-UpgradeWindowsAWSDrivers (p. 126)

AWSSupport-ActivateWindowsWithAmazonLicense

Description

The AWSSupport-ActivateWindowsWithAmazonLicense runbook activates an Amazon Elastic Compute Cloud (Amazon EC2) instance for Windows Server with a license provided by Amazon. The automation verifies and configures required key management service operating system settings and attempts activation. This includes operating system routes to Amazon's key management servers and key management service operating system settings. Setting the AllowOffline parameter to true allows the automation to successfully target instances that are not managed by AWS Systems Manager, but requires a stop and start of the instance.

Note

This runbook cannot be used on Bring Your Own License (BYOL) model Windows Server instances. For information about using your own license, see Microsoft Licensing on AWS.

Run this Automation (console)

Document '	type
------------	------

Automation

Owner

Amazon

Platforms

Windows

AWS Systems Manager Automation runbook reference User Guide

AWSSupport-ActivateWindowsWithAmazonLicense

Parameters

AllowOffline

Type: String

Valid values: true | false

Default: false

Description: (Optional) Set it to true if you allow an offline Windows activation remediation in case the online troubleshooting fails, or if the provided instance is not a managed instance.

Important

The offline method requires that the provided EC2 instance be stopped and then started. Data stored in instance store volumes will be lost. The public IP address will change if you are not using an Elastic IP.

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ForceActivation

Type: String

Valid values: true | false

Default: false

Description: (Optional) Set it to true if you want to proceed even if Windows is already activated.

Instanceld

Type: String

Description: (Required) ID of your managed EC2 instance for Windows Server.

SubnetId

Type: String

Default: CreateNewVPC

Description: (Optional) Offline only - The subnet ID for the EC2Rescue instance used to perform the offline troubleshooting. Use SelectedInstanceSubnet to use the same subnet as your instance, or use CreateNewVPC to create a new VPC. IMPORTANT: The subnet must be in the same Availability Zone as InstanceId, and it must allow access to the SSM endpoints.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

We recommend that the EC2 instance receiving the command has an IAM role with the AmazonSSMManagedInstanceCore Amazon managed policy attached. You must have at least ssm:StartAutomationExecution and ssm:SendCommand to run the automation and send the command to the instance, plus ssm:GetAutomationExecution to be able to read the automation output. For the offline remediation, see the permissions needed by AWSSupport-StartEC2RescueWorkflow.

AWS Systems Manager Automation runbook reference User Guide AWS-ASGEnterStandby

Document Steps

- 1. aws:assertAwsResourceProperty Check the provided instance's platform is Windows.
- 2. aws:assertAwsResourceProperty Confirm the provided instance is a managed instance:
 - a. (Online activation fix) If the input instance is a managed instance, then run aws:runCommand to run the PowerShell script to attempt to fix Windows activation.
 - b. (Offline activation fix) If the input instance is not a managed instance:
 - i. aws:assertAwsResourceProperty Verifies the AllowOffline flag is set to true. If so, the offline fix starts; otherwise the automation ends.
 - ii. aws:executeAutomation Invoke AWSSupport-StartEC2RescueWorkflow with the Windows activation offline fix script. The script uses either EC2Config or EC2Launch, depending on the OS version.
 - iii.aws:executeAwsApi Read the result from AWSSupport-StartEC2RescueWorkflow.

Outputs

activateWindows.Output

getActivateWindowsOfflineResult.Output

AWS-ASGEnterStandby

Description

Change the standby state of an Amazon Elastic Compute Cloud (Amazon EC2) instance in an Auto Scaling group.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) ID of an Amazon EC2 instance for which you want to change the standby state within an Auto Scaling group.

AWS Systems Manager Automation runbook reference User Guide AWS-ASGExitStandby

LambdaRoleArn

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

AWS-ASGExitStandby

Description

Change the standby state of an Amazon Elastic Compute Cloud (Amazon EC2) instance in an Auto Scaling group.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

InstanceId

Type: String

Description: (Required) ID of an EC2 instance for which you want to change the standby state within an Auto Scaling group.

LambdaRoleArn

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

AWSSupport-CheckXenToNitroMigrationRequirements

Description

AWS Systems Manager Automation runbook reference User Guide AWSSupport-

CheckXenToNitroMigrationRequirements

The AWSSupport-CheckXenToNitroMigrationRequirements runbook verifies that an Amazon Elastic Compute Cloud (Amazon EC2) instance meets the prerequistes to successfully change the instance type from a Xen type instance to Nitro-based instance type. This automation checks the following:

- The root device is an Amazon Elastic Block Store (Amazon EBS) volume.
- The enaSupport attribute is enabled.
- The ENA module is installed on the instance.
- The NVMe module is installed on the instance. If yes, the module is installed and a script verifies that the module is loaded in the initramfs image.
- Analyzes /etc/fstab and looks for block devices being mounted using device names.
- Determines whether the operating system (OS) uses predictable network interface names by default.

This runbook supports the following operating systems:

- · Red Hat Enterprise Linux
- CentOS
- Amazon Linux 2
- Amazon Linux
- Debian Server
- Ubuntu Server
- SUSE Linux Enterprise Server 15 SP2
- SUSE Linux Enterprise Server 12 SP5

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Default: false

Description: (Required) The ID of the Amazon EC2 instance which you want to check prerequisites for before migrating to a Nitro-based instance type.

AWS Systems Manager Automation runbook reference User Guide AWSEC2-CloneInstanceAndUpgradeWindows

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:DescribeAutomationExecutions
- ssm:DescribeAutomationStepExecutions
- ssm:DescribeAutomationStepExecutions
- ssm:DescribeInstanceInformation
- ssm:DescribeInstanceProperties
- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:GetDocument
- ssm:ListCommands
- ssm:ListCommandInvocations
- ssm:ListDocuments
- ssm:StartAutomationExecution
- ssm:SendCommand
- iam:ListRoles
- ec2:DescribeInstances
- ec2:DescribeInstancesTypes

Document Steps

- aws:executeAwsApi Gathers details about the instance.
- aws:executeAwsApi Gathers information about the hypervisor for the instance.
- aws:branch Branches based on whether the target instance is already running a Nitro-based instance type.
- aws:branch Checks whether the instance's OS is supported by Nitro-based instances.
- aws:assertAwsResourceProperty Verifies the instance you specified is managed by Systems Manager, and that the status is Online.
- aws:branch Branches based on whether the root device of the instance is an Amazon EBS volume.
- aws:branch Branches based on whether the ENA attribute is enabled for the instance.
- aws:runCommand Checks for ENA drivers on the instance.
- aws:runCommand Checks for NVMe drivers on the instance.
- aws:runCommand Checks the fstab file for unrecognized formats.
- aws:runCommand Checks for predictable interface name configuration on the instance.
- aws:executeScript Generates output based on previous steps.

Outputs

finalOutput.output - The results of the checks performed by the automation.

AWSEC2-CloneInstanceAndUpgradeWindows

Description

Create an Amazon Machine Image (AMI) from a Windows Server 2008 R2, 2012 R2, or 2016 instance, and then upgrade the AMI to Windows Server 2012 R2, 2016, or 2019. The supported upgrade paths are as follows.

AWS Systems Manager Automation runbook reference User Guide AWSEC2-CloneInstanceAndUpgradeWindows

- Windows Server 2008 R2 to Windows Server 2012 R2.
- Windows Server 2012 R2 to Windows Server 2016.
- Windows Server 2012 R2 to Windows Server 2019.
- Windows Server 2016 to Windows Server 2019.

To upgrade your instance from Windows Server 2008 R2 to Windows Server 2016 or 2019, the runbook performs two steps. The Windows Server 2008 R2 instance is upgraded to Windows Server 2012 R2. Then the Windows Server 2012 R2 instance is upgraded to the target version (Windows Server 2016 or 2019).

The upgrade operation is a multi-step process that can take 2 hours to complete. We recommend performing an operating system upgrade on instances with at least 2 vCPUs and 4GB of RAM. The automation creates an AMI from the instance and then launches a temporary instance from the newly created AMI in the SubnetId that you specify. The security groups associated with your original instance are applied to the temporary instance. The automation then performs an in-place upgrade to the TargetWindowsVersion on the temporary instance. To upgrade your Windows Server 2008 R2 instance to Windows Server 2016 or 2019, an in-place upgrade is performed twice because directly upgrading Windows Server 2008 R2 to Windows Server 2016 or 2019 is not supported. The automation also updates or installs the AWS drivers required by the temporary instance. After the upgrade, the automation creates a new AMI from the temporary instance and then terminates the temporary instance.

You can test application functionality by launching a test instance from the upgraded AMI in your Amazon Virtual Private Cloud (Amazon VPC). After you finish testing, and before you perform another upgrade, schedule application downtime before completely switching over to the upgraded AMI.

Run this Automation (console)

Document Type

Automation

Owner

Amazon

Platforms

Windows Server 2008 R2, 2012 R2 and 2016 Standard and Datacenter editions

Prerequisites

- Verify that SSM Agent is installed on your instance. For more information, see Installing and configuring SSM Agent on EC2 instances for Windows Server.
- Windows PowerShell 3.0 or later must be installed on your instance.
- For instances that are joined to a Microsoft Active Directory domain, we recommend specifying
 a SubnetId that does not have connectivity to your domain controllers to help avoid hostname
 conflicts
- The SubnetId specified must be a public subnet with the auto-assign public IPv4 address set to true. For more information, see Modifying the Public IPv4 Addressing Attribute for Your Subnet in the Amazon VPC User Guide.
- This Automation works only with Windows Server 2008 R2, 2012 R2, and 2016 instances.
- Configure the Windows Server instance with an AWS Identity and Access Management (IAM) instance profile that provides the requisite permissions for Systems Manager. For more information, see Create an IAM instance profile for Systems Manager.
- Verify that the instance has 20 GB of free disk space in the boot disk.

AWS Systems Manager Automation runbook reference User Guide

AWSEC2-CloneInstanceAndUpgradeWindows

- If the instance does not use an AWS-provided Windows license, then specify an Amazon EBS snapshot ID that includes Windows Server 2012 R2 installation media. To do this:
 - Verify that the EC2 instance is running Windows Server 2012 or later.
 - Create a 6 GB EBS volume in the same Availability Zone where the instance is running. Attach the volume to the instance. Mount it, for example, as drive D.
 - Right-click the ISO and mount it to an instance as, for example, drive E.
 - Copy the content of the ISO from drive E:\ to drive D:\
 - Create an EBS snapshot of the 6 GB volume created in step 2 above.

Limitations

This Automation doesn't support upgrading Windows domain controllers, clusters, or Windows desktop operating systems. This Automation also doesn't support EC2 instances for Windows Server with the following roles installed.

- · Remote Desktop Session Host (RDSH)
- Remote Desktop Connection Broker (RDCB)
- Remote Desktop Virtualization Host (RDVH)
- Remote Desktop Web Access (RDWA)

Parameters

· AlternativeKeyPairName

Type: String

Description: (Optional) The name of an alternative key pair to use during the upgrade process. This is useful in situations where the key pair assigned to the original instance is unavailable. If the original instance was not assigned a key pair, you must specify a value for this parameter.

BYOLWindowsMediaSnapshotId

Type: String

Description: (Optional) The ID of the Amazon EBS snapshot to copy that includes Windows Server 2012R2 installation media. Required only if you are upgrading a BYOL instance.

IamInstanceProfile

Type: String

Description: (Required) The name of the IAM instance profile that enables Systems Manager to manage the instance.

InstanceId

Type: String

Description: (Required) The EC2 instance running Windows Server 2008 R2 or 2012 R2.

KeepPreUpgradeImageBackUp

Type: String

Description: (Optional) If set True, the Automation doesn't delete the AMI created from the EC2 instance before the upgrade. If set to True, then you must delete the AMI. By default, the AMI is deleted.

SubnetId

AWS Systems Manager Automation runbook reference User Guide AWSEC2-CloneInstanceAndUpgradeSQLServer

Type: String

Description: (Required) This is the subnet for the upgrade process and where your source EC2 instance resides. Verify that the subnet has outbound connectivity to AWS services, Amazon S3, and Microsoft (to download patches).

TargetWindowsVersion

Type: String

Description: (Required) Select the target Windows version.

Default: 2012R2

RebootInstanceBeforeTakingImage

Type: String

Description: (Optional) If set True, the Automation reboots the instance before creating a pre-upgrade AMI. By default, the Automation doesn't reboot before upgrade.

AWSEC2-CloneInstanceAndUpgradeSQLServer

Description

Create an AMI from an EC2 instance for Windows Server running SQL Server 2008 or later, and then upgrade the AMI to a later version of SQL Server.

The following upgrade paths are supported:

- SQL Server 2008 to SQL Server 2017, 2016, or 2014
- SQL Server 2008 R2 to SQL Server 2017, 2016, or 2014
- SQL Server 2012 to SQL Server 2019, 2017, 2016, or 2014
- SQL Server 2014 to SQL Server 2019, 2017, or 2016
- SQL Server 2016 to SQL Server 2019 or 2017
- SQL Server 2017 to SQL Server 2019

If you are using an earlier version of Windows Server that is incompatible with SQL Server 2019, the automation document must upgrade your Windows Server version to 2016.

The upgrade is a multi-step process that can take 2 hours to complete. The automation creates the AMI from the instance, and then launches a temporary instance from the new AMI in the specified SubnetID. The security groups associated with your original instance are applied to the temporary instance. The automation then performs an in-place upgrade to the TargetSQLVersion on the temporary instance. After the upgrade, the automation creates a new AMI from the temporary instance and then terminates the temporary instance.

You can test application functionality by launching the new AMI in your VPC. After you finish testing, and before you perform another upgrade, schedule application downtime before completely switching over to the upgraded instance.

Note

If you want to modify the computer name of the EC2 instance launched from the new AMI, see Rename a Computer that Hosts a Stand-Alone Instance of SQL Server.

Run this Automation (console)

Document type

AWS Systems Manager Automation

	runbook reference User Guide
	AWSEC2-CloneInstanceAndUpgradeSQLServe
Automation	

Owner

Amazon

Platforms

Windows

Parameters

Prerequisites

- The EC2 instance must use a version of Windows Server that is Windows Server 2008 R2 (or later) and SQL Server 2008 (or later).
- · Verify that SSM Agent is installed on your instance. For more information, see Installing and configuring SSM Agent on EC2 instances for Windows Server.
- Configure the instance to use an AWS Identity and Access Management (IAM) instance profile role. For more information, see Create an IAM instance profile for Systems Manager.
- Verify that the instance has 20 GB of free disk space in the instance boot disk.
- For instances that use a Bring Your Own License (BYOL) SQL Server version, the following additional prerequisites apply:
 - Provide an EBS snapshot ID that includes the target SQL Server installation media. To do this:
 - 1. Verify that the EC2 instance is running Windows Server 2008 R2 or later.
 - 2. Create a 6 GB EBS volume in the same Availability Zone where the instance is running. Attach the volume to the instance. Mount it, for example, as drive D.
 - 3. Right-click the ISO and mount it to an instance as, for example, drive E.
 - 4. Copy the content of the ISO from drive E:\ to drive D:\
 - 5. Create an EBS snapshot of the 6 GB volume created in step 2.

Limitations

- The upgrade can be performed on only a SQL Server using Windows authentication.
- Verify that no security patch updates are pending on the instances. Open Control Panel, then choose Check for updates.
- SQL Server deployments in HA and mirroring mode are not supported.

Parameters

IamInstanceProfile

Type: String

Description: (Required) The IAM instance profile.

Instanceld

Type: String

Description: (Required) The instance running Windows Server 2008 R2 (or later) and SQL Server 2008 (or later).

KeepPreUpgradeImageBackUp

Type: String

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ConfigureEC2Metadata

Description: (Optional) If set to true, the automation doesn't delete the AMI created from the instance before the upgrade. If set to true, then you must delete the AMI. By default, the AMI is deleted.

SubnetId

Type: String

Description: (Required) Provide a subnet for the upgrade process. Verify that the subnet has outbound connectivity to AWS services, Amazon S3, and Microsoft (to download patches).

SQLServerSnapshotId

Type: String

Description: (Conditional) Snapshot ID for target SQL Server installation media. This parameter is required for instances that use a BYOL SQL Server version. This parameter is optional for SQL Server license-included instances (instances launched using an AWS provided Amazon Machine Image for Windows Server with Microsoft SQL Server).

RebootInstanceBeforeTakingImage

Type: String

Description: (Optional) If set to true, the automation reboots the instance before creating a preupgrade AMI. By default, the automation doesn't reboot before upgrade.

TargetSQLVersion

Type: String

Description: (Optional) Select the target SQL Server version.

Possible targets:

- SQL Server 2019
- SQL Server 2017
- SQL Server 2016
- SQL Server 2014

Default target: SQL Server 2016

Outputs

AMIId: The ID of the AMI created from the instance that was upgraded to a later version of SQL Server.

AWSSupport-ConfigureEC2Metadata

Description

This runbook helps you configure instance metadata service (IMDS) options for Amazon Elastic Compute Cloud (Amazon EC2) instances. Using this runbook, you can configure the following:

- Enforce the use of IMDSv2 for instance metadata.
- Configure the HttpPutResponseHopLimit value.
- Allow or deny instance metadata access.

For more information about instance metadata, see Configuring the Instance Metadata Service in the Amazon EC2 User Guide for Linux Instances.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ConfigureEC2Metadata

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

EnforceIMDSv2

Type: String

Valid values: required | optional

Default: optional

Description: (Optional) Enforce IMDSv2. If you choose required, the Amazon EC2 instance will only use IMDSv2. If you choose optional, you can choose between IMDSv1 and IMDSv2 for metadata access.

Important

If you enforce IMDSv2, applications that use IMDSv1 might not function correctly. Before enforcing IMDSv2, make sure your applications that use IMDS are upgraded to a version that support IMDSv2. For information about Instance Metadata Service Version 2 (IMDSv2), see Configuring the Instance Metadata Service in the Amazon EC2 User Guide for Linux Instances.

HttpPutResponseHopLimit

Type: Integer

Valid values: 0-64

Default: 0

Description: (Optional) The desired HTTP PUT response hop limit value (1-64) for instance metadata requests. This value controls the number of hops that the PUT response can traverse. To prevent the response from traveling outside of the instance, specify 1 for the parameter value.

Instanceld

Type: String

Description: (Required) The ID of the Amazon EC2 instance whose metadata settings you want to configure.

MetadataAccess

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ConfigureEC2Metadata

Type: String

Valid values: enabled | disabled

Default: enabled

Description: (Optional) Allow or deny instance metadata access in the Amazon EC2 instance. If you specify disabled, all other parameters will be ignored and the metadata access will be denied for the instance.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ec2:DescribeInstances
- ec2:ModifyInstanceMetadataOptions
- ssm:GetAutomationExecution
- ssm:StartAutomationExecution

Document Steps

- 1. branchOnMetadataAccess Branches automation based on the value of MetadataAccess parameter.
- disableMetadataAccess Calls the ModifyInstanceMetadataOptions API action to disable metadata endpoint access.
- branchOnHttpPutResponseHopLimit Branches automation based on the value of HttpPutResponseHopLimit parameter.
- 4. maintainHopLimitAndConfigureImdsVersion If HttpPutResponseHopLimit is 0, maintains current hop limit and changes other metadata options.
- 5. waitBeforeAssertingIMDSv2State Waits 30 seconds before asserting IMDSv2 status.
- 6. setHopLimitAndConfigureImdsVersion If HttpPutResponseHopLimit is greater than 0, configures the metadata options using the given input parameters.
- 7. waitBeforeAssertingHopLimit Waits 30 seconds before asserting metadata options.
- 8. assertHopLimit Asserts the HttpPutResponseHopLimit property is set to the value you specified.
- 9. branchVerificationOnIMDSv2Option Branches verification based on the value of EnforceIMDSv2 parameter.

10assertIMDSv2IsOptional - Asserts HttpTokens value set to optional.

11assertIMDSv2IsEnforced - Asserts HttpTokens value set to required.

12waitBeforeAssertingMetadataState - Waits 30 seconds before asserting the metadata state is disabled.

13assertMetadataIsDisabled - Asserts metadata is disabled.

14describeMetadataOptions - Gets the metadata options after the changes you've specified have been applied.

Outputs

describeMetadataOptions.State

describeMetadataOptions.MetadataAccess

describeMetadataOptions.IMDSv2

describeMetadataOptions.HttpPutResponseHopLimit

AWSEC2-ConfigureSTIG

Security Technical Implementation Guides (STIGs) are the configuration standards created by the Defense Information Systems Agency (DISA) to secure information systems and software. To make your systems compliant with STIG standards, you must install, configure, and test a variety of security settings.

Amazon EC2 provides a Systems Manager document, AWSEC2-ConfigureSTIG, which you can use to apply STIG to an instance. This document helps you to quickly build compliant images for STIG standards. The STIG Systems Manager document scans for misconfigurations and runs a remediation script. The STIG Systems Manager document installs InstallRoot on Windows AMIs from the Department of Defense (DoD) to install and update the DoD certificates and to remove unnecessary certificates to maintain STIG compliance. There are no additional charges for using the STIG Systems Manager document.

You can choose which STIG compliance category to apply.

Compliance levels

· High (Category I)

The most severe risk. Includes any vulnerability that can result in loss of confidentiality, availability, or integrity.

Medium (Category II)

Includes any vulnerability that can result in loss of confidentiality, availability, or integrity but the risk can be mitigated.

Low (Category III)

Includes any vulnerability that degrades measures to protect against loss of confidentiality, availability, or integrity.

Topics

- Windows STIG settings (p. 64)
- Linux STIG settings (p. 68)
- Version history (p. 71)

Windows STIG settings

Amazon EC2 Windows STIG AMIs and components are designed for standalone servers and they apply Local Group Policy. STIG-compliant components install InstallRoot on Windows AMIs from the Department of Defense (DoD) to install and update the DoD certificates. They also remove unnecessary certificates to maintain STIG compliance. Currently, STIG baselines are supported for the following versions of Windows Server: 2012 R2, 2016, and 2019.

You can apply low, medium, or high STIG settings.

Windows STIG Low (Category III)

The following list contains STIG settings that are applied to your image. Some STIG settings are not automatically applied. This can be due to technical limitations – for instance, the STIG setting might not be applicable for standalone servers. Organization-specific policies can also prevent automatic application of STIG settings, such as a requirement for administrators to review document settings. For more details about which STIGs are applied to Windows AMIs, you can download our spreadsheet.

AWS Systems Manager Automation runbook reference User Guide AWSEC2-ConfigureSTIG

For a complete list of Windows STIGs, see the STIGs Document Library. For information about how to view the complete list, see How to View SRGs and STIGs.

Windows Server 2019 STIG Version 2 Release 3

V-205691, V-205819, V-205858, V-205859, V-205860, V-205870, V-205871, and V-205923

• Windows Server 2016 STIG Version 2 Release 3

V-224916, V-224917, V-224918, V-224919, V-224931, V-224942, and V-225060

Windows Server 2012 R2 STIG Version 3 Release 3

```
V-225537, V-225536, V-225526, V-225525, V-225514, V-225511, V-225490, V-225489, V-225488, V-225487, V-225485, V-225484, V-225483, V-225482, V-225481, V-225480, V-225479, V-225476, V-225473, V-225468, V-225462, V-225460, V-225459, V-225412, V-225394, V-225392, V-225376, V-225363, V-225362, V-225360, V-225359, V-225358, V-225357, V-225355, V-225343, V-225342, V-225336, V-225335, V-225334, V-225333, V-225331, V-225330, V-225328, V-225327, V-225324, V-225318, and V-225250
```

• Microsoft .NET Framework 4.0 STIG Version 2 Release 1

No STIG settings are applied to the Microsoft .NET Framework for Category III vulnerabilities.

• Windows Firewall STIG Version 2 Release 1

V-241994, V-241995, V-241996, V-241999, V-242000, V-242001, V-242006, V-242007, and V-242008

Internet Explorer 11 STIG Version 1 Release 19

V-46477, V-46629, and V-97527

Windows STIG Medium (Category II)

The following list contains STIG settings that are applied to your image. Some STIG settings are not automatically applied. This can be due to technical limitations – for instance, the STIG setting might not be applicable for standalone servers. Organization-specific policies can also prevent automatic application of STIG settings, such as a requirement for administrators to review document settings. For more details about which STIGs are applied to Windows AMIs, you can download our spreadsheet.

For a complete list of Windows STIGs, see the STIGs Document Library. For information about how to view the complete list, see How to View SRGs and STIGs.

Note

The Windows STIG Medium category includes all of the STIG settings that apply to Windows STIG low (Category III), in addition to the STIG settings that are applied specifically for Category II vulnerabilities.

Windows Server 2019 STIG Version 2 Release 3

Includes all STIG settings that are applied for Category III (Low) vulnerabilities, plus:

```
V-205625, V-205626, V-205627, V-205629, V-205630, V-205633, V-205634, V-205635, V-205636, V-205637, V-205638, V-205639, V-205643, V-205644, V-205648, V-205649, V-205650, V-205651, V-205652, V-205655, V-205656, V-205659, V-205660, V-205662, V-205671, V-205672, V-205673, V-205675, V-205676, V-205678, V-205679, V-205680, V-205681, V-205682, V-205683, V-205684, V-205685, V-205686, V-205687, V-205688, V-205689, V-205690, V-205692, V-205693, V-205694, V-205697, V-205698, V-205708, V-205712, V-205714, V-205716, V-205717, V-205718, V-205719, V-205720, V-205722, V-205729, V-205730, V-205733, V-205747, V-205751, V-205752, V-205754, V-205756, V-205756, V-205758, V-205769, V-205760, V-205761, V-205762, V-205764, V-205767, V-205767, V-205776, V-205776, V-205776, V-205776, V-205776, V-205777, V-205778, V-205779, V-205780, V-205781, V-205782, V-205783, V-205776, V-205776, V-205776, V-205778, V-205779, V-205780, V-205781, V-205782, V-205783, V-205776, V-205776, V-205776, V-205778, V-205779, V-205780, V-205781, V-205782, V-205783, V-205776, V-205776, V-205776, V-205778, V-205779, V-205780, V-205781, V-205782, V-205783, V-205776, V-205776, V-205776, V-205778, V-205779, V-205780, V-205781, V-205782, V-205783, V-205776, V-205776, V-205776, V-205778, V-205779, V-2057780, V-205781, V-205782, V-205783, V-205776, V-205776, V-205776, V-205778, V-205779, V-205780, V-205781, V-205782, V-205783, V-205776, V-205776, V-205776, V-205778, V-205779, V-205780, V-205781, V-205782, V-205782, V-205781, V-205782, V-205
```

```
V-205784, V-205795, V-205796, V-205797, V-205798, V-205801, V-205808, V-205809, V-205810, V-205811, V-205812, V-205813, V-205814, V-205815, V-205816, V-205817, V-205821, V-205822, V-205823, V-205824, V-205825, V-205826, V-205827, V-205828, V-205830, V-205832, V-205834, V-205835, V-205836, V-205837, V-205838, V-205839, V-205840, V-205841, V-205861, V-205863, V-205865, V-205866, V-205867, V-205868, V-205869, V-205872, V-205873, V-205874, V-205911, V-205912, V-205915, V-205916, V-205917, V-205918, V-205920, V-205921, V-205922, V-205924, V-205925, and V-236001
```

Windows Server 2016 STIG Version 2 Release 3

Includes all STIG settings that are applied for Category III (Low) vulnerabilities, plus:

```
V-224850, V-224852, V-224853, V-224854, V-224855, V-224856, V-224857, V-224858, V-224859,
V-224866, V-224867, V-224868, V-224869, V-224870, V-224871, V-224872, V-224873, V-224881,
V-224882, V-224883, V-224884, V-224885, V-224886, V-224887, V-224888, V-224889, V-224890,
V-224891, V-224892, V-224893, V-224894, V-224895, V-224896, V-224897, V-224898, V-224899,
V-224900, V-224901, V-224902, V-224903, V-224904, V-224905, V-224906, V-224907, V-224908,
V-224909, V-224910, V-224911, V-224912, V-224913, V-224914, V-224915, V-224920, V-224922,
V-224924, V-224925, V-224926, V-224927, V-224928, V-224929, V-224930, V-224935, V-224936,
V-224937, V-224938, V-224939, V-224940, V-224941, V-224943, V-224944, V-224945, V-224946,
V-224947, V-224948, V-224949, V-224951, V-224952, V-224953, V-224955, V-224956, V-224957,
V-224959, V-224960, V-224962, V-224963, V-225010, V-225013, V-225014, V-225015, V-225016,
V-225017, V-225018, V-225019, V-225021, V-225022, V-225023, V-225024, V-225028, V-225029,
V-225030, V-225031, V-225032, V-225033, V-225034, V-225035, V-225038, V-225039, V-225040,
V-225041, V-225042, V-225043, V-225047, V-225049, V-225050, V-225051, V-225052, V-225055,
V-225056, V-225057, V-225058, V-225061, V-225062, V-225063, V-225064, V-225065, V-225066,
V-225067, V-225068, V-225069, V-225072, V-225073, V-225074, V-225076, V-225078, V-225080,
V-225081, V-225082, V-225083, V-225084, V-225086, V-225087, V-225088, V-225089, V-225092,
V-225093 and V-236000
```

Windows Server 2012 R2 STIG Version 3 Release 3

Includes all STIG settings that are applied for Category III (Low) vulnerabilities, plus:

```
V-225574, V-225573, V-225572, V-225571, V-225570, V-225569, V-225568, V-225567, V-225566,
V-225565, V-225564, V-225563, V-225562, V-225561, V-225560, V-225559, V-225558, V-225557,
V-225555, V-225554, V-225553, V-225551, V-225550, V-225549, V-225548, V-225546, V-225545,
V-225544, V-225543, V-225542, V-225541, V-225540, V-225539, V-225538, V-225535, V-225534,
V-225533, V-225532, V-225531, V-225530, V-225529, V-225528, V-225527, V-225524, V-225523,
V-225522, V-225521, V-225520, V-225519, V-225518, V-225517, V-225516, V-225515, V-225513,
V-225510, V-225509, V-225508, V-225506, V-225504, V-225503, V-225502, V-225501, V-225500,
V-225494, V-225486, V-225478, V-225477, V-225475, V-225474, V-225472, V-225471, V-225470,
V-225469, V-225464, V-225463, V-225461, V-225458, V-225457, V-225456, V-225455, V-225454,
V-225453, V-225452, V-225448, V-225443, V-225442, V-225441, V-225415, V-225414, V-225413,
V-225411, V-225410, V-225409, V-225408, V-225407, V-225406, V-225405, V-225404, V-225402,
V-225401, V-225400, V-225398, V-225397, V-225395, V-225393, V-225391, V-225389, V-225386,
V-225385, V-225384, V-225383, V-225382, V-225381, V-225380, V-225379, V-225378, V-225377,
V-225375, V-225374, V-225373, V-225372, V-225371, V-225370, V-225369, V-225368, V-225367,
V-225356, V-225353, V-225352, V-225351, V-225350, V-225349, V-225348, V-225347, V-225346,
V-225345, V-225344, V-225341, V-225340, V-225339, V-225338, V-225337, V-225329, V-225326,
V-225325, V-225317, V-225316, V-225315, V-225314, V-225305, V-225304, V-225303, V-225302,
V-225301, V-225300, V-225299, V-225298, V-225297, V-225296, V-225295, V-225294, V-225293,
V-225292, V-225291, V-225290, V-225289, V-225288, V-225287, V-225286, V-225285, V-225284,
V-225283, V-225282, V-225281, V-225280, V-225279, V-225278, V-225277, V-225276, V-225275,
V-225273, V-225272, V-225271, V-225270, V-225269, V-225268, V-225267, V-225266, V-225265,
V-225264, V-225263, V-225261, V-225260, V-225259, and V-225239
```

Microsoft .NET Framework STIG 4.0 Version 2 Release 1

Includes all STIG settings that are applied for Category III (Low) vulnerabilities, plus:

V-225238

Windows Firewall STIG Version 2 Release 1

Includes all STIG settings that are applied for Category III (Low) vulnerabilities, plus:

V-241989, V-241990, V-241991, V-241993, V-241998, and V-242003

Internet Explorer 11 STIG Version 1 Release 19

Includes all STIG settings that are applied for Category III (Low) vulnerabilities, plus:

```
V-46473, V-46475, V-46481, V-46483, V-46501, V-46507, V-46509, V-46511, V-46513, V-46515, V-46517, V-46521, V-46523, V-46525, V-46543, V-46545, V-46547, V-46549, V-46553, V-46555, V-46573, V-46575, V-46577, V-46579, V-46581, V-46583, V-46587, V-46589, V-46591, V-46593, V-46597, V-46599, V-46601, V-46603, V-46605, V-46607, V-46609, V-46615, V-46617, V-46619, V-46621, V-46625, V-46633, V-46635, V-46637, V-46639, V-46641, V-46643, V-46645, V-46647, V-46649, V-46653, V-46663, V-46665, V-46669, V-46681, V-46685, V-46689, V-46691, V-46693, V-46695, V-46701, V-46705, V-46709, V-46711, V-46713, V-46715, V-46717, V-46719, V-46721, V-46723, V-46725, V-46727, V-46729, V-46731, V-46733, V-46779, V-46781, V-46787, V-46789, V-46847, V-46849, V-46853, V-46853, V-46801, V-46861, V-46865, V-46869, V-46829, V-46841, V-46847, V-46849, V-46853, V-46857, V-46859, V-46861, V-46865, V-46869, V-46927, V-46939, V-46885, V-46889, V-46987, V-46997, V-46903, V-46907, V-46921, V-46927, V-46939, V-46713, V-46715, V-46715, V-64711, V-64713, V-64715, V-64715, V-64719, V-64721, V-64723, V-64725, V-64729, V-72757, V-72759, V-72761, V-72763, V-75169, and V-75171
```

Windows STIG High (Category I)

The following list contains STIG settings that are applied to your image. Some STIG settings are not automatically applied. This can be due to technical limitations – for instance, the STIG setting might not be applicable for standalone servers. Organization-specific policies can also prevent automatic application of STIG settings, such as a requirement for administrators to review document settings. For more details about which STIGs are applied to Windows AMIs, you can download our spreadsheet.

For a complete list of Windows STIGs, see the STIGs Document Library. For information about how to view the complete list, see How to View SRGs and STIGs.

Note

The Windows STIG High category includes all of the STIG settings that apply for Windows STIG Medium and Low categories, in addition to the STIG settings that apply specifically to Category I vulnerabilities.

Windows Server 2019 STIG Version 2 Release 3

Includes all STIG settings that are applied for Categories II and III (Medium and Low) vulnerabilities, plus:

V-205653, V-205654, V-205711, V-205713, V-205724, V-205725, V-205757, V-205802, V-205804, V-205805, V-205806, V-205849, V-205908, V-205913, V-205914, and V-205919

Windows Server 2016 STIG Version 2 Release 3

Includes all STIG settings that are applied for Categories II and III (Medium and Low) vulnerabilities, plus:

V-224874, V-224932, V-224933, V-224934, V-224954, V-224958, V-224961, V-225025, V-225044, V-225045, V-225046, V-225048, V-225053, V-225054, and V-225079

• Windows Server 2012 R2 STIG Version 3 Release 3

Includes all STIG settings that are applied for Categories II and III (Medium and Low) vulnerabilities, plus:

V-225556, V-225552, V-225547, V-225507, V-225505, V-225498, V-225497, V-225496, V-225493, V-225492, V-225491, V-225449, V-225444, V-225399, V-225396, V-225390, V-225366, V-225365, V-225364, V-225354, and V-225274

Microsoft .NET Framework STIG 4.0 Version 2 Release 1

Includes all STIG settings that are applied for Categories II and III (Medium and Low) vulnerabilities for the Microsoft .NET Framework. No additional STIG settings are applied for Category I vulnerabilities.

Windows Firewall STIG Version 2 Release 1

Includes all STIG settings that are applied for Categories II and III (Medium and Low) vulnerabilities, plus:

V-241992, V-241997, and V-242002

• Internet Explorer 11 STIG Version 1 Release 19

Includes all STIG settings that are applied for Categories II and III (Medium and Low) vulnerabilities for Internet Explorer 11. No additional STIG settings are applied for Category I vulnerabilities.

Linux STIG settings

This section contains information about Linux STIG settings. If the Linux distribution does not have STIG settings of its own, RHEL settings are applied. STIG settings are applied to Amazon EC2 Linux AMIs and components based on the Linux distribution, as follows:

- Red Hat Enterprise Linux (RHEL) 7 STIG settings
 - RHEL 7
 - CentOS 7
 - Amazon Linux 2 (AL2)
- RHEL 8 STIG settings
 - RHEL 8
 - CentOS 8

Linux STIG Low (Category III)

The following list contains STIG settings that are applied to your image. Some STIG settings are not automatically applied. This can be due to technical limitations – for instance, the STIG setting might not be applicable for standalone servers. Organization-specific policies can also prevent automatic application of STIG settings, such as a requirement for administrators to review document settings. For more details about which STIGs are applied to Linux AMIs, you can download our spreadsheet.

For a complete list, see the STIGs Document Library. For information about how to view the complete list, see SRG / STIG Tools.

RHEL 7 STIG Version 3 Release 6

RHEL 7/CentOS 7

V-204452, V-204576, and V-204605

AL2

V-204452, V-204576, and V-204605

RHEL 8 STIG Version 1 Release 5

RHEL 8/CentOS 8

```
V-230241, V-230253, V-230269, V-230270, V-230281, V-230285, V-230346, V-230381, V-230395, V-230468, V-230469, V-230485, V-230496, V-230491, V-230494, V-230495, V-230496, V-230497, V-230498, V-230499, and V-244527
```

Linux STIG Medium (Category II)

The following list contains STIG settings that are applied to your image. Some STIG settings are not automatically applied. This can be due to technical limitations – for instance, the STIG setting might not be applicable for standalone servers. Organization-specific policies can also prevent automatic application of STIG settings, such as a requirement for administrators to review document settings. For more details about which STIGs are applied to Linux AMIs, you can download our spreadsheet.

For a complete list, see the STIGs Document Library. For information about how to view the complete list, see SRG / STIG Tools.

Note

The Linux STIG Medium category includes all of the STIG settings that are applied to Linux STIG Low (Category III), in addition to the STIG settings that are applied specifically for Category II vulnerabilities.

RHEL 7 STIG Version 3 Release 6

Includes all STIG settings that are applied for Category III (Low) vulnerabilities, plus:

RHEL 7/CentOS 7

```
V-204405, V-204406, V-204407, V-204408, V-204409, V-204410, V-204411, V-204412, V-204413, V-204414, V-204415, V-204416, V-204417, V-204418, V-204422, V-204423, V-204426, V-204427, V-204428, V-204431, V-204435, V-204437, V-204449, V-204450, V-204451, V-204457, V-204466, V-204503, V-204516, V-204517, V-204521, V-204524, V-204531, V-204536, V-204537, V-204538, V-204539, V-204540, V-204541, V-204542, V-204543, V-204544, V-204545, V-204546, V-204547, V-204548, V-204549, V-204550, V-204551, V-204552, V-204553, V-204554, V-204555, V-204556, V-204557, V-204558, V-204559, V-204560, V-204562, V-204563, V-204564, V-204565, V-204566, V-204567, V-204568, V-204572, V-204579, V-204584, V-204585, V-204586, V-204587, V-204590, V-204591, V-204592, V-204593, V-204599, V-204600, V-204601, V-204602, V-204609, V-204610, V-204611, V-204612, V-204613, V-204615, V-204615, V-204616, V-204617, V-204619, V-204622, V-204624, V-204625, V-204630, V-204631, V-204633, V-233307, V-237634, V-237635, and V-251703
```

AL2:

```
V-204405, V-204406, V-204407, V-204408, V-204409, V-204410, V-204411, V-204412, V-204413, V-204414, V-204415, V-204416, V-204417, V-204418, V-204422, V-204423, V-204426, V-204427, V-204428, V-204431, V-204435, V-204437, V-204449, V-204450, V-204451, V-204457, V-204457, V-204503, V-204516, V-204517, V-204521, V-204524, V-204531, V-204536, V-204537, V-204538, V-204539, V-204540, V-204541, V-204542, V-204543, V-204544, V-204545, V-204546, V-204547, V-204548, V-204549, V-204550, V-204551, V-204552, V-204553, V-204554, V-204555, V-204556, V-204557, V-204558, V-204559, V-204560, V-204562, V-204563, V-204564, V-204565, V-204566, V-204567, V-204568, V-204591, V-204592, V-204593, V-204598, V-204598, V-204599, V-204590, V-204600, V-204601, V-204601, V-204602, V-204610, V-204611, V-204612, V-204631, V-204631, V-204633, V-233307, V-237634, V-237635, and V-251703
```

RHEL 8 STIG Version 1 Release 5

Includes all STIG settings that are applied for Category III (Low) vulnerabilities, plus:

RHEL 8/CentOS 8

```
V-230228, V-230231, V-230233, V-230236, V-230237, V-230239, V-230240, V-230244, V-230255,
V-230266, V-230267, V-230268, V-230273, V-230275, V-230277, V-230278, V-230279, V-230280,
V-230282, V-230288, V-230289, V-230290, V-230291, V-230296, V-230298, V-230310, V-230311,
V-230312, V-230313, V-230314, V-230315, V-230324, V-230330, V-230332, V-230333, V-230334,
V-230335, V-230336, V-230337, V-230338, V-230339, V-230340, V-230341, V-230342, V-230343,
V-230344, V-230345, V-230348, V-230349, V-230353, V-230356, V-230357, V-230358, V-230359,
V-230360, V-230361, V-230362, V-230363, V-230365, V-230368, V-230369, V-230370, V-230375,
V-230377, V-230378, V-230382, V-230383, V-230386, V-230387, V-230390, V-230392, V-230402,
V-230403, V-230404, V-230405, V-230406, V-230407, V-230408, V-230409, V-230410, V-230411,
V-230412, V-230413, V-230418, V-230419, V-230421, V-230422, V-230423, V-230424, V-230425,
V-230426, V-230427, V-230428, V-230429, V-230430, V-230431, V-230432, V-230433, V-230434,
V-230435, V-230436, V-230437, V-230438, V-230439, V-230444, V-230446, V-230447, V-230448,
V-230449, V-230455, V-230456, V-230462, V-230463, V-230464, V-230465, V-230466, V-230467,
V-230478, V-230480, V-230488, V-230489, V-230502, V-230503, V-230526, V-230527, V-230532,
V-230535, V-230536, V-230537, V-230538, V-230539, V-230540, V-230541, V-230542, V-230543,
V-230544, V-230545, V-230546, V-230547, V-230548, V-230549, V-230555, V-230556, V-230559,
V-230560, V-230561, V-237640, V-237642, V-237643, V-244523, V-244524, V-244525, V-244526,
V-244528, V-244533, V-244534, V-244537, V-244542, V-244549, V-244550, V-244551, V-244552,
V-244553, V-244554, V-250317, V-251711, V-251714, V-251715, V-251716, V-251717, and V-251718
```

Linux STIG High (Category I)

The following list contains STIG settings that are applied to your image. Some STIG settings are not automatically applied. This can be due to technical limitations – for instance, the STIG setting might not be applicable for standalone servers. Organization-specific policies can also prevent automatic application of STIG settings, such as a requirement for administrators to review document settings. For more details about which STIGs are applied to Linux AMIs, you can download our spreadsheet.

For a complete list, see the STIGs Document Library. For information about how to view the complete list, see SRG / STIG Tools.

Note

The Linux STIG High category includes all of the STIG settings that are applied for Linux STIG Medium and Low categories, in addition to the STIG settings that are applied specifically for Category I vulnerabilities.

RHEL 7 STIG Version 3 Release 6

Includes all STIG settings that are applied for Categories II and III (Medium and Low) vulnerabilities, plus:

RHEL 7/CentOS 7

V-204425, V-204442, V-204443, V-204447, V-204448, V-204455, V-204502, V-204620, and V-204621

AL2:

V-204425, V-204442, V-204443, V-204447, V-204448, V-204455, V-204502, V-204620, and V-204621

RHEL 8 STIG Version 1 Release 5

Includes all STIG settings that are applied for Categories II and III (Medium and Low) vulnerabilities, plus:

RHEL 8/CentOS 8

V-230264, V-230265, V-230487, V-230492, V-230529, V-230531, V-230533, and V-230558

Version history

The following table describes important changes to the STIG environment and settings described in this document.

Change	Description	Date
Quarterly updates	Updated STIG settings for 2022 Q1.	04/26/2022
Environme updates	nthanged staging directory and adjusted permissions.	02/01/2022
Quarterly updates	Updated STIG settings for 2021 Q4.	12/20/2021
Quarterly updates	Updated STIG settings for 2021 Q3.	09/30/2021
Quarterly updates	Updated STIG settings for 2021 Q2.	08/06/2021
Prior changes	The STIG Systems Manager document, AWSEC2-ConfigureSTIG, was introduced in May, 2020. Since then, it has received quarterly updates to reflect changes in official STIG guidelines.	05/06/2020

AWSSupport-CopyEC2Instance

Description

The AWSSupport-CopyEC2Instance runbook provides an automated solution for the procedure outlined in the Knowledge Center article How do I move my EC2 instance to another subnet, Availability Zone, or VPC? The automation branches depending on the values you specify for the Region and SubnetId parameters.

If you specify a value for the SubnetId parameter but not a value for the Region parameter, the automation creates an Amazon Machine Image (AMI) of the target instance and launches a new instance from the AMI in the subnet you specified.

If you specify a value for the SubnetId parameter and the Region parameter, the automation creates an AMI of the target instance, copies the AMI to the AWS Region you specified, and launches a new instance from the AMI in the subnet you specified.

If you specify a value for the Region parameter but not a value for the SubnetId parameter, the automation creates an AMI of the target instance, copies the AMI to the Region you specified, and launches a new instance from the AMI in the default subnet of your virtual private cloud (VPC) in the destination Region.

If no value is specified for either the Region or SubnetId parameters, the automation creates an AMI of the target instance, and launches a new instance from the AMI in the default subnet of your VPC.

To copy an AMI to a different Region, you must provide a value for the AutomationAssumeRole parameter. If the automation times out during the waitForAvailableDestinationAmi step, the AMI

AWS Systems Manager Automation runbook reference User Guide AWSSupport-CopyEC2Instance

might still be copying. If this is the case, you can wait for the copy to complete and launch the instance manually.

Before running this automation, note the following:

- AMIs are based on Amazon Elastic Block Store (Amazon EBS) snapshots. For large file systems without
 a previous snapshot, AMI creation can take several hours. To decrease the AMI creation time, create an
 Amazon EBS snapshot before you create the AMI.
- Creating an AMI doesn't create a snapshot for instance store volumes on the instance. For information about backing up instance store volumes to Amazon EBS, see How do I back up an instance store volume on my Amazon EC2 instance to Amazon EBS?
- The new Amazon EC2 instance has a different private IPv4 or public IPv6 IP address. You must update all references to the old IP addresses (for example, in DNS entries) with the new IP addresses that are assigned to the new instance. If you're using an Elastic IP address on your source instance, be sure to attach it to the new instance.
- Domain security identifier (SID) conflict issues can occur when the copy launches and tries to contact
 the domain. Before you capture the AMI, use Sysprep or remove the domain-joined instance from
 the domain to prevent conflict issues. For more information, see How can I use Sysprep to create and
 install custom reusable Windows AMIs?

Run this Automation (console)

Important

We do not recommend using this runbook to copy Microsoft Active Directory Domain Controller instances.

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) The ID of the instance that you want to copy.

KeyPair

Type: String

Description: (Optional) The key pair you want to associate with the new copied instance. If you're copying the instance to a different Region, make sure the key pair exists in the specified Region.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-CopyEC2Instance

· Region

Type: String

Description: (Optional) The Region you want to copy the instance to. If you specify a value for this parameter, but do not specify values for the SubnetId and SecurityGroupIds parameters, the automation attempts to launch the instance in the default VPC with the default security group. If EC2-Classic is enabled in the destination Region, the launch will fail.

SubnetId

Type: String

Description: (Optional) The ID of the subnet you want to copy the instance to. If EC2-Classic is enabled in the destination Region, you must provide a value for this parameter.

InstanceType

Type: String

Description: (Optional) The instance type the copied instance should be launched as. If you do not specify a value for this parameter, the source instance type is used. If the source instance type is not supported in the Region the instance is being copied to, the automation fails.

SecurityGroupIds

Type: String

Description: (Optional) A comma-separated list of security group IDs you want to associate with the copied instance. If you do not specify a value for this parameter, and the instance is not being copied to a different Region, the security groups associated with the source instance are used. If you're copying the instance to a different Region, the default security group for the default VPC in the destination Region is used.

KeepImageSourceRegion

Type: Boolean

Valid values: true | false

Default: true

Description: (Optional) If you specify true for this parameter, the automation does not delete the AMI of the source instance. If you specify false for this parameter, the automation deregisters the AMI and deletes the associated snapshots.

KeepImageDestinationRegion

Type: Boolean

Valid values: true | false

Default: true

Description: (Optional) If you specify true for this parameter, the automation does not delete the AMI that is copied to the Region you specified. If you specify false for this parameter, the automation deregisters the AMI and deletes the associated snapshots.

NoRebootInstanceBeforeTakingImage

Type: Boolean

Valid values: true | false

Default: false

AWS Systems Manager Automation runbook reference User Guide AWSSupport-CopyEC2Instance

Description: (Optional) If you specify true for this parameter, the source instance will not be restarted before creating the AMI. When this option is used, file system integrity on the created image can't be quaranteed.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ec2:CreateImage
- ec2:DeleteSnapshot
- ec2:DeregisterImage
- ec2:DescribeInstances
- ec2:DescribeImages
- ec2:RunInstances

If you're copying the instance to a different Region, you will also need the following permissions.

• ec2:CopyImage

Document Steps

- describeOriginalInstanceDetails Gathers details from the instance to be copied.
- assertRootVolumeIsEbs Checks if the root volume device type is ebs, and if not, ends the
 automation.
- evalInputParameters Evaluates the values provided for the input parameters.
- createLocalAmi Creates an AMI of the source instance.
- tagLocalAmi Tags the AMI created in the previous step.
- branchAssertRegionIsSame Branches based on whether the instance is being copied within the same Region or to a different Region.
- branchAssertSameRegionWithKeyPair Branches based on whether a value was provided for the KeyPair parameter for an instance that's being copied within the same Region.
- sameRegionLaunchInstanceWithKeyPair Launches an Amazon EC2 instance from the AMI of the source instance in the same subnet or the subnet you specify using the key pair that you specified.
- sameRegionLaunchInstanceWithoutKeyPair Launches an Amazon EC2 instance from the AMI of the source instance in the same subnet or the subnet you specify without a key pair.
- copyAmiToRegion Copies the AMI to the destination Region.
- waitForAvailableDestinationAmi Waits for the copied AMI state to become available.
- destinationRegionLaunchInstance Launches an Amazon EC2 Instance using the copied AMI.
- branchAssertDestinationAmiToDelete Branches based on the value you provided for the KeepImageDestinationRegion parameter.
- deregisterDestinationAmiAndDeleteSnapshots Deregisters the copied AMI and deletes associated snapshots.
- branchAssertSourceAmiTodelete Branches based on the value you provided for the KeepImageSourceRegion parameter.
- deregisterSourceAmiAndDeleteSnapshots Deregisters the AMI created from the source instance and deletes associated snapshots.
- sleep Sleeps the automation for 2 seconds. This is a terminal step.

Outputs

sameRegionLaunchInstanceWithKeyPair.InstanceIds

same Region Launch Instance Without Key Pair. Instance Ids

destinationRegionLaunchInstance.DestinationInstanceId

AWS-CreateImage

Description

Create a new Amazon Machine Image (AMI) from an Amazon Elastic Compute Cloud (Amazon EC2) instance.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) The ID of the EC2 instance.

NoReboot

Type: Boolean

Description: (Optional) Do not reboot the instance before creating the image.

Required IAM permissions

AWS Systems Manager Automation runbook reference User Guide AWS-DeleteImage

```
],
    "Resource": [
        "*"
]
}
```

AWS-DeleteImage

Description

Delete an Amazon Machine Image (AMI) and all associated snapshots.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

• AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Imageld

Type: String

Description: (Required) The ID of the AMI.

Required IAM permissions

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

${\tt Enable AutoScaling Group ELB Health Check}$

```
{
    "Effect": "Allow",
    "Action": "ec2:DeregisterImage",
    "Resource": "*"
}
]
```

AWSConfigRemediation-EnableAutoScalingGroupELBHealthCheck

Description

The AWSConfigRemediation-EnableAutoScalingGroupELBHealthCheck runbook enables health checks for the Amazon EC2 Auto Scaling (Auto Scaling) group you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

AutoScalingGroupARN

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the auto scaling group that you want to enable health checks on.

HealthCheckGracePeriod

Type: Integer Default: 300

Description: (Optional) The amount of time, in seconds, that Auto Scaling waits before checking the health status of an Amazon Elastic Compute Cloud (Amazon EC2) instance that has come into service.

Required IAM permissions

AWS Systems Manager Automation runbook reference User Guide

AWSConfigRemediation-EnforceEC2InstanceIMDSv2

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeAutoScalingGroups
- ec2:UpdateAutoScalingGroup

Document Steps

• aws:executeScript - Enables health checks on the Auto Scaling group you specify in the AutoScalingGroupARN parameter.

AWSConfigRemediation-EnforceEC2InstanceIMDSv2

Description

The AWSConfigRemediation-EnforceEC2InstanceIMDSv2 runbook requires the Amazon Elastic Compute Cloud (Amazon EC2) instance you specify to use Instance Metadata Service Version 2 (IMDSv2).

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

InstanceId

Type: String

Description: (Required) The ID of the Amazon EC2 instance you want to require to use IMDSv2.

• AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeInstances

• ec2:ModifyInstanceMetadataOptions

Document Steps

- aws:executeScript Sets the HttpTokens option to required on the Amazon EC2 instance you specify in the InstanceId parameter.
- aws:assertAwsResourceProperty Verifies IMDSv2 is required on the Amazon EC2 instance.

AWSSupport-ExecuteEC2Rescue

Description

This runbook will use the EC2Rescue tool to troubleshoot and where possible repair common connectivity issues with the specified EC2 instance for Linux or Windows Server.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

EC2RescueInstanceType

Type: String

Valid values: t2.small | t2.medium | t2.large

Default: t2.small

Description: (Required) The EC2 instance type for the EC2Rescue instance. Recommended size: t2.small.

LogDestination

Type: String

Description: (Optional) S3 bucket name in your account where you want to upload the troubleshooting logs. Make sure the bucket policy does not grant unnecessary read/write permissions to parties that do not need access to the collected logs.

SubnetId

Type: String

Default: CreateNewVPC

Description: (Optional) The subnet ID for the EC2Rescue instance. By default, AWS Systems Manager Automation creates a new VPC. Alternatively, Use SelectedInstanceSubnet to use the same subnet as your instance, or specify a custom subnet ID. IMPORTANT: The subnet must be in the same Availability Zone as UnreachableInstanceId, and it must allow access to the SSM endpoints.

UnreachableInstanceId

Type: String

Description: (Required) ID of your unreachable EC2 instance. IMPORTANT: AWS Systems Manager Automation stops this instance, and creates an AMI before attempting any operations. Data stored in instance store volumes will be lost. The public IP address will change if you are not using an Elastic IP.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

You must have at least ssm:StartAutomationExecution and ssm:GetAutomationExecution to be able to read the automation output. For more information about the required permissions see AWSSupport-StartEC2RescueWorkflow

Document Steps

- 1. aws:assertAwsResourceProperty Assert if the provided instance is Windows
 - a. (EC2Rescue for Windows) If the provided instance is a Windows Server instance:
 - i. aws:executeAutomation Invoke AWSSupport-StartEC2RescueWorkflow with the EC2Rescue for Windows offline script
 - ii. aws:executeAwsApi Retrieve the backup AMI ID from the nested automation
 - iii. aws:executeAwsApi Retrieve the EC2Rescue summary from the nested automation
 - b. (EC2Rescue for Linux) If the provided instance is a Linux instance:
 - i. aws:executeAutomation Invoke AWSSupport-StartEC2RescueWorkflow with the EC2Rescue for Linux offline script
 - ii. aws:executeAwsApi Retrieve the backup AMI ID from the nested automation
 - iii. aws:executeAwsApi Retrieve the EC2Rescue summary from the nested automation

Outputs

getEC2RescueForWindowsResult.Output

getWindowsBackupAmi.ImageId

getEC2RescueForLinuxResult.Output

getLinuxBackupAmi.ImageId

AWSSupport-ListEC2Resources

Description

The AWSSupport-ListEC2Resources runbook returns information about Amazon EC2 instances and related resources like Amazon Elastic Block Store (Amazon EBS) volumes, Elastic IP addresses, and Amazon EC2 Auto Scaling groups from the AWS Regions you specify. By default, the information is

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ListEC2Resources

gathered from all Regions and is displayed in the output of the automation. Optionally, you can specify an Amazon Simple Storage Service (Amazon S3) bucket for the information to be uploaded to as a comma-separated values (.csv) file.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Bucket

Type: String

Description: (Optional) The name of the S3 bucket where the information gathered is uploaded to.

• DisplayResourceDeletionDocumentation

Type: String
Default: true

Description: (Optional) If set to true, the automation creates links in the output to documentation related to deleting your resources.

RegionsToQuery

Type: String
Default: All

Description: (Optional) The Regions you want to gather Amazon EC2 related information from.

Required IAM permissions

- autoscaling:DescribeAutoScalingGroups
- ec2:DescribeAddresses
- ec2:DescribeImages
- ec2:DescribeInstances
- ec2:DescribeNetworkInterfaces
- ec2:DescribeRegions

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ManageRDPSettings

- ec2:DescribeVolumes
- ec2:DescribeSnapshots
- elasticloadbalancing:DescribeLoadBalancers

Additionally, to successfully upload the information gathered to the S3 bucket you specify, the AutomationAssumeRole requires the following actions:

- s3:GetBucketAcl
- s3:GetBucketPolicyStatus
- s3:PutObject

Document Steps

- aws:executeAwsApi Gathers the Regions enabled for the account.
- aws:executeScript Confirms the Regions enabled for the account support the Regions specified in the RegionsToQuery parameter.
- aws:branch If no Regions are enabled for the account, the automation ends.
- aws:executeScript Lists all EC2 instances for the account and Regions you specify.
- aws:executeScript Lists all Amazon Machine Images (AMI) for the account and Regions you specify.
- aws:executeScript Lists all EBS volumes for the account and Regions you specify.
- aws:executeScript Lists all Elastic IP addresses for the account and Regions you specify.
- aws:executeScript Lists all elastic network interfaces for the account and Regions you specify.
- aws:executeScript Lists all Auto Scaling groups for the account and Regions you specify.
- aws:executeScript Lists all load balancers for the account and Regions you specify.
- aws:executeScript Uploads the information gathered to the S3 bucket specified if you provide a
 value for the Bucket parameter.

AWSSupport-ManageRDPSettings

Description

The AWSSupport-ManageRDPSettings runbook allows the user to manage common Remote Desktop Protocol (RDP) settings, such as the RDP port and Network Layer Authentication (NLA). By default, the runbook reads and outputs the values of the settings.

Important

Changes to the RDP settings should be carefully reviewed before running this runbook.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Windows

Parameters

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ManageRDPSettings

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) The ID of the managed instance to manage the RDP settings of.

NLASettingAction

Type: String

Valid values: Check | Enable | Disable

Default: Check

Description: (Required) An action to perform on the NLA setting: Check, Enable, Disable.

RDPPort

Type: String
Default: 3389

Description: (Optional) Specify the new RDP port. Used only when the action is set to Modify. The port number must be between 1025-65535. Note: After the port is changed, the RDP service is restarted.

RDPPortAction

Type: String

Valid values: Check | Modify

Default: Check

Description: (Required) An action to apply to the RDP port.

RemoteConnections

Type: String

Valid values: Check | Enable | Disable

Default: Check

Description: (Required) An action to perform on the fDenyTSConnections setting.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

The EC2 instance receiving the command must have an IAM role with the

AmazonSSMManagedInstanceCore Amazon managed policy attached. The user must have at least **ssm:SendCommand** to send the command to the instance, plus **ssm:GetCommandInvocation** to be able to read the command output.

Document Steps

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ManageWindowsService

aws:runCommand - Run the PowerShell script to change or check the RDP settings on the target instance.

Outputs

manageRDPSettings.Output

AWSSupport-ManageWindowsService

Description

The AWSSupport-ManageWindowsService runbook enables you to stop, start, restart, pause, or disable any Windows service on the target instance.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) The ID of the managed instance to manage the RDP settings of.

ServiceAction

Type: String

Valid values: Check | Restart | Force-Restart | Start | Stop | Force-Stop | Pause

Default: Check

Description: (Required) An action to apply to the Windows service. Note that Force-Restart and Force-Stop can be used to restart and to stop a service that has dependent services.

StartupType

Type: String

Valid values: Check | Auto | Demand | Disabled | DelayedAutoStart

Default: Check

Description: (Required) A startup type to apply to the Windows service.

· WindowsServiceName

Type: String

Description: (Required) A valid Windows service name.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

It is recommended that the EC2 instance receiving the command has an IAM role with the AmazonSSMManagedInstanceCore Amazon managed policy attached. The user must have at least ssm:StartAutomationExecution and ssm:SendCommand to run the automation and send the command to the instance, plus ssm:GetAutomationExecution to be able to read the automation output.

Document Steps

aws:runCommand - Run the PowerShell script to apply the desired configuration to the Windows service
on the target instance.

Outputs

manageWindowsService.Output

AWSSupport-MigrateEC2ClassicToVPC

Description

The AWSSupport-MigrateEC2ClassicToVPC runbook migrates an Amazon Elastic Compute Cloud (Amazon EC2) instance from EC2-Classic to a virtual private cloud (VPC). This runbook supports migrating Amazon EC2 instances of the hardware virtual machine (HVM) virtualization type with Amazon Elastic Block Store (Amazon EBS) root volumes.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

ApproverIAM

Type: StringList

Description: (Optional) The Amazon Resource Names (ARNs) of IAM users who can approve or deny the action. This parameter only applies if you specify the CutOver value for the MigrationType parameter.

DestinationSecurityGroupId

Type: StringList

Description: (Optional) The ID of the security group you want to associate with the Amazon EC2 instance that is launched in your VPC. If you do not specify a value for this parameter, the automation creates a security group in your VPC and copies the rules from the security group in EC2-Classic. If the rules fail to copy to the new security group, the default security group of your VPC is associated with the Amazon EC2 instance.

DestinationSubnetId

Type: String

Description: (Optional) The ID of the subnet you want to migrate your Amazon EC2 instance to. If you do not specify a value for this parameter, the automation randomly chooses a subnet from your VPC.

InstanceId

Type: String

Description: (Required) The ID of the Amazon EC2 instance you want to migrate.

MigrationType

Type: String

Valid values: CutOver | Test

Description: (Required) The type of migration you want to perform.

The CutOver option requires approval to stop your Amazon EC2 instance that's running in EC2-Classic. After this action is approved, the Amazon EC2 instance is stopped and the automation creates an Amazon Machine Image (AMI). When the AMI status is available, a new Amazon EC2 instance is launched from this AMI in the DestinationSubnetId you specify in your VPC. If your Amazon EC2 instance that's running in EC2-Classic has an Elastic IP address attached, the instance will be moved to the newly created Amazon EC2 instance in your VPC. If the Amazon EC2 instance launching in your VPC fails to create for any reason, it is terminated and approval is requested to start your Amazon EC2 instance in EC2-Classic.

The Test option creates an AMI of your Amazon EC2 instance that's running in EC2-Classic without rebooting. Because the Amazon EC2 instance does not reboot, we can't guarantee the file system integrity of the created image. When the AMI status is available, a new Amazon EC2 instance is launched from this AMI in the DestinationSubnetId you specify in your VPC. If your Amazon EC2 instance that's running in EC2-Classic has an Elastic IP address attached, the automation verifies the DestinationSubnetId you specify is public. If the Amazon EC2 instance launching in your VPC fails to create for any reason, it is terminated and the automation ends.

SNSNotificationARNforApproval

Type: String

Description: (Optional) The ARN of the Amazon Simple Notification Service (Amazon SNS) topic you want to send approval requests to. This parameter only applies if you specify the CutOver value for the MigrationType parameter.

TargetInstanceType

Type: String

Default: t2.2xlarge

Description: (Optional) The type of Amazon EC2 instance you want to launch in your VPC. Only Xenbased instance types, such as T2, M4 or C4, are supported.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:GetDocument
- ssm:ListDocumentVersions
- ssm:ListDocuments
- ssm:StartAutomationExecution
- sns:GetTopicAttributes
- sns:ListSubscriptions
- sns:ListTopics
- sns:Publish
- ec2:AssociateAddress
- ec2:AuthorizeSecurityGroupIngress
- ec2:CreateImage
- ec2:CreateSecurityGroup
- ec2:DeleteSecurityGroup
- ec2:MoveAddressToVpc
- ec2:RunInstances
- ec2:StopInstances
- ec2:CreateTags
- ec2:DescribeAddresses
- ec2:DescribeInstanceAttribute
- ec2:DescribeInstances
- ec2:DescribeInstanceStatus
- ec2:DescribeRouteTables
- ec2:DescribeSecurityGroupReferences
- ec2:DescribeSecurityGroups
- ec2:DescribeSubnets
- ec2:DescribeTags
- ec2:DescribeVpcs
- ec2:DescribeInstanceTypes
- ec2:DescribeImages

Document Steps

- aws:executeAwsApi Gathers details about the Amazon EC2 instance you specify in the InstanceId parameter.
- aws:assertAwsResourceProperty Confirms the instance type you specify in the TargetInstanceType parameter is Xen-based.

- aws:assertAwsResourceProperty Confirms the Amazon EC2 instance you specify in the InstanceId parameter is of the HVM virtualization type.
- aws:assertAwsResourceProperty Confirms the Amazon EC2 instance you specify in the InstanceId parameter has an Amazon EBS root volume.
- aws:executeScript Creates a security group as needed depending on the value you specify for the DestinationSecurityGroupId parameter.
- aws:branch Branches based on the value you specify in the DestinationSubnetId parameter.
- aws:executeAwsApi Identifies the default VPC in the AWS Region where you run this automation.
- aws:executeAwsApi Randomly chooses the ID of a subnet located in the default VPC.
- aws:createImage Creates an AMI without rebooting the Amazon EC2 instance.
- aws:branch Branches based on the value you specify for the MigrationType parameter.
- aws:branch Branches based on the value you specify for the DestinationSubnetId parameter.
- aws:runInstances Launches a new instance from the AMI created without rebooting the Amazon EC2 instance in EC2-Classic.
- aws:changeInstanceState Terminates the newly launched Amazon EC2 instance if the previous step fails for any reason.
- aws:runInstances Launches a new instance from the AMI created without rebooting the Amazon EC2 instance in EC2-Classic in the DestinationSubnetId if provided.
- aws:changeInstanceState Terminates the newly launched Amazon EC2 instance if the previous step fails for any reason.
- aws:assertAwsResourceProperty Confirms the stop behavior for the Amazon EC2 instance running in EC2-Classic.
- aws:approve Waits for approval to stop the Amazon EC2 instance.
- aws:changeInstanceState Stops the Amazon EC2 instance running in EC2-Classic.
- aws:changeInstanceState Force stops the Amazon EC2 instance running in EC2-Classic if needed.
- aws:createImage Creates an AMI of the Amazon EC2 instance after it has stopped.
- aws:branch Branches based on the value specified for the DestinationSubnetId parameter.
- aws:runInstances Launches a new instance from the AMI created of the stopped Amazon EC2 instance in EC2-Classic.
- aws:approve Waits for approval to terminate the newly launched instance and start the Amazon EC2 instance in EC2-Classic if the previous step fails for any reason.
- aws:changeInstanceState Terminates the newly launched Amazon EC2 instance.
- aws:runInstances Launches a new instance from the AMI created of the stopped Amazon EC2 instance in EC2-Classic in the DestinationSubnetId.
- aws:approve Waits for approval to terminate the newly launched instance and start the Amazon EC2 instance in EC2-Classic if the previous step fails for any reason.
- aws:changeInstanceState Terminates the newly launched Amazon EC2 instance.
- aws:changeInstanceState Starts the Amazon EC2 instance that was stopped in EC2-Classic.
- aws:branch Branches based on whether the Amazon EC2 instance has a public IP address.
- aws:executeAwsApi Verifies whether the public IP address is an EIP.
- aws:branch Branches based on the value you specify in the MigrationType parameter.
- aws:executeAwsApi Moves the EIP to your VPC.
- aws:executeAwsApi Gathers the allocation ID of the EIP that was moved to your VPC.
- aws:branch Branches based on which subnet the Amazon EC2 instance running in your VPC was launched.
- aws:executeAwsApi Attaches the EIP to the newly launched instance in your VPC.
- aws:executeScript Confirms the subnet your newly launched Amazon EC2 instance running in your VPC is public.

AWS Systems Manager Automation runbook reference User Guide AWS-PatchAsqInstance

Outputs

getInstanceProperties.virtualizationType - The virtualization type of the Amazon EC2 instance running in EC2-Classic.

getInstanceProperties.rootDeviceType - The root device type of the Amazon EC2 instance running in EC2-Classic.

createAMIWithoutReboot.ImageId - The ID of the AMI created without rebooting the Amazon EC2 instance running in EC2-Classic.

getDefaultVPC.VpcId - The ID of the default VPC where the new Amazon EC2 instance will be launched if a value for the DestinationSubnetId parameter is not provided.

getSubnetIdinDefaultVPC.subnetIdFromDefaultVpc - The ID of the subnet in the default VPC where the new Amazon EC2 instance will be launched if a value for the DestinationSubnetId parameter is not provided.

launchTestInstanceDefaultVPC.InstanceIds - The ID of the newly launched Amazon EC2 instance in your default VPC during the Test migration type.

launchTestInstanceProvidedSubnet.InstanceIds - The ID of the newly launched Amazon EC2 instance in the DestinationSubnetId you specified during the Test migration type.

createAMIAfterStoppingInstance.ImageId - The ID of the AMI created after stopping the Amazon EC2 instance running in EC2-Classic.

launchCutOverInstanceProvidedSubnet.InstanceIds - The ID of the newly launched Amazon EC2 instance in the DestinationSubnetId you specified during the CutOver migration type.

launchCutOverInstanceDefaultVPC.InstanceIds - The ID of the newly launched Amazon EC2 instance in your default VPC during the CutOver migration type.

verifySubnetIsPublicTestDefaultVPC.IsSubnetPublic - Whether the subnet chosen by the automation in your default VPC is public or not.

verifySubnetIsPublicTestProvidedSubnet.IsSubnetPublic - Whether the subnet you specified in the DestinationSubnetId is public or not.

AWS-PatchAsgInstance

Description

Patch EC2 instances in an Auto Scaling group.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

AWS Systems Manager Automation runbook reference User Guide AWS-PatchInstanceWithRollback

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) ID of the instance to patch. Don't specify an instance ID that is configured to run during a Maintenance Window.

LambdaRoleArn

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

WaitForInstance

Type: String
Default: PT2M

Description: (Optional) Duration the Automation should sleep to allow the instance to come back into service.

WaitForReboot

Type: String
Default: PT5M

Description: (Optional) Duration the Automation should sleep to allow a patched instance to reboot.

AWS-PatchInstanceWithRollback

Description

Brings an EC2 instance into compliance with the applicable patch baseline. Rolls back root volume on failure.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

AWS Systems Manager Automation runbook reference User Guide AWS-PatchInstanceWithRollback

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) EC2 InstanceId to which we apply the patch-baseline.

• LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

• ReportS3Bucket

Type: String

Description: (Optional) Amazon S3 Bucket destination for the Compliance Report generated during process.

Document Steps

Step number	Step name	Automation action
1	createDocumentStack	aws:createStack
2	IdentifyRootVolume	aws:invokeLambdaFunction
3	PrePatchSnapshot	aws:executeAutomation
4	installMissingUpdates	aws:runCommand
5	SleepThruInstallation	aws:invokeLambdaFunction
6	CheckCompliance	aws:invokeLambdaFunction
7	SaveComplianceReportToS3	aws:invokeLambdaFunction
8	ReportSuccessOrFailure	aws:invokeLambdaFunction
9	RestoreFromSnapshot	aws:invokeLambdaFunction
10	DeleteSnapshot	aws:invokeLambdaFunction
11	deleteCloudFormationTemplate	aws:deleteStack

Outputs

IdentifyRootVolume.Payload

PrePatchSnapshot.Output

SaveComplianceReportToS3.Payload

RestoreFromSnapshot.Payload

CheckCompliance.Payload

AWSEC2-PatchLoadBalancerInstance

Description

Upgrade and patch minor version of an Amazon EC2 instance (Windows or Linux) attached to any load balancer (classic, ALB, or NLB). The default connection draining time is applied before the instance is patched. You can override the wait time by entering your custom draining time in minutes (1-59) for the **ConnectionDrainTime** parameter.

The automation workflow is as follows:

- 1. The load balancer or target group to which the instance is attached is determined, and the instance is verified as healthy.
- 2. The instance is removed from the load balancer or target group.
- 3. The automation waits for the period of time specified for the connection draining time.
- 4. The AWS-RunPatchBaseline automation is called to patch the instance.
- 5. The instance is reattached to the load balancer or target group.

Run this Automation (console)

Document Type

Automation

Owner

Amazon

Prerequisites

 Verify that SSM Agent is installed on your instance. For more information, see Working with SSM Agent on EC2 instances for Windows Server.

Parameters

InstanceId

Type: String

Description: (Required) ID of the instance to patch that is associated with a load balancer (classic, ALB, or NLB).

ConnectionDrainTime

Type: String

Description: (Optional) The connection draining time of the load balancer, in minutes (1-59).

AWSSupport-ResetAccess

Description

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ResetAccess

This runbook will use the EC2Rescue tool on the specified EC2 instance to re-enable password decryption using the EC2 Console (Windows) or to generate and add a new SSH key pair (Linux). If you lost your key pair, this automation will create a password-enabled AMI that you can use to launch a new EC2 instance with a key pair you own (Windows).

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

EC2RescueInstanceType

Type: String

Valid values: t2.small | t2.medium | t2.large

Default: t2.small

Description: (Required) The EC2 instance type for the EC2Rescue instance. Recommended size: t2.small.

InstanceId

Type: String

Description: (Required) ID of the EC2 instance you want to reset access for.

Important

Systems Manager Automation stops this instance, and creates an AMI before attempting any operations. Data stored in instance store volumes will be lost. The public IP address will change if you are not using an Elastic IP.

SubnetId

Type: String

Default: CreateNewVPC

Description: (Optional) The subnet ID for the EC2Rescue instance. By default, Systems Manager Automation creates a new VPC. Alternatively, Use SelectedInstanceSubnet to use the same subnet as your instance, or specify a custom subnet ID.

Important

The subnet must be in the same Availability Zone as InstanceId, and it must allow access to the SSM endpoints.

AWS Systems Manager Automation runbook reference User Guide AWS-ResizeInstance

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

You must have at least ssm:StartAutomationExecution, ssm:GetParameter (to retrieve the SSH key parameter name) and ssm:GetAutomationExecution to be able to read the automation output. For more information about the required permissions, see AWSSupport-StartEC2RescueWorkflow (p. 105).

Document Steps

- 1. aws:assertAwsResourceProperty Assert if the provided instance is Windows.
 - a. (EC2Rescue for Windows) If the provided instance is Windows:
 - i. aws:executeAutomation Invoke AWSSupport-StartEC2RescueWorkflow with the EC2Rescue for Windows offline password reset script
 - ii. aws:executeAwsApi Retrieve the backup AMI ID from the nested automation
 - iii. aws: executeAwsApi Retrieve the password-enabled AMI ID from the nested automation
 - iv. aws: executeAwsApi Retrieve the EC2Rescue summary from the nested automation
 - b. (EC2Rescue for Linux) If the provided instance is Linux:
 - i. aws:executeAutomation Invoke AWSSupport-StartEC2RescueWorkflow with the EC2Rescue for Linux offline SSH key injection script
 - ii. aws:executeAwsApi Retrieve the backup AMI ID from the nested automation
 - iii.aws:executeAwsApi Retrieve the SSM parameter name for the injected SSH key
 - iv. aws:executeAwsApi Retrieve the EC2Rescue summary from the nested automation

Outputs

getEC2RescueForWindowsResult.Output
getWindowsBackupAmi.ImageId
getWindowsPasswordEnabledAmi.ImageId
getEC2RescueForLinuxResult.Output
getLinuxBackupAmi.ImageId
getLinuxSSHKeyParameter.Name

AWS-ResizeInstance

Description

Change the instance type of an Amazon Elastic Compute Cloud (Amazon EC2) instance.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

AWS Systems Manager Automation runbook reference User Guide AWS-RestartEC2Instance

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) The ID of the instance.

InstanceType

Type: String

Description: (Required) The instance type.

• LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role assumed by Lambda.

AWS-RestartEC2Instance

Description

Restart one or more Amazon Elastic Compute Cloud (Amazon EC2) instances.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

InstanceId

Type: StringList

Description: (Required) The IDs of the Amazon EC2 instances to restart.

AWSSupport-RestoreEC2InstanceFromSnapshot

Description

The AWSSupport-RestoreEC2InstanceFromSnapshot runbook helps you identify and restore an Amazon Elastic Compute Cloud (Amazon EC2) instance from a working Amazon Elastic Block Store (Amazon EBS) snapshot of the root volume.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

EndDate

Type: String

Description: (Optional) The last date you want the automation to look for a snapshot.

InplaceSwap

Type: Boolean

Valid values: true | false

Description: (Optional) If the value for this parameter is set to true, the newly created volume from the snapshot replaces the existing root volume attached to your instance.

Instanceld

Type: String

Description: (Required) The ID of the instance you want to restore from a snapshot.

LookForInstanceStatusCheck

Type: Boolean

AWS Systems Manager Automation runbook reference User Guide

AWSSupport-RestoreEC2InstanceFromSnapshot

Valid values: true | false

Default: true

Description: (Optional) If the value for this parameter is set to true, the automation checks whether instance status checks fail on the test instances launched from the snapshots.

SkipSnapshotsBy

Type: String

Description: (Optional) The interval at which snapshots are skipped when searching for snapshots to restore your instance. For example, if there are 100 snapshots available, and you specify a value of 2 for this parameter, then every third snapshot is reviewed.

Default: 0
• SnapshotId

Type: String

Description: (Optional) The ID of a snapshot you want to restore the instance from.

StartDate

Type: String

Description: (Optional) The first date you want the automation to look for a snapshot.

TotalSnapshotsToLook

Type: String

Description: (Optional) The number of snapshots the automation reviews.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:DescribeInstanceInformation
- ec2:AttachVolume
- ec2:CreateImage
- ec2:CreateTags
- ec2:CreateVolume
- ec2:DeleteTags
- ec2:DeregisterImage
- ec2:DescribeInstances
- ec2:DescribeInstanceStatus
- ec2:DescribeImages
- ec2:DescribeSnapshots
- ec2:DescribeVolumes
- ec2:DetachVolume
- ec2:RunInstances
- ec2:StartInstances

AWS Systems Manager Automation runbook reference User Guide

AWSSupport-RestoreEC2InstanceFromSnapshot

- ec2:StopInstances
- ec2:TerminateInstances
- cloudwatch:GetMetricData

Document Steps

- 1. aws:executeAwsApi Gathers details about the target instance.
- 2. aws:assertAwsResourceProperty Verifies the target instance exists.
- 3. aws:assertAwsResourceProperty Verifies the root volume is an Amazon EBS volume.
- 4. aws:assertAwsResourceProperty Verifies that another automation isn't already running that targets this instance.
- 5. aws:executeAwsApi Tags the target instance.
- 6. aws:executeAwsApi Creates an AMI of the instance.
- aws:executeAwsApi Gathers details about the AMI created in the previous step.
- aws:waitForAwsResourceProperty Waits for the AMI state to become available before proceeding.
- 9. aws:executeScript Launches a new instance from the newly created AMI.

10aws:assertAwsResourceProperty - Verifies the instance state is available.

11aws:executeAwsApi - Gathers details about the newly launched instance.

12aws:branch - Branches based on whether you provided a value for the SnapshotId parameter.

13aws: executeScript - Returns a list of snapshots within the time period specified.

14aws: executeAwsApi - Stops the instance.

15aws:waitForAwsResourceProperty - Waits for the volume state to be available.

16aws:waitForAwsResourceProperty - Waits for the instance state to be stopped.

17aws:executeAwsApi - Detaches the root volume.

18aws:waitForAwsResourceProperty - Waits for the root volume to be detached.

19aws: executeAwsApi - Attaches the new root volume.

20aws:waitForAwsResourceProperty - Waits for the new volume to be attached.

21aws: executeAwsApi - Starts the instance.

22aws:waitForAwsResourceProperty - Waits for the instance state to be available.

- 23aws:waitForAwsResourceProperty Waits for system and instance status checks to pass for the instance.
- 24aws: executeScript Runs a script to find a snapshot that can be used to successfully create a volume.
- 25aws:executeScript Runs a script to recover the instance using the newly created volume from the snapshot identified by the automation, or using the volume created from the snapshot you specified in the SnapshotId parameter.

26aws: executeScript - Deletes resources created by the automation.

Outputs

launchCloneInstance.InstanceIds

ListSnapshotByDate.finalSnapshots

List Snapshot By Date. remaining Snapshot To Be Checked In Same Date Range

findWorkingSnapshot.workingSnapshot

InstanceRecovery.result

AWSSupport-SendLogBundleToS3Bucket

Description

The AWSSupport-SendLogBundleToS3Bucket runbook uploads a log bundle generated by the EC2Rescue tool from the target instance to the specified S3 bucket. The runbook installs the platform specific version of EC2Rescue based on the platform of the target instance. EC2Rescue is then used to collect all the available operating system (OS) logs.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) The ID of the Windows or Linux managed instance you want to collect logs from.

S3BucketName

Type: String

Description: (Required) S3 bucket to upload the logs to.

S3Path

Type: String

Default: AWSSupport-SendLogBundleToS3Bucket/

Description: (Optional) S3 path for the collected logs.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

It is recommended that the EC2 instance receiving the command has an IAM role with the **AmazonSSMManagedInstanceCore** Amazon managed policy attached. The user must have at least

ssm:StartAutomationExecution and **ssm:SendCommand** to run the automation and send the command to the instance, plus **ssm:GetAutomationExecution** to be able to read the automation output.

Document Steps

- 1. aws:runCommand Install EC2Rescue via AWS-ConfigureAWSPackage.
- aws:runCommand Run the PowerShell script to collect Windows troubleshooting logs with EC2Rescue.
- 3. aws:runCommand Run the bash script to collect Linux troubleshooting logs with EC2Rescue.

Outputs

collect And Upload Windows Log Bundle. Output

collect And Upload Linux Log Bundle. Output

AWSEC2-SQLServerDBRestore

Description

The AWSEC2-SQLServerDBRestore runbook restores Microsoft SQL Server database backups stored in Amazon S3 to SQL Server 2017 running on an Amazon Elastic Compute Cloud (EC2) Linux instance. You may provide your own EC2 instance running SQL Server 2017 Linux. If an EC2 instance is not provided, the automation launches and configures a new Ubuntu 16.04 EC2 instance with SQL Server 2017. The automation supports restoring full, differential, and transactional log backups. This automation accepts multiple database backup files and automatically restores the most recent valid backup of each database in the files provided.

To automate both backup and restore of an on-premises SQL Server database to an EC2 instance running SQL Server 2017 Linux, you can use the AWS-signed PowerShell script MigrateSQLServerToEC2Linux.

Important

This runbook resets the SQL Server server administrator (SA) user password every time the automation runs. After the automation is complete, you must set your own SA user password again before you connect to the SQL Server instance.

Run this Automation (console)

Document Type

Automation

Owner

Amazon

Platforms

Linux

Prerequisites

To run this automation, you must meet the following prerequisites:

- The IAM user or role that runs this automation must have an inline policy attached with the permissions outlined in Required IAM permissions (p. 102).
- If you provide your own EC2 instance:
 - The EC2 instance that you provide must be a Linux instance running Microsoft SQL Server 2017.

AWS Systems Manager Automation runbook reference User Guide AWSEC2-SQLServerDBRestore

- The EC2 instance that you provide must be configured with an AWS Identity and Access
 Management (IAM) instance profile that has the AmazonSSMManagedInstanceCore managed
 policy attached. For more information, see Create an IAM instance profile for Systems Manager.
- The SSM Agent must be installed on your EC2 instance. For more information, see Installing and configuring SSM Agent on EC2 instances for Linux.
- The EC2 instance must have enough free disk space to download and restore the SQL Server backups.

Limitations

This automation does not support restoring to SQL Server running on EC2 instances for Windows Server. This automation only restores database backups that are compatible with SQL Server Linux 2017. For more information, see Editions and Supported Features of SQL Server 2017 on Linux.

Parameters

This automation has the following parameters:

DatabaseNames

Type: String

Description: (Optional) Comma-separated list of the names of databases to restore.

DataDirectorySize

Type: String

Description: (Optional) Desired volume size (GiB) of the SQL Server Data directory for the new EC2

instance.

Default value: 100

KeyPair

Type: String

Description: (Optional) Key pair to use when creating the new EC2 instance.

• IamInstanceProfileName

Type: String

Description: (Optional) The IAM instance profile to attach to the new EC2 instance. The IAM instance profile must have the AmazonSSMManagedInstanceCore managed policy attached.

InstanceId

Type: String

Description: (Optional) The instance running SQL Server 2017 on Linux. If no InstanceId is provided, the automation launches a new EC2 instance using the InstanceType and SQLServerEdition provided.

InstanceType

Type: String

Description: (Optional) The instance type of the EC2 instance to be launched.

IsS3PresignedUrl

Type: String

AWS Systems Manager Automation runbook reference User Guide AWSEC2-SQLServerDBRestore

Description: (Optional) If S3Input is a pre-signed S3 URL, indicate yes.

Default value: no
Valid values: yes | no
LogDirectorySize

Type: String

Description: (Optional) Desired volume size (GiB) of the SQL Server Log directory for the new EC2

instance.

Default value: 100

S3Input

Type: String

Description: (Required) S3 bucket name, comma-separated list of S3 object keys, or comma-separated list of pre-signed S3 URLs containing the SQL backup files to be restored.

SQLServerEdition

Type: String

Description: (Optional) The edition of SQL Server 2017 to be installed on the newly created EC2 instance.

Valid values: Standard | Enterprise | Web | Express

SubnetId

Type: String

Description: (Optional) The subnet in which to launch the new EC2 instance. The subnet must have outbound connectivity to AWS services. If a value for SubnetId is not provided, the automation uses the default subnet.

TempDbDirectorySize

Type: String

Description: (Optional) Desired volume size (GiB) of the SQL Server TempDB directory for the new EC2 instance.

Default value: 100

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

AWS Systems Manager Automation runbook reference User Guide AWS-StartEC2Instance

```
"ec2:RunInstances",
    "ssm:DescribeInstanceInformation",
    "ssm:GetAutomationExecution",
    "ssm:ListCommandInvocations",
    "ssm:ListCommands",
    "ssm:SendCommand",
    "ssm:StartAutomationExecution"
],
    "Resource": "*"
},
{
    "Effect": "Allow",
    "Action": "iam:PassRole",
    "Resource": "arn:aws:iam::ACCOUNTID:role/ROLENAME"
}
]
```

Document Steps

To use this automation, follow the steps that apply to your instance type:

For new EC2 instances:

- 1. aws:executeAwsApi Retrieve the AMI ID for SQL Server 2017 on Ubuntu 16.04.
- 2. aws:runInstances Launch a new EC2 instance for Linux.
- 3. aws:waitForAwsResourceProperty Wait for the newly created EC2 instance to be ready.
- 4. aws:executeAwsApi Reboot the instance if the instance is not ready.
- 5. aws:assertAwsResourceProperty Verify that SSM Agent is installed.
- 6. aws:runCommand Run the SQL Server restore script in PowerShell.

For existing EC2 instances:

- 1. aws:waitForAwsResourceProperty Verify that the EC2 instance is ready.
- 2. aws:executeAwsApi Reboot the instance if the instance is not ready.
- 3. aws:assertAwsResourceProperty Verify that SSM Agent is installed.
- 4. aws:runCommand Run the SQL Server restore script in PowerShell.

Outputs

getInstance.InstanceId

restoreToNewInstance.Output

restoreToExistingInstance.Output

AWS-StartEC2Instance

Description

Start one or more Amazon Elastic Compute Cloud (Amazon EC2) instances.

Run this Automation (console)

Document type

Automation

AWS Systems Manager Automation runbook reference User Guide AWS-StopEC2Instance

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: StringList

Description: (Required) EC2 instances to start.

AWS-StopEC2Instance

Description

Stops one or more Amazon Elastic Compute Cloud (Amazon EC2) instances.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

InstanceId

Type: StringList

Description: (Required) EC2 instances to stop.

AWSSupport-StartEC2RescueWorkflow

Description

The AWSSupport-StartEC2RescueWorkflow runbook runs the provided base64 encoded script (Bash or Powershell) on a helper instance created to rescue your instance. The root volume of your instance is attached and mounted to the helper instance, also known as the EC2Rescue instance. If your instance is Windows, provide a Powershell script. Otherwise, use Bash. The runbook sets some environment variables which you can use in your script. The environment variables contain information about the input you provided, as well as information about the offline root volume. The offline volume is already mounted and ready to use. For example, you can save a Desired State Configuration file to an offline Windows root volume, or chroot to an offline Linux root volume and perform an offline remediation.

Run this Automation (console)

Important

Amazon EC2 instances created from Marketplace Amazon Machine Images (AMIs) are not supported by this automation.

Additional Information

To base64 encode a script, you can use either Powershell or Bash. Powershell:

[System.Convert]::ToBase64String([System.Text.Encoding]::Unicode.GetBytes([System.IO.File]::ReadAllText

Bash:

base64 PATH_TO_FILE

Here is a list of environment variables you can use in your offline scripts, depending on the target OS Windows:

Variable	Description	Example value	
\$env:EC2RESCUE_ACCOUNT_ID	{{ global:ACCOUNT_ID }}	123456789012	
\$env:EC2RESCUE_DATE	{{ global:DATE }}	2018-09-07	
\$env:EC2RESCUE_DATE_TIME	{{ global:DATE_TIME }}	2018-09-07_18.09.59	
\$env:EC2RESCUE_EC2RW_DIR	EC2Rescue for Windows installation path	C:\Program Files\Amazon \EC2Rescue	
\$env:EC2RESCUE_EC2RW_DIR	EC2Rescue for Windows installation path	C:\Program Files\Amazon \EC2Rescue	
\$env:EC2RESCUE_EXECUTION_ID	{{ automation:EXECUTION_ID }}	7ef8008e-219b-4aca-8bb5-65e2e	898e20b
\$env:EC2RESCUE_OFFLINE_CURR	E NFf<u>l</u>tt@NWR:d b <u>v</u> &Etturrent Control Set path	HKLM:\AWSTempSystem \ControlSet001	
\$env:EC2RESCUE_OFFLINE_DRIVE	Offline Windows drive letter	D:\	
\$env:EC2RESCUE_OFFLINE_EBS_E	EVIIILIEne root volume EBS device	xvdf	
\$env:EC2RESCUE_OFFLINE_KERN	EIQ MER e Windows Kernel version	6.1.7601.24214	
\$env:EC2RESCUE_OFFLINE_OS_A	RCHITEETWREOWS architecture	AMD64	

AWS Systems Manager Automation runbook reference User Guide AWSSupport-StartEC2RescueWorkflow

Variable	Description	Example value
\$env:EC2RESCUE_OFFLINE_OS_CA	A DiffOn e Windows caption	Windows Server 2008 R2 Datacenter
\$env:EC2RESCUE_OFFLINE_OS_T	PEffline Windows OS type	Server
\$env:EC2RESCUE_OFFLINE_PROG	R @M<u>li</u>គីដ រស់ n្ន ៧ស ws Program files directory path	D:\Program Files
\$env:EC2RESCUE_OFFLINE_PROG	R ଜ୍ଞଳା ଅଧି <mark>ନଧ୍ୟ ଅଧିକ ଅଧିକ ଅଧିକ ଅଧିକ ଅଧିକ ଅଧିକ ଅଧିକ ଅଧିକ</mark>	D:\Program Files (x86)
\$env:EC2RESCUE_OFFLINE_REGIS	T QYf<u>l</u>Dk RWindows registry directory path	D:\Windows\System32\config
\$env:EC2RESCUE_OFFLINE_SYSTE	N <u>O</u> fRO@TWindows system root directory path	D:\Windows
\$env:EC2RESCUE_REGION	{{ global:REGION }}	us-west-1
\$env:EC2RESCUE_S3_BUCKET	{{ S3BucketName }}	mybucket
\$env:EC2RESCUE_S3_PREFIX	{{ S3Prefix }}	myprefix/
\$env:EC2RESCUE_SOURCE_INSTA	N{{EnstanceId }}	i-abcdefgh123456789
\$script:EC2RESCUE_OFFLINE_WIN	ID บวิทีฟิลิ<u>e</u>IMSกิสโป พร Installation metadata	Customer Powershell Object

Linux:

Variable	Description	Example value	
EC2RESCUE_ACCOUNT_ID	{{ global:ACCOUNT_ID }}	123456789012	
EC2RESCUE_DATE	{{ global:DATE }}	2018-09-07	
EC2RESCUE_DATE_TIME	{{ global:DATE_TIME }}	2018-09-07_18.09.59	
EC2RESCUE_EC2RL_DIR	EC2Rescue for Linux installation path	/usr/local/ec2rl-1.1.3	
EC2RESCUE_EXECUTION_ID	{{ automation:EXECUTION_ID }}	7ef8008e-219b-4aca-8bb5-65e2e89	98e2
EC2RESCUE_OFFLINE_DEVICE	Offline device name	/dev/xvdf1	
EC2RESCUE_OFFLINE_EBS_DEVIC	EOffline root volume EBS device	/dev/sdf	
EC2RESCUE_OFFLINE_SYSTEM_RC	Offline root volume mount point	/mnt/mount	
EC2RESCUE_PYTHON	Python version	python2.7	
EC2RESCUE_REGION	{{ global:REGION }}	us-west-1	
EC2RESCUE_S3_BUCKET	{{ S3BucketName }}	mybucket	
EC2RESCUE_S3_PREFIX	{{ S3Prefix }}	myprefix/	
EC2RESCUE_SOURCE_INSTANCE	{{ InstanceId }}	i-abcdefgh123456789	

AWS Systems Manager Automation runbook reference User Guide AWSSupport-StartEC2RescueWorkflow

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AMIPrefix

Type: String

Default: AWSSupport-EC2Rescue

Description: (Optional) A prefix for the backup AMI name.

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

CreatePostEC2RescueBackup

Type: String

Valid values: true | false

Default: false

Description: (Optional) Set it to true to create an AMI of InstanceId after running the script, before starting it. The AMI will persist after the automation completes. It is your responsibility to secure access to the AMI, or to delete it.

CreatePreEC2RescueBackup

Type: String

Valid values: true | false

Default: false

Description: (Optional) Set it to true to create an AMI of InstanceId before running the script. The AMI will persist after the automation completes. It is your responsibility to secure access to the AMI, or to delete it.

EC2RescueInstanceType

Type: String

Valid values: t2.small | t2.medium | t2.large

Default: t2.small

Description: (Optional) The EC2 instance type for the EC2Rescue instance.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-StartEC2RescueWorkflow

Instanceld

Type: String

Description: (Required) ID of your EC2 instance. IMPORTANT: AWS Systems Manager Automation stops this instance. Data stored in instance store volumes will be lost. The public IP address will change if you are not using an Elastic IP.

OfflineScript

Type: String

Description: (Required) Base64 encoded script to run against the helper instance. Use Bash if your source instance is Linux, and PowerShell if it is Windows.

S3BucketName

Type: String

Description: (Optional) S3 bucket name in your account where you want to upload the troubleshooting logs. Make sure the bucket policy does not grant unnecessary read/write permissions to parties that do not need access to the collected logs.

S3Prefix

Type: String

Default: AWSSupport-EC2Rescue

Description: (Optional) A prefix for the S3 logs.

SubnetId

Type: String

Default: SelectedInstanceSubnet

Description: (Optional) The subnet ID for the EC2Rescue instance. By default, the same subnet where the provided instance resides is used. IMPORTANT: If you provide a custom subnet, it must be in the same Availability Zone as InstanceId, and it must allow access to the SSM endpoints.

Uniqueld

Type: String

Default: {{ automation:EXECUTION_ID }}

Description: (Optional) A unique identifier for the automation.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

It is recommended the user who runs the automation have the **AmazonSSMAutomationRole** IAM managed policy attached. In addition to that policy, the user must have:

```
"Resource": "arn:aws:lambda:*:An-AWS-Account-
ID: function: AWSSupport-EC2Rescue-*",
                           "Effect": "Allow"
                       },
                           "Action": [
                              "s3:GetObject",
                              "s3:GetObjectVersion"
                           ],
                           "Resource": [
                              "arn:aws:s3:::awssupport-ssm.*/*.template",
                              "arn:aws:s3:::awssupport-ssm.*/*.zip"
                           ],
                           "Effect": "Allow"
                        },
                           "Action": [
                              "iam:CreateRole",
                              "iam:CreateInstanceProfile",
                              "iam:GetRole",
                              "iam:GetInstanceProfile",
                              "iam:PutRolePolicy",
                              "iam:DetachRolePolicy",
                              "iam:AttachRolePolicy",
                              "iam:PassRole",
                              "iam:AddRoleToInstanceProfile",
                              "iam:RemoveRoleFromInstanceProfile",
                              "iam:DeleteRole",
                              "iam:DeleteRolePolicy",
                              "iam:DeleteInstanceProfile"
                          ],
                           "Resource": [
                              "arn:aws:iam::An-AWS-Account-ID:role/AWSSupport-EC2Rescue-*",
                              "arn:aws:iam::An-AWS-Account-ID:instance-profile/AWSSupport-
EC2Rescue-*"
                           ],
                           "Effect": "Allow"
                       },
                           "Action": [
                              "lambda:CreateFunction",
                              "ec2:CreateVpc",
                              "ec2:ModifyVpcAttribute",
                              "ec2:DeleteVpc",
                              "ec2:CreateInternetGateway",
                              "ec2:AttachInternetGateway",
                              "ec2:DetachInternetGateway",
                              "ec2:DeleteInternetGateway",
                              "ec2:CreateSubnet",
                              "ec2:DeleteSubnet",
                              "ec2:CreateRoute",
                              "ec2:DeleteRoute",
                              "ec2:CreateRouteTable",
                              "ec2:AssociateRouteTable",
                              "ec2:DisassociateRouteTable",
                              "ec2:DeleteRouteTable",
                              "ec2:CreateVpcEndpoint",
                              "ec2:DeleteVpcEndpoints",
                              "ec2:ModifyVpcEndpoint",
                              "ec2:Describe*"
                           "Resource": "*",
                           "Effect": "Allow"
                       }
                    ]
```

AWS Systems Manager Automation runbook reference User Guide AWSSupport-StartEC2RescueWorkflow

}

Document Steps

- 1. aws:executeAwsApi Describe the provided instance
- 2. aws:executeAwsApi Describe the provided instance's root volume
- 3. aws:assertAwsResourceProperty Check the root volume device type is EBS
- 4. aws:assertAwsResourceProperty Check the root volume is not encrypted
- 5. aws:assertAwsResourceProperty Check the provide subnet ID
 - a. (Use current instance subnet) If *SubnetId = SelectedInstanceSubnet* then run aws:createStack to deploy the EC2Rescue CloudFormation stack
 - b. (Create new VPC) If *SubnetId = CreateNewVPC* then run aws:createStack to deploy the EC2Rescue CloudFormation stack
 - c. (Use custom subnet) In all other cases:

aws:assertAwsResourceProperty - Check the provided subnet is in the same Availability Zone
as the provided instance

aws:createStack - Deploy the EC2Rescue CloudFormation stack

- 6. aws:invokeLambdaFunction Perform additional input validation
- 7. aws:executeAwsApi Update the EC2Rescue CloudFormation stack to create the EC2Rescue helper instance
- 8. aws:waitForAwsResourceProperty Wait for the EC2Rescue CloudFormation stack update to complete
- aws:executeAwsApi Describe the EC2Rescue CloudFormation stack output to obtain the EC2Rescue helper instance ID

10aws:waitForAwsResourceProperty - Wait for the EC2Rescue helper instance to become a managed instance

11aws:changeInstanceState - Stop the provided instance

12aws:changeInstanceState - Stop the provided instance

13aws:changeInstanceState - Force stop the provided instance

14aws:assertAwsResourceProperty - Check the CreatePreEC2RescueBackup input value

- a. (Create pre-EC2Rescue backup) If *CreatePreEC2RescueBackup = true*
- b. aws:executeAwsApi Create an AMI backup of the provided instance
- c. aws:createTags Tag the AMI backup

15aws:runCommand - Install EC2Rescue on the EC2Rescue helper instance

16aws:executeAwsApi - Detach the root volume from the provided instance

17aws:assertAwsResourceProperty - Check the provided instance platform

a. (Instance is Windows):

aws:executeAwsApi - Attach the root volume to the EC2Rescue helper instance as *xvdf*

aws:sleep - Sleep 10 seconds

aws:runCommand - Run the provided offline script in Powershell

b. (Instance is Linux):

aws:executeAwsApi - Attach the root volume to the EC2Rescue helper instance as */dev/sdf*

aws:sleep - Sleep 10 seconds

aws:runCommand - Run the provided offline script in Bash

AWS Systems Manager Automation runbook reference User Guide AWS-TerminateEC2Instance

18aws:changeInstanceState - Stop the EC2Rescue helper instance

19aws:changeInstanceState - Force stop the EC2Rescue helper instance

20aws:executeAwsApi - Detach the root volume from the EC2Rescue helper instance

21aws:executeAwsApi - Attach the root volume back to the provided instance

22aws:assertAwsResourceProperty - Check the CreatePostEC2RescueBackup input value

a. (Create post-EC2Rescue backup) - If *CreatePostEC2RescueBackup = true*

b. aws:executeAwsApi - Create an AMI backup of the provided instance

c. aws:createTags - Tag the AMI backup

23aws:executeAwsApi - Restore the initial delete on termination state for the root volume of the provided instance

24aws:changeInstanceState - Restore the initial state of the provided instance (running/stopped)

25aws:deleteStack - Delete the EC2Rescue CloudFormation stack

Outputs

runScriptForLinux.Output

runScriptForWindows.Output

preScriptBackup.ImageId

postScriptBackup.ImageId

AWS-TerminateEC2Instance

Description

Terminate one or more Amazon Elastic Compute Cloud (Amazon EC2) instances.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

InstanceId

Type: StringList

Description: (Required) IDs of one or more EC2 instances to terminate.

AWSPremiumSupport-TroubleshootEC2DiskUsage

Description

The AWSPremiumSupport-TroubleshootEC2DiskUsage runbook helps you investigate and potentially remediate issues with Amazon Elastic Compute Cloud (Amazon EC2) instance root and non-root disk usage. If possible, the runbook attempts to remediate issues by extending the volume and its file system. To perform these tasks, this runbook orchestrates the execution of several runbooks based on the operating system of the affected instance.

The first runbook, AWSPremiumSupport-DiagnoseDiskUsageOnWindows or AWSPremiumSupport-DiagnoseDiskUsageOnLinux, determines if disk issues can be mitigated by expanding the volume.

The second runbook, AWSPremiumSupport-ExtendVolumesOnWindows or AWSPremiumSupport-ExtendVolumesOnLinux, uses the output of the first runbook to run Python code that modifies the volume. After the volume has been modified, the runbook extends the partition and file system of the affected volumes.

Important

Access to AWSPremiumSupport-* runbooks requires an Enterprise or Business Support Subscription. For more information, see Compare AWS Support Plans.

This document was built in collaboration with AWS Managed Services (AMS). AMS helps you manage your AWS infrastructure more efficiently and securely. AMS also provides operational flexibility, enhanced security and compliance, capacity optimization, and cost-savings identification. For more information, see AWS Managed Services.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, Windows

Parameters

InstanceId

Type: String

Allowed values: ^i-[a-z0-9]{8,17}\$

Description: (Required) ID of your Amazon EC2 instance.

VolumeExpansionEnabled

Type: Boolean

Description: (Optional) Flag to control whether the document will extend the volumes and partitions affected.

Default: true

VolumeExpansionUsageTrigger

AWS Systems Manager Automation runbook reference User Guide

AWSPremiumSupport-TroubleshootEC2DiskUsage

Type: String

Description: (Optional) Minimum usage of partition space required to trigger extension (in percentage).

Allowed values: ^[0-9]{1,2}\$

Default: 85

VolumeExpansionCapSize

Type: String

Description: (Optional) Maximum size that the Amazon Elastic Block Store (Amazon EBS) volume will

be increased to (in GiB).

Allowed values: ^[0-9]{1,4}\$

Default: 2048

VolumeExpansionGibIncrease

Type: String

Description: (Optional) Increase in GiB of the volume. The biggest net increase between VolumeExpansionGibIncrease and VolumeExpansionPercentageIncrease will be used.

Allowed values: ^[0-9]{1,4}\$

Default: 20

VolumeExpansionPercentageIncrease

Type: String

Description: (Optional) Increase in percentage of the volume. The biggest net increase between VolumeExpansionGibIncrease and VolumeExpansionPercentageIncrease will be used.

Allowed values: ^[0-9]{1,2}\$

Default: 20

· AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ec2:DescribeVolumes
- ec2:DescribeVolumesModifications
- ec2:ModifyVolume
- ec2:DescribeInstances
- ec2:CreateImage
- ec2:DescribeImages

AWSPremiumSupport-TroubleshootEC2DiskUsage

- ec2:DescribeTags
- ec2:CreateTags
- ec2:DeleteTags
- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:DescribeAutomationStepExecutions
- ssm:DescribeAutomationExecutions
- ssm:SendCommand
- ssm:DescribeInstanceInformation
- ssm:ListCommands
- ssm:ListCommandInvocations

Document Steps

- 1. aws:assertAwsResourceProperty Check if the instance is managed by Systems Manager
- 2. aws:executeAwsApi Describes the instance to get the platform.
- 3. aws:branch Branches automation based on the instance's platform.
 - a. If the instance is Windows:
 - i. aws:executeAutomation Run the AWSPremiumSupport-DiagnoseDiskUsageOnWindows runbook in order to diagnose disk usage issues on the instance.
 - ii. aws:executeAwsApi Gets the output of the previous automation.
 - iii. aws:branch Branches based on the output of the diagnostics, and if there are volumes that can be expanded to mitigate the alert.
 - A. There are no volumes that need to be expanded: End the automation.
 - B. There are volumes that need to be expanded:
 - I. aws:executeAwsApi Create an Amazon Machine Image (AMI) of the instance.
 - II. aws:waitForAwsResourceProperty Waits for the AMI state to be available.
 - III. aws:executeAutomation Run the AWSPremiumSupport-ExtendVolumesOnWindows runbook in order to perform the volume modification as well as the required steps in the operating system (OS) to make the new space available.
 - b. (Platform is not windows) If the input instance is not Windows:
 - i. aws:executeAutomation Run the AWSPremiumSupport-DiagnoseDiskUsageOnLinux runbook in order to diagnose disk usage issues on the instance.
 - ii. aws:executeAwsApi Gets the output of the previous automation.
 - iii. aws:branch Branches based on the output of the diagnostics, and if there are volumes that can be expanded to mitigate the alert.
 - A. There are no volumes that need to be expanded: End the automation.
 - B. There are volumes that need to be expanded:
 - I. aws:executeAwsApi Create an AMI of the instance.
 - II. aws:waitForAwsResourceProperty Waits for AMI state to be available.
 - III. aws: executeAutomation Run the AWSPremiumSupport-ExtendVolumesOnLinux runbook in order to perform the volume modification as well as the required steps in the OS to make the new space available.

Outputs

diagnoseDiskUsageAlertOnWindows.Output

extend Volumes On Windows. Output

diagnoseDiskUsageAlertOnLinux.Output

extendVolumesOnLinux.Output

BackupAMILinux.ImageId

BackupAMIWindows.ImageId

AWSSupport-TroubleshootRDP

Description

The AWSSupport-TroubleshootRDP runbook allows the user to check or modify common settings on the target instance which may impact Remote Desktop Protocol (RDP) connections, such as the RDP port, Network Layer Authentication (NLA) and Windows Firewall profiles. Optionally, changes can be applied offline by stopping and starting the instance, if the user explicitly allows for offline remediation. By default, the runbook reads and outputs the values of the settings.

Important

Changes to the RDP settings, RDP service and Windows Firewall profiles should be carefully reviewed before using this runbook.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Windows

Parameters

Action

Type: String

Valid values: CheckAll | FixAll | Custom

Default: Custom

Description: (Optional) [Custom] Use the values from Firewall, RDPServiceStartupType, RDPServiceAction, RDPPortAction, NLASettingAction and RemoteConnections to manage the settings. [CheckAll] Read the values of the settings without changing them. [FixAll] Restore RDP default settings, and disable the Windows Firewall.

AllowOffline

Type: String

Valid values: true | false

Default: false

Description: (Optional) Fix only - Set it to true if you allow an offline RDP remediation in case the online troubleshooting fails, or the provided instance is not a managed instance. Note: For the

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootRDP

offline remediation, SSM Automation stops the instance, and creates an AMI before attempting any operations.

• AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Firewall

Type: String

Valid values: Check | Disable

Default: Check

Description: (Optional) Check or disable the Windows firewall (all profiles).

Instanceld

Type: String

Description: (Required) The ID of the instance to troubleshoot the RDP settings of.

NLASettingAction

Type: String

Valid values: Check | Disable

Default: Check

Description: (Optional) Check or disable Network Layer Authentication (NLA).

RDPPortAction

Type: String

Valid values: Check | Modify

Default: Check

Description: (Optional) Check the current port used for RDP connections, or modify the RDP port back to 3389 and restart the service.

RDPServiceAction

Type: String

Valid values: Check | Start | Restart | Force-Restart

Default: Check

Description: (Optional) Check, start, restart, or force-restart the RDP service (TermService).

• RDPServiceStartupType

Type: String

Valid values: Check | Auto

Default: Check

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootRDP

Description: (Optional) Check or set the RDP service to automatically start when Windows boots.

RemoteConnections

Type: String

Valid values: Check | Enable

Default: Check

Description: (Optional) An action to perform on the fDenyTSConnections setting: Check, Enable.

S3BucketName

Type: String

Description: (Optional) Offline only - S3 bucket name in your account where you want to upload the troubleshooting logs. Make sure the bucket policy does not grant unnecessary read/write permissions to parties that do not need access to the collected logs.

SubnetId

Type: String

Default: SelectedInstanceSubnet

Description: (Optional) Offline only - The subnet ID for the EC2Rescue instance used to perform the offline troubleshooting. If no subnet ID is specified, AWS Systems Manager Automation will create a new VPC. IMPORTANT: The subnet must be in the same Availability Zone as InstanceId, and it must allow access to the SSM endpoints.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

It is recommended that the EC2 instance receiving the command has an IAM role with the AmazonSSMManagedInstanceCore Amazon managed policy attached. For the online remediation, the user must have at least ssm:DescribeInstanceInformation, ssm:StartAutomationExecution and ssm:SendCommand to run the automation and send the command to the instance, plus ssm:GetAutomationExecution to be able to read the automation output. For the offline remediation, the user must have at least ssm:DescribeInstanceInformation, ssm:StartAutomationExecution, ec2:DescribeInstances, plus ssm:GetAutomationExecution to be able to read the automation output. AWSSupport-TroubleshootRDP calls AWSSupport-ExecuteEC2Rescue to perform the offline remediation - please review the permissions for AWSSupport-ExecuteEC2Rescue to ensure you can run the automation successfully.

Document Steps

- 1. aws:assertAwsResourceProperty Check if the instance is a Windows Server instance
- 2. aws:assertAwsResourceProperty Check if the instance is a managed instance
- 3. (Online troubleshooting) If the instance is a managed instance, then:
 - a. aws:assertAwsResourceProperty Check the provided Action value
 - b. (Online check) If the Action = CheckAll, then:

aws:runPowerShellScript - Runs the PowerShell script to get the Windows Firewall profiles status.

 ${\tt aws:executeAutomation-Calls\ AWSSupport-ManageWindowsService\ to\ get\ the\ RDP\ service\ status.}$

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootRDP

aws:executeAutomation - Calls AWSSupport-ManageRDPSettings to get the RDP settings.

c. (Online fix) If the Action = FixAll, then:

aws:runPowerShellScript - Runs the PowerShell script to disable all Windows Firewall profiles.

aws:executeAutomation - Calls AWSSupport-ManageWindowsService to start the RDP service.

aws:executeAutomation - Calls AWSSupport-ManageRDPSettings to enable remote connections and disable NLA.

d. (Online management) If the Action = Custom, then:

aws:runPowerShellScript - Runs the PowerShell script to manage the Windows Firewall
profiles.

 ${\tt aws:executeAutomation-Calls\ AWSSupport-ManageWindowsService\ to\ manage\ the\ RDP\ service.}$

aws:executeAutomation - Calls AWSSupport-ManageRDPSettings to manage the RDP settings.

- 4. (Offline remediation) If the instance is not a managed instance then:
 - a. aws:assertAwsResourceProperty Assert AllowOffline = true
 - b. aws:assertAwsResourceProperty Assert Action = FixAll
 - c. aws:assertAwsResourceProperty Assert the value of SubnetId

(Use the provided instance's subnet) If SubnetId is SELECTED_INSTANCE_SUBNET

aws:executeAwsApi - Retrieve the current instance's subnet.

aws:executeAutomation - Run AWSSupport-ExecuteEC2Rescue with provided instance's subnet.

d. (Use the provided custom subnet) If SubnetId is not SELECTED_INSTANCE_SUBNET

 ${\tt aws:executeAutomation-Run\,AWSSupport-ExecuteEC2Rescue\,with\,provided\,SubnetId\,value.}$

Outputs

manageFirewallProfiles.Output

manageRDPServiceSettings.Output

manageRDPSettings.Output

checkFirewallProfiles.Output

checkRDPServiceSettings.Output

checkRDPSettings.Output

disableFirewallProfiles.Output

restore Default RDP Service Settings. Output

restoreDefaultRDPSettings.Output

troubleshootRDPOffline.Output

trouble shoot RDPOffline With Subnet Id. Output

AWSSupport-TroubleshootSSH

Description

The AWSSupport-TroubleshootSSH runbook installs the Amazon EC2Rescue tool for Linux, and then uses the EC2Rescue tool to check or attempt to fix common issues that prevent a remote connection to the Linux machine via SSH. Optionally, changes can be applied offline by stopping and starting the instance, if the user explicitly allows for offline remediation. By default, the runbook operates in read-only mode.

Run this Automation (console)

For information about working with the AWSSupport-TroubleshootSSH runbook, see this AWSSupport-TroubleshootSSH troubleshooting topic from AWS Premium Support.

Document type

Automation

Owner

Amazon

Platforms

Linux

Parameters

Action

Type: String

Valid values: CheckAll | FixAll

Default: CheckAll

Description: (Required) Specify whether to check for issues without fixing them or to check and automatically fix any discovered issues.

· AllowOffline

Type: String

Valid values: true | false

Default: false

Description: (Optional) Fix only - Set it to true if you allow an offline SSH remediation in case the online troubleshooting fails, or the provided instance is not a managed instance. Note: For the offline remediation, SSM Automation stops the instance, and creates an AMI before attempting any operations.

· AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootSSH

behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) ID of your EC2 instance for Linux.

S3BucketName

Type: String

Description: (Optional) Offline only - S3 bucket name in your account where you want to upload the troubleshooting logs. Make sure the bucket policy does not grant unnecessary read/write permissions to parties that do not need access to the collected logs.

SubnetId

Type: String

Default: SelectedInstanceSubnet

Description: (Optional) Offline only - The subnet ID for the EC2Rescue instance used to perform the offline troubleshooting. If no subnet ID is specified, AWS Systems Manager Automation will create a new VPC.

Important

The subnet must be in the same Availability Zone as InstanceId, and it must allow access to the SSM endpoints.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

It is recommended that the EC2 instance receiving the command has an IAM role with the AmazonSSMManagedInstanceCore Amazon managed policy attached. For the online remediation, the user must have at least ssm:DescribeInstanceInformation, ssm:StartAutomationExecution and ssm:SendCommand to run the automation and send the command to the instance, plus ssm:GetAutomationExecution to be able to read the automation output. For the offline remediation, the user must have at least ssm:DescribeInstanceInformation, ssm:StartAutomationExecution, ec2:DescribeInstances, plus ssm:GetAutomationExecution to be able to read the automation output. AWSSupport-TroubleshootSSH calls AWSSupport-ExecuteEC2Rescue to perform the offline remediation - please review the permissions for AWSSupport-ExecuteEC2Rescue to ensure you can run the automation successfully.

Document Steps

- 1. aws:assertAwsResourceProperty Check if the instance is a managed instance
 - a. (Online remediation) If the instance is a managed instance, then:
 - i. aws:configurePackage Install EC2Rescue for Linux via AWS-ConfigureAWSPackage.
 - ii. aws:runCommand Run the bash script to run EC2Rescue for Linux.
 - b. (Offline remediation) If the instance is not a managed instance then:
 - i. aws:assertAwsResourceProperty Assert AllowOffline = true
 - ii. aws:assertAwsResourceProperty Assert Action = FixAll
 - iii.aws:assertAwsResourceProperty Assert the value of SubnetId
 - iv. (Use the provided instance's subnet) If SubnetId is SelectedInstanceSubnet us aws:executeAutomation to run AWSSupport-ExecuteEC2Rescue with provided instance's subnet.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootSUSERegistration

v. (Use the provided custom subnet) If SubnetId is not SelectedInstanceSubnet use aws:executeAutomation to run AWSSupport-ExecuteEC2Rescue with provided SubnetId

Outputs

troubleshootSSH.Output

troubleshootSSHOffline.Output

troubleshootSSHOfflineWithSubnetId.Output

AWSSupport-TroubleshootSUSERegistration

Description

The AWSSupport-TroubleshootSUSERegistration runbook helps you to identify why registering an Amazon Elastic Compute Cloud (Amazon EC2) SUSE Linux Enterprise Server instance with SUSE Update Infrastructure failed. The automation output provides steps to resolve, or helps you troubleshoot, the issue. If the instance passes all checks during the automation, the instance is registered with SUSE Update Infrastructure.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) The ID of the Amazon EC2 instance you want to troubleshoot.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

• ssm:StartAutomationExecution

AWS Systems Manager Automation runbook reference User Guide AWS-UpdateLinuxAmi

- ssm:DescribeInstanceProperties
- ssm:DescribeInstanceInformation
- ssm:ListCommandInvocations
- ssm:SendCommand
- ssm:ListCommands

Document Steps

- aws:assertAwsResourceProperty Checks if the Amazon EC2 instance is managed by AWS Systems Manager.
- aws:runCommand Checks if the Amazon EC2 instance platform is SLES.
- aws:runCommand Checks if the package cloud-regionsrv-client version is greater than or equal to the required version 9.0.10.
- aws:runCommand Checks if the symbolic link for base product is broken, and fixes the link it it is broken.
- aws:runCommand Checks if the hosts file (/etc/hosts) contains records for smt-ec2-suscloud.net. The automation removes any duplicate entries.
- aws:runCommand Checks if the curl command is installed.
- aws:runCommand Checks if the Amazon EC2 instance can access the Instance Metadata Service (IMDS) address 169.254.169.254.
- aws:runCommand Checks if the Amazon EC2 instance has a billing code or AWS Marketplace product code.
- aws:runCommand Checks if the Amazon EC2 instance can reach at least 1 regional server over HTTPS.
- aws:runCommand Checks if the Amazon EC2 instance can reach the Subscription Management Tool (SMT) servers over HTTP.
- aws:runCommand Checks if the Amazon EC2 instance can reach the Subscription Management Tool (SMT) servers over HTTPS.
- aws:runCommand Checks if the Amazon EC2 instance can reach the smt-ec2.susecloud.net address over HTTPS.
- aws:runCommand Registers the Amazon EC2 instance with SUSE Update Infrastructure.
- aws:executeScript Gathers and outputs the output of all the previous steps.

AWS-UpdateLinuxAmi

Description

Update an Amazon Machine Image (AMI) with Linux distribution packages and Amazon software.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

AWS Systems Manager Automation runbook reference User Guide AWS-UpdateLinuxAmi

Linux, macOS, Windows

Parameters

· AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ExcludePackages

Type: String

Default: none

Description: (Optional) Names of packages to hold back from updates, under all conditions. By default ("none"), no package is excluded.

IamInstanceProfileName

Type: String

Default: ManagedInstanceProfile

Description: (Required) The instance profile that enables Systems Manager to manage the instance.

IncludePackages

Type: String

Default: all

Description: (Optional) Only update these named packages. By default ("all"), all available updates are applied.

InstanceType

Type: String

Default: t2.micro

Description: (Optional) Type of instance to launch as the workspace host. Instance types vary by Region.

PostUpdateScript

Type: String

Default: none

Description: (Optional) URL of a script to run after package updates are applied. Default ("none") is to not run a script.

PreUpdateScript

Type: String

Default: none

Description: (Optional) URL of a script to run before updates are applied. Default ("none") is to not run a script.

AWS Systems Manager Automation runbook reference User Guide AWS-UpdateWindowsAmi

SourceAmild

Type: String

Description: (Required) The source Amazon Machine Image ID.

SubnetId

Type: String

Description: (Optional) The ID of the subnet you want to launch the instance into. If you have deleted your default VPC, this parameter is required.

TargetAmiName

Type: String

Default: UpdateLinuxAmi_from_{{SourceAmild}}_on_{{global:DATE_TIME}}

Description: (Optional) The name of the new AMI that will be created. Default is a system-generated string including the source AMI id, and the creation time and date.

AWS-UpdateWindowsAmi

Description

Update a Microsoft Windows Amazon Machine Image (AMI). By default, this runbook installs all Windows updates, Amazon software, and Amazon drivers. It then runs Sysprep to create a new AMI. Supports Windows Server 2008 R2 or later.

Important

If your instances connect to AWS Systems Manager using VPC endpoints, this runbook will fail unless used in the us-east-1 Region.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Categories

Type: String

AWS Systems Manager Automation runbook reference User Guide AWS-UpdateWindowsAmi

Description: (Optional) Specify one or more update categories. You can filter categories using commaseparated values. Options: Application, Connectors, CriticalUpdates, DefinitionUpdates, DeveloperKits, Drivers, FeaturePacks, Guidance, Microsoft, SecurityUpdates, ServicePacks, Tools, UpdateRollups, Updates. Valid formats include a single entry, for example: CriticalUpdates. Or you can specify a comma separated list: CriticalUpdates, SecurityUpdates. NOTE: There cannot be any spaces around the commas.

ExcludeKbs

Type: String

Description: (Optional) Specify one or more Microsoft Knowledge Base (KB) article IDs to exclude. You can exclude multiple IDs using comma-separated values. Valid formats: KB9876543 or 9876543.

IamInstanceProfileName

Type: String

Default: ManagedInstanceProfile

Description: (Required) The name of the role that enables Systems Manager to manage the instance.

IncludeKbs

Type: String

Description: (Optional) Specify one or more Microsoft Knowledge Base (KB) article IDs to include. You can install multiple IDs using comma-separated values. Valid formats: KB9876543 or 9876543.

InstanceType

Type: String

Default: t2.medium

Description: (Optional) Type of instance to launch as the workspace host. Instance types vary by region. Default is t2.medium.

PostUpdateScript

Type: String

Description: (Optional) A script provided as a string. It will run after installing OS updates.

PreUpdateScript

Type: String

Description: (Optional) A script provided as a string. It will run prior to installing OS updates.

• PublishedDateAfter

Type: String

Description: (Optional) Specify the date that the updates should be published after. For example, if 01/01/2017 is specified, any updates that were found during the Windows Update search that have been published on or after 01/01/2017 will be returned.

PublishedDateBefore

Type: String

Description: (Optional) Specify the date that the updates should be published before. For example, if 01/01/2017 is specified, any updates that were found during the Windows Update search that have been published on or before 01/01/2017 will be returned.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-UpgradeWindowsAWSDrivers

· PublishedDaysOld

Type: String

Description: (Optional) Specify the amount of days old the updates must be from the published date. For example, if 10 is specified, any updates that were found during the Windows Update search that have been published 10 or more days ago will be returned.

· SeverityLevels

Type: String

Description: (Optional) Specify one or more MSRC severity levels associated with an update. You can filter severity levels using comma-separated values. By default patches for all security levels are selected. If value supplied, the update list is filtered by those values. Options: Critical, Important, Low, Moderate or Unspecified. Valid formats include a single entry, for example: Critical. Or, you can specify a comma separated list: Critical, Important, Low.

SourceAmild

Type: String

Description: (Required) The source Amazon Machine Image ID.

SubnetId

Type: String

Description: (Optional) The ID of the subnet you want to launch the instance into. If you have deleted your default VPC, this parameter is required.

TargetAmiName

Type: String

Default: UpdateWindowsAmi_from_{{SourceAmild}}_on_{{global:DATE_TIME}}

Description: (Optional) The name of the new AMI that will be created. Default is a system-generated string including the source AMI id, and the creation time and date.

AWSSupport-UpgradeWindowsAWSDrivers

Description

The AWSSupport-UpgradeWindowsAWSDrivers runbook upgrades or repairs storage and network AWS drivers on the specified EC2 instance. The runbook attempts to install the latest versions of AWS drivers online by calling SSM Agent. If SSM Agent is not contactable, the runbook can perform an offline installation of the AWS drivers if explicitly requested.

Note

Both the online and offline upgrade will create an AMI before attempting any operations, which will persist after the automation completes. It is your responsibility to secure access to the AMI, or to delete it. The online method restarts the instance as part of the upgrade process, while the offline method requires the provided EC2 instance be stopped and then started.

Important

If your instances connect to AWS Systems Manager using VPC endpoints, this runbook will fail unless used in the us-east-1 Region. This runbook will also fail on a domain controller. To update AWS PV drivers on a domain controller, see Upgrade a Domain Controller (AWS PV Upgrade).

Run this Automation (console)

Document type

AWS Systems Manager Automation runbook reference User Guide AWSSupport-UpgradeWindowsAWSDrivers

ΔΠ	t∩r	mati	ınn

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AllowOffline

Type: String

Valid values: true | false

Default: false

Description: (Optional) Set it to true if you allow an offline drivers upgrade in case the online installation cannot be performed. Note: The offline method requires the provided EC2 instance be stopped and then started. Data stored in instance store volumes will be lost. The public IP address will change if you are not using an Elastic IP.

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ForceUpgrade

Type: String

Valid values: true | false

Default: false

Description: (Optional) Offline only - Set it to true if you allow the offline drivers upgrade to proceed even though your instance already has the latest drivers installed.

Instanceld

Type: String

Description: (Required) ID of your EC2 instance for Windows Server.

SubnetId

Type: String

Default: SelectedInstanceSubnet

Description: (Optional) Offline only - The subnet ID for the EC2Rescue instance used to perform the offline drivers upgrade. If no subnet ID is specified, Systems Manager Automation will create a new VPC.

Important

The subnet must be in the same Availability Zone as InstanceId, and it must allow access to the SSM endpoints.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-UpgradeWindowsAWSDrivers

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

The EC2 instance receiving the command must at minimum have an IAM role that includes permissions for ssm:StartAutomationExecution and ssm:SendCommand to run the automation and send the command to the instance, plus ssm:GetAutomationExecution to be able to read the automation output. You can attach the AmazonSSMManagedInstanceCore Amazon managed policy to your IAM role to provide these permissions. We recommend, however, using the Automation IAM role AmazonSSMAutomationRole for this purpose. For more information, see Use IAM to configure roles for Automation.

If you are performing an offline upgrade, see the permissions required by AWSSupport-StartEC2RescueWorkflow (p. 105).

Document Steps

- 1. aws:assertAwsResourceProperty Verifies the input instance is Windows.
- 2. aws:assertAwsResourceProperty Verifies the input instance is a managed instance. If so, the online upgrade starts, otherwise the offline upgrade is evaluated.
 - a. (Online upgrade) If the input instance is a managed instance:
 - i. aws:createImage Creates an AMI backup.
 - ii. aws:createTags Tags the AMI backup.
 - iii. aws:runCommand Installs ENA network driver via AWS-ConfigureAWSPackage.
 - iv. aws:runCommand Installs NVMe driver via AWS-ConfigureAWSPackage.
 - v. aws:runCommand Installs AWS PV driver via AWS-ConfigureAWSPackage.
 - b. (Offline upgrade) If the input instance is not a managed instance:
 - i. aws:assertAwsResourceProperty Verifies the AllowOffline flag is set to true. If so, the offline upgrade starts, otherwise the automation ends.
 - ii. aws:changeInstanceState Stop the source instance.
 - iii.aws:changeInstanceState Force-stop the source instance.
 - iv. aws:createImage Create an AMI backup of the source instance.
 - v. aws:createTags Tag the AMI backup of the source instance.
 - vi.aws:executeAwsApi Enable ENA for the instance
 - vii.aws:assertAwsResourceProperty Assert the ForceUpgrade flag.
 - viiiForce offline upgrade) If ForceUpgrade = true then run aws: executeAutomation to invoke AWSSupport-StartEC2RescueWorkflow with the drivers force upgrade script. This installs the drivers regardless of the current version that is installed
 - ix. (Offline upgrade) If ForceUpgrade = false then run aws: executeAutomation to invoke AWSSupport-StartEC2RescueWorkflow with the drivers upgrade script.

Outputs

preUpgradeBackup.ImageId

preOfflineUpgradeBackup.ImageId

installAwsEnaNetworkDriverOnInstance.Output

installAWSNVMeOnInstance.Output

installAWSPVDriverOnInstance.Output

upgradeDriversOffline.Output

forceUpgradeDriversOffline.Output

Amazon ECS

AWS Systems Manager Automation provides predefined runbooks for Amazon Elastic Container Service. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSSupport-CollectECSInstanceLogs (p. 129)
- AWS-InstallECSContainerAgent (p. 131)
- AWSSupport-TroubleshootECSContainerInstance (p. 132)
- AWS-UpdateECSContainerAgent (p. 133)

AWSSupport-CollectECSInstanceLogs

Description

The AWSSupport-CollectECSInstanceLogs runbook collects operating system and Amazon Elastic Container Service (Amazon ECS) related log files from an Amazon Elastic Compute Cloud (Amazon EC2) instance to help you troubleshoot common Amazon ECS issues. While the automation is collecting the associated log files, changes are made to the file system. These changes include the creation of temporary directories and a log directory, the copying of log files to these directories, and compressing the log files into an archive.

If you specify a value for the LogDestination parameter, the automation evaluates the policy status of the Amazon Simple Storage Service (Amazon S3) bucket you specify. To help with the security of the logs gathered from your Amazon EC2 instance, if the policy status isPublic is set to true, or if the access control list (ACL) grants READ | WRITE permissions to the All Users Amazon S3 predefined group, the logs are not uploaded. Additionally, if the provided bucket is not available in your account, the logs are not uploaded. For more information about Amazon S3 predefined groups, see Amazon S3 predefined groups in the Amazon Simple Storage Service User Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your

AWS Systems Manager Automation runbook reference User Guide AWSSupport-CollectECSInstanceLogs

behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ECSInstanceId

Type: String

Description: (Required) The ID of the instance you want to collect logs from. The instance you specify must be managed by Systems Manager.

LogDestination

Type: String

Description: (Optional) The Amazon S3 bucket in your AWS account to upload the archived logs to.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:SendCommand
- ssm:DescribeInstanceInformation

We recommend that the Amazon EC2 instance you specify in the ECSInstanceId parameter has an IAM role with the AmazonSSMManagedInstanceCore Amazon managed policy attached. To upload the log archive to the Amazon S3 bucket you specify in the LogDestination parameter, you must add following permissions:

- s3:PutObject
- s3:ListBucket
- s3:GetBucketPolicyStatus
- s3:GetBucketAcl

Document Steps

- assertInstanceIsManaged Verifies whether the instance you specify in the ECSInstanceId parameter is managed by Systems Manager.
- getInstancePlatform Gets information about the operating system (OS) platform of the instance specified in the ECSInstanceId parameter.
- verifyInstancePlatform Branches the automation based on the OS platform.
- runLogCollectionScriptOnLinux Gathers operating system and Amazon ECS related log files on Linux instances and creates an archive file in the /var/log/collectECSlogs directory.
- runLogCollectionScriptOnWindows Gathers operating system and Amazon ECS related log
 files on Windows instances and creates an archive file in the C:\ProgramData\collectECSlogs
 directory.
- verifyIfS3BucketProvided Verifies whether a value was specified for the LogDestination parameter.
- runUploadScript Branches the automation step based on the OS platform.
- runUploadScriptOnLinux Uploads the log archive to the Amazon S3 bucket specified in the LogDestination parameter and deletes the archived log file from OS.
- runUploadScriptOnWindows Uploads the log archive to the Amazon S3 bucket specified in the LogDestination parameter and deletes the archived log file from OS.

AWS-InstallECSContainerAgent

Description

The AWS-InstallECSContainerAgent runbook installs the Amazon Elastic Container Service (Amazon ECS) agent on the Amazon Elastic Compute Cloud (Amazon EC2) instance you specify. This runbook only supports Amazon Linux and Amazon Linux 2 instances.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instancelds

Type: StringList

Description: (Required) The IDs of the Amazon EC2 instances you want to install the Amazon ECS agent on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:GetCommandInvocation
- ec2:DescribeImages
- ec2:DescribeInstanceAttribute
- ec2:DescribeInstances

Document Steps

aws:executeScript - Installs the Amazon ECS agent on the Amazon EC2 instances you specify in the InstanceIds parameter.

Outputs

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootECSContainerInstance

InstallAmazonECSAgent.SuccessfulInstances - The ID of the instance where installation of the Amazon ECS agent succeeded.

InstallAmazonECSAgent.FailedInstances - The ID of the instance where installation of the Amazon ECS agent failed.

InstallAmazonECSAgent.InProgressInstances - The ID of the instance where installation of the Amazon ECS agent is in progress.

AWSSupport-TroubleshootECSContainerInstance

Description

The AWSSupport-TroubleshootECSContainerInstance runbook helps you troubleshoot an Amazon Elastic Compute Cloud (Amazon EC2) instance that fails to register with an Amazon ECS cluster. This automation reviews whether the user data for the instance contains the correct cluster information, whether the instance profile contains the required permissions, and network configuration issues.

Important

To successfully run this automation, the state of your Amazon EC2 instance must be running, and the Amazon ECS cluster state must be ACTIVE.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

• AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ClusterName

Type: String

Description: (Required) The name of the Amazon ECS cluster that the instance failed to register with.

Instanceld

Type: String

Description: (Required) The ID of the Amazon EC2 instance you want to troubleshoot.

Required IAM permissions

AWS Systems Manager Automation runbook reference User Guide AWS-UpdateECSContainerAgent

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ec2:DescribeIamInstanceProfileAssociations
- ec2:DescribeInstanceAttribute
- ec2:DescribeInstances
- ec2:DescribeNetworkAcls
- ec2:DescribeRouteTables
- ec2:DescribeSecurityGroups
- ec2:DescribeSubnets
- ec2:DescribeVpcEndpoints
- ec2:DescribeVpcs
- iam:GetInstanceProfile
- iam:GetRole
- iam:SimulateCustomPolicy
- iam:SimulatePrincipalPolicy

Document Steps

aws:executeScript: Reviews whether the Amazon EC2 instance meets the prerequisites needed to register with an Amazon ECS cluster.

AWS-UpdateECSContainerAgent

Description

The AWS-UpdateECSContainerAgent runbook updates the Amazon Elastic Container Service (Amazon ECS) agent on the Amazon Elastic Compute Cloud (Amazon EC2) instance you specify. This runbook only supports Amazon Linux and Amazon Linux 2 instances.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ClusterARN

Type: StringList

AWS Systems Manager Automation runbook reference User Guide Amazon EFS

Description: (Required) The Amazon Resource Name (ARN) of the Amazon ECS cluster your container instances is registered with.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:GetCommandInvocation
- ec2:DescribeImages
- ec2:DescribeInstanceAttribute
- ec2:DescribeImage
- ec2:DescribeInstance
- ec2:DescribeInstanceAttribute
- ecs:DescribeContainerInstances
- ecs:DescribeClusters
- ecs:ListContainerInstances
- ecs:UpdateContainerAgent

Document Steps

aws:executeScript - Updates the Amazon ECS agent on the Amazon ECS cluster you specify in the ClusterARN parameters.

Outputs

UpdateAmazonECSAgent.UpdatedContainers - The ID of the instance where the update of the Amazon ECS agent succeeded.

UpdateAmazonECSAgent.FailedContainers - The ID of the instance where the update of the Amazon ECS agent failed.

UpdateAmazonECSAgent.InProgressContainers - The ID of the instance where the update of the Amazon ECS agent is in progress.

Amazon EFS

AWS Systems Manager Automation provides predefined runbooks for Amazon Elastic File System. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

AWSSupport-CheckAndMountEFS (p. 134)

AWSSupport-CheckAndMountEFS

Description

The AWSSupport-CheckAndMountEFS runbook verifies the prerequisites to mount your Amazon Elastic File System (Amazon EFS) file system and mounts the file system on the Amazon Elastic Compute Cloud

AWS Systems Manager Automation runbook reference User Guide AWSSupport-CheckAndMountEFS

(Amazon EC2) instance you specify. This runbook supports mounting your Amazon EFS file system with the DNS name, or using the mount target's IP address.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Action

Type: String

Valid values: Check | CheckAndMount

Description: (Required) Determines whether the runbook verifies prerequisites, or verifies prerequisites and mounts the file system.

EfsId

Type: String

Description: (Required) The ID of the file system you want to mount.

InstanceId

Type: String

Description: (Required) The ID of the Amazon EC2 instance on which you want to mount the file system.

MountOptions

Type: String

Description: (Optional) The options supported by the Amazon EFS mount helper that you want to use when mounting the file system. If you specify the tls option, verify stunnel has been upgraded on the target instance.

MountPoint

Type: String

Description: (Optional) The directory where you want to mount the file system. If you specify the Check value for the Action parameter, this parameter should not be specified.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-CheckAndMountEFS

MountTargetIP

Type: String

Description: (Optional) The mount target's IP address. Mounting by IP address works in environments where DNS is disabled, such as virtual private clouds (VPCs) with DNS hostnames disabled. Also, you can use this option if your environment uses a DNS provider other than Amazon Route 53 (Route 53).

Region

Type: String

Description: (Required) The AWS Region where the Amazon EC2 instance and file system are located.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:DescribeAutomationExecutions
- ssm:DescribeAutomationStepExecutions
- ssm:DescribeAutomationStepExecutions
- ssm:DescribeInstanceInformation
- ssm:DescribeInstanceProperties
- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:GetDocument
- ssm:ListCommands
- ssm:ListCommandInvocations
- ssm:ListDocuments
- ssm:StartAutomationExecution
- iam:ListRoles
- ec2:DescribeInstances
- ec2:DescribeSecurityGroups
- elasticfilesystem:DescribeFileSystemPolicy
- elasticfilesystem:DescribeMountTargets
- elasticfilesystem:DescribeMountTargetSecurityGroups
- resource-groups:*

Document Steps

- aws:executeScript Gathers details about the Amazon EC2 instance you specify in the InstanceId parameter.
- aws:executeScript Gathers details about the file system you specify in the EfsId parameter.
- aws:executeScript Verifies the security group associated with the file system allows traffic on port 2049 from the Amazon EC2 instance you specify in the InstanceId parameter.
- aws:assertAwsResourceProperty Verifies the Amazon EC2 instance you specify in the InstanceId parameter is managed by Systems Manager and that the status is Online.
- aws:branch Branches based on the value you specify for the Action parameter.
- aws:runCommand Verifies prerequisites for mounting the file system you specify in the EfsId parameter.

AWS Systems Manager Automation runbook reference User Guide Amazon EKS

• aws:runCommand - Verifies prerequisites for mounting the file system you specify in the EfsId parameter, and mounts the file system on the Amazon EC2 instance you specify in the InstanceId parameter.

Amazon EKS

AWS Systems Manager Automation provides predefined runbooks for Amazon Elastic Kubernetes Service. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSSupport-CollectEKSInstanceLogs (p. 137)
- AWS-DeleteEKSCluster (p. 138)
- AWSPremiumSupport-TroubleshootEKSCluster (p. 140)
- AWSSupport-TroubleshootEKSWorkerNode (p. 143)
- AWS-UpdateEKSManagedNodegroupVersion (p. 144)

AWSSupport-CollectEKSInstanceLogs

Description

The AWSSupport-CollectEKSInstanceLogs runbook gathers operating system and Amazon Elastic Kubernetes Service (Amazon EKS) related log files from an Amazon Elastic Compute Cloud (Amazon EC2) instance to help you troubleshoot common issues. While the automation is gathering the associated log files, changes are made to the file system structure including the creation of temporary directories, the copying of log files to the temporary directories, and compressing the log files into an archive. This activity can result in increased CPUUtilization on the EC2 instance. For more information about CPUUtilization, see Instance metrics in the Amazon CloudWatch User Guide.

If you specify a value for the LogDestination parameter, the automation evaluates the policy status of the Amazon Simple Storage Service (Amazon S3) bucket you specify. To help with the security of the logs gathered from your EC2 instance, if the policy status isPublic is set to true, or if the access control list (ACL) grants READ | WRITE permissions to the All Users Amazon S3 predefined group, the logs are not uploaded. For more information about Amazon S3 predefined groups, see Amazon S3 predefined groups in the Amazon Simple Storage Service User Guide.

Note

Linux

This automation requires at least 10 percent of available disk space on the root Amazon Elastic Block Store (Amazon EBS) volume attached to your EC2 instance. If there is not enough available disk space on the root volume, the automation stops.

available disk space on the root volume, the automation stops.
Run this Automation (console)
Document type
Automation
Owner
Amazon
Platforms

AWS Systems Manager Automation runbook reference User Guide AWS-DeleteEKSCluster

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

EKSInstanceId

Type: String

Description: (Required) ID of the Amazon EKS EC2 instance you want to collect logs from.

LogDestination

Type: String

Description: (Optional) The S3 bucket in your account to upload the archived logs to.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:SendCommand

We recommend that the EC2 instance receiving the command has an IAM role with the AmazonSSMManagedInstanceCore Amazon managed policy attached. To upload the log archive to the S3 bucket you specify in the LogDestination parameter, you must add the s3:PutObject permission.

Document Steps

- aws:assertAwsResourceProperty Confirms the operating system of the value specified in the EKSInstanceId parameter is Linux.
- aws:runCommand Gathers operating system and Amazon EKS related log files, compressing them into an archive in the /var/log directory.
- aws:branch Confirms whether a value was specified for the LogDestination parameter.
- aws:runCommand Uploads the log archive to the S3 bucket you specify in the LogDestination parameter.

AWS-DeleteEKSCluster

Description

This runbook deletes the resources associated with an Amazon EKS cluster, including node groups and Fargate profiles. Optionally, you can choose to delete all self-managed nodes, the AWS CloudFormation stacks used to create the nodes, and the VPC CloudFormation stack for your cluster. For more information about deleting a cluster, see Deleting a cluster in the Amazon EKS User Guide.

Note

If you have active services in your cluster that are associated with a load balancer, you must delete those services before deleting the cluster. If you don't, the system can't delete the load

AWS Systems Manager Automation runbook reference User Guide AWS-DeleteEKSCluster

balancers. Use the following procedure to find and delete services before you run the AWS-DeleteEKSCluster runbook.

To locate and delete services in your cluster

- 1. Install the Kubernetes command line utility, kubectl. For more information, see Installing kubectl in the Amazon EKS User Guide.
- 2. Run the following command to list all services running in your cluster.

```
kubectl get svc --all-namespaces
```

3. Run the following command to delete any services that have an associated EXTERNAL-IP value. These services are fronted by a load balancer, and you must delete them in Kubernetes to allow the load balancer and associated resources to be properly released.

```
kubectl delete svc service-name
```

You can now run the AWS-DeleteEKSCluster runbook.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

EKSClusterName

Type: String

Description: (Required) The name of the Amazon EKS Cluster to be deleted.

• VPCCloudFormationStack

Type: String

Description: (Optional) AWS CloudFormation stack name for VPC for the EKS cluster being deleted. This deletes the AWS CloudFormation stack for VPC and any resources created by the stack.

VPCCloudFormationStackRole

Type: String

AWSPremiumSupport-TroubleshootEKSCluster

Description: (Optional) The ARN of an IAM role that AWS CloudFormation assumes to delete the VPC CloudFormation stack. AWS CloudFormation uses the role's credentials to make calls on your behalf.

SelfManagedNodeStacks

Type: String

Description: (Optional) Comma-separated list of AWS CloudFormation stack names for self-managed nodes, This will delete the AWS CloudFormation stacks for self-managed nodes.

SelfManagedNodeStacksRole

Type: String

Description: (Optional) The ARN of an IAM role that AWS CloudFormation assumes to delete the Selfmanaged Node Stacks. AWS CloudFormation uses the role's credentials to make calls on your behalf.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- sts:AssumeRole
- eks:ListNodegroups
- eks:DeleteNodegroup
- eks:ListFargateProfiles
- eks:DeleteFargateProfile
- eks:DeleteCluster
- cfn:DescribeStacks
- cfn:DeleteStack

Document Steps

- aws:executeScript DeleteNodeGroups: Find and delete all node groups in the EKS cluster.
- aws:executeScript DeleteFargateProfiles: Find and delete all Fargate profiles in the EKS cluster.
- aws:executeScript DeleteSelfManagedNodes: Delete all self-managed nodes and the CloudFormation stacks used to create the nodes.
- aws:executeScript DeleteEKSCluster: Delete EKS cluster.
- aws:executeScript DeleteVPCCloudFormationStack: Delete the VPC CloudFormation stack.

AWSPremiumSupport-TroubleshootEKSCluster

Description

The AWSPremiumSupport-TroubleshootEKSCluster runbook diagnoses common issues with an Amazon Elastic Kubernetes Service (Amazon EKS) cluster, underlying infrastructure, and provides recommended remediation steps.

Important

Access to **AWSPremiumSupport-*** runbooks requires an Enterprise or Business Support Subscription. For more information, see Compare AWS Support Plans.

If you specify a value for the S3BucketName parameter, the automation evaluates the policy status of the Amazon Simple Storage Service (Amazon S3) bucket you specify. To help with the security of the logs

AWSPremiumSupport-TroubleshootEKSCluster

gathered from your EC2 instance, if the policy status isPublic is set to true, or if the access control list (ACL) grants READ | WRITE permissions to the All Users Amazon S3 predefined group, the logs are not uploaded. For more information about Amazon S3 predefined groups, see Amazon S3 predefined groups in the Amazon Simple Storage Service User Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ClusterName

Type: String

Description: (Required) The name of the Amazon EKS cluster that you want to troubleshoot.

S3BucketName

Type: String

Description: (Optional) The name of the private Amazon S3 bucket where the report generated by the runbook should be uploaded.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeInstances
- ec2:DescribeInstanceTypes
- ec2:DescribeSubnets
- ec2:DescribeSecurityGroups
- ec2:DescribeRouteTables
- ec2:DescribeNatGateways
- ec2:DescribeVpcs
- ec2:DescribeNetworkAcls

AWSPremiumSupport-TroubleshootEKSCluster

- iam:GetInstanceProfile
- iam:ListInstanceProfiles
- iam:ListAttachedRolePolicies
- eks:DescribeCluster
- eks:ListNodegroups
- eks:DescribeNodegroup
- autoscaling:DescribeAutoScalingGroups

In addition, the AWS Identity and Access Management (IAM) policy attached to the IAM user or role that starts the automation must allow the ssm:GetParameter operation to the following public AWS Systems Manager parameters to get the latest recommended Amazon EKS Amazon Machine Image (AMI) for the worker nodes.

- arn:aws:ssm:::parameter/aws/service/eks/optimized-ami/*/amazon-linux-2/recommended/image id
- arn:aws:ssm:::parameter/aws/service/ami-windows-latest/Windows_Server-2019-English-Core-EKS_Optimized-*/image_id
- arn:aws:ssm:::parameter/aws/service/ami-windows-latest/Windows_Server-2019-English-Full-EKS_Optimized-*/image_id
- arn:aws:ssm:::parameter/aws/service/ami-windows-latest/Windows_Server-1909-English-Core-EKS_Optimized-*/image_id
- arn:aws:ssm:::parameter/aws/service/eks/optimized-ami/*/amazon-linux-2-gpu/recommended/image_id

To upload the report generated by the runbook to an Amazon S3 bucket, the following permissions are required for the specified Amazon S3 bucket you specify.

- s3:GetBucketPolicyStatus
- s3:GetBucketAcl
- s3:PutObject

Document Steps

- aws:executeAwsApi Gathers details for the specified Amazon EKS cluster.
- aws:executeScript Gathers details of the Amazon Elastic Compute Cloud (Amazon EC2) instances, Auto Scaling groups, AMIs, and Amazon EC2 GPU graphic instance types.
- aws:executeScript Gathers details of the virtual private cloud (VPC), subnets, network address translation (NAT) gateways, subnet routes, security groups and network access control lists (ACLs) of the Amazon EKS cluster.
- aws:executeScript Gathers details of attached IAM instance profiles and role policies.
- aws:executeScript Gathers details of the Amazon S3 bucket you specify in the S3BucketName parameter.
- aws:executeScript Classifies the Amazon VPC subnets as public or private.
- aws:executeScript Checks the Amazon VPC subnets for tags that are required as part of an Amazon EKS cluster.
- aws:executeScript Checks the Amazon VPC subnets for the tags that are required for Elastic Load Balancing subnets.
- aws:executeScript Checks if the worker node Amazon EC2 instances use the latest Amazon EKS optimized AMIs

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootEKSWorkerNode

- aws:executeScript Checks if the Amazon VPC security groups attached to worker nodes for the tags that are required.
- aws:executeScript Checks the Amazon EKS cluster and worker node Amazon VPC security group rules for the recommended ingress rules to the Amazon EKS cluster.
- aws:executeScript Checks the Amazon EKS cluster and worker node Amazon VPC security group rules for the recommended egress rules from the Amazon EKS cluster.
- aws:executeScript Checks the network ACL configuration of the Amazon VPC subnets.
- aws:executeScript Checks if the worker node Amazon EC2 instances have the required managed policies.
- aws:executeScript Checks if the Auto Scaling groups have the necessary tags for cluster autoscaling.
- aws:executeScript Checks if the worker node Amazon EC2 instances are connected to the internet.
- aws:executeScript Generates a report based on the outputs from the previous steps. If a value
 is specified for the S3BucketName parameter, the generated report is uploaded to the Amazon S3
 bucket.

AWSSupport-TroubleshootEKSWorkerNode

Description

The AWSSupport-TroubleshootEKSWorkerNode runbook analyzes an Amazon Elastic Compute Cloud (Amazon EC2) worker node and Amazon Elastic Kubernetes Service (Amazon EKS) cluster to help you identify and troubleshoot common causes that prevent worker nodes from joining a cluster. The runbook outputs guidance to help you resolve any issues that are identified.

Important

To successfully run this automation, the state of your Amazon EC2 worker node must be running, and the Amazon EKS cluster state must be ACTIVE.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ClusterName

AWS Systems Manager Automation runbook reference User Guide AWS-UpdateEKSManagedNodegroupVersion

Type: String

Description: (Required) The name of the Amazon EKS cluster.

WorkerID

Type: String

Description: (Required) The ID of the Amazon EC2 worker node that failed to join the cluster.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ec2:DescribeDhcpOptions
- ec2:DescribeImages
- ec2:DescribeInstanceAttribute
- ec2:DescribeInstances
- ec2:DescribeInstanceStatus
- ec2:DescribeNatGateways
- ec2:DescribeNetworkAcls
- ec2:DescribeNetworkInterfaces
- ec2:DescribeRouteTables
- ec2:DescribeSecurityGroups
- ec2:DescribeSubnets
- ec2:DescribeVpcAttribute
- ec2:DescribeVpcEndpoints
- ec2:DescribeVpcs
- eks:DescribeCluster
- iam:GetInstanceProfile
- iam:GetRole
- iam:ListAttachedRolePolicies
- ssm:DescribeInstanceInformation
- ssm:ListCommandInvocations
- ssm:ListCommands
- ssm:SendCommand

Document Steps

- aws:assertAwsResourceProperty Confirms that the Amazon EKS cluster you specify in the ClusterName parameter exists and is in an ACTIVE state.
- aws:assertAwsResourceProperty Confirms that the Amazon EC2 worker node you specify in the WorkerID parameter exists and is in a running state.
- aws:executeScript Runs a Python script that helps identify possible causes for the worker node failing to join the cluster.

AWS-UpdateEKSManagedNodegroupVersion

Description

AWS Systems Manager Automation runbook reference User Guide AWS-UpdateEKSManagedNodegroupVersion

This runbook updates managed node groups in your Amazon EKS cluster to the latest AMI version. For more information about this update process, see Updating a managed node group in the Amazon EKS User Guide. We also recommend that you review the following topics before you use the AWS-UpdateEKSManagedNodegroupVersion runbook.

- · Managed node groups
- · Managed node update behavior
- UpdateNodegroupVersion

If your cluster uses autoscaling, scale the deployment down to zero replicas to avoid conflicting scaling actions.

To scale a deployment to zero replicas

- Install the Kubernetes command line utility, kubect1. For more information, see Installing kubectl
 in the Amazon EKS User Guide.
- 2. Run the following command.

```
kubectl scale deployments/cluster-autoscaler --replicas=0 -n kube-system
```

- 3. Run the AWS-UpdateEKSManagedNodegroupVersion runbook.
- 4. Scale the deployment back to the desired number of replicas by running the following command.

kubectl scale deployments/cluster-autoscaler --replicas=number -n kube-system

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ClusterName

Type: String

Description: (Required) The name of the Amazon EKS cluster.

NodeGroupName

AWS Systems Manager Automation runbook reference User Guide Elastic Beanstalk

Type: String

Description: (Required) The name of the managed node group.

LaunchTemplateVersion

Type: String

Description: (Optional) The Amazon Elastic Compute Cloud (Amazon EC2) launch template version. This parameter is only valid if a node group was created from a launch template.

ForceUpgrade

Type: Boolean

Description: (Optional) If true, the update won't fail in response to a pod disruption budget violation.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- eks:DescribeNodegroup
- eks:UpdateNodegroupVersion

Document Steps

aws:executeScript - UpdateEKSManagedNodegroupVersion: Updates the AMI version used by a managed node group in an Amazon EKS cluster.

Elastic Beanstalk

AWS Systems Manager Automation provides predefined runbooks for AWS Elastic Beanstalk. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSSupport-CollectElasticBeanstalkLogs (p. 146)
- AWSConfigRemediation-EnableElasticBeanstalkEnvironmentLogStreaming (p. 148)
- AWSConfigRemediation-EnableBeanstalkEnvironmentNotifications (p. 149)

AWSSupport-CollectElasticBeanstalkLogs

Description

The AWSSupport-CollectElasticBeanstalkLogs runbook gathers AWS Elastic Beanstalk related log files from an Amazon Elastic Compute Cloud (Amazon EC2) Windows Server instance launched by Elastic Beanstalk to help you troubleshoot common issues. While the automation is gathering the associated log files, changes are made to the file system structure including the creation of temporary directories, the copying of log files to the temporary directories, and compressing the log files into an archive. This activity can result in increased CPUUtilization on the Amazon EC2 instance. For more information about CPUUtilization, see Instance metrics in the Amazon CloudWatch User Guide.

If you specify a value for the S3BucketName parameter, the automation evaluates the policy status of the Amazon Simple Storage Service (Amazon S3) bucket you specify. To help with the security of the logs

AWS Systems Manager Automation runbook reference User Guide AWSSupport-CollectElasticBeanstalkLogs

gathered from your Amazon EC2 instance, if the policy status isPublic is set to true, or if the access control list (ACL) grants READ | WRITE permissions to the All Users Amazon S3 predefined group, the logs are not uploaded. For more information about Amazon S3 predefined groups, see Amazon S3 predefined groups in the Amazon Simple Storage Service User Guide.

If you do not specify a value for the S3BucketName parameter, the automation uploads the log bundle to the default Elastic Beanstalk Amazon S3 bucket in the AWS Region where you run the automation. The directory is named according to the following structure, elasticbeanstalk-region-accountID. The region and accountID values will differ based on the Region and AWS account you run the automation in. The log bundle will be saved to the resources/environments/logs/bundle/environmentID/instanceID directory. The environmentID and instanceID values will differ based on your Elastic Beanstalk environment and the Amazon EC2 instance you're gathering logs from.

By default, the AWS Identity and Access Management (IAM) instance profile attached to the Amazon EC2 instances of the Elastic Beanstalk environment has the required permissions to upload the bundle to the default Elastic Beanstalk Amazon S3 bucket for your environment. If you specify a value for the S3BucketName parameter, the instance profile attached to the Amazon EC2 instance must allow the s3:GetBucketAcl, s3:GetBucketPolicy, s3:GetBucketPolicyStatus, and s3:PutObject actions for the specified Amazon S3 bucket and path.

Note

Document type

This automation requires at least 500 MB of available disk space on the root Amazon Elastic Block Store (Amazon EBS) volume attached to your Amazon EC2 instance. If there is not enough available disk space on the root volume, the automation stops.

Run this Automation (console)

Automation	
Owner	
Amazon	

Platforms

Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

EnvironmentId

Type: String

Description: (Required) The ID of your Elastic Beanstalk environment you want to collect the log bundle from.

Instanceld

Type: String

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableElasticBeanstalkEnvironmentLogStreaming

(Required) The ID of the Amazon EC2 instance in your Elastic Beanstalk environment you want to collect the log bundle from.

S3BucketName

Type: String

(Optional) The Amazon S3 bucket you want to upload the archived logs to.

S3BucketPath

Type: String

(Optional) The Amazon S3 bucket path you want to upload the log bundle to. This parameter is ignored if you do not specify a value for the S3BucketName parameter.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:SendCommand
- ssm:DescribeInstanceInformation
- ec2:DescribeInstances

Document Steps

- aws:assertAwsResourceProperty Confirms the Amazon EC2 instance you specify in the InstanceId parameter is managed by AWS Systems Manager.
- aws:assertAwsResourceProperty Confirms the Amazon EC2 instance you specify in the InstanceId parameter is a Windows Server instance.
- aws:runCommand Checks whether the instance is part of an Elastic Beanstalk environment, if there is sufficient disk space to bundle the logs, and whether the Amazon S3 bucket to which the logs would be uploaded to is public.
- aws:runCommand Collects the log files and uploads the archive to the Amazon S3 bucket specified
 in the S3BucketName parameter or to the default bucket for your Elastic Beanstalk environment if a
 value is not specified.

AWSConfigRemediation-EnableElasticBeanstalkEnvironmentLogStreaming

Description

The AWSConfigRemediation-EnableElasticBeanstalkEnvironmentLogStreaming runbook enables logging on the AWS Elastic Beanstalk (Elastic Beanstalk) environment you specify.

Run this Automation (console)

Document type

Automation

Owner

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableBeanstalkEnvironmentNotifications

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

EnvironmentId

Type: String

Description: (Required) The ID of the Elastic Beanstalk environment that you want to enable logging on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- elasticbeanstalk:DescribeConfigurationSettings
- elasticbeanstalk:DescribeEnvironments
- elasticbeanstalk:UpdateEnvironment

Document Steps

- aws:executeAwsApi Enables logging on the Elastic Beanstalk environment you specify in the EnvironmentId parameter.
- aws:waitForAwsResourceProperty Waits for the status of the environment to change to Ready.
- aws:executeScript Verifies logging has been enabled on the Elastic Beanstalk environment.

AWSConfigRemediation-EnableBeanstalkEnvironmentNotifications

Description

The AWSConfigRemediation-EnableBeanstalkEnvironmentNotifications runbook enables notifications for the AWS Elastic Beanstalk (Elastic Beanstalk) environment you specify.

Run this Automation (console)

Document type

Automation

AWS Systems Manager Automation runbook reference User Guide Elastic Load Balancing

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

EnvironmentId

Type: String

Description: (Required) The ID of the Elastic Beanstalk environment that you want to enable notifications for.

TopicArn

Type: String

Description: (Required) The ARN of the Amazon Simple Notification Service (Amazon SNS) topic you want to send notifications to.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- elasticbeanstalk:DescribeConfigurationSettings
- elasticbeanstalk:DescribeEnvironments
- elasticbeanstalk:UpdateEnvironment

Document Steps

- aws:executeAwsApi Enables notifications for the Elastic Beanstalk environment you specify in the EnvironmentId parameter.
- aws:waitForAwsResourceProperty Waits for the status of the environment to change to Ready.
- aws:executeScript Verifies notifications have been enabled for the Elastic Beanstalk environment.

Elastic Load Balancing

AWS Systems Manager Automation provides predefined runbooks for Elastic Load Balancing. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DropInvalidHeadersForALB

Topics

- AWSConfigRemediation-DropInvalidHeadersForALB (p. 151)
- AWSConfigRemediation-EnableCLBCrossZoneLoadBalancing (p. 152)
- AWSConfigRemediation-EnableELBDeletionProtection (p. 153)
- AWSConfigRemediation-EnableLoggingForALBAndCLB (p. 154)
- AWSConfigRemediation-EnableNLBCrossZoneLoadBalancing (p. 155)

AWSConfigRemediation-DropInvalidHeadersForALB

Description

The AWSConfigRemediation-DropInvalidHeadersForALB runbook enables the application load balancer you specify to remove HTTP headers with invalid headers.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $^{r.}(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

LoadBalancerArn

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the load balancer that you want to drop invalid headers.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- elasticloadbalancing:DescribeLoadBalancerAttributes

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableCLBCrossZoneLoadBalancing

• elasticloadbalancing:ModifyLoadBalancerAttributes

Document Steps

- aws:executeAwsApi Enables the drop invalid headers setting for the load balancer you specify in the LoadBalancerArn parameter.
- aws:executeScript Verifies the drop invalid headers setting has been enabled on the load balancer you specify in the LoadBalancerArn parameter.

AWSConfigRemediation-EnableCLBCrossZoneLoadBalancing

Description

The AWSConfigRemediation-EnableClbCrossZoneLoadBalancing runbook enables cross-zone load balancing for the Classic Load Balancer (CLB) you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

· AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

LoadBalancerName

Type: String

Description: (Required) The name of the CLB that you want to enable cross-zone load balancing on.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- elb:DescribeLoadBalancerAttributes

• elb:ModifyLoadBalancerAttributes

Document Steps

- aws:executeAwsApi Enables cross-zone load balancing for the CLB you specify in the LoadBalancerName parameter.
- aws:assertAwsResourceProperty Verifies cross-zone load balancing has been enabled on the CLB.

AWSConfigRemediation-EnableELBDeletionProtection

Description

The AWSConfigRemediation-EnableELBDeletionProtection runbook enables deletion protection for the elastic load balancer (ELB) you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

LoadBalancerArn

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the ELB that you want to enable deletion protection on.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableLoggingForALBAndCLB

- elasticloadbalancing:DescribeLoadBalancerAttributes
- elasticloadbalancing:DescribeLoadBalancers
- elasticloadbalancing:ModifyLoadBalancerAttributes

Document Steps

 aws:executeScript - Enables deletion protection on the ELB you specify in the LoadBalancerArn parameter.

AWSConfigRemediation-EnableLoggingForALBAndCLB

Description

The AWSConfigRemediation-EnableLoggingForALBAndCLB runbook enables logging for the specified AWS Application Load Balancer or a Classic Load Balancer (CLB).

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

LoadBalancerId

Type: String

Description: (Required) The Classic Load Balancer name or the Application Load Balancer ARN.

S3BucketName

Type: String

Description: (Required) The Amazon S3 bucket name.

S3BucketPrefix

Type: String

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableNLBCrossZoneLoadBalancing

Description: (Optional) The logical hierarchy you created for your Amazon Simple Storage Service (Amazon S3) bucket, for example my-bucket-prefix/prod. If the prefix is not provided, the log is placed at the root level of the bucket.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- elasticloadbalancing:DescribeLoadBalancerAttributes
- elasticloadbalancing:ModifyLoadBalancerAttributes

Document Steps

 aws:executeScript - Enables and verifies the logging for the Classic Load Balancer or the Application Load Balancer.

AWSConfigRemediation-EnableNLBCrossZoneLoadBalancing

Description

The AWSConfigRemediation-EnableNLBCrossZoneLoadBalancing runbook enables cross zone load balancing for the network load balancer (NLB) you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $^{r}(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

LoadBalancerArn

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the NLB that you want to enable cross zone load balancing on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- elbv2:DescribeLoadBalancerAttributes
- elbv2:ModifyLoadBalancerAttributes

Document Steps

- aws:executeAwsApi Enables cross zone load balancing for the NLB you specify in the LoadBalancerArn parameter.
- aws:executeScript Verifies cross zone load balancing has been enabled on the NLB.

Amazon EMR

AWS Systems Manager Automation provides predefined runbooks for Amazon EMR. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

AWSSupport-AnalyzeEMRLogs (p. 156)

AWSSupport-AnalyzeEMRLogs

Description

This runbook helps identify errors while running a job on an Amazon EMR cluster. The runbook analyzes a list of defined logs on the file system and looks for a list of predefined keywords. These log entries are used to create Amazon CloudWatch Events events so you can take any needed actions based on the events. Optionally, the runbook publishes log entries to the Amazon CloudWatch Logs log group of your choosing. This runbook currently looks for the following errors and patterns in log files:

- container out of memory YARN container ran out of memory, running job may fail.
- yarn_nodemanager_health: CORE or TASK node is running low on disk space and will not be able to run tasks.
- node_state_change: CORE or TASK node is unreachable by the MASTER node.
- step_failure: An EMR Step has failed.
- no_core_nodes_running: No CORE nodes are currently running, cluster is unhealthy.
- hdfs_missing_blocks: There are missing HDFS blocks which could lead to data loss.
- hdfs_high_util: HDFS Utilization is high, which may affect jobs and cluster health.
- instance_controller_restart: Instance-Controller process has restarted. This process is essential for cluster health.
- instance_controller_restart_legacy: Instance-Controller process has restarted. This process is essential for cluster health.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-AnalyzeEMRLogs

- high_load: High Load Average detected, may affect node health reporting or result in timeouts or slowdowns.
- yarn_node_blacklisted: CORE or TASK node has been blacklisted by YARN from running tasks.
- yarn_node_lost: CORE or TASK node has been marked as LOST by YARN, possible connectivity issues.

Instances associated with the ClusterID that you specify must be managed by AWS Systems Manager. You can run this automation once, schedule the automation to run at a specific time interval, or remove a schedule created previously by an automation. This runbook supports Amazon EMR release versions 5.20 to 6.30.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ClusterID

Type: String

Description: (Required) The ID of the cluster whose nodes logs you want to analyze.

Operation

Type: String

Valid values: Run Once | Schedule | Remove Schedule

Description: (Required) The operation to perform on the cluster.

IntervalTime

Type: String

Valid values: 5 minutes | 10 minutes | 15 minutes

Description: (Optional) The duration of time between running the automation. This parameter is only applicable if you specify Schedule for the Operation parameter.

LogToCloudWatchLogs

Type: String

Valid values: yes | no

AWS Systems Manager Automation runbook reference User Guide AWSSupport-AnalyzeEMRLogs

Description: (Optional) If you specify yes for the value of this parameter, the automation creates a CloudWatch Logs log group with the name specified in the CloudWatchLogGroup parameter to store any matched log entries.

CloudWatchLogGroup

Type: String

Description: (Optional) The name of the CloudWatch Logs log group you want to store any matched log entries in. This parameter is only applicable if you specify yes for the LogToCloudWatchLogs parameter.

· CreateLogInsightsDashboard

Type: String

Valid values: yes | no

Description: (Optional) If you specify yes, CloudWatch dashboard is created if it does not already exist. This parameter is only applicable if you specify yes for the LogToCloudWatchLogs parameter.

CreateMetricFilters

Type: String

Valid values: yes | no

Description: (Optional) Specify yes if you want to create metric filters for the CloudWatch Logs log group. This parameter is only applicable if you specify yes for the LogToCloudWatchLogs parameter.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetDocument
- ssm:ListDocuments
- ssm:DescribeAutomationExecutions
- ssm:DescribeAutomationStepExecutions
- ssm:GetAutomationExecution
- ssm:DescribeInstanceInformation
- ssm:ListCommandInvocations
- ssm:ListCommands
- ssm:SendCommand
- iam:CreateRole
- iam:DeleteRole
- iam:GetRolePolicy
- iam:PutRolePolicy
- iam:DeleteRolePolicy
- iam:passrole
- cloudformation:DescribeStacks
- cloudformation:DeleteStack
- cloudformation:CreateStack
- events:DeleteRule

AWS Systems Manager Automation runbook reference User Guide AWSSupport-AnalyzeEMRLogs

- events:RemoveTargets
- events:PutTargets
- events:PutRule
- events:DescribeRule
- logs:DescribeLogGroups
- logs:CreateLogGroup
- logs:PutMetricFilter
- · cloudwatch:PutDashboard
- elasticmapreduce:ListInstances
- elasticmapreduce:DescribeCluster

Document Steps

- aws:executeAwsApi Gathers information about the Amazon EMR cluster specified in the ClusterID parameter.
- aws:branch Branches based on input.
 - If the provided operation is Run Once or Schedule:
 - aws:assertAwsResourceProperty Verifies the cluster is available.
 - aws:executeAwsApi Gathers the IDs of all instances running in the cluster.
 - aws:assertAwsResourceProperty Verifies the SSM Agent is running on all instances in the cluster.
 - aws:branch Branches based on whether you specified to run the automation once or on a schedule.
 - If the provided operation is Run Once:
 - aws:branch Branches based on the value specified in the LogToCloudWatchLogs parameter.
 - If LogToCloudWatchLogs value is yes:
 - aws:executeScript Checks if a CloudWatch Logs log group with the name specified in parameter CloudWatchLogGroup already exists. If not, the group is created with the name specified.
 - aws:branch Branches based on the value specified in the CreateMetricFilters parameter.
 - If CreateMetricFilters value is yes:
 - aws:executeAwsApi 12 steps are ran for each metric filter
 - aws:branch Branches based on the value specified in the CreateLogInsightsDashboard parameter.
 - If CreateLogInsightsDashboard value is yes:
 - aws:executeAwsApi Creates a CloudWatch dashboard with the same name specified in the CloudWatchLogGroup parameter, if it does not already exist.
 - If CreateLogInsightsDashboard value is no:
 - aws:runCommand Runs a shell script to find log patterns on each instance in the cluster.
 - If CreateMetricFilters value is no:
 - aws:branch Branches based on the value specified in CreateLogInsightsDashboard parameter.
 - If CreateLogInsightsDashboard value is yes:
 - aws:executeAwsApi Creates a CloudWatch dashboard with the same name
 specified in the CloudWatchLogGroup parameter, if it does not already exist.

- If CreateLogInsightsDashboard value is no:
 - aws:runCommand Runs a shell script to find log patterns on each instance in the cluster.
- If LogToCloudWatchLogs value is no:
 - aws:executeAwsApi Runs a shell script to find log patterns on each instance in the cluster.
- If the provided operation is Schedule:
 - aws:createStack Creates an Amazon EventBridge event that targets this runbook.
- If the provided operation is Remove Schedule:
 - aws:executeAwsApi Verifies a schedule exists for the cluster.
 - aws:deleteStack Deletes the schedule.

Outputs

GetClusterInformation.ClusterName

GetClusterInformation.ClusterState

ListingClusterInstances.InstanceIDs

CreatingScheduleCloudFormationStack.StackStatus

Removing Schedule By Deleting Schedule Cloud Formation Stack. Stack Status

CheckIfLogGroupExists.output

FindLogPatternOnEMRNode.CommandId

Amazon OpenSearch Service

AWS Systems Manager Automation provides predefined runbooks for Amazon OpenSearch Service. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-DeleteOpenSearchDomain (p. 160)
- AWSConfigRemediation-EnforceHTTPSOnOpenSearchDomain (p. 161)
- AWSConfigRemediation-UpdateOpenSearchDomainSecurityGroups (p. 162)

AWSConfigRemediation-DeleteOpenSearchDomain

Description

The AWSConfigRemediation-DeleteOpenSearchDomain runbook deletes the given Amazon OpenSearch Service domain using the DeleteDomain API.

Run this Automation (console)

Document type

Automation

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnforceHTTPSOnOpenSearchDomain

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

DomainName

Type: String

Allowed values: (\d{12}/)?[a-z]{1}[a-z0-9-]{2,28}

Description: (Required) The name of the Amazon OpenSearch Service domain that you want to delete.

• AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- es:DeleteDomain
- es:DescribeDomain

Document Steps

 aws:executeScript - Accepts the Amazon OpenSearch Service domain name as input, deletes it, and verifies the deletion.

AWSConfigRemediation-EnforceHTTPSOnOpenSearchDomain

Description

The AWSConfigRemediation-EnforceHTTPSOnOpenSearchDomain runbook enables EnforceHTTPS on a given Amazon OpenSearch Service domain using the UpdateDomainConfig API.

Run this Automation (console)

Document type

Automation

Owner

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

UpdateOpenSearchDomainSecurityGroups

Amazon

Platforms

Linux, macOS, Windows

Parameters

DomainName

Type: String

Allowed values: (\d{12}/)?[a-z]{1}[a-z0-9-]{2,28}

Description: (Required) The name of the Amazon OpenSearch Service domain that you want to use to enforce HTTPS.

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- es:DescribeDomain
- es:UpdateDomainConfig

Document Steps

• aws:executeScript - Enables the EnforceHTTPS endpoint option on the Amazon OpenSearch Service domain you specify in the DomainName parameter.

AWSConfigRemediation-UpdateOpenSearchDomainSecurityGroups

Description

The AWSConfigRemediation-UpdateOpenSearchDomainSecurityGroups runbook updates the security group configuration on a given Amazon OpenSearch Service domain using the UpdateDomainConfig API.

Note

AWS Security groups can only be applied to Amazon OpenSearch Service domains configured for Amazon Virtual Private Cloud (VPC) Access, and not to Amazon OpenSearch Service domains configured for Public Access.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

DomainName

Type: String

Description: (Required) The name of the Amazon OpenSearch Service domain that you want to use to update security groups.

SecurityGroupList

Type: StringList

Description: (Required) The security group IDs that you want to assign to the Amazon OpenSearch Service domain.

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- es:DescribeDomain
- es:UpdateDomainConfig

Document Steps

• aws:executeScript - Updates the security group configuration on the Amazon OpenSearch Service domain you specify in the DomainName parameter.

EventBridge

AWS Systems Manager Automation provides predefined runbooks for Amazon EventBridge. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

AWS Systems Manager Automation runbook reference User Guide AWS-AddOpsItemDedupStringToEventBridgeRule

Topics

- AWS-AddOpsItemDedupStringToEventBridgeRule (p. 164)
- AWS-DisableEventBridgeRule (p. 165)

AWS-

AddOpsItemDedupStringToEventBridgeRule

Description

The AWS-AddOpsItemDedupStringToEventBridgeRule runbook adds a deduplication string for all AWS Systems Manager OpsItems associated with an Amazon EventBridge rule. The runbook doesn't add a deduplication string to the rule if one has already been applied. To learn more deduplication strings and OpsItems, see Reducing duplicate OpsItems in the AWS Systems Manager User Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

DedupString

Type: String

Description: (Required) The deduplication string you want to add to the rule.

• RuleName

Type: String

Description: (Required) The name of the rule you want to add the deduplication string to.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

AWS Systems Manager Automation runbook reference User Guide AWS-DisableEventBridgeRule

• events:ListTargetsByRule

• events:PutTargets

Document Steps

• aws:executeScript - Adds a deduplication string to the EventBridge rule you specify in the RuleName parameter.

AWS-DisableEventBridgeRule

Description

The AWS-DisableEventBridgeRule runbook disables the Amazon EventBridge rule you specify. To learn more about EventBridge rules, see Amazon EventBridge rules in the Amazon EventBridge User Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

EventBusName

Type: String

Default: default

Description: (Optional) The event bus associated with the rule you want to disable.

RuleName

Type: String

Description: (Required) The name of the rule you want to disable.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- events:DisableRule

Document Steps

aws:executeAwsApi - Disables the EventBridge rule you specify in the RuleName parameter.

GuardDuty

AWS Systems Manager Automation provides predefined runbooks for Amazon GuardDuty. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

AWSConfigRemediation-CreateGuardDutyDetector (p. 166)

AWSConfigRemediation-CreateGuardDutyDetector

Description

The AWSConfigRemediation-CreateGuardDutyDetector runbook creates an Amazon GuardDuty (GuardDuty) detector in the AWS Region where you run the automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- guardduty:CreateDetector
- guardduty:GetDetector

Document Steps

- aws:executeAwsApi Creates a GuardDuty detector.
- aws:assertAwsResourceProperty Verifies the Status of the detector is ENABLED.

IAM

AWS Systems Manager Automation provides predefined runbooks for AWS Identity and Access Management. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWS-AttachIAMToInstance (p. 167)
- AWSConfigRemediation-DeleteIAMRole (p. 169)
- AWSConfigRemediation-DeletelAMUser (p. 170)
- AWSConfigRemediation-DeleteUnusedIAMGroup (p. 172)
- AWSConfigRemediation-DeleteUnusedIAMPolicy (p. 173)
- AWSConfigRemediation-DetachIAMPolicy (p. 174)
- AWSConfigRemediation-EnableAccountAccessAnalyzer (p. 175)
- AWSSupport-GrantPermissionsTolAMUser (p. 176)
- AWSConfigRemediation-RemoveUserPolicies (p. 179)
- AWSConfigRemediation-ReplaceIAMInlinePolicy (p. 180)
- AWSConfigRemediation-RevokeUnusedIAMUserCredentials (p. 182)
- AWSConfigRemediation-SetIAMPasswordPolicy (p. 183)

AWS-AttachIAMToInstance

Description

Attach an AWS Identity and Access Management (IAM) role to a managed instance.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

AWS Systems Manager Automation runbook reference User Guide AWS-AttachIAMToInstance

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

ForceReplace

Type: Boolean

Description: (Optional) Flag to specify whether to replace the existing IAM profile or not.

Default: true
• InstanceId

Type: String

Description: (Required) The ID of the instance on which you want to assign an IAM role.

RoleName

Type: String

Description: (Required) The IAM role name to add to the managed instance.

Document Steps

- aws:executeAwsApi DescribeInstanceProfile Find the IAM instance profile attached to the EC2 instance.
- 2. aws:branch CheckInstanceProfileAssociations Check the IAM instance profile attached to the EC2 instance.
 - a. If an IAM instance profile is attached and ForceReplace is set to true:
 - i. aws:executeAwsApi DisassociateIamInstanceProfile Disassociate the IAM instance profile from the EC2 instance.
 - b. aws:executeAwsApi ListInstanceProfilesForRole List instance profiles for the IAM role provided.
 - c. aws:branch CheckInstanceProfileCreated Check if the IAM role provided has an associated instance profile.
 - i. If the IAM role has an associated instance profile:
 - A. aws:executeAwsApi AttachIAMProfileToInstance Attach the IAM instance profile role to the EC2 instance.
 - i. If the IAM role does not have an associated instance profile:
 - A. aws: executeAwsApi CreateInstanceProfileForRole Create an instance profile role for the specified IAM role.
 - B. aws:executeAwsApi AddRoleToInstanceProfile Attach the instance profile role to the specified IAM role.
 - C. aws:executeAwsApi GetInstanceProfile Get the instance profile data for the specified IAM role.
 - D. aws:executeAwsApi AttachIAMProfileToInstanceWithRetry Attach the IAM instance profile role to the EC2 instance.

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteIAMRole

Outputs

AttachIAMProfileToInstanceWithRetry.AssociationId

GetInstanceProfile.InstanceProfileName

GetInstanceProfile.InstanceProfileArn

AttachIAMProfileToInstance.AssociationId

ListInstanceProfilesForRole.InstanceProfileName

ListInstanceProfilesForRole.InstanceProfileArn

AWSConfigRemediation-DeleteIAMRole

Description

The AWSConfigRemediation-DeleteIAMRole runbook deletes the AWS Identity and Access Management (IAM) role you specify. This automation does not delete instance profiles associated with the IAM role, or service-linked roles.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

IAMRoleID

Type: String

Description: (Required) The ID of the IAM role you want to delete.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteIAMUser

- iam:DeleteRole
- iam:DeleteRolePolicy
- iam:GetRole
- iam:ListAttachedRolePolicies
- iam:ListInstanceProfilesForRole
- iam:ListRolePolicies
- iam:ListRoles
- iam:RemoveRoleFromInstanceProfile

Document Steps

- aws:executeScript Gathers the name of the IAM role you specify in the IAMRoleID parameter.
- aws:executeScript Gathers policies and instance profiles associated with the IAM role.
- aws:executeScript Deletes attached policies.
- aws:executeScript Deletes the IAM role and verifies the role has been deleted.

AWSConfigRemediation-DeleteIAMUser

Description

The AWSConfigRemediation-DeleteIAMUser runbook deletes the AWS Identity and Access Management (IAM) user you specify. This automation deletes or detaches the following resources associated with the IAM user:

- Access keys
- Attached managed policies
- · Git credentials
- IAM group memberships
- IAM user password
- Inline policies
- Multi-factor authentication (MFA) devices
- Signing certificates
- · SSH public keys

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteIAMUser

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

IAMUserId

Type: String

Description: (Required) The ID of the IAM user you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- iam:DeactivateMFADevice
- iam:DeleteAccessKey
- iam:DeleteLoginProfile
- iam:DeleteServiceSpecificCredential
- iam:DeleteSigningCertificate
- iam:DeleteSSHPublicKey
- iam:DeleteVirtualMFADevice
- iam:DeleteUser
- iam:DeleteUserPolicy
- iam:DetachUserPolicy
- iam:GetUser
- iam:ListAttachedUserPolicies
- iam:ListAccessKeys
- iam:ListGroupsForUser
- iam:ListMFADevices
- iam:ListServiceSpecificCredentials
- iam:ListSigningCertificates
- iam:ListSSHPublicKeys
- iam:ListUserPolicies
- iam:ListUsers
- iam:RemoveUserFromGroup

Document Steps

- aws:executeScript Gathers the user name of the IAM user you specify in the IAMUserId parameter.
- aws:executeScript Gathers access keys, certificates, credentials, MFA devices, and SSH keys associated with the IAM user.
- aws:executeScript Gathers group memberships and policies for the IAM user.

AWSConfigRemediation-DeleteUnusedIAMGroup

- aws:executeScript Deletes access keys, certificates, credentials, MFA devices, and SSH keys associated with the IAM user.
- aws:executeScript Deletes group memberships and policies for the IAM user.
- aws:executeScript Deletes the IAM user and verifies the user has been deleted.

AWSConfigRemediation-DeleteUnusedIAMGroup

Description

The AWSConfigRemediation-DeleteUnusedIAMGroup runbook deletes an IAM group that does not contain any IAM users.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

GroupName

Type: String

Description: (Required) The name of the IAM group that you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- iam:DeleteGroup
- iam:DeleteGroupPolicy
- iam:DetachGroupPolicy

Document Steps

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteUnusedIAMPolicy

aws:executeScript - Removes managed and inline IAM policies attached to the target IAM group,

AWSConfigRemediation-DeleteUnusedIAMPolicy

Description

The AWSConfigRemediation-DeleteUnusedIAMPolicy runbook deletes an AWS Identity and Access Management (IAM) policy that is not attached to any IAM users, groups, or roles.

Run this Automation (console)

and then deletes the IAM group.

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

IAMResourceId

Type: String

Description: (Required) The resource identifier of the IAM policy that you want to delete.

Required IAM permissions

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- config:GetResourceConfigHistory
- config:ListDiscoveredResources
- iam:DeletePolicy
- iam:DeletePolicyVersion
- iam:GetPolicy
- iam:ListEntitiesForPolicy

• iam:ListPolicyVersions

Document Steps

• aws:executeScript - Deletes the policy you specify in the IAMResourceId parameter, and verifies the policy was deleted.

AWSConfigRemediation-DetachIAMPolicy

Description

The AWSConfigRemediation-DetachIAMPolicy runbook detaches the AWS Identity and Access Management (IAM) policy you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

IAMResourceId

Type: String

Description: (Required) The ID of the IAM policy you want to detach.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- config:GetResourceConfigHistory
- config:ListDiscoveredResources
- iam:DetachGroupPolicy
- iam:DetachRolePolicy

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnableAccountAccessAnalyzer

EnableAcco

- iam:DetachUserPolicy
- iam:GetPolicy
- iam:ListEntitiesForPolicy

Document Steps

• aws:executeScript - Detaches the IAM policy from all resources.

AWSConfigRemediation-EnableAccountAccessAnalyzer

Description

The AWSConfigRemediation-EnableAccountAccessAnalyzer runbook creates an AWS Identity and Access Management (IAM) Access Analyzer in your AWS account. For information about Access Analyzer, see Using AWS IAM Access Analyzer in the IAM User Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

· AnalyzerName

Type: String

Description: (Required) The name of the analyzer to create.

• AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- access-analyzer:CreateAnalyzer

• access-analyzer:GetAnalyzer

Document Steps

- aws:executeAwsApi Creates an access analyzer for your account.
- aws:waitForAwsResourceProperty Waits for the status of the access analyzer to be ACTIVE.
- aws:assertAwsResourceProperty Confirms the status of the access analyzer is ACTIVE.

AWSSupport-GrantPermissionsToIAMUser

Description

This runbook grants the specified permissions to an IAM group (new or existing), and adds the existing IAM user to it. Policies you can choose from: Billing or Support. To enable billing access for IAM, remember to also activate IAM user and federated user access to the Billing and Cost Management pages.

Important

If you provide an existing IAM group, all current IAM users in the group receive the new permissions.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

IAMGroupName

Type: String

Default: ExampleSupportAndBillingGroup

Description: (Required) Can be a new or existing group. Must comply with IAM Entity Name Limits.

IAMUserName

Type: String

Default: ExampleUser

AWS Systems Manager Automation runbook reference User Guide AWSSupport-GrantPermissionsToIAMUser

Description: (Required) Must be an existing user.

• LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role assumed by lambda.

Permissions

Type: String

Valid values: SupportFullAccess | BillingFullAccess | SupportAndBillingFullAccess

Default: SupportAndBillingFullAccess

Description: (Required) Choose one of: SupportFullAccess grants full access to the Support center. BillingFullAccess grants full access to the Billing dashboard. SupportAndBillingFullAccess grants full access to both Support center and the Billing dashboard. More info on policies under Document details.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

 $The \ permissions \ required \ depend \ on \ how \ {\tt AWSSupport-GrantPermissionsToIAMUser} \ is \ run.$

Running as the currently logged in user or role

It is recommended you have the AmazonSSMAutomationRole Amazon managed policy attached, and the following additional permissions to be able to create the Lambda function and the IAM role to pass to Lambda:

```
{
                     "Version": "2012-10-17",
                     "Statement": [
                         {
                             "Action": [
                                 "lambda: InvokeFunction",
                                 "lambda:CreateFunction",
                                 "lambda:DeleteFunction",
                                 "lambda:GetFunction"
                             ],
                             "Resource": "arn:aws:lambda:*:ACCOUNTID:function:AWSSupport-*",
                             "Effect": "Allow"
                         },
                             "Effect" : "Allow",
                             "Action" : [
                                 "iam:CreateGroup",
                                 "iam:AddUserToGroup",
                                 "iam:ListAttachedGroupPolicies",
                                 "iam:GetGroup",
                                 "iam:GetUser"
                             ],
                             "Resource" : [
                                 "arn:aws:iam::*:user/*",
                                 "arn:aws:iam::*:group/*"
                             ]
                         },
                             "Effect" : "Allow",
```

```
"Action" : [
            "iam:AttachGroupPolicy"
        ],
        "Resource": "*",
        "Condition": {
            "ArnEquals": {
                "iam:PolicyArn": [
                    "arn:aws:iam::aws:policy/job-function/Billing",
                    "arn:aws:iam::aws:policy/AWSSupportAccess"
                ]
            }
        }
    },
        "Effect" : "Allow",
        "Action" : [
            "iam:ListAccountAliases",
            "iam:GetAccountSummary"
        "Resource" : "*"
    }
]
```

Using AutomationAssumeRole and LambdaAssumeRole

The user must have the **ssm:StartAutomationExecution** permissions on the runbook, and **iam:PassRole** on the IAM roles passed as **AutomationAssumeRole** and **LambdaAssumeRole**. Here are the permissions each IAM role needs:

```
"Resource" : [
                "arn:aws:iam::*:user/*",
                "arn:aws:iam::*:group/*"
        },
{
            "Effect" : "Allow",
            "Action" : [
                "iam:AttachGroupPolicy"
            "Resource": "*",
             "Condition": {
                "ArnEquals": {
                     "iam:PolicyArn": [
                         "arn:aws:iam::aws:policy/job-function/Billing",
                         "arn:aws:iam::aws:policy/AWSSupportAccess"
                }
            }
            "Effect" : "Allow",
            "Action" : [
                "iam:ListAccountAliases",
                "iam:GetAccountSummary"
             "Resource" : "*"
        }
    ]
}
```

Document Steps

- 1. aws:createStack Run AWS CloudFormation Template to create a Lambda function.
- 2. aws:invokeLambdaFunction Run Lambda to set IAM permissions.
- 3. aws:deleteStack Delete CloudFormation Template.

Outputs

configureIAM.Payload

AWSConfigRemediation-RemoveUserPolicies

Description

The AWSConfigRemediation-RemoveUserPolicies runbook deletes the AWS Identity and Access Management (IAM) inline policies and detaches any managed policies attached to the IAM user you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-ReplaceIAMInlinePolicy

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

IAMUserID

Type: String

Description: (Required) The ID of the IAM user you want to remove policies from.

PolicyType

Type: String

Valid values: All | Inline | Managed

Default: All

Description: (Required) The type of IAM policies you want to remove from the IAM user.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- iam:DeleteUserPolicy
- iam:DetachUserPolicy
- iam:ListAttachedUserPolicies
- iam:ListUserPolicies
- iam:ListUsers

Document Steps

• aws:executeScript - Deletes and detaches IAM policies from the IAM user you specify in the IAMUserID parameter.

AWSConfigRemediation-ReplaceIAMInlinePolicy

Description

The AWSConfigRemediation-ReplaceIAMInlinePolicy runbook replaces an inline AWS Identity and Access Management (IAM) policy with a replicated managed IAM policy. For an inline policy attached

AWS Systems Manager Automation runbook reference User Guide

AWSConfigRemediation-ReplaceIAMInlinePolicy

to an IAM user, group, or role, the inline policy permissions are cloned into a managed IAM policy. The managed IAM policy is added to the resource, and the inline policy is removed. AWS Config must be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

• AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

InlinePolicyName

Type: StringList

Description: (Required) The inline IAM policy you want to replace.

Resourceld

Type: String

Description: (Required) The ID of the IAM user, group, or role whose inline policy you want to replace.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- iam: AttachGroupPolicy
- iam:AttachRolePolicy
- iam:AttachUserPolicy
- iam:CreatePolicy
- iam:CreatePolicyVersion
- iam:DeleteGroupPolicy
- iam:DeleteRolePolicy
- iam:DeleteUserPolicy
- iam:GetGroupPolicy
- iam:GetRolePolicy

RevokeUnusedIAMUserCredentials

- iam:GetUserPolicy
- iam:ListGroupPolicies
- iam:ListRolePolicies
- iam:ListUserPolicies

Document Steps

• aws:executeScript - Replace the inline IAM policy with an AWS replicated policy on the resource that you specify.

AWSConfigRemediation-RevokeUnusedIAMUserCredentials

Description

The AWSConfigRemediation-RevokeUnusedIAMUserCredentials runbook revokes unused AWS Identity and Access Management (IAM) passwords and active access keys. This runbook also deactivates expired access keys, and deletes expired login profiles. AWS Config must be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

IAMResourceld

Type: String

Description: (Required) The ID of the IAM resource you want to revoke unused credentials from.

MaxCredentialUsageAge

Type: String

Default: 90

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-SetIAMPasswordPolicy

Description: (Required) The number of days within which the credential must have been used.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- config:ListDiscoveredResources
- iam:DeleteAccessKey
- iam:DeleteLoginProfile
- iam:GetAccessKeyLastUsed
- iam:GetLoginProfile
- iam:GetUser
- iam:ListAccessKeys
- iam:UpdateAccessKey

Document Steps

• aws:executeScript - Revokes IAM credentials for the user specified in the IAMResourceId parameter. Expired access keys are deactivated, and expired login profiles are deleted.

AWSConfigRemediation-SetIAMPasswordPolicy

Description

The AWSConfigRemediation-SetIAMPasswordPolicy runbook sets the AWS Identity and Access Management (IAM) user password policy for your AWS account.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

AWS Systems Manager Automation runbook reference User Guide

AWSConfigRemediation-SetIAMPasswordPolicy

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

AllowUsersToChangePassword

Type: Boolean
Default: false

Description: (Optional) If set to true, all IAM users in your AWS account can use the AWS Management Console to change their passwords.

HardExpiry

Type: Boolean

Default: false

Description: (Optional) If set to true, IAM users are prevented from resetting their passwords after their password expires.

MaxPasswordAge

Type: Integer

Default: 0

Description: (Optional) The number of days an IAM user's password is valid.

· MinimumPasswordLength

Type: Integer

Default: 6

Description: (Optional) The minimum number of characters an IAM user's password can be.

· PasswordReusePrevention

Type: Integer

Default: 0

Description: (Optional) The number of previous passwords that an IAM user is prevented from reusing.

• RequireLowercaseCharacters

Type: Boolean
Default: false

Description: (Optional) If set to true, an IAM user's password must contain a lowercase character from the ISO basic Latin alphabet (a to z).

• RequireNumbers

Type: Boolean

Default: false

Description: (Optional) If set to true, an IAM user's password must contain a numeric character (0-9).

RequireSymbols

Type: Boolean

AWS Systems Manager Automation runbook reference User Guide AWS KMS

Default: false

Description: (Optional) If set to true, an IAM user's password must contain a non-alphanumeric character (! @ # % ^ * () _ + - = [] { } | ').

RequireUppercaseCharacters

Type: Boolean
Default: false

Description: (Optional) If set to true, an IAM user's password must contain an uppercase character from the ISO basic Latin alphabet (A to Z).

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- iam:GetAccountPasswordPolicy
- iam:UpdateAccountPasswordPolicy

Document Steps

• aws:executeScript - Sets the IAM user password policy based on the values you specify for the runbook parameters for your AWS account.

AWS KMS

AWS Systems Manager Automation provides predefined runbooks for AWS Key Management Service. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-CancelKeyDeletion (p. 185)
- AWSConfigRemediation-EnableKeyRotation (p. 186)

AWSConfigRemediation-CancelKeyDeletion

Description

The AWSConfigRemediation-CancelKeyDeletion runbook cancels deletion of the AWS Key Management Service (AWS KMS) customer managed key that you specify.

Run this Automation (console)

Document type

Automation

Owner

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnableKeyRotation

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $^{r}(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Keyld

Type: String

Description: (Required) The ID of the customer managed key that you want to cancel deletion for.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- kms:CancelKeyDeletion
- kms:DescribeKey

Document Steps

- aws:executeAwsApi Cancels deletion for the customer managed key you specify in the KeyId parameter.
- aws:assertAwsResourceProperty Confirms key deletion is disabled on your customer managed key.

AWSConfigRemediation-EnableKeyRotation

Description

The AWSConfigRemediation-EnableKeyRotation runbook enables automatic key rotation for the symmetric AWS Key Management Service (AWS KMS) customer managed key.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide Lambda

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Keyld

Type: String

Description: (Required) The ID of the customer managed key you want to enable automatic key rotation on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- kms:EnableKeyRotation
- kms:GetKeyRotationStatus

Document Steps

- aws:executeAwsApi Enables automatic key rotation on the customer managed key you specify in the KeyId parameter.
- aws:assertAwsResourceProperty Confirms that automatic key rotation is enabled on your customer managed key.

Lambda

AWS Systems Manager Automation provides predefined runbooks for AWS Lambda. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-ConfigureLambdaFunctionXRayTracing (p. 188)
- AWSConfigRemediation-DeleteLambdaFunction (p. 189)
- AWSConfigRemediation-EncryptLambdaEnvironmentVariablesWithCMK (p. 190)
- AWSConfigRemediation-MoveLambdaToVPC (p. 191)
- AWSSupport-RemediateLambdaS3Event (p. 192)
- AWSSupport-TroubleshootLambdaInternetAccess (p. 194)
- AWSSupport-TroubleshootLambdaS3Event (p. 196)

ConfigureLambdaFunctionXRayTracing

AWSConfigRemediation-ConfigureLambdaFunctionXRayTracing

Description

The AWSConfigRemediation-ConfigureLambdaFunctionXRayTracing runbook enables AWS X-Ray live tracing on the AWS Lambda function you specify in the FunctionName parameter.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

FunctionName

Type: String

Description: (Required) The name or ARN of the Lambda function to enable tracing on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- lambda:UpdateFunctionConfiguration
- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

Document Steps

- aws:executeAwsApi Enables X-Ray tracing on the Lambda function you specify in the FunctionName parameter.
- aws:assertAwsResourceProperty Verifies that X-Ray tracing has been enabled on the Lambda function.

Outputs

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteLambdaFunction

UpdateLambdaConfig.UpdateFunctionConfigurationResponse - Response from the UpdateFunctionConfiguration API call.

AWSConfigRemediation-DeleteLambdaFunction

Description

The AWSConfigRemediation-DeleteLambdaFunction runbook deletes the AWS Lambda function you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

LambdaFunctionName

Type: String

Description: (Required) The name of the Lambda function that you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- lambda:DeleteFunction
- lambda:GetFunction

Document Steps

- aws:executeAwsApi Deletes the Lambda function specified in the LambdaFunctionName parameter.
- aws:executeScript Verifies the Lambda function has been deleted.

EncryptLambdaEnvironmentVariablesWithCMK

AWSConfigRemediation-EncryptLambdaEnvironmentVariablesWithCMK

Description

The AWSConfigRemediation-EncryptLambdaEnvironmentVariablesWithCMK runbook encrypts, at rest, the environment variables for the AWS Lambda (Lambda) function you specify using an AWS Key Management Service (AWS KMS) customer managed key. This runbook should only be used as a baseline to ensure that your Lambda function's environment variables are encrypted according to minimum recommended security best practices. We recommend encrypting multiple functions with different customer managed keys.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

FunctionName

Type: String

Description: (Required) The name or ARN of the Lambda function whose environment variables you want to encrypt.

KMSKeyArn

Type: String

Description: (Required) The ARN of the AWS KMS customer managed key you want to use to encrypt your Lambda function's environment variables.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- lambda:GetFunctionConfiguration
- lambda: UpdateFunctionConfiguration

Document Steps

- aws:waitForAwsResourceProperty Waits for the LastUpdateStatus property to be Successful.
- aws:executeAwsApi Encrypts the environment variables for the Lambda function you specify
 in the FunctionName parameter using the AWS KMS customer managed key you specify in the
 KMSKeyArn parameter.
- aws:assertAwsResourceProperty Confirms encryption is enabled on the environment variables for your Lambda function.

AWSConfigRemediation-MoveLambdaToVPC

Description

The AWSConfigRemediation-MoveLambdaToVPC runbook moves an AWS Lambda (Lambda) function to an Amazon Virtual Private Cloud (Amazon VPC).

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

FunctionName

Type: String

Description: (Required) The name of the Lambda function to move to an Amazon VPC.

SecurityGroupIds

Type: String

Description: (Required) The security group IDs you want to assign to the elastic network interfaces (ENIs) associated with your Lambda function.

SubnetIds

Type: String

Description: (Required) The subnet IDs you want to create the elastic network interfaces (ENIs) associated with your Lambda function.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-RemediateLambdaS3Event

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- lambda:GetFunction
- lambda:GetFunctionConfiguration
- lambda: UpdateFunctionConfiguration

Document Steps

- aws:executeAwsApi Updates the Amazon VPC configuration for the Lambda function you specify in the FunctionName parameter.
- aws:waitForAwsResourceProperty Waits for the Lambda function LastUpdateStatus to be successful.
- aws:executeScript Verifies the Lambda function Amazon VPC configuration has been successfully updated.

AWSSupport-RemediateLambdaS3Event

Description

The AWSSupport-TroubleshootLambdaS3Event runbook provides an automated solution for the procedures outlined in the AWS Knowledge Center articles Why doesn't my Amazon S3 event notification trigger my Lambda function? and Why do I get the error "Unable to validate the following destination configurations" when creating an Amazon S3 event notification to trigger my Lambda function? This runbook helps you identify and remediate why an Amazon Simple Storage Service (Amazon S3) event notification failed to trigger the AWS Lambda function you specified. If the runbook output suggests validating and configuring your Lambda function concurrency, see Asynchronous invocation and AWS Lambda Function scaling.

Note

"Unable to validate the following destination configurations" errors can also occur due to incorrect Amazon Simple Notification Service (Amazon SNS) and Amazon Simple Queue Service (Amazon SQS) Amazon S3 event configurations. This runbook only checks Lambda function configurations. If after using the runbook, you are still receiving the "Unable to validate the following destination configurations" error, please review any existing Amazon SNS and Amazon SQS Amazon S3 event configurations.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

AWS Systems Manager Automation runbook reference User Guide AWSSupport-RemediateLambdaS3Event

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

• LambdaFunctionArn

Type: String

Description: (Required) The ARN of the Lambda function.

S3BucketName

Type: String

Description: (Required) The name of the Amazon S3 bucket whose event notifications triggers the Lambda function.

Action

Type: String

Valid values: Troubleshoot | Remediate

Description: (Required) The action you want the runbook to perform. The Troubleshoot option helps identify any issues, but does not perform any mutating actions to resolve the issue. The Remediate option helps identify and attempts to resolve issues for you.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetDocument
- ssm:ListDocuments
- ssm:DescribeAutomationExecutions
- ssm:DescribeAutomationStepExecutions
- ssm:GetAutomationExecution
- lambda:GetPolicy
- lambda:AddPermission
- s3:GetBucketNotification

Document Steps

• aws:branch - Branches based on the input specified for the Action parameter.

If the value specified is Troubleshoot:

- $\bullet \ \ \text{aws:executeAutomation} Runs \ the \ \ \text{AWSSupport-TroubleshootLambdaS3Event runbook}.$
- aws:executeAwsApi Checks the output of the AWSSupport-TroubleshootLambdaS3Event runbook that ran in the previous step.

If the value specified is Remediate:

aws:executeScript - Runs a script to remediate the issues outlined in the Why doesn't my
 Amazon S3 event notification trigger my Lambda function? and Why do I get the error "Unable to

AWS Systems Manager Automation runbook reference User Guide

AWSSupport-TroubleshootLambdaInternetAccess

validate the following destination configurations" when creating an Amazon S3 event notification to trigger my Lambda function? Knowledge Center articles.

Outputs

checkoutput.Output

remediatelambdas3event.Output

AWSSupport-TroubleshootLambdaInternetAccess

Description

The AWSSupport-TroubleshootLambdaInternetAccess runbook helps you troubleshoot internet access issues for a AWS Lambda function that was launched into Amazon Virtual Private Cloud (Amazon VPC). Resources such as subnet routes, security groups rules, and network access control list (ACL) rules are reviewed to confirm outbound internet access is allowed.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

• AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

FunctionName

Type: String

Description: (Required) The name of the Lambda function you want to troubleshoot internet access for.

destinationlp

Type: String

Description: (Required) The destination IP address you want to establish an outbound connection to.

destinationPort

Type: String
Default: 443

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootLambdaInternetAccess

Description: (Optional) The destination port you want to establish an outbound connection on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- lambda:GetFunction
- ec2:DescribeRouteTables
- ec2:DescribeNatGateways
- ec2:DescribeSecurityGroups
- ec2:DescribeNetworkAcls

Document Steps

- aws:executeScript Verifies the configuration of various resources in your VPC where the Lambda function was launched.
- aws:branch Branches based on whether the Lambda function specified is in a VPC or not.
- aws:executeScript Reviews the route table routes for the subnet where the Lambda function was launched, and verifies that routes to a network address translation (NAT) gateway, and internet gateway are present. Confirms the Lambda function is not in a public subnet.
- aws:executeScript Verifies the security group associated with the Lambda function allows outbound internet access based on the values specified for the destinationIp and destinationPort parameters.
- aws:executeScript Verifies the ACL rules associated with the subnets of the Lambda function and the NAT gateway allow outbound internet access based on the values specified for the destinationIp and destinationPort parameters.

Outputs

checkVpc.vpc - The ID of the VPC where your Lambda function was launched.

checkVpc.subnet - The IDs of the subnets where your Lambda function was launched.

checkVpc.securityGroups - Security groups associated with the Lambda function.

checkNACL.NACL - Analysis message with resource names. LambdaIp refers to the private IP address of the elastic network interface for your Lambda function. The LambdaIpRules object is only generated for subnets that have a route to a NAT gateway. The following content is an example of the output.

```
{
   "subnet-1234567890":{
      "NACL": "acl-1234567890",
      "destinationIp_Egress": "Allowed",
      "destinationIp_Ingress": "notAllowed",
      "Analysis": "This NACL has an allow rule for Egress traffic but there is no Ingress
rule. Please allow the destination IP / destionation port in Ingress rule",
      "LambdaIpRules":{
         "{LambdaIp}":{
            "Egress": "notAllowed",
            "Ingress": "notAllowed",
            "Analysis": "This is a NAT subnet NACL. It does not have ingress or egress rule
allowed in it for Lambda's corresponding private ip {LambdaIp} Please allow this IP in
your egress and ingress NACL rules"
         }
      }
```

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootLambdaS3Event

```
},
  "subnet-0987654321":{
     "NACL":"acl-0987654321",
     "destinationIp_Egress":"Allowed",
     "destinationIp_Ingress":"notAllowed",
     "Analysis":"This NACL has an allow rule for Egress traffic but there is no Ingress rule. Please allow the destination IP / destionation port in Ingress rule"
  }
}
```

checkSecurityGroups.secgrps - Analysis for the security group associated with your Lambda function. The following content is an example of the output.

```
{
    "sg-123456789":{
        "Status":"Allowed",
        "Analysis":"This security group has allowed destintion IP and port in its outbuond
    rule."
    }
}
```

checkSubnet.subnets - Analysis for the subnets in your VPC associated with your Lambda function. The following content is an example of the output.

AWSSupport-TroubleshootLambdaS3Event

Description

The AWSSupport-TroubleshootLambdaS3Event runbook provides an automated solution for the procedures outlined in the AWS Knowledge Center articles Why doesn't my Amazon S3 event notification trigger my Lambda function? and Why do I get the error "Unable to validate the following destination configurations" when creating an Amazon S3 event notification to trigger my Lambda function? This runbook helps you identify why an Amazon Simple Storage Service (Amazon S3) event notification failed to trigger the AWS Lambda function you specified. If the runbook output suggests validating and configuring your Lambda function concurrency, see Asynchronous invocation and AWS Lambda Function scaling.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide Amazon RDS

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

LambdaFunctionArn

Type: String

Description: (Required) The ARN of the Lambda function that the Amazon S3 event notification triggers.

S3BucketName

Type: String

Description: (Required) The name of the Amazon S3 bucket whose event notifications triggers the Lambda function.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- lambda:GetPolicy
- s3:GetBucketNotification

Document Steps

aws:executeScript - Runs the script to validate configuration settings for the Amazon S3 event
notification. Validates the resource-based IAM policy for your Lambda function, and generates an
AWS Command Line Interface (AWS CLI) command to add the needed permissions if the required
permissions are missing from the policy. Validates other Lambda functions resource policies which are
part of event notifications for the same S3 bucket and generates an AWS CLI command as output if
the required permissions are missing.

Outputs

lambdaS3Event.output

Amazon RDS

AWS Systems Manager Automation provides predefined runbooks for Amazon Relational Database Service. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

• AWS-CreateRdsSnapshot (p. 198)

AWS Systems Manager Automation runbook reference User Guide AWS-CreateRdsSnapshot

- AWSConfigRemediation-DeleteRDSCluster (p. 199)
- AWSConfigRemediation-DeleteRDSClusterSnapshot (p. 200)
- AWSConfigRemediation-DeleteRDSInstance (p. 201)
- AWSConfigRemediation-DeleteRDSInstanceSnapshot (p. 202)
- AWSConfigRemediation-DisablePublicAccessToRDSInstance (p. 203)
- AWSConfigRemediation-EnableCopyTagsToSnapshotOnRDSCluster (p. 204)
- AWSConfigRemediation-EnableCopyTagsToSnapshotOnRDSDBInstance (p. 206)
- AWSConfigRemediation-EnableEnhancedMonitoringOnRDSInstance (p. 207)
- AWSConfigRemediation-EnableMinorVersionUpgradeOnRDS (p. 208)
- AWSConfigRemediation-EnableMultiAZOnRDSInstance (p. 209)
- AWSConfigRemediation-EnablePerformanceInsightsOnRDSInstance (p. 211)
- AWSConfigRemediation-EnableRDSClusterDeletionProtection (p. 212)
- AWSConfigRemediation-EnableRDSInstanceBackup (p. 213)
- AWSConfigRemediation-EnableRDSInstanceDeletionProtection (p. 215)
- AWSConfigRemediation-ModifyRDSInstancePortNumber (p. 216)
- AWSSupport-ModifyRDSSnapshotPermission (p. 217)
- AWS-RebootRdsInstance (p. 219)
- AWSSupport-ShareRDSSnapshot (p. 219)
- AWS-StartRdsInstance (p. 222)
- AWSSupport-TroubleshootConnectivityToRDS (p. 222)

AWS-CreateRdsSnapshot

Description

Create an Amazon Relational Database Service (Amazon RDS) snapshot for an Amazon RDS instance.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

DBInstanceIdentifier

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteRDSCluster

Type: String

Description: (Required) The DBInstanceId ID of the RDS Instance to create Snapshot from.

DBSnapshotIdentifier

Type: String

Description: (Optional) The DBSnapshotIdentifier ID of the RDS snapshot to create.

InstanceTags

Type: String

Description: (Optional) Tags to create for instance.

SnapshotTags

Type: String

Description: (Optional) Tags to create for snapshot.

Document Steps

createRDSSnapshot - Creates the RDS snapshot and returns the snapshot ID.

verifyRDSSnapshot - Checks that the snapshot created in the previous step exists.

Outputs

createRDSSnapshot.SnapshotId - The ID of the created snapshot.

AWSConfigRemediation-DeleteRDSCluster

Description

The AWSConfigRemediation-DeleteRDSCluster runbook deletes the Amazon Relational Database Service (Amazon RDS) cluster you specify. AWS Config must be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

AWS Systems Manager Automation runbook reference User Guide

AWSConfigRemediation-DeleteRDSClusterSnapshot

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DBClusterId

Type: String

Description: (Required) The resource identifier for the DB cluster you want to enable deletion protection on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- config:GetResourceConfigHistory
- rds:DeleteDBCluster
- rds:DeleteDBInstance
- rds:DescribeDBClusters

Document Steps

• aws:executeScript - Deletes the DB cluster you specify in the DBClusterId parameter.

AWSConfigRemediation-DeleteRDSClusterSnapshot

Description

The AWSConfigRemediation-DeleteRDSClusterSnapshot runbook deletes the given Amazon Relational Database Service (Amazon RDS) cluster snapshot.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: r : r

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteRDSInstance

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your

DBClusterSnapshotId

Type: String

Description: (Required) The Amazon RDS cluster snapshot identifier to be deleted.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- rds:DeleteDBClusterSnapshot
- rds:DescribeDBClusterSnapshots

Document Steps

- aws:branch Checks if the cluster snapshot is in the available state. If it is not available, the flow ends.
- aws:executeAwsApi Deletes the given Amazon RDS cluster snapshot using the database (DB) cluster snapshot identifier.
- aws:executeScript Verifies that the given Amazon RDS cluster snapshot was deleted.

AWSConfigRemediation-DeleteRDSInstance

Description

The AWSConfigRemediation-DeleteRDSInstance runbook deletes the Amazon Relational Database Service (Amazon RDS) instance you specify. When you delete a database (DB) instance, all automated backups for that instance are deleted and can't be recovered. Manual DB snapshots are not deleted. If the DB instance you want to delete is in the failed, incompatible-network, or incompatible-restore state, you must set the SkipFinalSnapshot parameter to true.

Note

If the DB instance you want to delete is in an Amazon Aurora DB cluster, the runbook will not delete the DB instance if it is a read replica and the only instance in the DB cluster.

Run this Automation (console)

| υ | 0 | cι | ım | er | ìτ | ty | pe | |
|---|---|----|----|----|----|----|----|--|
| | | | | | | | | |

Automation

Owner

Amazon

Platforms

Databases

Parameters

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteRDSInstanceSnapshot

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DbiResourceId

Type: String

Description: (Required) The resource identifier for the DB instance you want to delete.

SkipFinalSnapshot

Type: Boolean
Default: false

Description: (Optional) If set to true, a final snapshot is not created before the DB instance is deleted.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- rds:DeleteDBInstance
- rds:DescribeDBInstances

Document Steps

- aws:executeAwsApi Gathers the DB instance name from the value you specify in the DbiResourceId parameter.
- aws:branch Branches based on the value you specify in the SkipFinalSnapshot parameter.
- aws:executeAwsApi-Deletes the DB instance you specify in the DbiResourceId parameter.
- aws:executeAwsApi Deletes the DB instance you specify in the DbiResourceId parameter after the final snapshot is created.
- aws:assertAwsResourceProperty Verifies the DB instance was deleted.

AWSConfigRemediation-DeleteRDSInstanceSnapshot

Description

The AWSConfigRemediation-DeleteRDSInstanceSnapshot runbook deletes the Amazon Relational Database Service (Amazon RDS) instance snapshot you specify. Only snapshots in the available state are deleted. This runbook does not support deleting snapshots from Amazon Aurora database instances.

Run this Automation (console)

Document type

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DisablePublicAccessToRDSInstance

Automation

Owner

Amazon

Platforms

Databases

Parameters

· AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DbSnapshotId

Type: String

Description: (Required) The ID of the snapshot you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- rds:DeleteDBSnapshot
- rds:DescribeDBSnapshots

Document Steps

- aws:executeAwsApi Gathers the state of the snapshot specified in the DbSnapshotId parameter.
- aws:assertAwsResourceProperty Confirms the state of the snapshot is available.
- aws:executeAwsApi Deletes the snapshot specified in the DbSnapshotId parameter.
- aws:executeScript Verifies the snapshot has been deleted.

AWSConfigRemediation-DisablePublicAccessToRDSInstance

Description

The AWSConfigRemediation-DisablePublicAccessToRDSInstance runbook disables public accessibility for the Amazon Relational Database Service (Amazon RDS) database (DB) instance that you specify.

Run this Automation (console)

Document type

EnableCopyTagsToSnapshotOnRDSCluster

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DbInstanceResourceId

Type: String

Description: (Required) The resource identifier for the DB instance that you want to disable public accessibility for.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- rds:DescribeDBInstances
- rds:ModifyDBInstance

Document Steps

- $\bullet \ \ \text{aws:executeAwsApi-Gathers the DB instance identifier from the DB instance resource identifier.}$
- aws:assertAwsResourceProperty Verifies the DB instances is in an AVAILABLE state.
- aws:executeAwsApi Disables public accessibility on your DB instance.
- aws:waitForAwsResourceProperty Waits for the DB instance to change to a MODIFYING state.
- aws:waitForAwsResourceProperty Waits for the DB instance to change to an AVAILABLE state.
- aws:assertAwsResourceProperty Confirms public accessibility is disabled on the DB instance.

AWSConfigRemediation-EnableCopyTagsToSnapshotOnRDSCluster

Description

The AWSConfigRemediation-EnableCopyTagsToSnapshotOnRDSCluster runbook enables the CopyTagsToSnapshot setting on the Amazon Relational Database Service (Amazon RDS) cluster

EnableCopyTagsToSnapshotOnRDSCluster

you specify. Enabling this setting copies all tags from the DB cluster to snapshots of the DB cluster. The default is not to copy them. AWS Config must be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

ApplyImmediately

Type: Boolean
Default: false

Description: (Optional) If you specify true for this parameter, the modifications in this request and any pending modifications are asynchronously applied as soon as possible, regardless of the PreferredMaintenanceWindow setting for the DB cluster.

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DbClusterResourceId

Type: String

Description: (Required) The resource identifier for the DB cluster you want to enable the CopyTagsToSnapshot setting on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- config:GetResourceConfigHistory
- rds:DescribeDBClusters
- rds:ModifyDBCluster

Document Steps

• aws:executeAwsApi - Gathers the DB cluster identifier from the DB cluster resource identifier.

EnableCopyTagsToSnapshotOnRDSDBInstance

- aws:assertAwsResourceProperty Confirms the DB cluster is in an AVAILABLE state.
- aws:executeAwsApi Enables the CopyTagsToSnapshot setting on your DB cluster.
- aws:assertAwsResourceProperty Confirms the CopyTagsToSnapshot setting is enabled on your DB cluster.

AWSConfigRemediation-EnableCopyTagsToSnapshotOnRDSDBInstance

Description

The AWSConfigRemediation-EnableCopyTagsToSnapshotOnRDSDBInstance runbook enables the CopyTagsToSnapshot setting on the Amazon Relational Database Service (Amazon RDS) instance you specify. Enabling this setting copies all tags from the DB instance to snapshots of the DB instance. The default is not to copy them. AWS Config must be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

· ApplyImmediately

Type: Boolean

Default: false

Description: (Optional) If you specify true for this parameter, the modifications in this request and any pending modifications are asynchronously applied as soon as possible, regardless of the PreferredMaintenanceWindow setting for the DB instance.

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DbiResourceId

Type: String

Description: (Required) The resource identifier for the DB instance you want to enable the CopyTagsToSnapshot setting on.

EnableEnhancedMonitoringOnRDSInstance

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- config:GetResourceConfigHistory
- rds:DescribeDBInstances
- rds:ModifyDBInstance

Document Steps

- aws:executeAwsApi Gathers the DB instance identifier from the DB instance resource identifier.
- aws:assertAwsResourceProperty Confirms the DB instance is in an AVAILABLE state.
- aws:executeAwsApi Enables the CopyTagsToSnapshot setting on your DB instance.
- aws:assertAwsResourceProperty Confirms the CopyTagsToSnapshot setting is enabled on your DB instance.

AWSConfigRemediation-EnableEnhancedMonitoringOnRDSInstance

Description

The AWSConfigRemediation-EnableEnhancedMonitoringOnRDSInstance runbook enables Enhanced Monitoring on the Amazon RDS database instance you specify. For information on Enhanced Monitoring, see Enhanced Monitoring in the Amazon RDS User Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· MonitoringInterval

Type: Integer

EnableMinorVersionUpgradeOnRDS

Valid values: 1 | 5 | 10 | 15 | 30 | 60

Description: (Required) The interval in seconds when Enhanced Monitoring metrics are collected from the DB instance.

MonitoringRoleArn

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the IAM role that allows Amazon RDS to send Enhanced Monitoring metrics to Amazon CloudWatch Logs.

Resourceld

Type: String

Description: (Required) The resource identifier for the DB instance you want to enable Enhanced Monitoring on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- rds:DescribeDBInstances
- rds:ModifyDBInstance

Document Steps

- aws:executeAwsApi Gathers the DB instance identifier from the DB instance resource identifier.
- aws:assertAwsResourceProperty Confirms the DB Instance is in an AVAILABLE state.
- aws:executeAwsApi Enables Enhanced Monitoring on your DB instance.
- aws:executeScript Confirms that Enhanced Monitoring is enabled on your DB instance.

AWSConfigRemediation-EnableMinorVersionUpgradeOnRDS

Description

The AWSConfigRemediation-EnableMinorVersionUpgradeOnRDS runbook enables the AutoMinorVersionUpgrade setting on the Amazon RDS database instance you specify. Enabling this setting means that minor version upgrades are applied automatically to the DB instance during the maintenance window.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnableMultiAZOnRDSInstance

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DbiResourceId

Type: String

Description: (Required) The resource identifier for the DB instance you want to the AutoMinorVersionUpgrade setting on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- rds:DescribeDBInstances
- rds:ModifyDBInstance

Document Steps

- aws:executeAwsApi Gathers the DB instance identifier from the DB instance resource identifier.
- aws:assertAwsResourceProperty Confirms the DB Instance is in an AVAILABLE state.
- aws:executeAwsApi Enables the AutoMinorVersionUpgrade setting on your DB instance.
- aws:executeScript Confirms that the AutoMinorVersionUpgrade setting is enabled on your DB instance.

AWSConfigRemediation-EnableMultiAZOnRDSInstance

Description

The AWSConfigRemediation-EnableMultiAZOnRDSInstance runbook changes your Amazon Relational Database Service (Amazon RDS) database (DB) instance to a Multi-AZ deployment. Changing this setting doesn't result in an outage. The change is applied during the next maintenance window unless you set the ApplyImmediately parameter to true.

Run this Automation (console)

Document type

Automation

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnableMultiAZOnRDSInstance

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

ApplyImmediately

Type: Boolean

Default: false

Description: (Optional) If you specify true for this parameter, the modifications in this request and any pending modifications are asynchronously applied as soon as possible, regardless of the PreferredMaintenanceWindow setting for the DB instance.

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DbiResourceId

Type: String

Description: (Required) The AWS Region-unique, immutable identifier for the DB instance to enable the MultiAZ setting.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- rds:DescribeDBInstances
- rds:ModifyDBInstance
- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

Document Steps

- aws:executeAwsApi Retrieves the DB instance name using the value provided in the DBInstanceId parameter.
- \bullet aws:executeAwsApi Verifies the DBInstanceStatus is available.
- aws:branch Checks whether the MultiAZ is already set to true on the DB instance you specify in the DbiResourceId parameter.
- aws:executeAwsApi Changes the MultiAZ setting to true on the DB instance you specify in the DbiResourceId parameter.
- aws:assertAwsResourceProperty Verifies the MultiAZ is set to true on the DB instance you specify in the DbiResourceId parameter.

EnablePerformanceInsightsOnRDSInstance

AWSConfigRemediation-EnablePerformanceInsightsOnRDSInstance

Description

The AWSConfigRemediation-EnablePerformanceInsightsOnRDSInstance runbook enables Performance Insights on the Amazon RDS DB instance you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DbiResourceId

Type: String

Description: (Required) The resource identifier for the DB instance you want to enable Performance Insights on.

· PerformanceInsightsKMSKeyId

Type: String

Default: alias/aws/rds

Description: (Optional) The Amazon Resource Name (ARN), key ID, or the key alias of the AWS Key Management Service (AWS KMS) customer managed key you want Performance Insights to use to encrypt all potentially sensitive data. If you enter the key alias for this parameter, prefix the value with alias/. If you do not specify a value for this parameter, the AWS managed key is used.

PerformanceInsightsRetentionPeriod

Type: Integer

Valid values: 7, 731

Default: 7

Description: (Optional) The number of days you want to retain Performance Insights data.

${\tt Enable RDSCluster Deletion Protection}$

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- kms:CreateGrant
- kms:DescribeKey
- rds:DescribeDBInstances
- rds:ModifyDBInstance

Document Steps

- aws:executeAwsApi Gathers the DB instance identifier from the DB instance resource identifier.
- aws:assertAwsResourceProperty Confirms the DB instance status is available.
- aws:executeAwsApi Gathers the ARN of the AWS KMS customer managed key specified in the PerformanceInsightsKMSKeyId parameter.
- aws:branch Checks whether a value is already assigned to the PerformanceInsightsKMSKeyId property of the DB instance.
- aws:executeAwsApi Enables Performance Insights on the DB instance you specify in the DbiResourceId parameter.
- aws:assertAwsResourceProperty Confirms the value specified for the PerformanceInsightsKMSKeyId parameter was used to enable encryption for Performance Insights on the DB instance.
- aws:assertAwsResourceProperty Confirms Performance Insights is enabled on the DB instance.

AWSConfigRemediation-EnableRDSClusterDeletionProtection

Description

The AWSConfigRemediation-EnableRDSClusterDeletionProtection runbook enables deletion protection on the Amazon Relational Database Service (Amazon RDS) cluster you specify. AWS Configmust be enabled in the AWS Region where you run this automation.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

AWS Systems Manager Automation runbook reference User Guide

AWSConfigRemediation-EnableRDSInstanceBackup

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

ClusterId

Type: String

Description: (Required) The resource identifier for the DB cluster you want to enable deletion protection on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- config:GetResourceConfigHistory
- rds:DescribeDBClusters
- rds:ModifyDBCluster

Document Steps

- aws:executeAwsApi Gathers the DB cluster name from the DB cluster resource identifier.
- aws:assertAwsResourceProperty Verifies the DB cluster status is available.
- aws:executeAwsApi Enables deletion protection on the DB cluster you specify in the ClusterId parameter.
- aws:assertAwsResourceProperty Verifies deletion protection has been enabled on the DB cluster.

AWSConfigRemediation-EnableRDSInstanceBackup

Description

The AWSConfigRemediation-EnableRDSInstanceBackup runbook enables backups for the Amazon Relational Database Service (Amazon RDS) database instance you specify. This runbook does not support enabling backups for Amazon Aurora database instances.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

AWS Systems Manager Automation runbook reference User Guide

AWSConfigRemediation-EnableRDSInstanceBackup

Databases

Parameters

ApplyImmediately

Type: Boolean
Default: false

Description: (Optional) If you specify true for this parameter, the modifications in this request and any pending modifications are asynchronously applied as soon as possible, regardless of the PreferredMaintenanceWindow setting for the DB instance.

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· BackupRetentionPeriod

Type: Integer

Valid values: 1-35

Description: (Required) The number of days that backups are retained.

DbiResourceId

Type: String

Description: (Required) The resource identifier for the DB instance you want to enable backups for.

PreferredBackupWindow

Type: String

Description: (Optional) The daily time range (in UTC) during which backups are created.

Constraints:

- Must be in the format hh24:mi-hh24:mi
- Must be in Coordinated Universal Time (UTC)
- · Must not conflict with the preferred maintenance window
- Must be at least 30 minutes

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- rds:DescribeDBInstances
- rds:ModifyDBInstance

Document Steps

EnableRDSInstanceDeletionProtection

• aws:executeScript - Gathers the DB instance identifier from the DB instance resource identifier. Enables backups for your DB instance. Confirms backups are enabled on the DB instance.

AWSConfigRemediation-EnableRDSInstanceDeletionProtection

Description

The AWSConfigRemediation-EnableRDSInstanceDeletionProtection runbook enables deletion protection on the Amazon RDS database instance you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

ApplyImmediately

Type: Boolean

Default: false

Description: (Optional) If you specify true for this parameter, the modifications in this request and any pending modifications are asynchronously applied as soon as possible, regardless of the PreferredMaintenanceWindow setting for the DB instance.

• AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DbInstanceResourceId

Type: String

Description: (Required) The resource identifier for the DB instance you want to enable deletion protection on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

• ssm:StartAutomationExecution

ModifyRDSInstancePortNumber

- ssm:GetAutomationExecution
- rds:DescribeDBInstances
- rds:ModifyDBInstance

Document Steps

- aws:executeAwsApi Gathers the DB instance identifier from the DB instance resource identifier.
- aws:executeAwsApi Enables deletion protection on your DB instance.
- aws:assertAwsResourceProperty Confirms deletion protection is enabled on the DB instance.

AWSConfigRemediation-ModifyRDSInstancePortNumber

Description

The AWSConfigRemediation-ModifyRDSInstancePortNumber runbook modifies the port number on which the Amazon Relational Database Service (Amazon RDS) instance accepts connections. Running this automation will restart the database.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

PortNumber

Type: String

Description: (Optional) The port number you want the DB instance to accept connections on.

RDSDBInstanceResourceId

Type: String

Description: (Required) The resource identifier for the DB instance whose inbound port number you want to modify.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ModifyRDSSnapshotPermission

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- rds:DescribeDBInstances
- rds:ModifyDBInstance

Document Steps

- aws:executeAwsApi Gathers the DB instance identifier from the DB instance resource identifier.
- aws:assertAwsResourceProperty Confirms the DB Instance is in an AVAILABLE state.
- aws:executeAwsApi Modifies the inbound port number on which your DB instance accepts connections.
- aws:waitForAwsResourceProperty Waits for the DB Instance to be in a MODIFYING state.
- aws:waitForAwsResourceProperty Waits for the DB Instance to be in in an AVAILABLE state.

AWSSupport-ModifyRDSSnapshotPermission

Description

The AWSSupport-ModifyRDSSnapshotPermission runbook helps you modify permissions for multiple Amazon Relational Database Service (Amazon RDS) snapshots. Using this runbook, you can make snapshots Public or Private and share them with other AWS accounts. Snapshots encrypted with a default KMS key can't be shared with other accounts using this runbook.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Accountlds

Type: StringList

Default: none

AWS Systems Manager Automation runbook reference User Guide

AWSSupport-ModifyRDSSnapshotPermission

Description: (Optional) The IDs of the accounts you want to share snapshots with. This parameter is required if you enter No for the value of the Private parameter.

• AccountPermissionOperation

Type: String

Valid values: add | remove

Default: none

Description: (Optional) The type of operation to perform.

Private

Type: String

Valid values: Yes | No

Description: (Required) Enter No for the value if you want to share snapshots with specific accounts.

SnapshotIdentifiers

Type: StringList

Description: (Required) The names of the Amazon RDS snapshots whose permission you want to modify.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- rds:DescribeDBSnapshots
- rds:ModifyDBSnapshotAttribute

Document Steps

- aws:executeScript Verifies the IDs of the snapshots provided in the SnapshotIdentifiers
 parameter. After verifying the IDs, the script checks for encrypted snapshots and outputs a list if any
 are found.
- 2. aws:branch Branches the automation based on the value you enter for the Private parameter.
- aws:executeScript Modifies permissions of the snapshots specified to share it with the accounts specified.
- aws:executeScript Modifies permissions of the snapshots to change them from Public to Private.

Outputs

ValidateSnapshots.EncryptedSnapshots

SharewithOtherAccounts.Result

MakePrivate.Result

MakePrivate.Commands

AWS-RebootRdsInstance

Description

The AWS-RebootRdsInstance runbook reboots an Amazon Relational Database Service (Amazon RDS) DB instance if it isn't already rebooting.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) The ID of the Amazon RDS DB instance that you want to reboot.

Document Steps

RebootInstance - Reboots the DB instance if it is not already rebooting.

WaitForAvailableState - Waits for the DB instance to complete the reboot process.

Outputs

This automation has no outputs.

AWSSupport-ShareRDSSnapshot

Description

The AWSSupport-ShareRDSSnapshot runbook provides an automated solution for the procedure outlined in the Knowledge Center article How can I share an encrypted Amazon RDS DB snapshot with another account? If your Amazon Relational Database Service (Amazon RDS) snapshot was encrypted using the default AWS managed key, you cannot share the snapshot. In this case, you must copy the snapshot using a customer managed key, and then share the snapshot with the target account. This automation performs these steps using the value you specify in the SnapshotName parameter, or the latest snapshot found for the selected Amazon RDS DB instance or cluster.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ShareRDSSnapshot

Note

If you do not specify a value for the KMSKey parameter, the automation creates a new AWS KMS customer managed key in your account that is used to encrypt the snapshot.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

Accountlds

Type: StringList

Description: (Required) Comma-separated list of account IDs to share the snapshot with.

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Database

Type: String

Description: (Required) The name of the Amazon RDS DB instance or cluster whose snapshot you want to share. This parameter is optional if you specify a value for the SnapshotName parameter.

KMSKey

Type: String

Description: (Optional) The full Amazon Resource Name (ARN) of the AWS KMS customer managed key used to encrypt the snapshot.

SnapshotName

Type: String

Description: (Optional) The ID of the DB cluster or instance snapshot that you want to use.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- rds:DescribeDBInstances
- rds:DescribeDBSnapshots

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ShareRDSSnapshot

- rds:CopyDBSnapshot
- rds:ModifyDBSnapshotAttribute

The AutomationAssumeRole requires the following actions to successfully start the runbook for a DB cluster.

- ssm:StartAutomationExecution
- rds:DescribeDBClusters
- rds:DescribeDBClusterSnapshots
- rds:CopyDBClusterSnapshot
- rds:ModifyDBClusterSnapshotAttribute

The IAM role used to run the automation must be added as a key user to use the KMS key specified in the ARNKmsKey parameter. For information about adding key users to a KMS key, see Changing a key policy in the AWS Key Management Service Developer Guide.

The AutomationAssumeRole requires the following additional actions to successfully start the runbook if you do not specify a value for the KMSKey parameter.

- kms:CreateKey
- kms:ScheduleKeyDeletion

Document Steps

- 1. aws:executeScript Checks whether a value was provided for the KMSKey parameter, and creates a AWS KMS customer managed key if no value is found.
- 2. aws:branch Checks whether a value was provided for the SnapshotName parameter, and branches accordingly.
- 3. aws:executeAwsApi Checks whether the snapshot provided is from a DB instance.
- 4. aws:executeScript Formats the SnapshotName parameter replacing colons with a hyphen.
- 5. aws:executeAwsApi Copies the snapshot using the specified KMSKey.
- 6. aws:waitForAwsResourceProperty Waits for the copy snapshot operation to complete.
- 7. aws:executeAwsApi Shares the new snapshot with the AccountIds specified.
- 8. aws:executeAwsApi Checks whether the snapshot provided is from a DB cluster.
- 9. aws:executeScript Formats the SnapshotName parameter replacing colons with a hyphen.
- 10aws:executeAwsApi Copies the snapshot using the specified KMSKey.
- 11aws:waitForAwsResourceProperty Waits for the copy snapshot operation to complete.
- 12aws:executeAwsApi Shares the new snapshot with the AccountIds specified.
- 13aws:executeAwsApi Checks whether the value provided for the Database parameter is a DB instance.
- 14aws:executeAwsApi Checks whether the value provided for the Database parameter is a DB cluster.
- 15aws:executeAwsApi Retrieves a list of snapshots for the specified Database.
- 16aws: executeScript Determines the latest snapshot available from the list assembled in the previous step.
- 17aws:executeAwsApi Copies the DB instance snapshot using the specified KMSKey.
- 18aws:waitForAwsResourceProperty Waits for the copy snapshot operation to complete.
- 19aws:executeAwsApi Shares the new snapshot with the AccountIds specified.

AWS Systems Manager Automation runbook reference User Guide AWS-StartRdsInstance

20aws:executeAwsApi - Retrieves a list of snapshots for the specified Database.

21aws:executeScript - Determines the latest snapshot available from the list assembled in the previous step.

22aws:executeAwsApi - Copies the DB instance snapshot using the specified KMSKey.

23aws:waitForAwsResourceProperty - Waits for the copy snapshot operation to complete.

24aws:executeAwsApi - Shares the new snapshot with the AccountIds specified.

25aws:executeScript - Deletes the AWS KMS customer managed key created by the automation if you did not specify a value for the KMSKey parameter and the automation fails.

AWS-StartRdsInstance

Description

Start an Amazon Relational Database Service (Amazon RDS) instance.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) ID of the Amazon RDS instance to start.

AWSSupport-TroubleshootConnectivityToRDS

Description

The AWSSupport-TroubleshootConnectivityToRDS runbook diagnoses connectivity issues between an EC2 instance and an Amazon Relational Database Service instance. The automation ensures the DB instance is available, and then checks the associated security group rules, network access control lists (network ACLs), and route tables for potential connectivity issues.

Run this Automation (console)

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootConnectivityToRDS

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

DBInstanceIdentifier

Type: String

Description: (Required) The DB instance ID to test connectivity to.

SourceInstance

Type: String

Allowed pattern: ^i-[a-z0-9]{8,17}\$

Description: (Required) The ID of the EC2 instance to test connectivity from.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ec2:DescribeInstances
- ec2:DescribeNetworkAcls
- ec2:DescribeRouteTables
- ec2:DescribeSecurityGroups
- ec2:DescribeSubnets
- rds:DescribeDBInstances

Document Steps

- aws:assertAwsResourceProperty Confirms the DB instance status is available.
- aws:executeAwsApi Gets information about the DB instance.
- aws:executeAwsApi Gets information about the DB instance network ACLs.
- aws:executeAwsApi Gets the DB instance subnet CIDR.
- aws:executeAwsApi Gets information about the EC2 instance.
- aws:executeAwsApi Gets information about the EC2 instance network ACLs.
- aws:executeAwsApi Gets information about the security groups associated with the EC2 instance.

AWS Systems Manager Automation runbook reference User Guide Amazon Redshift

- aws:executeAwsApi Gets information about the security groups associated with the DB instance.
- aws:executeAwsApi Gets information about the route tables associated with the EC2 instance.
- aws:executeAwsApi Gets information about the main route table associated with the Amazon VPC for the EC2 instance.
- aws:executeAwsApi Gets information about the route tables associated with the DB instance.
- aws:executeAwsApi Gets information about the main route table associated with the Amazon VPC for the DB instance.
- aws:executeScript Evaluates security group rules.
- aws:executeScript Evaluates network ACLs.
- aws:executeScript Evaluates route tables.
- aws:sleep Ends the automation.

Outputs

getRDSInstanceProperties.DBInstanceIdentifier - The DB instance used in the automation.

getRDSInstanceProperties.DBInstanceStatus - The current status of the DBInstance.

evalSecurityGroupRules.SecurityGroupEvaluation - Results from comparing the SourceInstance security group rules to the DB instance security group rules.

evalNetworkAclRules.NetworkAclEvaluation - Results from comparing the SourceInstance network ACLs to the DB instance network ACLs.

evalRouteTableEntries.RouteTableEvaluation - Results from comparing the SourceInstance route table to the DB instance routes.

Amazon Redshift

AWS Systems Manager Automation provides predefined runbooks for Amazon Redshift. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-DeleteRedshiftCluster (p. 224)
- AWSConfigRemediation-DisablePublicAccessToRedshiftCluster (p. 226)
- AWSConfigRemediation-EnableRedshiftClusterAuditLogging (p. 227)
- AWSConfigRemediation-EnableRedshiftClusterAutomatedSnapshot (p. 228)
- AWSConfigRemediation-EnableRedshiftClusterEncryption (p. 229)
- AWSConfigRemediation-EnableRedshiftClusterEnhancedVPCRouting (p. 230)
- AWSConfigRemediation-EnforceSSLOnlyConnectionsToRedshiftCluster (p. 231)
- AWSConfigRemediation-ModifyRedshiftClusterMaintenanceSettings (p. 232)
- AWSConfigRemediation-ModifyRedshiftClusterNodeType (p. 234)

AWSConfigRemediation-DeleteRedshiftCluster

Description

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteRedshiftCluster

The AWSConfigRemediation-DeleteRedshiftCluster runbook deletes the Amazon Redshift cluster you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

ClusterIdentifier

Type: String

Description: (Required) The ID of the Amazon Redshift cluster that you want to delete.

SkipFinalClusterSnapshot

Type: Boolean

Default: false

Description: (Optional) If set to false, the automation creates a snapshot before deleting the Amazon Redshift cluster. If set to true, a final cluster snapshot is not created.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- redshift:DeleteCluster
- redshift:DescribeClusters

Document Steps

- aws:branch Branches based on the value you specify for the SkipFinalClusterSnapshot parameter.
- aws:executeAwsApi Deletes the Amazon Redshift cluster specified in the ClusterIdentifier parameter.

DisablePublicAccessToRedshiftCluster

• aws:assertAwsResourceProperty - Verifies the Amazon Redshift cluster has been deleted.

AWSConfigRemediation-DisablePublicAccessToRedshiftCluster

Description

The AWSConfigRemediation-DisablePublicAccessToRedshiftCluster runbook disables public accessibility for the Amazon Redshift cluster that you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: $\arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

ClusterIdentifier

Type: String

Description: (Required) The unique identifier of the cluster that you want to disable public accessibility for.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- redshift:DescribeClusters
- redshift:ModifyCluster

Document Steps

• aws:executeAwsApi - Disables public accessibility for the cluster specified in the ClusterIdentifier parameter.

EnableRedshiftClusterAuditLogging

- aws:waitForAwsResourceProperty Waits for the state of the cluster to change to available.
- aws:assertAwsResourceProperty Confirms the public accessibility setting is disabled on the cluster.

AWSConfigRemediation-EnableRedshiftClusterAuditLogging

Description

The AWSConfigRemediation-EnableRedshiftClusterAuditLogging runbook enables audit logging for the Amazon Redshift cluster you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

BucketName

Type: String

Description: (Required) The name of the Amazon Simple Storage Service (Amazon S3) bucket you want to upload logs to.

ClusterIdentifier

Type: String

Description: (Required) The unique identifier of the cluster you want to enable audit logging on.

S3KeyPrefix

Type: String

Description: (Optional) The Amazon S3 key prefix (subfolder) you want to upload logs to.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

${\tt Enable Red Shift Cluster Automated Snap shot}$

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- redshift:DescribeLoggingStatus
- redshift: EnableLogging
- s3:GetBucketAcl
- s3:PutObject

Document Steps

- aws:branch Branches based on whether a value was specified for the S3KeyPrefix parameter.
- aws:executeAwsApi Enables audit logging on the cluster specified in the ClusterIdentifier parameter.
- aws:assertAwsResourceProperty Verifies audit logging was enabled on the cluster.

AWSConfigRemediation-EnableRedshiftClusterAutomatedSnapshot

Description

The AWSConfigRemediation-EnableRedshiftClusterAutomatedSnapshot runbook enables automated snapshots for the Amazon Redshift cluster you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· AutomatedSnapshotRetentionPeriod

Type: Integer

Valid values: 1-35

Description: (Required) The number of days that automated snapshots are retained.

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnableRedshiftClusterEncryption

ClusterIdentifier

Type: String

Description: (Required) The unique identifier of the cluster you want to enable automated snapshots on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- redshift:DescribeClusters
- redshift:ModifyCluster

Document Steps

- aws:executeAwsApi Enables automation snapshots on the cluster specified in the ClusterIdentifier parameter.
- aws:waitForAwsResourceProperty Waits for the state of the cluster to change to available.
- aws:executeScript Confirms automated snapshots were enabled on the cluster.

AWSConfigRemediation-EnableRedshiftClusterEncryption

Description

The AWSConfigRemediation-EnableRedshiftClusterEncryption runbook enables encryption on the Amazon Redshift cluster you specify using an AWS Key Management Service (AWS KMS) customer managed key. This runbook should only be used as a baseline to ensure that your Amazon Redshift clusters are encrypted according to minimum recommended security best practices. We recommend encrypting multiple clusters with different customer managed keys. This runbook cannot change the AWS KMS customer managed key used on an already encrypted cluster. To change the AWS KMS customer managed key used to encrypt a cluster, you must first disable encryption on the cluster.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

EnableRedshiftClusterEnhancedVPCRouting

Allowed values: \(^arn:(?:aws\)aws-us-gov\]aws-cn\):iam::\\(d\{12\}:role\/[\w+=,.@/-]+\\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

ClusterIdentifier

Type: String

Description: (Required) The unique identifier of the cluster you want to enable encryption on.

KMSKeyARN

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the AWS KMS customer managed key you want to use to encrypt the cluster's data.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- redshift:DescribeClusters
- redshift:ModifyCluster

Document Steps

- aws:executeAwsApi Enables encryption on the Amazon Redshift cluster specified in the ClusterIdentifier parameter.
- aws:assertAwsResourceProperty Verifies encryption has been enabled on the cluster.

AWSConfigRemediation-EnableRedshiftClusterEnhancedVPCRouting

Description

The AWSConfigRemediation-EnableRedshiftClusterEnhancedVPCRouting runbook enables enhanced virtual private cloud (VPC) routing for the Amazon Redshift cluster you specify. For information about enhanced VPC routing, see Amazon Redshift enhanced VPC routing in the Amazon Redshift Cluster Management Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

EnforceSSLOnlyConnectionsToRedshiftCluster

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

ClusterIdentifier

Type: String

Description: (Required) The unique identifier of the cluster you want to enable enhanced VPC routing on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- redshift:DescribeClusters
- redshift:ModifyCluster

Document Steps

- aws:executeAwsApi Enables enhanced VPC routing on the cluster specified in the ClusterIdentifier parameter.
- assertAwsResourceProperty Confirms enhanced VPC routing was enabled on the cluster.

AWSConfigRemediation-EnforceSSLOnlyConnectionsToRedshiftCluster

Description

The AWSConfigRemediation-EnforceSSLOnlyConnectionsToRedshiftCluster runbook requires incoming connections to use SSL for the Amazon Redshift cluster you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

ModifyRedshiftClusterMaintenanceSettings

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

ClusterIdentifier

Type: String

Description: (Required) The unique identifier of the cluster you want to enable enhanced VPC routing on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- redshift:DescribeClusters
- redshift:DescribeClusterParameters
- redshift:ModifyClusterParameterGroup

Document Steps

- aws:executeAwsApi Gathers parameter details from the cluster specified in the ClusterIdentifier parameter.
- aws:executeAwsApi Enables the require_ssl setting on the cluster specified in the ClusterIdentifier parameter.
- aws:assertAwsResourceProperty Confirms the require_ssl setting was enabled on the cluster.
- aws:executeScript Verifies the require_ssl setting for the cluster.

AWSConfigRemediation-ModifyRedshiftClusterMaintenanceSettings

Description

The AWSConfigRemediation-ModifyRedshiftClusterMaintenanceSettings runbook modifies the maintenance settings for the Amazon Redshift cluster you specify.

Run this Automation (console)

Document type

Automation

ModifyRedshiftClusterMaintenanceSettings

Owner

Amazon

Platforms

Databases

Parameters

AllowVersionUpgrade

Type: Boolean

Description: (Required) If set to true, major version upgrades are applied automatically to the cluster during the maintenance window.

• AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· AutomatedSnapshotRetentionPeriod

Type: Integer

Valid values: 1-35

Description: (Required) The number of days automated snapshots are retained.

ClusterIdentifier

Type: String

Description: (Required) The unique identifier of the cluster you want to enable enhanced VPC routing on.

PreferredMaintenanceWindow

Type: String

Description: (Required) The weekly time range (in UTC) during which system maintenance can occur.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- redshift:DescribeClusters
- redshift:ModifyCluster

Document Steps

 aws:executeAwsApi - Modifies the maintenance settings for the cluster specified in the ClusterIdentifier parameter.

ModifyRedshiftClusterNodeType

 aws:assertAwsResourceProperty - Confirms the modified maintenance settings were configured for the cluster.

AWSConfigRemediation-ModifyRedshiftClusterNodeType

Description

The AWSConfigRemediation-ModifyRedshiftClusterNodeType runbook modifies the node type and number of nodes for the Amazon Redshift cluster you specify.

Run this Automation (console)

| Do | CII | m | ent | tν | ne |
|----|-----|---|-----|----|--------|
| | ··· | | | | \sim |

Automation

Owner

Amazon

Platforms

Databases

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Classic

Type: Boolean

Description: (Optional) If set to true, the resize operation uses the classic resize process.

ClusterIdentifier

Type: String

Description: (Required) The unique identifier of the cluster whose node type you want to modify.

ClusterType

Type: String

Valid values: single-node | multi-node

Description: (Required) The type of cluster you want to assign to your cluster.

NodeType

Type: String

AWS Systems Manager Automation runbook reference User Guide Amazon S3

Valid values: ds2.xlarge | ds2.8xlarge | dc1.large | dc1.8xlarge | dc2.large | dc2.8xlarge | ra3.4xlarge | ra3.16xlarge

Description: (Required) The type of node you want to assign to your cluster.

NumberOfNodes

Type: Integer

Valid values: 2-100

Description: (Optional) The number of nodes you want to assign to your cluster. If your cluster is a single-node type, do not specify a value for this parameter.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- redshift:DescribeClusters
- redshift:ResizeCluster

Document Steps

 aws:executeScript - Modifies the node type and number of nodes for the cluster specified in the ClusterIdentifier parameter.

Amazon S3

AWS Systems Manager Automation provides predefined runbooks for Amazon Simple Storage Service. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWS-ConfigureS3BucketLogging (p. 235)
- AWS-ConfigureS3BucketVersioning (p. 237)
- AWSConfigRemediation-ConfigureS3BucketPublicAccessBlock (p. 238)
- AWSConfigRemediation-ConfigureS3PublicAccessBlock (p. 239)
- AWS-DisableS3BucketPublicReadWrite (p. 241)
- AWS-EnableS3BucketEncryption (p. 241)
- AWSConfigRemediation-RemovePrincipalStarFromS3BucketPolicy (p. 242)
- AWSConfigRemediation-RestrictBucketSSLRequestsOnly (p. 243)
- AWSSupport-TroubleshootS3PublicRead (p. 244)

AWS-ConfigureS3BucketLogging

Description

Enable logging on an Amazon Simple Storage Service (Amazon S3) bucket.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

BucketName

Type: String

Description: (Required) The name of the Amazon S3 Bucket for which you want to configure logging.

• GrantedPermission

Type: String

Valid values: FULL_CONTROL | READ | WRITE

Description: (Required) Logging permissions assigned to the grantee for the bucket.

GranteeEmailAddress

Type: String

(Optional) Email address of the grantee.

Granteeld

Type: String

Description: (Optional) The canonical user ID of the grantee.

GranteeType

Type: String

Valid values: CanonicalUser | AmazonCustomerByEmail | Group

Description: (Required) Type of grantee.

GranteeUri

Type: String

Description: (Optional) URI of the grantee group.

TargetBucket

AWS Systems Manager Automation runbook reference User Guide AWS-ConfigureS3BucketVersioning

Type: String

Description: (Required) Specifies the bucket where you want Amazon S3 to store server access logs. You can have your logs delivered to any bucket that you own. You can also configure multiple buckets to deliver their logs to the same target bucket. In this case you should choose a different TargetPrefix for each source bucket so that the delivered log files can be distinguished by key.

TargetPrefix

Type: String

Default: /

Description: (Optional) Specifies a prefix for the keys under which the log files will be stored.

AWS-ConfigureS3BucketVersioning

Description

Configure versioning for an Amazon Simple Storage Service (Amazon S3) bucket.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

BucketName

Type: String

Description: (Required) The name of the Amazon S3 bucket you want to configure versioning for.

VersioningState

Type: String

Valid values: Enabled | Suspended

Default: Enabled

Description: (Optional) Applied to the VersioningConfiguration. Status. When set to 'Enabled', this process enables versioning for the objects in the bucket, all objects added to the bucket receive a

ConfigureS3BucketPublicAccessBlock

unique version ID. When set to Suspended, this process disables versioning for the objects in the bucket. All objects added to the bucket receive the version ID null.

AWSConfigRemediation-ConfigureS3BucketPublicAccessBlock

Description

The AWSConfigRemediation-ConfigureS3BucketPublicAccessBlock runbook configures the Amazon Simple Storage Service (Amazon S3) public access block settings for an Amazon S3 bucket based on the values you specify in the runbook parameters.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

BlockPublicAcls

Type: Boolean

Default: true

Description: (Optional) If set to true, Amazon S3 blocks public access control lists (ACLs) for the S3 bucket, and objects stored in the S3 bucket you specify in the BucketName parameter.

BlockPublicPolicy

Type: Boolean

Default: true

Description: (Optional) If set to true, Amazon S3 blocks public bucket policies for the S3 bucket you specify in the BucketName parameter.

BucketName

Type: String

Description: (Required) The name of the S3 bucket you want to configure.

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-ConfigureS3PublicAccessBlock

IgnorePublicAcls

Type: Boolean
Default: true

Description: (Optional) If set to true, Amazon S3 ignores all public ACLs for the S3 bucket you specify in the BucketName parameter.

RestrictPublicBuckets

Type: Boolean
Default: true

Description: (Optional) If set to true, Amazon S3 restricts public bucket policies for the S3 bucket you specify in the BucketName parameter.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- s3:GetAccountPublicAccessBlock
- s3:PutAccountPublicAccessBlock
- s3:GetBucketPublicAccessBlock
- s3:PutBucketPublicAccessBlock

Document Steps

- aws:executeAwsApi Creates or modifies the PublicAccessBlock configuration for the S3 bucket specified in the BucketName parameter.
- aws:executeScript Returns the PublicAccessBlock configuration for the S3 bucket specified
 in the BucketName parameter, and verifies the changes were successfully made based on the values
 specified in the runbook parameters.

AWSConfigRemediation-ConfigureS3PublicAccessBlock

Description

The AWSConfigRemediation-ConfigureS3PublicAccessBlock runbook configures an AWS account's Amazon Simple Storage Service (Amazon S3) public access block settings based on the values you specify in the runbook parameters.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-ConfigureS3PublicAccessBlock

Platforms

Linux, macOS, Windows

Parameters

AccountId

Type: String

Description: (Required) The ID of the AWS account that owns the S3 bucket you are configuring.

· AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

• BlockPublicAcls

Type: Boolean

Default: true

Description: (Optional) If set to true, Amazon S3 blocks public access control lists (ACLs) for S3 buckets owned by the AWS account you specify in the Account1d parameter.

BlockPublicPolicy

Type: Boolean

Default: true

Description: (Optional) If set to true, Amazon S3 blocks public bucket policies for S3 buckets owned by the AWS account you specify in the AccountId parameter.

IgnorePublicAcls

Type: Boolean

Default: true

Description: (Optional) If set to true, Amazon S3 ignores all public ACLs for S3 buckets owned by the AWS account you specify in the AccountId parameter.

RestrictPublicBuckets

Type: Boolean

Default: true

Description: (Optional) If set to true, Amazon S3 restricts public bucket policies for S3 buckets owned by the AWS account you specify in the AccountId parameter.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

- s3:GetAccountPublicAccessBlock
- s3:PutAccountPublicAccessBlock

Document Steps

- aws:executeAwsApi Creates or modifies the PublicAccessBlock configuration for the AWS account specified in the AccountId parameter.
- aws:executeScript Returns the PublicAccessBlock configuration for the AWS account specified in the AccountId parameter, and verifies the changes were successfully made based on the values specified in the runbook parameters.

AWS-DisableS3BucketPublicReadWrite

Description

Use Amazon Simple Storage Service (Amazon S3) Block Public Access to disable read and write access for a public S3 bucket. For more information, see Using Amazon S3 Block Public Access in the Amazon Simple Storage Service User Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

S3BucketName

Type: String

Description: (Required) S3 bucket on which you want to restrict access.

AWS-EnableS3BucketEncryption

Description

Enable encryption for an Amazon Simple Storage Service (Amazon S3) bucket (encrypt the contents of the bucket).

RemovePrincipalStarFromS3BucketPolicy

Run this Automation (console)

| Document | : tvpe |
|-----------------|--------|
|-----------------|--------|

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

BucketName

Type: String

Description: (Required) The name of the S3 bucket where you want to encrypt the contents.

· SSEAlgorithm

Type: String

Default: AES256

Description: (Optional) Server-side encryption algorithm to use for the default encryption.

AWSConfigRemediation-RemovePrincipalStarFromS3BucketPolicy

Description

The AWSConfigRemediation—RemovePrincipalStarFromS3BucketPolicy runbook removes principal policy statements that have wildcards (Principal: * or Principal: "AWS": *) for Allow actions from your Amazon Simple Storage Service (Amazon S3) bucket policy. Policy statements with conditions are also removed.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-RestrictBucketSSLRequestsOnly

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

BucketName

Type: String

Description: (Required) The name of the Amazon S3 bucket whose policy you want to modify.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- s3:DeleteBucketPolicy
- s3:GetBucketPolicy
- s3:PutBucketPolicy

Document Steps

• aws:executeScript - Modifies the bucket policy and verifies principal policy statements with wildcards have been removed from the Amazon S3 bucket you specify in the BucketName parameter.

AWSConfigRemediation-RestrictBucketSSLRequestsOnly

Description

The AWSConfigRemediation-RestrictBucketSSLRequestsOnly runbook creates an Amazon Simple Storage Service (Amazon S3) bucket policy statement that explicitly denies HTTP requests to the Amazon S3 bucket you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootS3PublicRead

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

BucketName

Type: String

Description: (Required) The name of the S3 bucket that you want to deny HTTP requests.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- s3:DeleteBucketPolicy
- s3:GetBucketPolicy
- s3:PutEncryptionConfiguration
- s3:PutBucketPolicy

Document Steps

 aws:executeScript - Creates a bucket policy for the S3 bucket specified in the BucketName parameter that explicitly denies HTTP requests.

AWSSupport-TroubleshootS3PublicRead

Description

The AWSSupport-TroubleshootS3PublicRead runbook diagnoses issues reading objects from the public Amazon Simple Storage Service (Amazon S3) bucket you specify in the S3BucketName parameter. A subset of settings are also analyzed for objects in the S3 bucket.

Run this Automation (console)

Limitations

- This automation does not check for access points that allow public access to objects.
- This automation does not evaluate condition keys in the S3 bucket policy.
- If you're using AWS Organizations, this automation does not evaluate service control policies to confirm that access to Amazon S3 is allowed.

Document type

Automation

Owner

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootS3PublicRead

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

CloudWatchLogGroupName

Type: String

Description: (Optional) The Amazon CloudWatch Logs log group where you want to send the automation output. If a log group is not found that matches the value you specify, the automation will create a log group using this parameter value. The retention period for the log group created by this automation is 14 days.

CloudWatchLogStreamName

Type: String

Description: (Optional) The CloudWatch Logs log stream where you want to send the automation output. If a log stream is not found that matches the value you specify, the automation will create a log stream using this parameter value. If you do not specify a value for this parameter, the automation will use the ExecutionId for the name of the log stream.

HttpGet

Type: Boolean

Valid values: true | false

Default: true

Description: (Optional) If this parameter is set to true, the automation makes a partial HTTP request to the objects in the S3BucketName you specify. Only the first byte of the object is returned using the Range HTTP header.

IgnoreBlockPublicAccess

Type: Boolean

Valid values: true | false

Default: false

Description: (Optional) If this parameter is set to true, the automation ignores the public access block settings of the S3 bucket you specify in the S3BucketName parameter. Changing this parameter from the default value is not recommended.

MaxObjects

Type: Integer

Valid values: 1-25

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootS3PublicRead

Default: 5

Description: (Optional) The number of objects to analyze in the S3 bucket you specify in the S3BucketName parameter.

S3BucketName

Type: String

Description: (Required) The name of the S3 bucket to troubleshoot.

S3PrefixName

Type: String

Description: (Optional) The key name prefix of the objects you want to analyze in your S3 bucket. For more information, see Object keys in the Amazon Simple Storage Service User Guide.

StartAfter

Type: String

Description: (Optional) The object key name where you want the automation to begin analyzing objects in your S3 bucket.

ResourcePartition

Type: String

Valid values: aws | aws-us-gov | aws-cn

Default: aws

Description: (Required) The partition where your S3 bucket is located.

Verbose

Type: Boolean

Valid values: true | false

Default: false

Description: (Optional) To return more detailed information during the automation, set this parameter to true. Only warning and error messages will be returned if the parameter is set to false.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

The logs:CreateLogGroup, logs:CreateLogStream, and logs:PutLogEvents permissions are only required if you want the automation to send log data to CloudWatch Logs.

```
"logs:PutLogEvents",
                "logs:PutRetentionPolicy",
                "s3:GetAccountPublicAccessBlock"
            "Resource": "*",
            "Effect": "Allow"
        },
            "Action": [
                "s3:GetObject",
                "s3:GetObjectAcl",
                "s3:GetObjectTagging"
            "Resource": "arn:aws:s3:::awsexamplebucket1/*",
            "Effect": "Allow"
        },
            "Action": [
                "s3:ListBucket",
                "s3:GetBucketLocation",
                "s3:GetBucketPublicAccessBlock",
                "s3:GetBucketRequestPayment",
                "s3:GetBucketPolicyStatus",
                "s3:GetBucketPolicy",
                "s3:GetBucketAcl"
            "Resource": "arn:aws:s3:::awsexamplebucket1",
            "Effect": "Allow"
        }
    ]
}
```

Document Steps

- aws:assertAwsResourceProperty Confirms the S3 bucket exists, and is accessible.
- aws:executeScript Returns the S3 bucket location and your canonical user ID.
- aws:executeScript Returns the public access block settings for your account and the S3 bucket.
- aws:assertAwsResourceProperty Confirms the S3 bucket payer is set to BucketOwner. If Requester Pays is enabled on the S3 bucket, the automation ends.
- aws:executeScript Returns the S3 bucket policy status and determines whether it is considered public. For more information about public S3 buckets, see The meaning of "public" in the Amazon Simple Storage Service User Guide.
- aws:executeAwsApi Returns the S3 bucket policy.
- aws:executeAwsApi Returns all context keys found in the S3 bucket policy.
- aws:assertAwsResourceProperty Confirms whether there is an explicit deny in the S3 bucket policy for the GetObject API action.
- aws:executeAwsApi Returns the access control list (ACL) for the S3 bucket.
- aws:executeScript Creates a CloudWatch Logs log group and log stream if you specify a value for the CloudWatchLogGroupName parameter.
- aws:executeScript Based on the values you specify in the runbook input parameters, evaluates whether any of the S3 bucket settings gathered during the automation are preventing objects from being accessed by the public. This script performs the following functions:
 - Evaluates public access block settings
 - Returns objects from your S3 bucket based on the values you specify in the MaxObjects, S3PrefixName, and StartAfter parameters.
 - Returns the S3 bucket policy to simulate a custom IAM policy for the objects returned from your S3 bucket.

AWS Systems Manager Automation runbook reference User Guide Secrets Manager

- Performs a partial HTTP request to the returned objects if the HttpGet parameter is set to true.
 Only the first byte of the object is returned using the Range HTTP header.
- Checks the returned object's key name to confirm whether it ends with one or two periods. Object key names that end in periods can't be downloaded from the Amazon S3 console.
- Checks whether the returned object's owner matches the owner of the S3 bucket.
- · Checks whether the object's ACL grants READ or FULL_CONTROL permissions to anonymous users.
- · Returns tags associated with the object.
- Uses the simulated IAM policy to confirm whether there is an explicit deny for this object in the S3 bucket policy for the GetObject API action.
- Returns the object's metadata to confirm that the storage class is supported.
- Checks the object's server-side encryption settings to confirm whether the object is encrypted using a AWS Key Management Service (AWS KMS) customer managed key.

Outputs

AnalyzeObjects.bucket

AnalyzeObjects.object

Secrets Manager

AWS Systems Manager Automation provides predefined runbooks for AWS Secrets Manager. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-DeleteSecret (p. 248)
- AWSConfigRemediation-RotateSecret (p. 249)

AWSConfigRemediation-DeleteSecret

Description

The AWSConfigRemediation-RotateSecret runbook deletes a secret and all of the versions stored in AWS Secrets Manager. You can optionally specify the recovery window during which you can restore the secret. If you don't specify a value for the RecoveryWindowInDays parameter, the operation defaults to 30 days.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-RotateSecret

AutomationAssumeRole

Type: String

Allowed values: $\arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

RecoveryWindowInDays

Type: Integer

Valid values: 7-30

Default: 30

Description: (Optional) The number of days which you can restore the secret.

SecretId

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the secret you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- secretsmanager:DeleteSecret
- secretsmanager:DescribeSecret

Document Steps

- aws:executeAwsApi Deletes the secret you specify in the SecretId parameter.
- aws:executeScript Verifies the secret has been scheduled for deletion.

AWSConfigRemediation-RotateSecret

Description

The AWSConfigRemediation-RotateSecret runbook rotates a secret stored in AWS Secrets Manager.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

AWS Systems Manager Automation runbook reference User Guide Security Hub

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

RotationInterval

Type: Interval

Valid values: 1-365

Description: (Required) The number of days between rotations of the secret.

RotationLambdaArn

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the AWS Lambda funtion that can rotate the secret.

SecretId

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the secret you want to rotate.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- lambda:InvokeFunction
- secretsmanager:DescribeSecret
- secretsmanager:RotateSecret

Document Steps

- aws:executeAwsApi Rotates the secret you specify in the SecretId parameter.
- aws:executeScript Verifies rotation has been enabled on the secret.

Security Hub

AWS Systems Manager Automation provides predefined runbooks for AWS Security Hub. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

• AWSConfigRemediation-EnableSecurityHub (p. 251)

AWSConfigRemediation-EnableSecurityHub

Description

The AWSConfigRemediation-EnableSecurityHub runbook enables AWS Security Hub (Security Hub) for the AWS account and AWS Region where you run the automation. For information about Security Hub, see What is AWS Security Hub? in the AWS Security Hub User Guide.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $\arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· EnableDefaultStandards

Type: Boolean

Default: true

Description: (Required) If set to true, the default security standards designated by Security Hub are enabled.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- securityhub:DescribeHub
- securityhub:EnableSecurityHub
- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

Document Steps

• aws:executeAwsApi - Enables Security Hub in the current account and Region.

• aws:executeAwsApi - Verifies that Security Hub has been enabled.

Amazon SNS

AWS Systems Manager Automation provides predefined runbooks for Amazon Simple Notification Service. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-EncryptSNSTopic (p. 252)
- AWS-PublishSNSNotification (p. 253)

AWSConfigRemediation-EncryptSNSTopic

Description

The AWSConfigRemediation-EncryptSNSTopic runbook enables encryption on the Amazon Simple Notification Service (Amazon SNS) topic you specify using an AWS Key Management Service (AWS KMS) customer managed key. This runbook should only be used as a baseline to ensure that your Amazon SNS topics are encrypted according to minimum recommended security best practices. We recommend encrypting multiple topics with different customer managed keys.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

KmsKeyArn

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the AWS KMS customer managed key you want to use to encrypt the Amazon SNS topic.

TopicArn

AWS Systems Manager Automation runbook reference User Guide AWS-PublishSNSNotification

Type: String

Description: (Required) The ARN of the Amazon SNS topic you want to encrypt.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- sns:GetTopicAttributes
- sns:SetTopicAttributes

Document Steps

- aws:executeAwsApi Encrypts the Amazon SNS topic you specify in the TopicArn parameter.
- aws:assertAwsResourceProperty Confirms encryption is enabled on the Amazon SNS topic.

AWS-PublishSNSNotification

Description

Publish a notification to Amazon SNS.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Message

Type: String

Description: (Required) The message to include in the SNS notification.

TopicArn

AWS Systems Manager Automation runbook reference User Guide Systems Manager

Type: String

Description: (Required) The ARN of the SNS topic to publish the notification to.

Systems Manager

AWS Systems Manager Automation provides predefined runbooks for Systems Manager. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWS-BulkEditOpsItems (p. 254)
- AWS-BulkResolveOpsItems (p. 256)
- AWS-CreateManagedLinuxInstance (p. 258)
- AWS-CreateManagedWindowsInstance (p. 259)
- AWSConfigRemediation-EnableCWLoggingForSessionManager (p. 261)
- AWS-ExportOpsDataToS3 (p. 262)
- AWS-ExportPatchReportToS3 (p. 263)
- AWS-SetupInventory (p. 265)
- AWS-SetupManagedInstance (p. 267)
- AWS-SetupManagedRoleOnEC2Instance (p. 268)
- AWSSupport-TroubleshootManagedInstance (p. 269)

AWS-BulkEditOpsItems

Description

The AWS-BulkEditOpsItems runbook helps you edit the status, severity, category, or priority of AWS Systems Manager OpsItems. This automation can edit a maximum of 50 OpsItems at a time.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your

AWS Systems Manager Automation runbook reference User Guide AWS-BulkEditOpsItems

behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Category

Type: String

Valid values:

- Availability
- Cost
- · No change
- Performance
- Recovery
- Security

Default: No change

Description: (Optional) The new category you want to specify for the edited OpsItems.

Opsitemids

Type: StringList

Description: (Required) A comma-separated list of OpsItems IDs you want to edit (for example, oi-XXXXXXXXXX,oi-XXXXXXXXXXX).

Priority

Type: String

Valid values:

- · No change
- 1
- 2
- 3
- 4
- 5

Default: No change

Description: (Optional) The importance of the edited OpsItems in relation to other OpsItems in the system.

Severity

Type: String

Valid values:

- · No change
- 1
- 2
- 3
- 4

Default: No change

Description: (Optional) The severity of the edited OpsItems.

WaitTimeBetweenEditsInSecs

AWS Systems Manager Automation runbook reference User Guide AWS-BulkResolveOpsItems

Type: String

Valid values: 0.0-2.0

Default: 0.8

Description: (Optional) The time the automation waits between calling the UpdateOpsItems operation.

Status

Type: String

Valid values:

- InProgress
- No change
- Open
- Resolved

Default: No change

Description: (Optional) The new status of the edited OpsItems.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:GetAutomationExecution
- ssm:StartAutomationExecution
- ssm:UpdateOpsItem

Document Steps

• aws:executeScript - Edits the OpsItems you specified in the OpsItemIds parameter based on the values you specify for the Category, Priority, Severity, and Status parameters.

AWS-BulkResolveOpsItems

Description

The AWS-BulkResolveOpsItems runbook resolves AWS Systems Manager OpsItems that match the filter you specify. You can also specify an OpsItemId to add to the resolved OpsItems using the OpsInsightsId parameter. If you specify a value for the S3BucketName parameter, a result summary is sent to the Amazon Simple Storage Service (Amazon S3) bucket. To receive a notification once the result summary has been sent to the Amazon S3 bucket, specify a value for the SnsTopicArn parameter. This automation will resolve a maximum of 1,000 OpsItems at a time.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide AWS-BulkResolveOpsItems

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Filters

Type: String

Description: (Required) The key-value pairs of filters to return the OpsItems you want to resolve. For example, [{"Key": "Status", "Values": ["Open"], "Operator": "Equals"}]. To learn more about the options available for filtering OpsItems responses, see OpsItemFilters in the AWS Systems Manager API Reference.

· OpsInsightId

Type: String

Description: (Optional) The related resource identifier you want to add to resolved OpsItems.

S3BucketName

Type: String

Description: (Optional) The name of the Amazon S3 bucket you want to send the result summary to.

SnsMessage

Type: String

Description: (Optional) The notification you want Amazon Simple Notification Service (Amazon SNS) to send when the automation completes.

SnsTopicArn

Type: String

Description: (Optional) The ARN of the Amazon SNS topic you want to notify when the result summary has been sent to Amazon S3.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- s3:GetBucketAcl
- s3:PutObject
- sns:Publish
- ssm:DescribeOpsItems
- ssm:GetAutomationExecution
- ssm:StartAutomationExecution
- ssm:UpdateOpsItem

Document Steps

- aws:executeScript Gathers and resolves the OpsItems based on the filters you specify. If you specified a value for the OpsInsightId parameter, the value is added as a related resource.
- aws:executeScript If you specified a value for the S3BucketName parameter, a result summary is then sent to the Amazon S3 bucket.
- aws:executeScript If you specified a value for the SnsTopicArn parameter, a notification is sent to the Amazon SNS topic after the result summary has been sent to Amazon S3 including the SnsMessage parameter value if specified.

AWS-CreateManagedLinuxInstance

Description

Create an EC2 instance for Linux that is configured for Systems Manager.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux

Parameters

Amild

Type: String

Description: (Required) AMI ID to use for launching the instance.

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

GroupName

Type: String

Default: SSMSecurityGroupForLinuxInstances

Description: (Required) Security group name to create.

InstanceType

Type: String

Default: t2.medium

AWS Systems Manager Automation runbook reference User Guide

AWS-CreateManagedWindowsInstance

Description: (Required) Type of instance to launch. Default is t2.medium.

KeyPairName

Type: String

Description: (Required) Key pair to use when creating instance.

RemoteAccessCidr

Type: String

Default: 0.0.0.0/0

Description: (Required) Creates Security group with port for SSH(Port range 22) open to IPs specified by CIDR (default is 0.0.0.0/0). If the security group already exists it will not be modified and rules will not be changed.

RoleName

Type: String

Default: SSMManagedInstanceProfileRole

Description: (Required) Role name to create.

StackName

Type: String

Default: CreateManagedInstanceStack{{automation:EXECUTION_ID}}

Description: (Optional) Specify stack name used by this runbook

SubnetId

Type: String

Default: Default

Description: (Required) New instance will be deployed into this subnet or in the default subnet if not specified.

VpcId

Type: String

Default: Default

Description: (Required) New instance will be deployed into this Amazon Virtual Private Cloud (Amazon VPC) or in the default Amazon VPC if not specified.

AWS-CreateManagedWindowsInstance

Description

Create an EC2 instance for a Windows Server that is configured for Systems Manager.

Run this Automation (console)

Document type

Automation

AWS Systems Manager Automation runbook reference User Guide AWS-CreateManagedWindowsInstance

| Owner |
|-------|
|-------|

Amazon

Platforms

Windows

Parameters

Parameters

Amild

Type: String

Default: {{ssm:/aws/service/ami-windows-latest/Windows_Server-2016-English-Full-Base}}

Description: (Required) AMI ID to use for launching the instance.

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

GroupName

Type: String

Default: SSMSecurityGroupForLinuxInstances

Description: (Required) Security group name to create.

InstanceType

Type: String

Default: t2.medium

Description: (Required) Type of instance to launch. Default is t2.medium.

KeyPairName

Type: String

Description: (Required) Key pair to use when creating instance.

RemoteAccessCidr

Type: String

Default: 0.0.0.0/0

Description: (Required) Creates security group with port for RDP (Port range 3389) open to IPs specified by CIDR (default is 0.0.0.0/0). If the security group already exists it will not be modified and rules will not be changed.

RoleName

Type: String

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableCWLoggingForSessionManager

Default: SSMManagedInstanceProfileRole

Description: (Required) Role name to create.

StackName

Type: String

Default: CreateManagedInstanceStack{{automation:EXECUTION_ID}}

Description: (Optional) Specify stack name used by this runbook

SubnetId

Type: String

Default: Default

Description: (Required) New instance will be deployed into this subnet or in the default subnet if not specified.

Vpcld

Type: String

Default: Default

Description: (Required) New instance will be deployed into this Amazon Virtual Private Cloud (Amazon VPC) or in the default Amazon VPC if not specified.

AWSConfigRemediation-EnableCWLoggingForSessionManager

Description

The AWSConfigRemediation-EnableCWLoggingForSessionManager runbook enables AWS Systems Manager Session Manager (Session Manager) sessions to store output logs to an Amazon CloudWatch (CloudWatch) log group.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $^{r.}(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

AWS Systems Manager Automation runbook reference User Guide AWS-ExportOpsDataToS3

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DestinationLogGroup

Type: String

Description: (Required) The name of the CloudWatch log group.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:GetDocument
- ssm:UpdateDocument
- ssm:CreateDocument
- ssm:UpdateDefaultDocumentVersion
- ssm:DescribeDocument

Document Steps

• aws:executeScript - Accepts the CloudWatch log group to update the document which stores Session Manager session output logs preferences, or creates one if it doesn't exist.

AWS-ExportOpsDataToS3

Description

This runbook retrieves a list of OpsData summaries in AWS Systems Manager Explorer and exports them to an object in a specified Amazon Simple Storage Service (Amazon S3) bucket.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your

AWS Systems Manager Automation runbook reference User Guide AWS-ExportPatchReportToS3

behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

columnFields

Type: StringList

Description: (Required) Column fields to write to the output file.

filters

Type: String

Description: (Optional) Filters for the getOpsSummary request.

resultAttribute

Type: String

Description: (Optional) The result attribute for getOpsSummary request.

s3BucketName

Type: String

Description: (Required) S3 bucket where you want to download the output file.

snsSuccessMessage

Type: String

Description: (Optional) Message to send when runbook finishes.

snsTopicArn

Type: String

Description: (Required) Amazon Simple Notification Service (Amazon SNS) topic ARN to notify when the download completes.

syncName

Type: String

Description: (Optional) The name of the resource data sync.

Document Steps

getOpsSummaryStep - Retrieves up to 5,000 ops summaries to export in a CSV file now.

Outputs

OpsData object – If the runbook runs successfully, you will find the exported OpsData object in your target S3 bucket.

AWS-ExportPatchReportToS3

Description

This runbook retrieves lists of patch summary data and patch details in AWS Systems Manager Patch Manager and exports them to .csv files in a specified Amazon Simple Storage Service (Amazon S3) bucket.

Run this Automation (console)

AWS Systems Manager Automation runbook reference User Guide AWS-ExportPatchReportToS3

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

assumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that runs this document.

s3BucketName

Type: String

Description: (Required) The S3 bucket where you want to download the output file.

snsTopicArn

Type: String

Description: (Optional) The Amazon Simple Notification Service (Amazon SNS) topic Amazon Resource Name (ARN) to notify when the download completes.

snsSuccessMessage

Type: String

Description: (Optional) Text of the message to send when the runbook finishes.

· targets

Type: String

Description: (Required) The instance ID or a wildcard character (*) to indicate whether to report patch data for a specific instance or for all instances.

Document Steps

ExportReportStep – The action for this step depends on the value of the targets parameter. If targets is in the format of instanceids=*, the step retrieves up to 10,000 patch summaries for instances in your account and exports the data to a .csv file.

If targets is in the format instanceids=<instance-id>, the step retrieves both the patch summary and all the patches for the specified instance in your account and exports them to a .csv file.

Outputs

PatchSummary/Patches object – If the runbook runs successfully, the exported patch report object is downloaded to your target S3 bucket.

AWS-SetupInventory

Description

Create a Systems Manager Inventory association for one or more managed instances. The system collects metadata from your instances according to the schedule in the association. For more information, see AWS Systems Manager Inventory.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

Applications

Type: String

Default: Enabled

Description: (Optional) Collect metadata about installed applications.

· AssociatedDocName

Type: String

Default: AWS-GatherSoftwareInventory

Description: (Optional) The name of the runbook used to collect Inventory from the managed instance.

AssociationName

Type: String

Description: (Optional) A name for the Inventory association that will be assigned to the instance.

AssocWaitTime

Type: String
Default: PT5M

Description: (Optional) Amount of time that Inventory collection should pause when the Inventory association start time is reached. The time uses ISO 8601 format.

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

AwsComponents

AWS Systems Manager Automation runbook reference User Guide AWS-SetupInventory

Type: String

Default: Enabled

Description: (Optional) Collect metadata for AWS Components like amazon-ssm-agent.

CustomInventory

Type: String

Default: Enabled

Description: (Optional) Collect custom inventory metadata.

Files

Type: String

Description: (Optional) Collect metadata about files on your instances. For more information about how to collect this type of Inventory data, see Working with file and Windows registry inventory. Requires SSMAgent version 2.2.64.0 or later. Linux example: [{"Path":"/usr/bin", "Pattern":["aws*", "*ssm*"], "Recursive":false}, {"Path":"/var/log", "Pattern": ["amazon*.*"], "Recursive":true, "DirScanLimit":1000}] Windows example: [{"Path":"%PROGRAMFILES%", "Pattern":["*.exe"], "Recursive":true}]

InstanceDetailedInformation

Type: String

Default: Enabled

Description: (Optional) Collect additional information about the instance, including the CPU model, speed, and the number of cores, to name a few.

InstanceIds

Type: String

Default: *

Description: (Required) EC2 instances that you want to inventory.

LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

NetworkConfig

Type: String

Default: Enabled

Description: (Optional) Collect metadata about network configurations.

· OutputS3BucketName

Type: String

Description: (Optional) Name of an Amazon S3 bucket where you want to write Inventory log data.

OutputS3KeyPrefix

Type: String

AWS Systems Manager Automation runbook reference User Guide AWS-SetupManagedInstance

Description: (Optional) An Amazon S3 key prefix (subfolder) where you want to write Inventory log

OutputS3Region

Type: String

Description: (Optional) The name of the AWS Region where the Amazon S3 exists.

Schedule

Type: String

Default: cron(0 */30 * * * ? *)

Description: (Optional) A cron expression for the Inventory association schedule. The default is every 30 minutes.

Services

Type: String

Default: Enabled

Description: (Optional, Windows OS only, requires SSMAgent version 2.2.64.0 and above) Collect data for service configurations.

WindowsRegistry

Type: String

Description: (Optional) Collect metadata about Microsoft Windows Registry keys. For more information about how to collect this type of Inventory data, see Working with file and Windows registry inventory. Requires SSM Agent version 2.2.64.0 or later. Example: [{"Path": "HKEY_CURRENT_CONFIG \System","Recursive":true},\{"Path":"HKEY_LOCAL_MACHINE\SOFTWARE\Amazon\MachineImage", "ValueNames":["AMIName"]}]

WindowsRoles

Type: String

Default: Enabled

Description: (Optional) Collect information about Windows roles on the instance. Applies to Windows operating systems only. Requires SSMAgent version 2.2.64.0 or later.

WindowsUpdates

Type: String

Default: Enabled

Description: (Optional) Collect data about all Windows Updates on the instance.

AWS-SetupManagedInstance

Description

Configure an instance with an AWS Identity and Access Management (IAM) role for Systems Manager access.

Run this Automation (console)

AWS Systems Manager Automation runbook reference User Guide AWS-SetupManagedRoleOnEC2Instance

| AWS-SetupManagedRo | leOnEC2Insta |
|--------------------|--------------|
| | |

Automation

Document type

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

InstanceId

Type: String

Description: (Required) ID of the EC2 instance to configure

LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

RoleName

Type: String

Default: SSMRoleForManagedInstance

Description: (Optional) The name of the IAM role for the EC2 instance. If this role does not exist, it will be created. When specifying this value, verify that the role contains the **AmazonSSMManagedInstanceCore** Managed Policy.

AWS-SetupManagedRoleOnEC2Instance

Description

Configure an instance with the SSMRoleForManagedInstance managed IAM role for Systems Manager access.

Run this Automation (console)

Document type

Automation

Owner

Amazon

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootManagedInstance

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) ID of the EC2 instance to configure

LambdaAssumeRole

Type: String

Description: (Optional) The ARN of the role that allows Lambda created by Automation to perform the actions on your behalf. If not specified a transient role will be created to run the Lambda function.

RoleName

Type: String

Default: SSMRoleForManagedInstance

Description: (Optional) The name of the IAM role for the EC2 instance. If this role does not exist, it will be created. When specifying this value, verify that the role contains the **AmazonSSMManagedInstanceCore** Managed Policy.

AWSSupport-TroubleshootManagedInstance

Description

The AWSSupport-TroubleshootManagedInstance runbook helps you to determine why an Amazon Elastic Compute Cloud (Amazon EC2) instance does not report as managed by AWS Systems Manager. This runbook reviews the VPC configuration for the instance including security group rules, VPC endpoints, network access control list (ACL) rules, and route tables. It also confirms an AWS Identity and Access Management (IAM) instance profile that contains the required permissions is attached to the instance.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

AWS Systems Manager Automation runbook reference User Guide AWSSupport-TroubleshootManagedInstance

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Instanceld

Type: String

Description: (Required) The ID of the Amazon EC2 instance that is not reporting as managed by Systems Manager.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:DescribeAutomationExecutions
- ssm:DescribeAutomationStepExecutions
- ssm:DescribeAutomationStepExecutions
- ssm:DescribeInstanceInformation
- ssm:DescribeInstanceProperties
- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ssm:GetDocument
- ssm:ListDocuments
- ssm:StartAutomationExecution
- iam:ListRoles
- iam:GetInstanceProfile
- iam:ListAttachedRolePolicies
- ec2:DescribeInstances
- ec2:DescribeNetworkAcls
- ec2:DescribeRouteTables
- ec2:DescribeSecurityGroups
- ec2:DescribeVpcEndpoints

Document Steps

- aws:executeScript Gathers the PingStatus of the instance.
- aws:branch Branches based on whether the instance is already reporting as managed by Systems Manager.
- aws:executeAwsApi Gathers details about the instance including the VPC configuration.
- aws:executeScript If applicable, gathers additional details related to VPC endpoints that have been deployed to use with Systems Manager, and confirms the security groups attached to the VPC endpoint allow inbound traffic on TCP port 443 from the instance.
- aws:executeScript Checks whether the route table allows traffic to the VPC endpoint or public Systems Manager endpoints.

AWS Systems Manager Automation runbook reference User Guide Third-party

- aws:executeScript Checks whether the network ACL rules allow traffic to the VPC endpoint or public Systems Manager endpoints.
- aws:executeScript Checks whether outbound traffic to the VPC endpoint or public Systems Manager endpoints is allowed by the security group associated with the instance.
- aws:executeScript Checks if the instance profile attached to the instance includes a managed policy that provides the required permissions.
- aws:branch Branches based on the operating system of the instance.
- aws:executeScript Provides reference to ssmagent-toolkit-linux shell script.
- aws:executeScript Provides reference to ssmagent-toolkit-windows PowerShell script.
- aws:executeScript Generates final output for the automation.
- aws:executeScript If the PingStatus of the instance is Online, returns that the instance is already managed by Systems Manager.

Third-party

AWS Systems Manager Automation provides predefined runbooks for third-party products and services. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWS-CreateJiralssue (p. 271)
- AWS-CreateServiceNowIncident (p. 273)
- AWS-RunPacker (p. 274)

AWS-CreateJiraIssue

Description

Create an issue in Jira.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AssigneeName

Type: String

Description: (Optional) The username of the person the issue should be assigned to.

DueDate

AWS Systems Manager Automation runbook reference User Guide AWS-CreateJiraIssue

Type: String

Description: (Optional) The due date for the issue in yyyy-mm-dd format.

IssueDescription

Type: String

Description: (Required) A detailed description of the issue.

IssueSummary

Type: String

Description: (Required) A brief summary of the issue.

IssueTypeName

Type: String

Description: (Required) The name of the type of issue you want to create (for example, Task, Sub-task, Buq, etc.).

JiraURL

Type: String

Description: (Required) The url of the Jira instance.

JiraUsername

Type: String

Description: (Required) The name of the user the issue will be created with.

PriorityName

Type: String

Description: (Optional) The name of the priority of the issue.

ProjectKey

Type: String

Description: (Required) The key of the project the issue should be created in.

• SSMParameterName

Type: String

Description: (Required) The name of an encrypted SSM Parameter containing the API key or password for the Jira user.

Document Steps

aws:createStack - Create CloudFormation stack to create Lambda IAM role and function.

aws:invokeLambdaFunction - Invoke Lambda function to create the Jira issue

aws:deleteStack - Delete the CloudFormation stack created.

Outputs

IssueId: ID of the newly created Jira issue

AWS-CreateServiceNowIncident

Description

Create an incident in the ServiceNow incident table.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Category

Type: String

Description: (Optional) The category of the incident.

Valid values: None | Inquiry/Help | Software | Hardware | Network | Database

Default Value: None

• Description

Type: String

Description: (Required) A detailed explanation on the incident.

Impact

Type: String

Description: (Optional) The effect an incident has on business.

Valid values: High | Medium | Low

Default Value: Low

ServiceNowInstanceUsername

Type: String

Description: (Required) The name of the user the incident will be created with.

ServiceNowInstancePassword

AWS Systems Manager Automation runbook reference User Guide AWS-RunPacker

Type: String

Description: (Required) The name of an encrypted SSM Parameter containing the password for the ServiceNow user.

ServiceNowInstanceURL

Type: String

Description: (Required) The URL of the ServiceNow instance

ShortDescription

Type: String

Description: (Required) A brief description of the incident.

Subcategory

Type: String

Description: (Optional) The subcategory of the incident.

Valid values: None | Antivirus | Email | Internal Application | Operating System | CPU | Disk | Keyboard | Hardware | Memory | Monitor | Mouse | DHCP | DNS | IP Address | VPN | Wireless | DB2 | MS SQL Server

| Oracle

Default Value: None

Document Steps

Push_incident - Pushes the incident information to ServiceNow.

Outputs

Push_incident.incidentID - The created incident ID.

AWS-RunPacker

Description

This runbook uses the HashiCorp Packer tool to validate, fix, or build packer templates that are used to create machine images. This runbook uses Packer v1.7.2.

Note

If you specify a vpc_id value, you must also specify the subnet_id value of a public subnet. Unless you modify your subnet's IPv4 public addressing attribute, you must also set associate_public_ip_address to true.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

AWS Systems Manager Automation runbook reference User Guide Amazon VPC

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Force

Type: Boolean

Description: A Packer option to force a builder to run when artifacts from a previous build otherwise prevent a build from running.

Mode

Type: String

Description: The mode, or command, in which to use Packer when validating against the template. Options include Build, Validate, and Fix.

TemplateFileName

Type: String

Description: The name, or key, of the template file in the S3 bucket.

TemplateS3BucketName

Type: String

Description: The name of the S3 bucket containing the packer template.

Document Steps

RunPackerProcessTemplate – Runs the selected mode against the template using the Packer tool.

Outputs

RunPackerProcessTemplate.output - The stdout from the Packer tool.

RunPackerProcessTemplate.fixed_template_key – The name of the template stored in an S3 bucket to use only when running in "Fix" mode.

RunPackerProcessTemplate.s3_bucket – The name of the S3 bucket that contains the fixed template to use only when running in "Fix" mode.

Amazon VPC

AWS Systems Manager Automation provides predefined runbooks for Amazon Virtual Private Cloud. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSSupport-ConfigureDNSQueryLogging (p. 276)
- AWSSupport-ConnectivityTroubleshooter (p. 278)

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ConfiqureDNSQueryLogging

- AWSConfigRemediation-DeleteEgressOnlyInternetGateway (p. 280)
- AWSConfigRemediation-DeleteUnusedENI (p. 281)
- AWSConfigRemediation-DeleteUnusedSecurityGroup (p. 282)
- AWSConfigRemediation-DeleteUnusedVPCNetworkACL (p. 283)
- AWSConfigRemediation-DeleteVPCFlowLog (p. 284)
- AWSConfigRemediation-DetachAndDeleteInternetGateway (p. 285)
- AWSConfigRemediation-DetachAndDeleteVirtualPrivateGateway (p. 287)
- AWS-DisablePublicAccessForSecurityGroup (p. 288)
- AWSConfigRemediation-DisableSubnetAutoAssignPublicIP (p. 289)
- AWSSupport-EnableVPCFlowLogs (p. 290)
- AWSConfigRemediation-EnableVPCFlowLogsToCloudWatch (p. 292)
- AWSConfigRemediation-EnableVPCFlowLogsToS3Bucket (p. 294)
- AWS-ReleaseElasticIP (p. 295)
- AWSConfigRemediation-RemoveUnrestrictedSourceIngressRules (p. 296)
- AWSConfigRemediation-RemoveVPCDefaultSecurityGroupRules (p. 297)
- AWSSupport-SetupIPMonitoringFromVPC (p. 298)
- AWSSupport-TerminateIPMonitoringFromVPC (p. 305)

AWSSupport-ConfigureDNSQueryLogging

Description

The AWSSupport-ConfigureDNSQueryLogging runbook configures logging for DNS queries that originate in your virtual private cloud (VPC) or for Amazon Route 53 hosted zones. You can choose to publish query logs to Amazon CloudWatch Logs, Amazon Simple Storage Service (Amazon S3), or Amazon Kinesis Data Firehose. For more information about query logging and resolver query logs, see Public DNS query logging and Resolver query logging.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

· AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

LogDestinationArn

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ConfiqureDNSQueryLogging

Type: String

Description: (Optional) The ARN of the CloudWatch Logs group, Amazon S3 bucket or Kinesis Data Firehose stream you want to send query logs to. Note that Route 53 public DNS query logging only supports CloudWatch Logs groups. If you do not specify a value for this parameter, the automation creates a CloudWatch Logs group with the format AWSSupport-ConfigureDNSQueryLogging-{automation: EXECUTION_ID}, and an IAM resource policy to publish the query logs. The CloudWatch Logs group created by the automation has a retention period of 14 days.

QueryLogType

Type: String

Description: (Optional) The types of queries you want to log.

Valid values: Public | Resolver/Private

Default: Public
ResourceId

Type: String

Description: (Required) The ID of the resource whose queries you want to log. If you specify Public for the QueryLogType parameter, the resource must be the ID of a Route 53 private hosted zone. If you specify Resolver/Private for the QueryLogType parameter, the resource must be the ID of a VPC.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ec2:DescribeVpcs
- firehose:ListTagsForDeliveryStream
- firehose:PutRecord
- firehose:PutRecordBatch
- firehose:TagDeliveryStream
- iam:AttachRolePolicy
- iam:CreatePolicy
- iam:CreateRole
- iam:CreateServiceLinkedRole
- iam:DeletePolicy
- iam:DeleteRole
- iam:DeleteRolePolicy
- iam:GetPolicy
- iam:GetRole
- iam:PassRole
- iam:PutRolePolicy
- iam:TagRole
- iam:UpdateRole
- logs:CreateLogDelivery
- logs:CreateLogGroup
- logs:DeleteLogDelivery
- logs:DeleteLogGroup

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ConnectivityTroubleshooter

- logs:DescribeLogGroups
- logs:DescribeLogStreams
- logs:DescribeResourcePolicies
- logs:ListLogDeliveries
- logs:PutResourcePolicy
- logs:PutRetentionPolicy
- logs:UpdateLogDelivery
- route53:CreateQueryLoggingConfig
- route53:DeleteQueryLoggingConfig
- route53:GetHostedZone
- route53resolver:AssociateResolverQueryLogConfig
- route53resolver:CreateResolverQueryLogConfig
- route53resolver:DeleteResolverQueryLogConfig
- s3:GetBucketAcl

Document Steps

- aws:executeScript Verifies the resource you specify for the ResourceId parameter exists, and checks whether the resource type matches the required QueryLogType option.
- aws:executeScript Verifies that the value you specify for the LogDestinationArn parameter matches the required QueryLogType.
- aws:executeScript Verifies the required permissions for Route 53 to publish logs to the CloudWatch Logs log group, and creates the required IAM resource policy if it doesn't exist.
- aws:executeScript Enables the DNS query logging on the selected destination.

AWSSupport-ConnectivityTroubleshooter

Description

The AWSSupport-ConnectivityTroubleshooter runbook diagnoses connectivity issues between the following:

- AWS resources within an Amazon Virtual Private Cloud (Amazon VPC)
- AWS resources in different Amazon VPCs within the same AWS Region that are connected using VPC peering
- · AWS resources in an Amazon VPC and an internet resource using an internet gateway
- AWS resources in an Amazon VPC and an internet resource using a network address translation (NAT) gateway

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

AWS Systems Manager Automation runbook reference User Guide AWSSupport-ConnectivityTroubleshooter

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

DestinationIP

Type: String

Description: (Required) The IPv4 address of the resource you want to connect to.

DestinationPort

Type: String

Default: true

Description: (Required) The port number you want to connect to on the destination resource.

DestinationVpc

Type: String

Default: All

Description: (Optional) The ID of the Amazon VPC you want to test connectivity to.

SourceIP

Type: String

Description: (Required) The private IPv4 address of the AWS resource in your Amazon VPC you want to test connectivity from.

SourcePortRange

Type: String

Description: (Optional) The port range used by the AWS resource in your Amazon VPC you want to test connectivity from.

SourceVpc

Type: String

Default: All

Description: (Optional) The ID of the Amazon VPC you want to test connectivity from.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ec2:DescribeNatGateways
- ec2:DescribeNetworkAcls
- ec2:DescribeNetworkInterfaces

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

DeleteEgressOnlyInternetGateway

- ec2:DescribeRouteTables
- ec2:DescribeSecurityGroups
- ec2:DescribeVpcPeeringConnections

Document Steps

- aws:executeScript Gathers details about the AWS resource you specify in the SourceIP parameter.
- aws:executeScript Determines the destination of network traffic from the AWS resource using the routes gathered from the previous step.
- aws:branch Branches based on the destination of the network traffic.
- aws:executeAwsApi Gathers details about the destination resource.
- aws:executeScript Confirms that the ID returned for the destination Amazon VPC matches the value specified, if any, in the DestinationVpc parameter.
- aws:executeAwsApi Gathers the security group rules for the source and destination resources.
- aws:executeScript Confirms whether the security group rules allow the needed traffic between the source and destination resources.
- aws:executeAwsApi Gathers the network access control lists (NACLs) associated with the subnets for the source and destination resources.
- aws:executeScript Confirms whether the NACLs allow the needed traffic between the source and destination resources.
- aws:executeScript Confirms whether the source has a public IP address associated with the resource, if the route destination is an internet gateway.
- aws:executeAwsApi Gathers the security group rules for the source resource.
- aws:executeScript Confirms whether the security group rules allow the needed traffic from the source to the destination resource.
- aws:executeAwsApi Gathers the NACLs associated with the subnet for the source resource.
- aws:executeScript Confirms whether the NACLs allow the needed traffic from the source resource.
- aws:executeAwsApi Gathers details about the NAT gateway.
- aws:executeAwsApi Gathers the NACLs associated with the subnet for the NAT gateway.
- aws:executeScript Confirms whether the NACLs allow the needed traffic from the subnet for the NAT gateway.
- aws:executeScript Gathers the routes associated with the subnet for the NAT gateway.
- aws:executeScript Confirms whether the NAT gateway has a route to an internet gateway.
- aws:executeAwsApi Gathers details about the VPC peering connection.
- aws:executeScript Confirms both VPCs are in the same Region and that the ID returned for the destination VPC matches the value specified, if any, in the DestinationVpc parameter.
- aws:executeAwsApi Returns the subnet of the destination resource.
- aws:executeScript Gathers the routes associated with the subnet for the peered VPC.
- aws:executeScript Confirms whether the peered VPC has a route to the peering connection.
- aws:executeScript Confirms whether traffic is allowed from the source resource if the destination is not supported by the automation.

AWSConfigRemediation-DeleteEgressOnlyInternetGateway

Description

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteUnusedENI

The AWSConfigRemediation-DeleteEgressOnlyInternetGateway runbook deletes the egress-only internet gateway you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

EgressOnlyInternetGatewayId

Type: String

Description: (Required) The ID of the egress-only internet gateway that you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DeleteEgressOnlyInternetGateway
- ec2:DescribeEgressOnlyInternetGateways

Document Steps

- aws:executeScript Deletes the egress-only internet gateway specified in the EgressOnlyInternetGatewayId parameter.
- aws:executeScript Verifies the egress-only internet gateway has been deleted.

AWSConfigRemediation-DeleteUnusedENI

Description

The AWSConfigRemediation-DeleteUnusedENI runbook deletes an elastic network interface (ENI) that has an attachment status of detached.

Run this Automation (console)

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteUnusedSecurityGroup

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

NetworkInterfaceId

Type: String

Description: (Required) The ID of the ENI that you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DeleteNetworkInterface
- ec2:DescribeNetworkInterfaces

Document Steps

- aws:executeAwsApi Deletes the ENI you specify in the NetworkInterfaceId parameter.
- aws:executeScript Verifies the ENI has been deleted.

AWSConfigRemediation-DeleteUnusedSecurityGroup

Description

The AWSConfigRemediation-DeleteUnusedSecurityGroup runbook deletes the security group you specify in the GroupId parameter. If you attempt to delete a security group that is associated with an Amazon Elastic Compute Cloud (Amazon EC2) instance, or is referenced by another security group, the automation fails. This automation does not delete a default security group.

Run this Automation (console)

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteUnusedVPCNetworkACL

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

• GroupId

Type: String

Description: (Required) The ID of the security group that you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeSecurityGroups
- ec2:DeleteSecurityGroup

Document Steps

- aws:executeAwsApi Returns the security group name using the value you provide in the GroupId parameter.
- aws:branch Confirms that the group name is not "default".
- aws:executeAwsApi Deletes the security group specified in the GroupId parameter.
- aws:executeScript Confirms the security group was deleted.

AWSConfigRemediation-DeleteUnusedVPCNetworkACL

Description

The AWSConfigRemediation-DeleteUnusedVPCNetworkACL runbook deletes a network access control list (ACL) that is not associated with a subnet.

Run this Automation (console)

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DeleteVPCFlowLog

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

NetworkAclId

Type: String

Description: (Required) The ID of the network ACL that you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DeleteNetworkAcl
- ec2:DescribeNetworkAcls

Document Steps

- aws:executeAwsApi Deletes the network ACL specified in the NetworkAclId parameter.
- aws:executeScript Confirms the network ACL specified in the NetworkAclId parameter was deleted.

AWSConfigRemediation-DeleteVPCFlowLog

Description

The AWSConfigRemediation-DeleteVPCFlowLog runbook deletes the virtual private cloud (VPC) flow log you specify.

Run this Automation (console)

Document type

Automation

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DetachAndDeleteInternetGateway

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

FlowLogId

Type: String

Description: (Required) The ID of the flow log that you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DeleteFlowLogs
- ec2:DescribeFlowLogs

Document Steps

- aws:executeAwsApi Deletes the flow log you specify in the FlowLogId parameter.
- aws:executeScript Verifies the flow log has been deleted.

AWSConfigRemediation-DetachAndDeleteInternetGateway

Description

The AWSConfigRemediation-DetachAndDeleteInternetGateway runbook detaches and deletes the internet gateway you specify. If any Amazon EC2 instances in your virtual private cloud (VPC) have elastic IP addresses or public IPv4 addresses associated with them, the runbook fails.

Run this Automation (console)

Document type

Automation

Owner

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-DetachAndDeleteInternetGateway

Amazon

Platforms

Linux, macOS, Windows

Parameters

· AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

InternetGatewayId

Type: String

Description: (Required) The ID of the internet gateway that you want to delete.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DeleteInternetGateway
- ec2:DescribeInternetGateways
- ec2:DetachInternetGateway

Document Steps

- aws:waitForAwsResourceProperty Accepts the ID of the virtual private gateway and waits until the virtual private gateway's state property changes to available or times out.
- aws:executeAwsApi Retrieves a specified virtual private gateway configuration.
- aws:branch Branches based on the VpcAttachments.state parameter value.
- aws:waitForAwsResourceProperty Accepts the ID of the virtual private gateway and waits until the virtual private gateway's VpcAttachments.state's property changes to attached or times out.
- aws:executeAwsApi Accepts the ID of the virtual private gateway and the ID of the Amazon VPC as input, and detaches the virtual private gateway from the Amazon VPC.
- aws:waitForAwsResourceProperty Accepts the ID of the virtual private gateway and waits until the virtual private gateway's VpcAttachments.state's property changes to detached or times out.
- aws:executeAwsApi Accepts the ID of the virtual private gateway as input and deletes it.
- aws:waitForAwsResourceProperty Accepts the ID of the virtual private gateway as input and verifies its deletion.
 - aws:executeAwsApi Gathers the VPC ID from the internet gateway ID.
- aws:executeAwsApi Detaches the internet gateway ID from the VPC.

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

DetachAndDeleteVirtualPrivateGateway

• aws:executeAwsApi - Deletes the internet gateway.

AWSConfigRemediation-DetachAndDeleteVirtualPrivateGateway

Description

The AWSConfigRemediation-DetachAndDeleteVirtualPrivateGateway runbook detaches and deletes a given Amazon Elastic Compute Cloud (Amazon EC2) virtual private gateway attached to a virtual private cloud (VPC) created with Amazon Virtual Private Cloud (Amazon VPC).

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

VpnGatewayId

Type: String

Description: (Required) The ID of the virtual private gateway to be deleted.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DeleteVpnGateway
- ec2:DetachVpnGateway
- ec2:DescribeVpnGateways

Document Steps

• aws:waitForAwsResourceProperty - Accepts the ID of the virtual private gateway and waits until the virtual private gateway's state property changes to available or times out.

AWS Systems Manager Automation runbook reference User Guide

AWS-DisablePublicAccessForSecurityGroup

- aws:executeAwsApi Retrieves a specified virtual private gateway configuration.
- aws:branch Branches based on the VpcAttachments.state parameter value.
- aws:waitForAwsResourceProperty Accepts the ID of the virtual private gateway and waits until the virtual private gateway's VpcAttachments.state's property changes to attached or times out.
- aws:executeAwsApi Accepts the ID of the virtual private gateway and the ID of the Amazon VPC as input, and detaches the virtual private gateway from the Amazon VPC.
- aws:waitForAwsResourceProperty Accepts the ID of the virtual private gateway and waits until the virtual private gateway's VpcAttachments.state's property changes to detached or times out.
- aws:executeAwsApi Accepts the ID of the virtual private gateway as input and deletes it.
- aws:waitForAwsResourceProperty Accepts the ID of the virtual private gateway as input and verifies its deletion.

AWS-DisablePublicAccessForSecurityGroup

Description

This runbook disables default SSH and RDP ports that are opened to all IP addresses.

Important

This runbook fails with an "InvalidPermission.NotFound" error for security groups that meet both of the following criteria: 1) The security group is located in a non-default VPC; and 2) The inbound rules for the security group don't specify open ports using all four of the following patterns:

```
0.0.0.0/0
::/0
SSH or RDP port + 0.0.0.0/0
SSH or RDP port + ::/0
```

Note

This runbook is not available in the AWS Regions located within China.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

DisableSubnetAutoAssignPublicIP

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

· GroupId

Type: String

Description: (Required) The ID of the security group for which the ports should be disabled.

IpAddressToBlock

Type: String

Description: (Optional) Additional IPv4 addresses from which access should be blocked, in the format 1.2.3.4/32.

Outputs

None

AWSConfigRemediation-DisableSubnetAutoAssignPublicIP

Description

The AWSConfigRemediation-DisableSubnetAutoAssignPublicIP runbook disables the IPv4 public addressing attribute for the subnet you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $\arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

SubnetId

Type: String

AWS Systems Manager Automation runbook reference User Guide AWSSupport-EnableVPCFlowLogs

Description: (Required) The ID of the subnet that you want to disable the auto-assign public IPv4 address attribute on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeSubnets
- ec2:ModifySubnetAttribute

Document Steps

- aws:executeAwsApi Disables the auto-assign public IPv4 address attribute for the subnet you specified in the SubnetId parameter.
- aws:assertAwsResourceProperty Verifies the attribute has been disabled.

AWSSupport-EnableVPCFlowLogs

Description

The AWSSupport-EnableVPCFlowLogs runbook creates Amazon Virtual Private Cloud (Amazon VPC) Flow Logs for subnets, network interfaces, and VPCs in your AWS account. If you create a flow log for a subnet or VPC, each elastic network interface in that subnet or Amazon VPC is monitored. Flow log data is published to the Amazon CloudWatch Logs log group or the Amazon Simple Storage Service (Amazon S3) bucket you specify. For more information about flow logs, see VPC Flow Logs in the Amazon VPC User Guide.

Important

Data ingestion and archival charges for vended logs apply when you publish flow logs to CloudWatch Logs or to Amazon S3. For more information, see Flow Logs pricing

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

AWS Systems Manager Automation runbook reference User Guide AWSSupport-EnableVPCFlowLogs

DeliverLogsPermissionArn

Type: String

Description: (Optional) The ARN for the IAM role that permits Amazon Elastic Compute Cloud (Amazon EC2) to publish flow logs to the CloudWatch Logs log group in your account. If you specify s3 for the LogDestinationType parameter, do not provide a value for this parameter. For more information, see Publish flow logs to CloudWatch Logs in the Amazon VPC User Guide.

LogDestinationARN

Type: String

Description: (Optional) The ARN of the resource to which the flow log data is published. If cloud-watch-logs is specified for the LogDestinationType parameter, provide the ARN of the CloudWatch Logs log group you want to publish flow log data to. Alternatively, use LogGroupName instead. If s3 is specified for the LogDestinationType parameter, you must specify the ARN of the Amazon S3 bucket you want to publish flow log data to for this parameter. You can also specify a folder in the bucket.

LogDestinationType

Type: String

Valid values: cloud-watch-logs | s3

Description: (Required) Determines where flow log data is published. If you specify LogDestinationType as s3, do not specify DeliverLogsPermissionArn or LogGroupName.

LogFormat

Type: String

Description: (Optional) The fields to include in the flow log, and the order in which they should appear in the record. For a list of available fields, see Flow log records in the *Amazon VPC User Guide*. If you do not provide a value for this parameter, the flow log is created using the default format. If you specify this parameter, you must specify at least one field.

LogGroupName

Type: String

Description: (Optional) The name of the CloudWatch Logs log group where flow log data is published. If you specify s3 for the LogDestinationType parameter, do not provide a value for this parameter.

Resourcelds

Type: StringList

Description: (Required) A comma-separated list of the IDs for the subnets, elastic network interfaces, or VPC for which you want to create a flow log.

TrafficType

Type: String

Valid values: ACCEPT | REJECT | ALL

Description: (Required) The type of traffic to log. You can log traffic that the resource accepts or rejects, or all traffic.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableVPCFlowLogsToCloudWatch

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:CreateFlowLogs
- ec2:DeleteFlowLogs
- ec2:DescribeFlowLogs
- iam:AttachRolePolicy
- iam:CreateRole
- iam:CreatePolicy
- iam:DeletePolicy
- iam:DeleteRole
- iam:DeleteRolePolicy
- iam:GetPolicy
- iam:GetRole
- iam:TagRole
- iam:PassRole
- iam:PutRolePolicy
- iam:UpdateRole
- logs:CreateLogDelivery
- logs:CreateLogGroup
- logs:DeleteLogDelivery
- logs:DeleteLogGroup
- logs:DescribeLogGroups
- logs:DescribeLogStreams
- s3:GetBucketAcl

Document Steps

- aws:branch Branches based on the value specified for the LogDestinationType parameter.
- aws:executeScript Creates a log group if no value is specified for the LogDestinationARN parameter, and cloud-watch-logs is specified for the LogDestinationType parameter.
- aws:executeScript Creates flow logs based on the values specified in the runbook parameters.

AWSConfigRemediation-EnableVPCFlowLogsToCloudWatch

Description

The AWSConfigRemediation-EnableVPCFlowLogsToCloudWatch runbook replaces an existing Amazon VPC flow log that publishes flow log data to Amazon Simple Storage Service (Amazon S3) with a flow log that publishes flow log data to the Amazon CloudWatch Logs (CloudWatch Logs) log group you specify.

Run this Automation (console)

Document type

Automation

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnableVPCFlowLogsToCloudWatch

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

DestinationLogGroup

Type: String

Description: (Required) The name of the CloudWatch Logs log group you want to publish flow log data to

· DeliverLogsPermissionArn

Type: String

Description: (Required) The ARN of the AWS Identity and Access Management (IAM) role you want to use that provides Amazon Elastic Compute Cloud (Amazon EC2) the requisite permissions to publish flow log data to CloudWatch Logs.

FlowLogId

Type: String

Description: (Required) The ID of the flow log that publishes to Amazon S3 you want to replace.

MaxAggregationInterval

Type: Integer

Valid values: 60 | 600

Description: (Optional) The maximum interval of time, in seconds, during which a flow of packets is captured and aggregated into a flow log record.

TrafficType

Type: String

Valid values: ACCEPT | REJECT | ALL

Description: (Required) The type of flow log data you want to record and publish.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-EnableVPCFlowLogsToS3Bucket

- ec2:CreateFlowLogs
- ec2:DeleteFlowLogs
- ec2:DescribeFlowLogs

Document Steps

- aws:executeAwsApi Gathers details about your VPC from the value you specify in the FlowLogId parameter.
- aws:executeAwsApi Creates a flow log based on the values you specify for the runbook parameters.
- aws:assertAwsResourceProperty Verifies the newly created flow log publishes to CloudWatch Logs.
- aws:executeAwsApi Deletes the flow log that publishes to Amazon S3.
- aws:executeScript Confirms the flow log that published to Amazon S3 was deleted.

AWSConfigRemediation-EnableVPCFlowLogsToS3Bucket

Description

The AWSConfigRemediation-EnableVPCFlowLogsToS3Bucket runbook replaces an existing Amazon VPC flow log that publishes flow log data to Amazon CloudWatch Logs (CloudWatch Logs) with a flow log that publishes flow log data to the Amazon Simple Storage Service (Amazon S3) bucket you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

• DestinationS3BucketArn

Type: String

Description: (Required) The ARN of the Amazon S3 bucket you want to publish flow log data to.

AWS Systems Manager Automation runbook reference User Guide AWS-ReleaseElasticIP

FlowLogId

Type: String

Description: (Required) The ID of the flow log that publishes to CloudWatch Logs you want to replace.

MaxAggregationInterval

Type: Integer

Valid values: 60 | 600

Description: (Optional) The maximum interval of time, in seconds, during which a flow of packets is captured and aggregated into a flow log record.

TrafficType

Type: String

Valid values: ACCEPT | REJECT | ALL

Description: (Required) The type of flow log data you want to record and publish.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:CreateFlowLogs
- ec2:DeleteFlowLogs
- ec2:DescribeFlowLogs

Document Steps

- aws:executeAwsApi Gathers details about your VPC from the value you specify in the FlowLogId parameter.
- aws:executeAwsApi Creates a flow log based on the values you specify for the runbook parameters.
- aws:assertAwsResourceProperty Verifies the newly created flow log publishes to Amazon S3.
- aws:executeAwsApi Deletes the flow log that publishes to CloudWatch Logs.
- aws:executeScript Confirms the flow log that published to CloudWatch Logs was deleted.

AWS-ReleaseElasticIP

Description

Release the specified Elastic IP address using the allocation ID.

Run this Automation (console)

Document type

Automation

Owner

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

RemoveUnrestrictedSourceIngressRules

Amazon

Platforms

Linux, macOS, Windows

Parameters

· AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

AllocationId

Type: String

Description: (Required) The Allocation ID of the Elastic IP address.

AWSConfigRemediation-RemoveUnrestrictedSourceIngressRules

Description

The AWSConfigRemediation-RemoveUnrestrictedSourceIngressRules runbook removes all ingress rules from the security group you specify that allow traffic from all source addresses.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

SecurityGroupId

Type: String

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

${\tt RemoveVPCDefaultSecurityGroupRules}$

Description: (Required) The ID of the security group that you want to remove ingress rules that allow traffic from all source addresses from.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeSecurityGroups
- ec2:RevokeSecurityGroupIngress

Document Steps

• aws:executeScript - Removes all ingress rules that allow traffic from all source addresses from the security group you specified in the SecurityGroupId parameter.

AWSConfigRemediation-RemoveVPCDefaultSecurityGroupRules

Description

The AWSConfigRemediation-RemoveVPCDefaultSecurityGroupRules runbook removes all rules from the default security group of the virtual private cloud (VPC) you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $^{r}(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

GroupId

Type: String

Description: (Required) The ID of the security group that you want to remove all rules from.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- ec2:DescribeSecurityGroups
- ec2:RevokeSecurityGroupEgress
- ec2:RevokeSecurityGroupIngress

Document Steps

- aws:assertAwsResourceProperty Confirms the security group you specified in the GroupId parameter is named default.
- aws:executeScript Removes all rules from the security group you specified in the GroupId parameter.

AWSSupport-SetupIPMonitoringFromVPC

Description

AWSSupport-SetupIPMonitoringFromVPC creates an Amazon Elastic Compute Cloud (Amazon EC2) instance in the specified subnet and monitors selected target IPs (IPv4 or IPv6) by continuously running ping, MTR, traceroute and tracetcp tests. The results are stored in Amazon CloudWatch Logs logs, and metric filters are applied to quickly visualize latency and packet loss statistics in a CloudWatch dashboard.

Additional Information

The CloudWatch Logs data can be used for network troubleshooting and analysis of pattern/trends. Additionally, you can configure CloudWatch alarms with Amazon SNS notifications when packet loss and/or latency reach a threshold. The data can also be used when opening a case with AWS Support, to help isolate an issue quickly and reduce time to resolution when investigating a network issue.

Note

To clean up resources created by AWSSupport-SetupIPMonitoringFromVPC, you can use the runbook AWSSupport-TerminateIPMonitoringFromVPC. For more information, see AWSSupport-TerminateIPMonitoringFromVPC (p. 305).

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

CloudWatchLogGroupNamePrefix

Type: String

Default: /AWSSupport-SetupIPMonitoringFromVPC

Description: (Optional) Prefix used for each CloudWatch log group created for the test results.

CloudWatchLogGroupRetentionInDays

Type: String

Valid values: 1 | 3 | 5 | 7 | 14 | 30 | 60 | 90 | 120 | 150 | 180 | 365 | 400 | 545 | 731 | 1827 | 3653

Default: 7

Description: (Optional) Number of days you want to keep the network monitoring results for.

InstanceType

Type: String

Valid values: t2.micro | t2.small | t2.medium | t2.large

Default: t2.micro

Description: (Optional) The EC2 instance type for the EC2Rescue instance. Recommended size: t2.micro.

SubnetId

Type: String

Description: (Required) The subnet ID for the monitor instance. Be aware that if you specify a private subnet, then you must make sure there is Internet access to allow the monitor instance to setup the test (meaning, install the CloudWatch Logs agent, interact with Systems Manager and CloudWatch).

TargetIPs

Type: String

Description: (Required) Comma separated list of IPv4s and/or IPv6s to monitor. No spaces allowed. Maximum size is 255 characters. Be aware that if you provide an invalid IP, then the automation will fail and rollback the test setup.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

It is recommended that the user who runs the automation have the **AmazonSSMAutomationRole** IAM managed policy attached. In addition, the user must have the following policy attached to their user account, group, or role:

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Action": [
                "iam:CreateRole",
                "iam:CreateInstanceProfile",
                "iam:GetRole",
                "iam:GetInstanceProfile",
                "iam:DetachRolePolicy",
                "iam: AttachRolePolicy",
                "iam:PassRole",
                "iam:AddRoleToInstanceProfile",
                "iam:RemoveRoleFromInstanceProfile",
                "iam:DeleteRole",
                "iam:DeleteInstanceProfile",
                "iam:PutRolePolicy",
                "iam:DeleteRolePolicy"
            "Resource": [
                "arn:aws:iam::AWS_account_ID:role/AWSSupport/SetupIPMonitoringFromVPC_*",
                "arn:aws:iam::AWS_account_ID:instance-profile/AWSSupport/
SetupIPMonitoringFromVPC_*"
            "Effect": "Allow"
        },
        {
            "Action": [
                "iam:DetachRolePolicy",
                "iam:AttachRolePolicy"
            "Resource": [
                "arn:aws:iam::aws:policy/service-role/AmazonSSMManagedInstanceCore"
            "Effect": "Allow"
        },
            "Action": [
                "cloudwatch:DeleteDashboards"
            "Resource": [
                " * "
            "Effect": "Allow"
        },
            "Action": [
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:CreateSecurityGroup",
                "ec2:DeleteSecurityGroup",
                "ec2:DescribeSubnets"
            "Resource": [
                " * "
            "Effect": "Allow"
        }
   ]
}
```

Document Steps

- 1. aws:executeAwsApi describe the provided subnet.
- 2. aws:branch evaluate the TargetIPs input.

(IPv6) If TargetIPs contains an IPv6:

aws:assertAwsResourceProperty - check the provided subnet has an IPv6 pool associated

- 3. aws:executeAwsApi get the latest Amazon Linux 2 AMI from Parameter Store.
- 4. aws:executeAwsApi create a security group for the test in the subnet's VPC.

(Cleanup) If the security group creation fails:

aws:executeAwsApi - delete the security group created by the automation, if it exists.

5. aws:executeAwsApi - allow all outbound traffic in the test security group.

(Cleanup) If the security group egress rule creation fails:

aws:executeAwsApi - delete the security group created by the automation, if it exists.

6. aws:executeAwsApi - create an IAM role for the test EC2 instance

(Cleanup) If the role creation fails:

- a. aws:executeAwsApi delete the IAM role created by the automation, if it exists.
- b. aws:executeAwsApi delete the security group created by the automation, if it exists.
- 7. aws:executeAwsApi attach the AmazonSSMManagedInstanceCore managed policy

(Cleanup) If the policy attachment fails:

- a. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation, if attached.
- b. aws:executeAwsApi delete the IAM role created by the automation.
- c. aws:executeAwsApi delete the security group created by the automation, if it exists.
- 8. aws:executeAwsApi attach an inline policy to allow setting CloudWatch log group retentions and creating a CloudWatch dashboard

(Cleanup) If the inline policy attachment fails:

- a. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation, if created.
- b. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- c. aws:executeAwsApi delete the IAM role created by the automation.
- d. aws:executeAwsApi delete the security group created by the automation, if it exists.
- 9. aws:executeAwsApi create an IAM instance profile.

(Cleanup) If the instance profile creation fails:

- a. aws:executeAwsApi delete the IAM instance profile created by the automation, if it exists.
- b. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- c. aws:executeAwsApi delete the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- d. aws:executeAwsApi delete the IAM role created by the automation.
- e. aws:executeAwsApi delete the security group created by the automation, if it exists.

10aws:executeAwsApi - associate the IAM instance profile to the IAM role.

(Cleanup) If the instance profile and role association fails:

- a. aws:executeAwsApi remove the IAM instance profile from the role, if associated.
- b. aws:executeAwsApi delete the IAM instance profile created by the automation.

- c. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- d. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- e. aws:executeAwsApi delete the IAM role created by the automation.
- f. aws:executeAwsApi delete the security group created by the automation, if it exists.

11aws:sleep - wait for the instance profile to become available.

12aws:runInstances - create the test instance in the specified subnet, and with the instance profile created earlier attached.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.

13aws:branch - evaluate the TargetIPs input.

(IPv6) If TargetIPs contains an IPv6:

aws:executeAwsApi - assign an IPv6 to the test instance.

14aws:waitForAwsResourceProperty - wait for the test instance to become a managed instance.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.

15aws:runCommand - install test pre-requisites:

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.

16aws:runCommand - validate the provided IPs are syntactically correct IPv4 and/or IPv6 addresses:

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.

17aws:runCommand - define the MTR test for each of the provided IPs.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.

18aws:runCommand - define the first ping test for each of the provided IPs.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.

19aws:runCommand - define the second ping test for each of the provided IPs.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.

20aws:runCommand - define the tracepath test for each of the provided IPs.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.
- 21aws:runCommand define the traceroute test for each of the provided IPs.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.
- 22aws:runCommand configure CloudWatch logs.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.
- 23aws:runCommand schedule cronjobs to run each test every minute.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.
- 24aws:sleep wait for the tests to generate some data.
- 25aws:runCommand set the desired CloudWatch log group retentions.

AWS Systems Manager Automation runbook reference User Guide

AWSSupport-TerminateIPMonitoringFromVPC

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.

26aws: runCommand - set the CloudWatch log group metric filters.

(Cleanup) If the step fails:

- a. aws:changeInstanceState terminate the test instance.
- b. aws:executeAwsApi remove the IAM instance profile from the role.
- c. aws:executeAwsApi delete the IAM instance profile created by the automation.
- d. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- e. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- f. aws:executeAwsApi delete the IAM role created by the automation.
- g. aws:executeAwsApi delete the security group created by the automation, if it exists.

27aws:runCommand - create the CloudWatch dashboard.

(Cleanup) If the step fails:

- a. aws:executeAwsApi delete the CloudWatch dashboard, if it exists.
- b. aws:changeInstanceState terminate the test instance.
- c. aws:executeAwsApi remove the IAM instance profile from the role.
- d. aws:executeAwsApi delete the IAM instance profile created by the automation.
- e. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- f. aws:executeAwsApi detach the AmazonSSMManagedInstanceCore managed policy from the role created by the automation.
- g. aws:executeAwsApi delete the IAM role created by the automation.
- h. aws:executeAwsApi delete the security group created by the automation, if it exists.

Outputs

createCloudWatchDashboards.Output - the URL of the CloudWatch dashboard.

createManagedInstance.InstanceIds - the test instance ID.

AWSSupport-TerminateIPMonitoringFromVPC

Description

AWSSupport-TerminateIPMonitoringFromVPC terminates an IP monitoring test previously started by AWSSupport-SetupIPMonitoringFromVPC. Data related to the specified test ID will be deleted.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

InstanceId

Type: String

Description: (Required) The instance ID for the monitor instance.

SubnetId

Type: String

Description: (Required) The subnet ID for the monitor instance.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

It is recommended that the user who runs the automation have the **AmazonSSMAutomationRole** IAM managed policy attached. In addition, the user must have the following policy attached to their user account, group, or role:

```
"Version": "2012-10-17",
   "Statement": [
         "Action": [
            "iam:DetachRolePolicy",
            "iam: RemoveRoleFromInstanceProfile",
            "iam:DeleteRole",
            "iam:DeleteInstanceProfile",
            "iam:DeleteRolePolicy"
         "Resource": [
            "arn:aws:iam::An-AWS-Account-ID:role/AWSSupport/SetupIPMonitoringFromVPC *",
            "arn:aws:iam::An-AWS-Account-ID:instance-profile/AWSSupport/
SetupIPMonitoringFromVPC_*"
         "Effect": "Allow"
      },
         "Action": [
            "iam:DetachRolePolicy"
         "Resource": [
```

AWS Systems Manager Automation runbook reference User Guide AWS WAF

Document Steps

- aws:assertAwsResourceProperty check AutomationExecutionId and InstanceId are related to the same test.
- 2. aws:assertAwsResourceProperty check SubnetId and InstanceId are related to the same test.
- 3. aws:executeAwsApi retrieve the test security group.
- 4. aws:executeAwsApi delete the CloudWatch dashboard.
- 5. aws:changeInstanceState terminate the test instance.
- 6. aws:executeAwsApi remove the IAM instance profile from the role.
- 7. aws:executeAwsApi delete the IAM instance profile created by the automation.
- 8. aws:executeAwsApi delete the CloudWatch inline policy from the role created by the automation.
- 9. aws:executeAwsApi detach the **AmazonSSMManagedInstanceCore** managed policy from the role created by the automation.

10aws:executeAwsApi - delete the IAM role created by the automation.

11aws:executeAwsApi - delete the security group created by the automation, if it exists.

Outputs

None

AWS WAF

AWS Systems Manager Automation provides predefined runbooks for AWS WAF. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

- AWSConfigRemediation-EnableWAFClassicLogging (p. 307)
- AWSConfigRemediation-EnableWAFClassicRegionalLogging (p. 309)
- AWSConfigRemediation-EnableWAFV2Logging (p. 310)

AWSConfigRemediation-EnableWAFClassicLogging

Description

AWS Systems Manager Automation runbook reference User Guide

AWSConfigRemediation-EnableWAFClassicLogging

The AWSConfigRemediation-EnableWAFClassicLogging runbook enables logging to Amazon Kinesis Data Firehose (Kinesis Data Firehose) for the AWS WAF web access control list (web ACL) you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· DeliveryStreamName

Type: String

Description: (Required) The name of the Kinesis Data Firehose delivery stream that you want to send logs to.

WebACLId

Type: String

Description: (Required) The ID of the AWS WAF web ACL that you want to enable logging on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- iam:CreateServiceLinkedRole
- waf:GetLoggingConfiguration
- waf:GetWebAcl
- waf:PutLoggingConfiguration

Document Steps

- aws:executeAwsApi Confirms the delivery stream you specify in the DeliveryStreamName exists.
- aws:executeAwsApi Gathers the ARN of the AWS WAF web ACL specified in the WebACLId parameter.

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-

EnableWAFClassicRegionalLogging

- aws:executeAwsApi Enables logging for the web ACL.
- aws:assertAwsResourceProperty Verifies logging has been enabled on the AWS WAF web ACL.

AWSConfigRemediation-EnableWAFClassicRegionalLogging

Description

The AWSConfigRemediation-EnableWAFClassicRegionalLogging runbook enables logging to Amazon Kinesis Data Firehose (Kinesis Data Firehose) for the AWS WAF web access control list (ACL) you specify.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: ^arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+\$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

· LogDestinationConfigs

Type: String

Description: (Required) The Amazon Resource Name (ARN) of the Kinesis Data Firehose delivery stream that you want to send logs to.

WebACLId

Type: String

Description: (Required) The ID of the AWS WAF web ACL that you want to enable logging on.

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- iam:CreateServiceLinkedRole

AWS Systems Manager Automation runbook reference User Guide

- AWSConfigRemediation-EnableWAFV2Logging
- waf-regional:GetLoggingConfiguration
- waf-regional:GetWebAcl
- waf-regional:PutLoggingConfiguration

Document Steps

- aws:executeAwsApi Gathers the ARN of the AWS WAF web ACL specified in the WebACLId parameter.
- aws:executeAwsApi Enables logging for the web ACL.
- aws:assertAwsResourceProperty Verifies logging has been enabled on the AWS WAF web ACL.

AWSConfigRemediation-EnableWAFV2Logging

Description

The AWSConfigRemediation-EnableWAFV2Logging runbook enables logging for an AWS WAF (AWS WAFV2) web access control list (web ACL) with the specified Amazon Kinesis Data Firehose (Kinesis Data Firehose) delivery stream.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $^{r}(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

LogDestinationConfigs

Type: String

Description: (Required) The Kinesis Data Firehose delivery stream ARN that you want to associate with the web ACL.

WebAclArn

Type: String

Description: (Required) ARN of the web ACL for which logging will be enabled.

AWS Systems Manager Automation runbook reference User Guide Amazon WorkSpaces

Required IAM permissions

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- firehose:DescribeDeliveryStream
- wafv2:PutLoggingConfiguration
- wafv2:GetLoggingConfiguration

Document Steps

aws:executeScript - Enables logging for the AWS WAFV2 web ACL and verifies that the logging has
the specified configuration.

Amazon WorkSpaces

AWS Systems Manager Automation provides predefined runbooks for Amazon WorkSpaces. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

• AWSSupport-RecoverWorkSpace (p. 311)

AWSSupport-RecoverWorkSpace

Description

The AWSSupport-RecoverWorkSpace runbook performs recovery steps on the Amazon WorkSpaces virtual desktop, known as a WorkSpace, you specify. The runbook reboots the WorkSpace, and if the state is still UNHEALTHY, restores or rebuilds the WorkSpace based on the values you specify for the input parameters. Before using this runbook we recommend reviewing Troubleshooting WorkSpaces Issues in the Amazon WorkSpaces Administration Guide.

Important

Restoring or rebuilding a WorkSpace is a potentially destructive action that can result in the loss of data. This is because the WorkSpace is restored from the last available snapshot and data recovered from snapshots can be as old as 12 hours.

The restore option recreates both the root volume and user volume based on the most recent snapshots. The rebuild option recreates the user volume from the most recent snapshot and recreates the WorkSpace from the image associated with the bundle the WorkSpace was created from. Applications that were installed or system settings that were changed after the WorkSpace was created are lost. For more information about restoring and rebuilding WorkSpaces, see Restore a WorkSpace and Rebuild a WorkSpace in the Amazon WorkSpaces Administration Guide.

Run this Automation (console)

Document type

Automation

Owner

AWS Systems Manager Automation runbook reference User Guide AWSSupport-RecoverWorkSpace

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Description: (Optional) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf. If no role is specified, Systems Manager Automation uses the permissions of the user that starts this runbook.

Acknowledge

Type: String

Valid values: Yes

Description: (Required) Entering yes means that you understand the restore and rebuild actions will try to recover the WorkSpace from the most recent snapshot, and that data restored from these snapshots can be as old as 12 hours.

Reboot

Type: String

Valid values: Yes | No

Default: Yes

Description: (Required) Determines whether the WorkSpace is rebooted.

Rebuild

Type: String

Valid values: Yes | No

Default: No

Description: (Required) Determines whether the WorkSpace is rebuilt.

Restore

Type: String

Valid values: Yes | No

Default: No

Description: (Required) Determines whether the WorkSpace is restored.

WorkspaceId

Type: String

Description: (Required) The ID of the WorkSpace you want to recover.

Required IAM permissions

AWS Systems Manager Automation runbook reference User Guide AWSSupport-RecoverWorkSpace

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- workspaces:DescribeWorkspaces
- workspaces:DescribeWorkspaceSnapshots
- workspaces: RebootWorkspaces
- workspaces:RebuildWorkspaces
- workspaces:RestoreWorkspace
- workspaces:StartWorkspaces

Document Steps

- aws:executeAwsApi Gathers the state of the WorkSpace you specify in the WorkspaceId parameter.
- aws:assertAwsResourceProperty Verifies the state of the WorkSpace is AVAILABLE, ERROR, IMPAIRED, STOPPED, or UNHEALTHY.
- aws:branch Branches based on the state of the WorkSpace.
- aws:executeAwsApi Starts the WorkSpace.
- aws:branch Branches based on the value you specify for the Action parameter.
- aws:waitForAwsResourceProperty Waits for the WorkSpace status after being started.
- aws:waitForAwsResourceProperty Waits for the WorkSpace state to change to AVAILABLE, ERROR, IMPAIRED, or UNHEALTHY after being started.
- aws:executeAwsApi Gathers the state of the WorkSpace after being started.
- aws:branch Branches based on the state of the WorkSpace after being started.
- aws:executeAwsApi Gathers the available snapshots for restoring or rebuilding the WorkSpace.
- aws:branch Branches based on the value you specify for the Reboot parameter.
- aws:executeAwsApi Reboots the WorkSpace.
- aws:executeAwsApi Gathers the state of the WorkSpace after being started.
- aws:waitForAwsResourceProperty Waits for the state of the WorkSpace to change to REBOOTING.
- aws:waitForAwsResourceProperty Waits for the WorkSpace state to change to AVAILABLE, ERROR, or UNHEALTHY after being rebooted.
- aws:executeAwsApi Gathers the state of the WorkSpace after being rebooted.
- aws:branch Branches based on the state of the WorkSpace after rebooting.
- aws:branch Branches based on the value you specify for the Restore parameter.
- aws:executeAwsApi Restores the WorkSpace. If the restore fails, the runbook tries to rebuild the WorkSpace.
- aws:waitForAwsResourceProperty Waits for the state of the WorkSpace to change to RESTORING.
- aws:waitForAwsResourceProperty Waits for the WorkSpace state to change to AVAILABLE, ERROR, or UNHEALTHY after being restored.
- aws:executeAwsApi Gathers the state of the WorkSpace after being restored.
- aws:branch Branches based on the state of the WorkSpace after restoring.
- aws:branch Branches based on the value you specify for the Rebuild parameter.
- aws:executeAwsApi Rebuilds the WorkSpace.
- aws:waitForAwsResourceProperty Waits for the state of the WorkSpace to change to REBUILDING.

AWS Systems Manager Automation runbook reference User Guide X-Ray

- aws:waitForAwsResourceProperty Waits for the WorkSpace state to change to AVAILABLE, ERROR, or UNHEALTHY after being rebuilt.
- aws:executeAwsApi Gathers the state of the WorkSpace after being rebuilt.
- aws:assertAwsResourceProperty Confirms the state of the WorkSpace is AVAILABLE.

X-Ray

AWS Systems Manager Automation provides predefined runbooks for AWS X-Ray. For more information about runbooks, see Working with runbooks. For information about how to view runbook content, see View runbook content (p. 2).

Topics

AWSConfigRemediation-UpdateXRayKMSKey (p. 314)

AWSConfigRemediation-UpdateXRayKMSKey

Description

The AWSConfigRemediation-UpdateXRayKMSKey runbook enables encryption on your AWS X-Ray data using an AWS Key Management Service (AWS KMS) key. This runbook should only be used as a baseline to ensure that your AWS X-Ray data is encrypted according to minimum recommended security best practices. We recommend encrypting multiple sets of data with different KMS keys.

Run this Automation (console)

Document type

Automation

Owner

Amazon

Platforms

Linux, macOS, Windows

Parameters

AutomationAssumeRole

Type: String

Allowed values: $\arn:(?:aws|aws-us-gov|aws-cn):iam::\d{12}:role\/[\w+=,.@/-]+$$

Description: (Required) The Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) role that allows Systems Manager Automation to perform the actions on your behalf.

Keyld

Type: String

Description: (Required) The Amazon Resource Name (ARN), key ID, or the key alias of the KMS key you want AWS X-Ray to use to encrypt data.

Required IAM permissions

AWS Systems Manager Automation runbook reference User Guide AWSConfigRemediation-UpdateXRayKMSKey

The AutomationAssumeRole parameter requires the following actions to successfully use the runbook.

- ssm:StartAutomationExecution
- ssm:GetAutomationExecution
- kms:DescribeKey
- xray:GetEncryptionConfig
- xray:PutEncryptionConfig

Document Steps

- aws:executeAwsApi Enables encryption on your X-Ray data using the KMS key you specify in the KeyId parameter.
- aws:waitForAwsResourceProperty Waits for the encryption configuration status of your X-Ray to be ACTIVE
- aws:executeAwsApi Gathers the ARN of the key you specify in the KeyId parameter.
- aws:assertAwsResourceProperty Verifies encryption has been enabled on your X-Ray.