


Lab 3 - Configuring Extended ACLs - Scenario 1

Topology



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/0	172.22.34.65	255.255.255.224	N/A
	G0/1	172.22.34.97	255.255.255.240	N/A
	G0/2	172.22.34.1	255.255.255.192	N/A
Server	NIC	172.22.34.62	255.255.255.192	172.22.34.1
PC1	NIC	172.22.34.66	255.255.255.224	172.22.34.65
PC2	NIC	172.22.34.98	255.255.255.240	172.22.34.97

Objectives

Part 1: Configure, Apply and Verify an Extended Numbered ACL

Part 2: Configure, Apply and Verify an Extended Named ACL

Background / Scenario

Two employees need access to services provided by the server. **PC1** needs only FTP access while **PC2** needs only web access. Both computers are able to ping the server, but not each other.

Part 1: Configure, Apply and Verify an Extended Numbered ACL

Step 1: Configure an ACL to permit FTP and ICMP.

a. From global configuration mode on **R1**, enter the following command to determine the first valid number for an extended access list.

```
<100-199> IP extended access list
```

b. Add 100 to the command, followed by a question mark.

```
R1(config) # access-list 100 ?

deny Specify packets to reject
permit Specify packets to forward
remark Access list entry comment
```

c. To permit FTP traffic, enter **permit**, followed by a question mark.

```
R1(config) # access-list 100 permit ?
        Authentication Header Protocol
 ahp
 eigrp Cisco's EIGRP routing protocol
        Encapsulation Security Payload
 esp
        Cisco's GRE tunneling
 gre
       Internet Control Message Protocol
 icmp
        Any Internet Protocol
 ip
        OSPF routing protocol
 ospf
        Transmission Control Protocol
 tcp
        User Datagram Protocol
 udp
```

d. This ACL permits FTP and ICMP. ICMP is listed above, but FTP is not, because FTP uses TCP. Therefore, enter **tcp** to further refine the ACL help.

```
R1(config)# access-list 100 permit tcp ?

A.B.C.D Source address

any Any source host

host A single source host
```

e. Notice that we could filter just for **PC1** by using the **host** keyword or we could allow **any** host. In this case, any device is allowed that has an address belonging to the 172.22.34.64/27 network. Enter the network address, followed by a question mark.

```
R1(config) # access-list 100 permit tcp 172.22.34.64 ?
   A.B.C.D Source wildcard bits
```

f. Calculate the wildcard mask determining the binary opposite of a subnet mask.

g. Enter the wildcard mask, followed by a question mark.

```
R1(config) # access-list 100 permit tcp 172.22.34.64 0.0.0.31 ?

A.B.C.D Destination address

any Apv destination host
```

```
any Any destination host
eq Match only packets on a given port number
gt Match only packets with a greater port number
host A single destination host
lt Match only packets with a lower port number
neq Match only packets not on a given port number
range Match only packets in the range of port numbers
```

h. Configure the destination address. In this scenario, we are filtering traffic for a single destination, which is the server. Enter the **host** keyword followed by the server's IP address.

```
R1(config) # access-list 100 permit tcp 172.22.34.64 0.0.0.31 host 172.22.34.62 ?
```

```
dscp
             Match packets with given dscp value
eq
             Match only packets on a given port number
established established
             Match only packets with a greater port number
qt
lt
             Match only packets with a lower port number
             Match only packets not on a given port number
neq
             Match packets with given precedence value
precedence
             Match only packets in the range of port numbers
range
<cr>
```

i. Notice that one of the options is <cr> (carriage return). In other words, you can press Enter and the statement would permit all TCP traffic. However, we are only permitting FTP traffic; therefore, enter the eq keyword, followed by a question mark to display the available options. Then, enter ftp and press Enter.

```
R1(config) # access-list 100 permit tcp 172.22.34.64 0.0.0.31 host 172.22.34.62 eq ?

<0-65535> Port number
ftp     File Transfer Protocol (21)
pop3     Post Office Protocol v3 (110)
smtp          Simple Mail Transport Protocol (25)
telnet          Telnet (23)
www          World Wide Web (HTTP, 80)

R1(config) # access-list 100 permit tcp 172.22.34.64 0.0.0.31 host 172.22.34.62 eq ftp
```

j. Create a second access list statement to permit ICMP (ping, etc.) traffic from **PC1** to **Server**. Note that the access list number remains the same and no particular type of ICMP traffic needs to be specified.

```
R1 (config) \# access-list 100 permit icmp 172.22.34.64 0.0.0.31 host 172.22.34.62
```

k. All other traffic is denied, by default.

Step 2: Apply the ACL on the correct interface to filter traffic.

From **R1**'s perspective, the traffic that ACL 100 applies to is inbound from the network connected to Gigabit Ethernet 0/0 interface. Enter interface configuration mode and apply the ACL.

```
R1(config)# interface gigabitEthernet 0/0
R1(config-if)# ip access-group 100 in
```

Step 3: Verify the ACL implementation.

- a. Ping from PC1 to Server. If the pings are unsuccessful, verify the IP addresses before continuing.
- b. FTP from **PC1** to **Server**. The username and password are both **cisco**.

```
PC> ftp 172.22.34.62
```

c. Exit the FTP service of the Server.

```
ftp> quit
```

d. Ping from **PC1** to **PC2**. The destination host should be unreachable, because the traffic was not explicitly permitted.

Part 2: Configure, Apply and Verify an Extended Named ACL

Step 1: Configure an ACL to permit HTTP access and ICMP.

a. Named ACLs start with the **ip** keyword. From global configuration mode of **R1**, enter the following command, followed by a question mark.

```
R1(config)# ip access-list ?
extended Extended Access List
standard Standard Access List
```

b. You can configure named standard and extended ACLs. This access list filters both source and destination IP addresses; therefore, it must be extended. Enter **HTTP_ONLY** as the name. (For Packet Tracer scoring, the name is case-sensitive.)

```
R1(config) # ip access-list extended HTTP ONLY
```

c. The prompt changes. You are now in extended named ACL configuration mode. All devices on the **PC2** LAN need TCP access. Enter the network address, followed by a question mark.

```
R1(config-ext-nacl)# permit tcp 172.22.34.96 ?
   A.B.C.D Source wildcard bits
```

d. An alternative way to calculate a wildcard is to subtract the subnet mask from 255.255.255.255.

```
255.255.255.255

- 255.255.255.240

------=

= 0. 0. 0. 15

R1(config-ext-nacl)# permit tcp 172.22.34.96 0.0.0.15 ?
```

e. Finish the statement by specifying the server address as you did in Part 1 and filtering www traffic.

```
R1(config-ext-nacl)# permit tcp 172.22.34.96 0.0.0.15 host 172.22.34.62 eq www
```

f. Create a second access list statement to permit ICMP (ping, etc.) traffic from **PC2** to **Server**. Note: The prompt remains the same and a specific type of ICMP traffic does not need to be specified.

```
R1(config-ext-nacl) # permit icmp 172.22.34.96 0.0.0.15 host 172.22.34.62
```

g. All other traffic is denied, by default. Exit out of extended named ACL configuration mode.

Step 2: Apply the ACL on the correct interface to filter traffic.

From **R1**'s perspective, the traffic that access list **HTTP_ONLY** applies to is inbound from the network connected to Gigabit Ethernet 0/1 interface. Enter the interface configuration mode and apply the ACL.

```
R1(config)# interface gigabitEthernet 0/1
R1(config-if)# ip access-group HTTP ONLY in
```

Step 3: Verify the ACL implementation.

- a. Ping from **PC2** to **Server**. The ping should be successful, if the ping is unsuccessful, verify the IP addresses before continuing.
- b. FTP from PC2 to Server. The connection should fail.
- c. Open the web browser on **PC2** and enter the IP address of **Server** as the URL. The connection should be successful.