Signals reference

This page references all available signals that you can listen to, triggered by ("Public") Repository API in eZ Platform.

For more information, check SignalSlot documentation and the cookbook recipe on how to listen to signals.

Signals are ordered by Repository service:

- ContentService
- ContentTypeService
- LanguageService
- LocationService
- ObjectStateService
- RoleService
- SectionService
- TrashService
- URLAliasService
- URLWildcardService
- UserService
 - Related topics:

All signals are relative to eZ\Publish\Core\SignalSlot\Signal namespace.

Transactions

As of eZ Publish Platform 5.3.3 and higher signals are sent after transactions are executed, making signals transaction safe.

ContentService

Signal type	Properties	Triggered by	When
ContentService\AddRelationSignal	srcContentId (source contentId, aka referrer) srcVersionNo dstContentId (destination contentId, aka target)	ContentService::addRelation()	After
ContentService\AddTranslationInfoSignal	N/A	ContentService::addTranslationInfo()	After
ContentService\CopyContentSignal	srcContentId (original content ID) srcVersionNo dstContentId (contentId of the copy) dstVersionNo dstParentLocationId (loc ationId where the content has been copied)	ContentService::copyContent()	After
ContentService\CreateContentDraftSignal	contentId versionNo userId (Id of user used to create the draft, or null - current user)	ContentService::createContentDraft()	After
ContentService\CreateContentSignal	• contentId • versionNo	ContentService::createContent()	After
ContentService\DeleteContentSignal	• contentId	ContentService::deleteContent()	After
ContentService\DeleteRelationSignal	• srcContentId • srcVersionNo • dstContentId	ContentService::deleteRelation()	After
ContentService\DeleteVersionSignal	• contentId • versionNo	ContentService::deleteVersion()	After

ContentService\PublishVersionSignal	• contentId • versionNo	ContentService:: publishVersion()	After
ContentService\TranslateVersionSignal	• contentId • versionNo • userId	ContentService::translationVersion()	After
ContentService\UpdateContentMetadataSignal	• contentId	ContentService::updateContentMetadata()	After
ContentService\UpdateContentSignal	• contentId • versionNo	ContentService::updateContent()	After

ContentTypeService

Signal type	Properties	Triggered by
ContentTypeService\AddFieldDefinitionSignal	• contentTypeDraftId	ContentTypeService::addFieldDefinition()
ContentTypeService\AssignContentTypeGroupSignal	contentTypeIdcontentTypeGroupId	ContentTypeService::assignContentTypeGroup()
ContentTypeService\CopyContentTypeSignal	contentTypeIduserId	ContentTypeService::copyContentType()
ContentTypeService\CreateContentTypeDraftSignal	• contentTypeId	ContentTypeService::createContentTypeDraft()
ContentTypeService\CreateContentTypeGroupSignal	• groupId	ContentTypeService::createContentTypeGroup()
ContentTypeService\CreateContentTypeSignal	• contentTypeId	ContentTypeService::createContentType()
ContentTypeService\DeleteContentTypeGroupSignal	• contentTypeGroupId	ContentTypeService::deleteContentTypeGroup()
ContentTypeService\DeleteContentTypeSignal	• contentTypeId	ContentTypeService::deleteContentType()
ContentTypeService\PublishContentTypeDraftSignal	• contentTypeDraftId	ContentTypeService::publishContentTypeDraft(
ContentTypeService\RemoveFieldDefinitionSignal	contentTypeDraftIdfieldDefinitionId	ContentTypeService::removeFieldDefinition()
ContentTypeService\UnassignContentTypeGroupSignal	• contentTypeId • contentTypeGroupId	ContentTypeService::unassignContentTypeGroup
ContentTypeService\UpdateContentTypeDraftSignal	• contentTypeDraftId	ContentTypeService::updateContentTypeDraft()
ContentTypeService\UpdateContentTypeGroupSignal	• contentTypeGroupId	ContentTypeService::updateContentTypeGroup()
ContentTypeService\UpdateFieldDefinitionSignal	contentTypeDraftIdfieldDefinitionId	ContentTypeService::updateFieldDefinition()

LanguageService

Signal type	Properties	Triggered by	When
LanguageService\CreateLanguageSignal	• languageId	LanguageService::createLanguage()	After
LanguageService\DeleteLanguageSignal	• languageId	LanguageService::deleteLanguage()	After
LanguageService\DisableLanguageSignal	• languageId	LanguageService::disableLanguage()	After
LanguageService\EnableLanguageSignal	• languageId	LanguageService::enableLanguage()	After
LanguageService\UpdateLanguageNameSignal	• languageId • newName	LanguageService::updateLanguageName()	After

LocationService

Signal type	Properties	Triggered by	When
LocationService\CopySubtreeSignal	 subtreeId (top locationId of the subtree to be copied) targetParentLocationId 	LocationService::copySubtree()	After

LocationService\CreateLocationSignal	• contentId • locationId	LocationService::createLocation()	After
LocationService\DeleteLocationSignal	• contentId • locationId	LocationService::deleteLocation()	After
LocationService\HideLocationSignal	• contentId • locationId	LocationService::hideLocation()	After
LocationService\UnhideLocationSignal	• contentId • locationId	LocationService::unhideLocation()	After
LocationService\MoveSubtreeSignal	subtreeIdnewParentLocationId	LocationService::moveSubtree()	After
LocationService\SwapLocationSignal	content1Idlocation1Idcontent2Idlocation2Id	LocationService::swapLocation()	After
LocationService\UpdateLocationSignal	• contentId • locationId	LocationService::updateLocation()	After

ObjectStateService

Signal type	Properties	Triggered by
ObjectStateService\CreateObjectStateGroupSignal	• objectStateGroupId	ObjectStateService::createObjectStateGroup()
ObjectStateService\CreateObjectStateSignal	• objectStateGroupId • objectStateId	ObjectStateService::createObjectState()
ObjectStateService\DeleteObjectStateGroupSignal	• objectStateGroupId	ObjectStateService::deleteObjectStateGroup()
ObjectStateService\DeleteObjectStateSignal	• objectStateId	ObjectStateService::deleteObjectState()
ObjectStateService\SetContentStateSignal	contentIdobjectStateGroupIdobjectStateId	ObjectStateService::setContentState()
ObjectStateService\SetPriorityOfObjectStateSignal	• objectStateId • priority	ObjectStateService::setPriorityOfObjectState
ObjectStateService\UpdateObjectStateGroupSignal	• objectStateGroupId	ObjectStateService::updateObjectStateGroup()
ObjectStateService\UpdateObjectStateSignal	• objectStateId	ObjectStateService::updateObjectState()

RoleService

Signal type	Properties	Triggered by	When
RoleService\AddPolicySignal	roleIdpolicyId	RoleService::addPolicy()	After
RoleService\AssignRoleToUserGroupSignal	roleIduserGroupIdroleLimitation	RoleService::assignRoleToUserGroup()	After
RoleService\AssignRoleToUserSignal	roleIduserIdroleLimitation	RoleService::assignRoleToUser()	After
RoleService\CreateRoleSignal	• roleId	RoleService::createRole()	After
RoleService\DeleteRoleSignal	• roleId	RoleService::deleteRole()	After
RoleService\RemovePolicySignal	• roleId • policyId	RoleService::removePolicy()	After
RoleService\UnassignRoleFromUserGroupSignal	• roleId • userGroupId	RoleService::unassignRoleFromUserGroup()	After
RoleService\UnassignRoleFromUserSignal	• roleId • userId	RoleService::unassignRoleFromUser()	After

RoleService\UpdatePolicySignal	• policyId	RoleService::updatePolicy()	After
RoleService\UpdateRoleSignal	• roleId	RoleService::updateRole()	After

SectionService

Signal type	Properties	Triggered by	When
SectionService\AssignSectionSignal	contentIdsectionId	SectionService::assignSection()	After
SectionService\CreateSectionSignal	• sectionId	SectionService::createSection()	After
SectionService\DeleteSectionSignal	• sectionId	SectionService::deleteSection()	After
SectionService\UpdateSectionSignal	• sectionId	SectionService::updateSection()	After

TrashService

Signal type	Properties	Triggered by	When
TrashService\DeleteTrashItemSignal	• trashItemId	<pre>TrashService::deleteTrashItem()</pre>	After
TrashService\EmptyTrashSignal	N/A	TrashService::emptyTrash()	After
TrashService\RecoverSignal	• trashItemId • newParentLocationId • newLocationId	TrashService::recover()	After
TrashService\TrashSignal	• locationId	TrashService::trash()	After

URLAliasService

Signal type	Properties	Triggered by	When
URLAliasService\CreateGlobalUrlAliasSignal	• urlAliasId	URLAliasService::createGlobalUrlAlias()	After
URLAliasService\CreateUrlAliasSignal	• urlAliasId	URLAliasService::createUrlAlias()	After
URLAliasService\RemoveAliasesSignal	• aliasList	URLAliasService::removeAliases()	After

URLWildcardService

Signal type	Properties	Triggered by	When
URLWildcardService\CreateSignal	• urlWildcardId	<pre>URLWildcardService::create()</pre>	After
URLWildcardService\RemoveSignal	• urlWildcardId	URLWildcardService::remove()	After
URLWildcardService\TranslateSignal	• url	URLWildcardService::translate()	After

UserService

Signal type	Properties	Triggered by	When
UserService\AssignUserToUserGroupSignal	• userId • userGroupId	UserService::assignUserToUserGroup()	After
UserService\CreateUserGroupSignal	• userGroupId	UserService::createUserGroup()	After
UserService\CreateUserSignal	• userId	UserService::createUser()	After
UserService\DeleteUserGroupSignal	• userGroupId	UserService::deleteUserGroup()	After

UserService\DeleteUserSignal	• userId	UserService::deleteUser()	After
UserService\MoveUserGroupSignal	userGroupIdnewParentId	UserService::moveUserGroup()	After
UserService\UnAssignUserFromUserGroupSignal	• userId • userGroupId	UserService::unAssignUserFromUserGroup()	After
UserService\UpdateUserGroupSignal	• userGroupId	UserService::updateUserGroup()	After
UserService\UpdateUserSignal	• userId	UserService::updateUser()	After

Related topics:

- Signal-SlotHow to listen to Core events