

Slot configurations for Snaplex nodes

Overview	2
Slot Configuration details	2

Overview

- Slot configurations are updated on the *Node Properties* tab of the Snaplex.

Settings Logging **Node properties** Node proxies Downloads

Max. slots

4000

Reserved slot %

15

Max. memory

85

<https://docs-snaplogic.atlassian.net/wiki/spaces/SD/pages/1438250/Updating+a+Snaplex>

<https://docs.snaplogic.com/public-apis/get-untime-org-ruuid.html>

slot_count	integer	Estimation of max threads that might be needed.
------------	---------	---

Slot Configuration details

Configuration	Comments
Maximum Slots	- The maximum number of slots available on each node in a Snaplex. - One slot = One Snap = One active thread on the node (**)

- **** Some Snaps such as Pipeline Execute, Bulk loaders, and Snaps performing input/output, can use a higher number of threads compared to other Snaps.**
- The Pipeline log will show an estimation of the max slots that would be needed.
- API to retrieve info about a Pipeline execution:
<https://docs.snaplogic.com/public-apis/get-runtime-org-ruuid.html>
- Each Snap in a Pipeline will consume a slot, so Pipelines will only be executed on nodes where the number of slots currently in use is below this threshold. Otherwise, they will fail or be placed in the Queued state, depending on how they were executed.
- The number of slots-in-use corresponds to the number of **active threads on a node**, which can be viewed on the **Active threads** metric.
<https://docs.snaplogic.com/monitor/analyze-metrics.html>
- **Default value: 4000.** The general recommendation is to configure this property based on the node memory configuration. Example: **8 GB - 2000 Slots / 16 GB - 4000 Slots**
- The above numbers can be increased if you see high thread usage in the metric graph mentioned above.
- A restart is not required with a change to this setting, which can be set to a user-specified value.

Reference:

<https://docs-snaplogic.atlassian.net/wiki/spaces/SD/pages/1438250/Updating+a+Snaplex#Node-Properties-Tab-Reference>


<https://community.snaplogic.com/discussions/sigma/snaplex-capacity-tuning-guide/23787>

	Note: For K8 deployments, the values of <code>sl_file_ulimit</code>, and <code>sl_process_ulimit</code> in <code>values.yaml</code> should be greater than the value of Maximum Slots under the Snaplex's node properties. If not set, then the node defaults will be used. (<code>/etc/security/limits.conf</code>). Ref: https://community.snaplogic.com/discussions/sigma/snaplogic-deployment-on-kubernetes---a-reference-guide/39794
Reserved slots %	The percentage of slots to reserve on a node for pipelines executed through the Designer tab. A restart is not required with a change to this setting. Default value: 15 Pipelines executed using Tasks do not have access to these slots.
Maximum memory %	The threshold at which no more pipelines will be assigned to a node. A restart is not required with a change to this setting. Default value: 85

Slot / Thread usage metrics

- The Slot / Thread usage metrics can be viewed on the Monitor for specific time intervals. The Metrics graph to view is “Active threads (count)”.

Active threads (count)



Number of active threads. [↗](#)

Avg: 312.93 | Max: 314.5

Avg: 199.09 | Max: 200.5

