

[Skip to content](#)

[Genymobile](#)

[scrcpy](#)

[Repository navigation](#)

[Code](#)

[Issues](#)

[2.8k](#)

[\(2.8k\)](#)

[Pull requests](#)

[82](#)

[\(82\)](#)

[scrcpy/doc](#)

[/connection.md](#)

[karasuhebirom1v](#)

[karasuhebi](#)

[and](#)

[rom1v](#)

[2 years ago](#)

[132 lines \(97 loc\) · 3.35 KB](#)

[Preview](#)

[Code](#)

[Blame](#)

[Connection](#)

[Selection](#)

If exactly one device is connected (i.e. listed by adb devices), then it is automatically selected.

However, if there are multiple devices connected, you must specify the one to use in one of 4 ways:

by its serial:

```
scrcpy --serial=0123456789abcdef
```

```
scrcpy -s 0123456789abcdef # short version
```

the serial is the ip:port if connected over TCP/IP (same behavior as adb)

```
scrcpy --serial=192.168.1.1:5555
```

the one connected over USB (if there is exactly one):

```
scrcpy --select-usb
```

```
scrcpy -d # short version
```

the one connected over TCP/IP (if there is exactly one):

```
scrcpy --select-tcpip
```

```
scrcpy -e # short version
```

a device already listening on TCP/IP (see below):

```
scrcpy --tcpip=192.168.1.1:5555
```

```
scrcpy --tcpip=192.168.1.1      # default port is 5555
```

The serial may also be provided via the environment variable `ANDROID_SERIAL` (also used by `adb`):

```
# in bash
```

```
export ANDROID_SERIAL=0123456789abcdef
```

```
scrcpy
```

```
:: in cmd
```

```
set ANDROID_SERIAL=0123456789abcdef
```

```
scrcpy
```

```
# in PowerShell
```

```
$env:ANDROID_SERIAL = '0123456789abcdef'
```

```
scrcpy
```

TCP/IP (wireless)

Scrcpy uses `adb` to communicate with the device, and `adb` can connect to a device over TCP/IP.

The device must be connected on the same network as the computer.

Automatic

An option `--tcpip` allows to configure the connection automatically. There are two variants.

If `adb` TCP/IP mode is disabled on the device (or if you don't know the IP address), connect the device over USB, then run:

```
scrcpy --tcpip # without arguments
```

It will automatically find the device IP address and `adb` port, enable TCP/IP mode if necessary, then connect to the device before starting.

If the device (accessible at 192.168.1.1 in this example) already listens on a port (typically 5555) for incoming `adb` connections, then run:

```
scrcpy --tcpip=192.168.1.1      # default port is 5555
```

```
scrcpy --tcpip=192.168.1.1:5555
```

Prefix the address with a '+' to force a reconnection:

```
scrcpy --tcpip=+192.168.1.1
```

Manual

Alternatively, it is possible to enable the TCP/IP connection manually using `adb`:

Plug the device into a USB port on your computer.

Connect the device to the same Wi-Fi network as your computer.

Get your device IP address, in Settings → About phone → Status, or by executing this command:

```
adb shell ip route | awk '{print $9}'
```

Enable adb over TCP/IP on your device: `adb tcpip 5555`.

Unplug your device.

Connect to your device: `adb connect DEVICE_IP:5555` (replace `DEVICE_IP` with the device IP address you found).

Run `scrcpy` as usual.

Run `adb disconnect` once you're done.

Since Android 11, a wireless debugging option allows you to bypass having to physically connect your device to your computer.

Autostart

A small tool (by the `scrcpy` author) allows you to run arbitrary commands whenever a new Android device is connected: `AutoAdb`. It can be used to start `scrcpy`:

```
autoadb scrcpy -s '{}'
```