CALIBER MINING AND LOGISTICS LIMITED · PULSE-II · UTILISATION & EXCEPTIONS

Breakdown & Idle Hours

Operating manual

For site in-charges, MIS staff and reviewers · Matches the system as of 9 November 2026 · The picture uses sample data, not real records

1. What this report shows

Shows every saved VLB and ELB log book in the chosen dates with its shift hours, its running hours from the HMR readings, the breakdown (BD) hours saved with it, and the hours left over. It also says where the BD hours came from. A site in-charge or MIS clerk uses it to see idle time shift by shift and to find log books whose breakdown hours are missing or were typed by hand.


> **One row.** One row is one saved log book: one door, on one date, in one shift.

2. Open the report and choose what to see

In the left menu open **Reports** → **Utilisation & Exceptions** → **Breakdown & Idle Hours**. Then set the selectors described below.

Selector or button	What it does
From	First book date to include. It opens on the 1st of the current month (India time). Dates before 1 November 2026 are not accepted.
To	Last book date to include. It cannot be earlier than From, and From to To can cover at most 366 days. If the dates are not valid the screen shows "Choose a valid date range of at most 366 days." and no report is shown. Keep in mind: Actions → Reset table also puts From back to the 1st of the current month and To back to today.
Site	Keeps only log books of that site. "All" means every site assigned to your login. Once a site is chosen, the Shift, Vehicle / equipment, Driver / operator and Work order lists show only that site's entries.
Shift	Keeps only log books saved against that shift.
Vehicle / equipment	Keeps only log books of that door number.
Driver / operator	Keeps only log books of that person. The list holds only people found on log books or scan cards in the chosen dates.
Work order	Keeps only log books saved against that work order.

3. What is on the screen



Picture 1. The report screen: selectors, totals and the table. *Sample data.*

On the screen	What it shows
Report	Picker at the top of the screen. It lists all reports under their groups; choosing a name opens that report.
Refresh	Loads the saved records for the chosen dates again. Press it after new log books have been saved. Changing Site, Shift or the other selectors does not need Refresh.
Filters:	One line showing what is selected in Site, Shift, Vehicle / equipment, Driver / operator and Work order, written as "site: …", "shift: …", "asset: …", "employee: …" and "workOrder: …". With nothing selected it reads "All sites, assets, shifts and employees". Site and Work order appear by name; Shift, Vehicle / equipment and Driver / operator appear as the system's internal number.
logbooks	Number of saved VLB and ELB log books that match the dates and selectors.
assets	Number of different doors on those log books.
trips	Total trips on those log books.
report rows	Number of rows in the table below. On this report it equals logbooks.

Residual idle = scheduled − running, and includes breakdown time. BD is the saved snapshot, not a live refresh; missing BD is unavailable.	Notice shown above the table on this report. It states how Residual idle HRS is worked out and that BD HRS is the figure stored with the log book.

4. The columns

Column	Meaning
Date	Book date of the log book.
Site	Site saved on the log book.
Book NO	Book number of the saved log book.
Door NO	Door number of the vehicle or equipment.
Caliber ID	Employee ID of the driver or operator on the log book.
Employee	Name of the driver or operator on the log book.
Shift	Shift name saved on the log book.
Scheduled HRS	Shift hours saved on the log book.
Running HRS	Closing HMR minus opening HMR. Shown as "—" if a reading is missing.
BD HRS	Breakdown hours saved with the log book. Shown as "—" when no breakdown hours were saved; this means not available, not zero.
Residual idle HRS	Scheduled HRS minus Running HRS. It includes the breakdown time. Shown as "—" when Running HRS is not available, and is a minus figure when running hours are more than the shift hours.
Source / warning	Where BD HRS came from. "Saved Pulse breakdown snapshot": taken from Pulse when the log book was saved. "Manual entry · Pulse unavailable": typed by hand because Pulse could not give the hours. "Breakdown unavailable": no BD hours were saved. Any other sentence, such as "Pulse breakdown connection unavailable.", is the warning stored with the log book when Pulse could not give the hours.

5. Keep in mind

- Residual idle HRS already contains the breakdown time. Do not add BD HRS to it.
- BD HRS is the figure stored when the log book was saved. If the breakdown is changed in Pulse afterwards, this report does not change.
- A "—" in BD HRS means the hours are not available. It does not mean there was no breakdown.
- A minus figure in Residual idle HRS means the HMR difference is more than the shift hours. Check the readings in Meter Reading Exceptions.
- Only saved VLB and ELB log books of sites assigned to your login are read. LMV log books, deleted log books and dates before 1 November 2026 are not included.

6. Download, print and search

- Tables on this page have a **Generate** button: **Download as PDF**, **Download as Excel** or **Smart Print**. The file contains the whole table, not only the rows visible on screen.
- Type in **Search this report** to find a door number, driver or card inside a table.
- Press a column heading to sort by that column.
- If the page looks old after an update, press **Ctrl + F5** once.

7. Review checklist

Step	Do this
1	Set From and To, then choose the Site.
2	Click the Source / warning heading to sort, and note every row that does not read "Saved Pulse breakdown snapshot".
3	For rows reading "Manual entry · Pulse unavailable", compare BD HRS with the breakdown entry in Pulse for the same door, date and shift.
4	Look for rows where Running HRS shows "—" or Residual idle HRS is a minus figure, and check those log books in Meter Reading Exceptions.
5	Where BD HRS is more than Residual idle HRS, running hours and breakdown hours together are more than the shift. Recheck the HMR readings on that log book.

> **This manual shows how to read and verify the report.** What action to take on its findings is as instructed by management.

8. Common questions

Question	Answer
Is Residual idle HRS the idle time without breakdown?	No. It is shift hours minus running hours, so the breakdown time is inside it.
Why does BD HRS show "—"?	No breakdown hours were saved with that log book. Source / warning tells you why, for example "Breakdown unavailable" or a Pulse warning.
The breakdown was corrected in Pulse. Why is BD HRS still the old figure?	The report shows the figure stored with the log book. It is not read again from Pulse.