VLB + ELB Batch: what changes for you

Team guide for site MIS users and Project Managers | Caliber Pulse-II (pulse-ll.cmll.in) | live from 01 November 2026, updated 02 November 2026 (PM approval by OTP)

1. In one paragraph

From today a batch is not finished when the tipper cards are in. The batch first locks the tipper side (VLB), then shows you every machine booked at your site with the trips it loaded already filled in, and asks you to save a shift status for each machine (ELB). The batch closes only when every machine has a saved status. If a card names a tipper or machine that belongs to another site, the card is kept on hold and the transfer can be completed on the spot with a one-time password (OTP) from the Project Manager of the site that currently owns the asset. A brand new machine or tipper can be added the same way with an OTP from your own PM.

Nothing about scanning, uploading or manual VLB entry has changed. The new part starts at Lock VLB.

2. The shift, step by step (MIS user)

1. Create the batch for your site, date and shift as before. The batch shows two steps at the top: 1 VLB and 2 ELB.
2. Enter all tipper cards by Manual, Scan or Upload, exactly as today.
3. Press Lock VLB. The system checks that every loading machine on the cards is a known machine and that no card is waiting for a transfer. If something blocks the lock, the message names the card or the asset. After the lock, tipper cards cannot be changed.
4. The machine list appears: every machine booked at your site in Pulse, loaders first with their trips, then dozers, graders and the rest with zero trips. Press Start machines.
5. A small dialog opens for one machine at a time. Choose the shift status, fill the fields it asks for, press Next. Use Previous to go back and Skip to leave one for later. Your typing is saved automatically every few seconds, so a dropped connection loses nothing.
6. When every machine is saved, press Close batch. If any machine is still missing, the message lists them, loaders first with their trip count.
7. The batch report now has a second table: machine-wise trips, hours and trips per hour for the shift.

> **Batches that were already open before today**
> They start at step 1 VLB. Press Lock VLB when the tipper cards are complete, then enter the machines. ELB cards for a site, date and shift whose batch is still at VLB cannot be saved until that batch is locked; the message says "Lock VLB first".

3. Shift status for each machine

Status	When to use it	You must enter
Working	The machine ran this shift (any trips, or a dozer/grader with no trips).	Operator, opening HMR, closing HMR. Hours must be above zero.
Working, partial breakdown	It ran part of the shift and was down for the rest.	Operator, HMR, breakdown hours (less than the shift) and the reason.
Breakdown	Down for the whole shift.	The reason. Breakdown hours are set to the full shift.

Maintenance	Planned service or maintenance.	The reason or the job card number.
No operator	Fit, but nobody to run it.	Nothing.
Not in use	Parked, no requirement.	Nothing.

- A machine that loaded trips must be Working or Working, partial breakdown. The dialog tells you how many trips and on which cards.
- Zero trips with zero hours is not Working. Choose maintenance, no operator, breakdown or not in use.
- Pulse breakdown hours, when available, are shown next to the field so you can accept or correct them.

4. A tipper or machine that belongs to another site

Earlier the card was rejected. Now it is saved and marked Awaiting transfer. It stays out of the lock, the close and the reports until the asset is transferred to your site in the Equipment master. You do not need to retype anything; the moment the transfer is done, every card naming that asset becomes normal.

Express transfer by OTP

1. In the Awaiting transfer panel on the batch, press Express transfer (OTP) on the asset row. One request covers every card naming that asset in this batch.
2. The system raises a vehicle transfer from the asset's current site to your site and sends the OTP to the Project Manager(s) of that current site, on Telegram, or on WhatsApp if Telegram is not linked.
3. Phone the PM. The PM reads the six-digit code to you. The PM should share it only after confirming the asset really is working at your site.
4. Type the code and press Verify. The transfer completes, the Equipment master moves the asset, the hold clears, and your own PM gets a notification.
5. The code is valid for ten minutes, allows five wrong attempts, and a new one can be requested after one minute.

> **Project Managers: what the message looks like**
> "Caliber Pulse: vehicle transfer approval. VPC-019 is being logged at JAYANT OC but is assigned to NIGAHI. Transfer VT-...: NIGAHI -> JAYANT OC, date 01-11-2026. Requested by <name>, batch CMLL/JAYANT OC/1ST-NOV-26/S1/B02. OTP 482913, valid 10 minutes. Share it only if you release VPC-019 to JAYANT OC." If you do not agree, ignore it; the code expires on its own.

If the PM of the other site has neither Telegram linked nor a mobile registered, the button tells you so. The normal Vehicle transfers workflow still works for that case.

5. A new tipper or machine that is not in the master at all

1. When a door number matches nothing anywhere, the entry field shows Create new equipment. Press it.
2. Fill door number, Vehicle or Equipment, name, make, model, registration and chassis. Chassis or registration is compulsory, because Pulse later links the asset by one of them. Site is fixed to your batch site.
3. If the same chassis, registration or door already exists at another site, the system says so and offers the express transfer instead. Do not create a second record.
4. The OTP goes to your own site's Project Manager. Enter it and the asset is created at your site; the waiting card can then be saved.

> **Pulse remains the only Equipment master**
> Pulse-II reads the master from Pulse. Until Pulse accepts these changes directly, each express transfer and each new asset is marked "local-only" in Pulse-II. The Pulse administrator must record the same transfer or asset in Pulse so the next sync agrees. MIS will share the list.

6. Reopen a batch or Unlock VLB with the PM's OTP

Both controls that need the site Project Manager can now be approved by phone. The PM does not have to sign in. The same six-digit code rules apply as for transfers: ten minutes, five wrong attempts, a new code after one minute, one use.

Reopen a closed batch

1. Open the closed batch and press Request PM approval as before. Type the reason.
2. Press Request reopen OTP. The code goes to the Project Manager(s) of your site on Telegram, or WhatsApp if Telegram is not linked, with the batch name and your reason.
3. Phone the PM. The PM reads the code to you. Enter it and press Verify OTP.
4. The batch reopens for you immediately, at the machine stage. If something else blocks the reopen (for example another batch is still open at the site), the approval is kept and the Reopen approved batch button works once that is cleared.
5. The on-screen approval still works. If the PM is at a desk, they can approve in Pulse-II as before.

Unlock VLB after the lock

1. At the machine stage press Unlock VLB (PM OTP). Type the reason: which tipper cards must change and why.
2. Press Request unlock OTP, phone the PM, enter the code, press Verify OTP.
3. VLB unlocks. The machine list is cleared and rebuilt at the next Lock VLB; machine entries already saved stay in the Equipment Log Book.

> **Project Managers: reading out the code is your approval**
> The batch audit records that the reopening or unlock was approved by OTP, which PM logins received it, who entered it, and the reason. Share the code only after you understand the reason. If you do not agree, ignore it; it expires on its own.

If you are both the site PM and the MIS user raising the request, you may approve your own reopening request on screen. The audit shows the same login in both roles.

7. For Project Managers

- Link your Telegram to the MIS bot. OTP requests for transfers out of your site arrive there. Without Telegram, the OTP goes to your registered mobile on WhatsApp; without either, nothing can be approved by phone.
- Reopening a closed batch still needs your approval: on screen as before, or by reading out the OTP the MIS user requests to your Telegram or WhatsApp. The batch reopens at the machine stage; if the tipper cards also need correction, Unlock VLB is available to you on screen, or the MIS user can request an unlock OTP from you.
- Reading out an OTP is a transfer approval. Treat it like signing the dispatch paper.

8. Quick answers

Question	Answer
Can I add a tipper card after Lock VLB?	Not directly. Press Unlock VLB (PM OTP), type the reason and enter the code your PM reads out; or ask the PM to Unlock VLB on screen. Add the card, lock again. The machine list is rebuilt.
The PM is not at a computer.	Use the OTP. Reopen and Unlock VLB can both be approved by phone; the PM only needs Telegram or WhatsApp.
The list shows a machine that left our site weeks ago.	Save it as Not in use with a remark and ask for the master correction in Pulse.
A machine is on the list twice.	The Equipment master has duplicate identifiers. Report it; closure is blocked until it is fixed.
My ELB scan was refused with "Lock VLB first".	The batch for that site, date and shift is still at the tipper stage. Lock VLB there, then the scan saves.
Wrong OTP five times.	That code is dead. Request a new one after a minute.
Does V19, VL19 or VPC 019 matter?	No. They are the same machine in the master and the system treats them as one.
Where are the day-wise machine numbers?	As before, in Reports -> Trips & Productivity. The shift view is now on the batch itself.

9. If something goes wrong

The whole new flow sits behind one server setting. MIS can switch the site back to the old single-step Save & lock batch in minutes without a redeploy, and switch it on again later. Report problems to MIS with the batch name, the machine or asset, and the exact message on screen.