X-TREME PHOTO

PHOTO PREP

Staff User Guide

Version 2.14.2 · November 2026

Door Mode, Meet and Greet and Group Photos

X-treme Photo Services
For staff use

Software by Ozark Mountain AI LLC
Licensed to X-treme Photo Services

CONTENTS

01	About this guide	1
02	Door Mode, Meet and Greet or Group Photos	1
03	Quick start: a normal night (Door Mode)	2
04	The screen at a glance	2
05	Step 1: Prep	3
06	Step 2: Edit — the photo list	5
07	Edit tools, one by one	6
08	AI Optimize + Verify	11
09	Templates	12
10	Step 3: Export	13
11	Meet and Greet	14
12	Group Photos	18
13	Installing, updating and uninstalling	20
14	Troubleshooting and FAQ	22
15	Keyboard shortcuts and glossary	23

New to Photo Prep? Read Quick start first, then keep this guide by the workstation. Problems go to the owner, with the photo and the error log (see Troubleshooting).

SECTION 01

About this guide

Photo Prep turns a night's photos into finished prints. It has three modes (Door Mode, Meet and Greet and Group Photos, below); Door Mode's three steps, **Prep**, **Edit**, **Export**, are the heart of it. It replaces FXhome PhotoKey 6 Pro at X-treme Photo Services and works the same way where it can: tools on the left, the photo in the middle, a toolbox on the right.

This guide is the reference for staff. Read Quick start once, then come back to the section for whatever you are doing.

Two rules hold everywhere in the app:

- **Nothing is tied to a venue or a person.** There are no logins and no venue lists. The app opens blank, and staff load the template for the show they are shooting. The only PIN is the supervisor's, for *Train* (Canvas).
- **Originals are never changed.** Prep writes copies into a separate folder. Edit and Export work from those copies. The photos off the camera card stay exactly as shot.

Photo Prep is developed by Ozark Mountain AI LLC and licensed to X-treme Photo Services. The version number is in the bottom-right corner of the window.

This guide is built into the app. Click **User Guide** at the bottom of the Photo Prep window, or press **F1**, to open it. It always matches the version installed.

SECTION 02

Door Mode, Meet and Greet or Group Photos

Photo Prep opens on a dashboard with three choices:

- **Door Mode** for photos from a memory card: **1 Prep → 2 Edit → 3 Export**. Most of this guide is about Door Mode.
- **Meet and Greet** for photos straight from the camera (Nikon D5300 over Wi-Fi, or USB): **1 Camera → 2 Edit**, with a **Print** button in Edit. See *Meet and Greet* below.
- **Group Photos** for big groups shot as they are, no green screen: **1 Prep** (load the photos and name each group) **→ 2 Edit → 3 Export**. See *Group Photos* below.

Photo folder (the strip under the three modes): click **Pick...** once and choose the photo backup folder, where each night's card folders are kept. From then on every "pick the photos" window (Prep's Browse, Group Photos' Browse, Edit's Import) opens there, or right beside the last card you picked inside it, so the other nights are one click away. **Open** shows it in File Explorer; **Change...** picks another. It's remembered on this PC. If the drive isn't plugged in, the strip says so and the windows open where they used to.

The last mode used on the PC is marked *Last used*. The mode button at the top, next to PHOTO PREP, takes you back to the dashboard to switch. Switching closes the photos that are open (nothing is deleted). **Each mode has its own templates**, in its own folder (see *Templates*). Each mode keeps its template while you're in another, so switching to Group Photos or Meet and Greet and back brings Door Mode's template back as it was, unsaved changes included (and the same for the others). Training in one mode never changes another mode's template. A Door Mode template opened in Meet and Greet (or the other way round) opens as a new template for the mode you're in; the file itself isn't changed. Group Photos templates only open in Group Photos. A folder's remembered setup only comes back in the same mode. Save the template to keep it for other nights and other PCs.

SECTION 03

Quick start: a normal night (Door Mode)

Most nights take five steps per card: open the show's template, Prep the card, check the AI's work, nudge what needs it, Export. Then Start New Card for the next one.

1. **Open the template.** Double-click the show's `.pptemplate` file, or in Edit click **Open...** next to the Template box. The backgrounds, overlay, caption and print size load with it.
2. **Prep the card.** Go to **1 Prep**, click **Browse...** next to *Pick the night's photos* and choose the card's folder. Tick **AI Optimize every photo when prep finishes**, then click **Start**.
3. **Check the AI's work.** When Prep finishes, click **Next: Edit**. Step through the photos with the **↓ / ↑ arrow keys** or the ▲ ▼ buttons under the preview. Photos the AI couldn't fix carry a **⚠ check** tag.
4. **Nudge what needs it.** Fix the tagged photos first. Whatever you change applies to the photo on screen only, so fixing one photo never touches the rest of the card.
5. **Export.** Go to **3 Export**, check the printer's hot folder, and click **Batch Export**. Tagged photos are held back until someone edits them.
6. **Next card.** Click **Start New Card** on the Export screen. You're back in Prep with the template still loaded; pick the next card's folder and click **Start**.

> **Tip.** no green screen at this account? Skip Prep. In Edit, click **Import** under the photo list instead. See *Importing without Prep* in the Edit section.

SECTION 04

The screen at a glance

The three steps are tabs at the top right; Edit, where most of the work happens, is laid out like PhotoKey.

AREA	WHERE	WHAT IT'S FOR
Step tabs	Top right: **1 Prep**, **2 Edit**, **3 Export**	Move between the three steps. You can go back and forth at any time.
Template bar	Edit, across the top	Template name box with **Open...**, **Save**, **New**; the view dropdown (**Full Color**, **Alpha**, **Foreground Original**); the sample dropdown (**Quarter**, **Half**, **Full Sample**) and how big the preview is shown (%); **Previous** / **Next** photo.
Tool list	Edit, left side	Canvas, Import, AI, Key, Masks, Filters, Position, Layers, Effects, Overlay, Text, Batch Export. In Group Photos: Canvas, Import, AI, **Frame**, Filters, Position, Layers, Text, Batch Export (no Key, Masks, Effects or Overlay: the photos are kept as shot, and Frame holds the frame). Click one to show its settings in the Toolbox.
Preview	Edit, centre	The finished print as it will export. Yellow boxes on it can be dragged.
Under the preview	Edit, below the photo	**Foreground** / **Background** tick boxes to hide either while you work, and ▲ ▼ to step through photos.
Toolbox	Edit, right side	The settings for the tool you picked, plus **Apply to all** and **Reset All** at the bottom.
Status line	Bottom of the Toolbox	Green = done, orange = needs a look. Read it after every action.
Footer	Very bottom	*Developed by Ozark Mountain AI LLC* (click for the About box), **User Guide (F1)**, **Send logs**, **AI:** what the AI runs on (see *The graphics card*), update messages, and the version number.

View modes. *Full Color* is the print. *Alpha* shows the cut-out in black and white (white = kept, black = keyed out): use it to spot holes or leftover green. *Foreground Original* shows the photo as shot.

Sample sizes. The preview opens on *Half Sample*: as sharp as the print at the size it's shown, and quick to update. *Quarter Sample* is faster but looks soft, so don't judge focus on it. *Full Sample* renders the whole print size; it's slower to update. You rarely need to pick it: zoom in with the mouse wheel and the preview switches to full size by itself while zoomed. Export always renders at full size.

SECTION 05

Step 1: Prep

Prep makes clean copies of the night's photos, ready to key: it fixes red eye and paints everything outside the green screen (walls, floor, light stands) the same green, so Edit only has one green to remove.

To run it:

1. Click **Browse...** next to *Pick the night's photos* and choose the folder from the card.
2. Leave the output folder as it is. Prepped copies go into a **Prepped** folder inside the input folder.
3. Tick the options you want (below) and click **Start**. **Stop** halts it; nothing already finished is lost.

4. When it's done, **Start** becomes **Next: Edit**, and the prepped photos open in Edit automatically.

OPTION	DEFAULT	WHAT IT DOES
Fix red eye	On	Finds faces and removes red from pupils. Only the pupils change, never skin.
Fill off-screen areas with green	On	Paints walls, floor and stands outside the curtain backdrop green. People, and anything they're holding, are left alone.
Warn if eyes look closed	On	Checks every face for closed eyes and marks the photo ⚠ **eyes** in Edit. A warning only: the photo isn't changed or held back.
AI Optimize every photo when prep finishes	Off	Runs AI Optimize + Verify on every photo right after Prep, so the card comes out print-ready. Recommended.
Skip photos already in output	Off	Re-running Prep on the same folder only does new photos. Photos prepped by an older version of the person rules are redone automatically.
Watch input folder for new photos	Off	Keeps running and preps new photos as they land in the folder, e.g. straight off a tethered camera. Pairs with Edit's **Hot Folder**.
Save before/after previews	Off	Writes side-by-side previews into a `_previews` folder, for checking Prep's work.
Green sensitivity	25	Lower = more shades count as green. Leave it at 25 unless the log flags problems.

The log. Prep writes `_photo_prep_log.csv` into the Prepped folder. Rows marked **CHECK** are worth a human look: *no green backdrop, fill skipped* (the photo had no green screen and was left alone), *large fill* (an unusually big area was painted), or *could not process* (the file wouldn't open).

What gets painted. Everything around the curtain that isn't a person: walls, stands, the high table and stools beside the backdrop, and the curtain's own dark, shadowed sides where it wraps round its frame (painted in gradually, so the lit curtain is never touched). Beside the curtain, where a black suit stands against a black wall and the AIs can't tell where one ends, Prep redraws that person's outline from the colours and edges, so an arm isn't painted off and a chunk of wall isn't kept. Furniture joined to someone at the side of the frame is painted; a stool or table standing clear of the frame's edge right against someone can still be kept, so check those in Edit's Masks.

Prep checks its own work. Before painting anything green, Prep checks its plan with a second AI, the face finder used for red eye. Everyone has a body under their face, so if the plan would paint the area right under a face, Prep has made a mistake (a dark green shirt read as curtain, say). It does the same for legs and anything held below the waist, like a walker or a cane, when the detailed AI sees them standing in front of the curtain. And when the people AI misses a whole guest (an olive sweater against the curtain) but the detailed AI and the face finder both see them, that guest is kept too. It leaves that body as shot, tells Edit it's a person, and writes *CHECK - Prep corrected itself* in the log. The photo is fine; send it to the owner so the rules can be tuned.

Closed eyes. With *Warn if eyes look closed* on, Prep looks at each face's eyelids. A photo where someone may have blinked shows ⚠ **eyes** in the photo list, and Edit shows an orange band on the preview saying who: *Eyes may be closed: 2nd from left* (counted across the photo, left to right). Prep's log and its last line

say how many. It's a warning only: nothing is changed, and Export and Print aren't held up. A big squinting smile can set it off, and a half-blink can slip past, so treat it as a pointer. Photos brought in with **Edit › Import** are checked too, with the same tick. Faces too small to judge (big groups, people far back) aren't checked, and Group Photos never are.

SECTION 06

Step 2: Edit — the photo list

The photo list lives under **Import › Foreground**: one row per photo, with its tag. Everything you do in Edit happens on the photo selected there.

Moving through photos. Press the **↓ / ↑ arrow keys** (they work wherever you are in Edit, even right after moving a slider), click a row, use ▲ ▼ under the preview, or **Previous** / **Next** in the top bar. Page Down / Page Up still work too. Stepping stops at the first and last photo (it doesn't jump round to the other end), and hovering over ▲ or ▼ shows the photo on screen in a bar above the pointer (*DSC_0012.jpg · 3 of 40*). Type in **Search** to filter by file name; **Name ↑ / Name ↓** flips the sort.

Red rows. A photo flagged for any reason (⚠ check, ⚠ Prep check or ⚠ eyes) shows as a **red row** with a red bar down its left edge, so it can't be missed while you scroll. A ⚠ check or ⚠ Prep check row goes back to normal once someone edits that photo; ⚠ eyes stays, since editing can't open eyes.

Tags on each row:

TAG	MEANING
⚠ check	The AI couldn't fix something. Held out of Export until someone edits the photo.
⚠ Prep check	Prep flagged the photo when it painted the green (its note shows in **Masks**). Check it; editing the photo clears the flag.
⚠ eyes	Someone's eyes may be closed. The preview's orange band says who. A warning only.
edited	Someone changed this photo by hand.
AI ✓	AI Optimize ran and verified it clean.
as shot	Imported with no green screen; used as shot (see below).

Hot Folder. Tick **Use Hot Folder** and new photos from Prep (with *Watch input folder* on) appear in the list as they're prepped.

Remove takes the selected photo out of this batch. The original and its prepped copy stay on disk; prepping it again brings it back.

Importing without Prep

Import (under the photo list) brings photos straight into Edit, skipping Prep. Use it for accounts that don't shoot on green screen, or to add a few photos to the open batch.

Drag and drop works too: drag photos, or a whole folder, from File Explorer onto the photo list. Only .jpg, .png and .tif files come in; anything else in the folder is skipped (subfolders aren't opened). The Import button opens in the **Photo folder** set on the dashboard (or beside the last card you picked in it); with none set, in the folder you last imported from.

- **No green screen:** the photo is used *as shot*. It fills the print and isn't keyed, and the row is tagged **as shot**. Red eye, filters, layers, overlay, text and AI Optimize all still work. The Key tool notes that its settings don't apply.
- **Green screen:** keyed as usual, without Prep's green fill.
- Red eye on imported photos is fixed live, so unticking *Red Eye* in the Key tool brings the original eyes back.
- If you later run the same photos through Prep, they're treated as normal prepped photos from then on.

Zooming in on the preview

Mouse wheel over the preview zooms in on the spot under the pointer (up to 8×), and out again down to the whole print. Zoomed in, **hold the left button and drag** to move the photo around (anywhere that isn't the yellow box or a mask point; a click still adds a mask point). The middle button drags too. **Ctrl+0** shows the whole print again. While zoomed, the preview is made at full size automatically, so it stays sharp; the toolbar shows how big it's shown. Zoom only changes the view, never the print.

Changes belong to one photo

Every change you make in Edit (key, filters, position, layers, effects, overlay size and spot, text, masks, red eye) applies to **the photo on screen only**. Photos you haven't touched show the template's look, so opening a template still reaches them.

- **Apply to All** puts this photo's look on every photo (each keeps its own position and masks). This is the one way to change the whole card at once.
- **Reset All** puts this photo back on the template's look. The small ↺ arrow on a section resets just that section.
- **Save Template** saves the template, not changes made on single photos. To save a photo's look as the template, click **Apply to All** first, then **Save**.

SECTION 07

Edit tools, one by one

Each tool on the left opens its settings in the Toolbox. Most have a tick box to switch the section on or off and a ↺ arrow to put it back to the template's setting. Yellow boxes on the preview work like PhotoKey's Position tool: **drag anywhere inside** to move; the **crosshair** in the middle has a **vertical arm: drag it up to make bigger, down to make smaller**, and a **horizontal arm: drag it right or left to rotate** (the arm being dragged turns blue). Corners still resize too.

Overlays and backgrounds don't turn, so their boxes only have the vertical arm. Scaling and turning happen round the box's pivot, the small square (for the people, their feet).

Canvas

- **Print Size:** 6 × 8 inch (default) or 8 × 10 inch, landscape, 300 dpi. Every photo exports at this size. Saved in the template. Meet and Greet always prints 8 × 10.
- **Canvas Color:** tick **Use Color** to put a plain colour behind the people instead of a background image.
- **Group Placement** (Group Photos only, in place of People Placement): see *Clay Cooper or King's Castle*.
- **People Placement:** how Auto-fit and the AI place the group, in X-treme house style. The bottom of the print cuts people at the **Cut-off** (share of standing height), then the group is made as big as fits under the **Headroom** (space above the tallest head) and no wider than **Max width**, centred. Feet never show.

GROUP	HEADROOM	MAX WIDTH	CUT-OFF
Couples and trios	13%	85%	56% (mid-thigh)
Big groups (5+)	10%	92%	84% (mid-shin)

A group of 4 is cut halfway between the two. These numbers were fitted to X-treme's own finished prints; change them only if the house style changes. They're saved in the template.

Keep the real floor (SIX). For shows photographed full length, like SIX's meet and greet, tick **Keep the real floor** under People Placement in that show's template:

- **The floor stays as shot.** Everything below the curtain's bottom edge (the carpet, feet, real shadows) is kept from the photo. Photo Prep finds that edge on every shot by itself. Above it, the green and anything beside the curtain (the concession stand, a pole) is replaced by the background. Floor masks aren't needed.
- **Full length.** The feet stand on a line **Feet at** % down the print. The group is as big as fits under the **Headroom** and no wider than **Max width**, centred. Cut-off isn't used. Ticking it sets X-treme's SIX numbers: feet at 90%, headroom 28%, max width 93%. Unticking goes back to the house style.
- **The carpet never ends on the print.** The shot always reaches the print's bottom and sides. If a shot has very little floor below the feet (framed tight), the group stands lower, down to the print's bottom edge. It is still full length on the strip of real floor the shot has; it isn't cut at the shins.
- **It's meant for Meet and Greet.** It works in Door Mode too, where it uses the photo as shot instead of Prep's green-painted floor.
- **Brightness:** SIX's shots come in exposed right, so set **Filters › Auto Brightness › Style** to **Light touch** in the SIX template.
- **Train** works here as well: it learns Feet at, Headroom and Max width from photos placed by hand. It leaves out shots that had too little floor to place freely.

If someone is cut off at the side or top of the original shot, the photo is scaled so the cut sits on the print's edge instead of floating inside it.

Train (supervisor). Photo Prep can learn the margins from photos a supervisor places by hand, in Door Mode, Meet and Greet and Group Photos:

1. Open a batch with the show's template. Place a few good photos by hand: **Position**, or drag the yellow box. Pick photos that show the house style well.
2. **Canvas › Train from photos placed by hand...**, then enter the supervisor PIN.
3. A box lists each margin, old → new, and how many photos it learned from. Photos that can't teach anything are left out, with the reason (turned, feet showing, someone off the print, no green screen). Nothing changes until you click **OK**.
4. **OK** sets the new margins in the template. The training photos go back on Auto-fit, which now puts them where you did, and every other photo follows the new margins. **Save** the template to keep them.

Training changes only the template open in the mode you're in: training in Meet and Greet leaves the Door Mode template alone, and the other way round.

A margin changes only when at least 2 photos of that kind were placed by hand: couples and trios (up to 4 people) for the top numbers, big groups (5+) for theirs, and group photos for **Group width** and **Front row** (Max zoom stays). A margin the photos don't show stays as it was: a wide group sits by its width, so it can't teach the headroom. Photos moved or sized by the AI or Auto-fit don't count, only ones a person placed.

Import

- **Foreground:** the photo list (see *Step 2: Edit*).
- **Background: Import** adds background images to the library (or drag them onto the panel from File Explorer); click one to put it behind every photo. **Remove** takes it out. **Zoom & Crop** uses just part of the picture: **Zoom** up to 500%, then **Left / Right** and **Up / Down** (±100 puts that edge of the picture on the print's edge), or drag its yellow box.

Key

The Key removes the green screen. The defaults suit X-treme's curtains; most nights you won't touch it.

- **Red Eye:** on by default (fixed in Prep, or live on imported photos). Untick to keep this photo's eyes as shot. **Missed one?** Click **Select Eyes**, drag an oval round each red eye (as many as you like; right-click takes the last one back), then click **Remove Red Eye**. Only the red of the pupil changes, never the skin. **Undo Manual Fixes** removes them. **Esc** leaves selecting.
- **Auto Color Difference: Color** (Green or Blue screen), **Removal** (how hard green is removed), **Detail** (more keeps finer hair), **Softness** (how soft the edge is).
- **Matte: Clip Backg.** / **Clip Foreg.** tidy almost-clear and almost-solid edges; **Erode/Expand** shrinks or grows the cut-out edge.
- **Alpha Blur:** softens the cut-out edge.
- **Spill Suppression:** removes green light bounced onto people. **Spill Simulation** replaces it with the new background's light; **Desaturate** greys it out. Green clothing (a green shirt, a purse, lettering) keeps its colour.

The AI person-finder guides the key: deep inside a person is always kept and far away from everyone is always removed, so green clothes stay and wrinkles in the curtain go.

Masks

For what the key gets wrong, like a stool left in the shot or a hand that went missing. Group Photos has no Masks (nothing is keyed); its **Theatre Seats** is under **Frame**.

Keep the real floor on one photo. For a one-off shot that should be full length, like a group of 15 standing in front of the backdrop with their feet in the shot, tick **Masks › Floor › Keep the real floor on this photo**:

- The floor stays as shot (carpet, feet, shadows), even where Prep painted it green.
- The backdrop is replaced only above the curtain's bottom edge, the same as the SIX template does.
- The photo is placed full length, with the feet 90% down the print.
- Only that photo changes. The rest of the card keeps the house style (cut at the shins), and Apply to All doesn't copy it.
- Untick it to go back.
- In a template that already keeps the real floor (SIX), the card just says so.

Undo Prep's fill. Prep paints the floor and anything near people that isn't part of them green *before* Edit sees the photo, so a mask alone can't bring back something Prep painted over (a walker, a cane, a foot). At the top of Masks, **Undo Prep's Fill on This Photo** switches that one photo to the original as shot (red eye still fixed). Then mask by hand: **Retain Alpha** round what should stay, **Remove Alpha** round floor or stands that should go. **Put Prep's Fill Back** returns to Prep's version. It only ever affects the photo you're on. If Prep flagged the photo, its note shows here too.

1. Click **Add Mask**, then click points around the area. Each point joins the last, and points can go outside the photo. The points are small so they can sit close together round fine detail: zoom in (below) for hair, fingers or the edge of a sign.
2. Close the loop by clicking the first (yellow) point, or press **Enter** / click **Done**. Nothing is cut until the loop is closed.
3. Drag points to adjust.

Leave and come back any time. A mask you haven't closed keeps its points. Go to another tool or another photo, and when you come back it's marked *(not closed yet)* and picks up where you left off: keep clicking, then click the first point to close it.

Type: Remove Alpha (default) cuts the area out; **Retain Alpha** forces it to stay. **Feather** softens the mask edge; **Invert** flips it. **Esc** stops drawing for now (the points stay).

Filters

Foreground filters act on the people; **Background** filters act on the background image.

- **Auto Brightness** and **Auto White Balance** are the AI's, measured on the people's faces. Auto Brightness has two **Styles**. A Style is the show's choice: picking one sets it on every photo and in the template (Save to keep it).
- **House** (the default; Door Mode): brings every face to X-treme's house brightness.
- **Light touch**: leaves faces that are already exposed right as shot, and only lifts dark ones or calms bright ones. Use it for shows whose shots come in correctly exposed, like SIX, where House washes the faces

out.

- PhotoKey's full list: Transparency, White Balance (eyedropper), Auto Levels, Auto Contrast, Auto Color, Brightness, Contrast, Saturation, Levels, Color Temperature, Color Balance, Hue Colorize, Hue Shift, Sharpen, Blur, Bilateral Blur, Defocus, Diffuse, Vibrance, Leave Color, Half Tone, Half Tone Color, Silhouette, and Shadow Cast (people only).
- Tick a filter to switch it on. The arrows change the order they're applied in.

Position

- **Foreground (the people): Auto-fit** sizes and centres them on the floor line using People Placement. **Position** (Horizontal / Vertical), **Scale**, **Rotation** (Angle) and **Flip Horizontal**. Or use the yellow box on the photo.
- **Background:** the same **Zoom & Crop** as in Import.

Layers

For a prop, sign or logo between the background and the people, or in front of them.

- **Add Layer** and pick a PNG with transparency. A JPG works but shows as a box.
- **Size**, **Angle**, **Horizontal** / **Vertical**, or drag its yellow box. Tick **In front of the people** to put it on top. **Change image…** swaps the picture; **Remove Layer** deletes it.

Effects

- **Shadow Cast:** a soft shadow on the floor under the group. **Strength** sets how dark.
- **Light Wrap:** bleeds the background's light onto the edges of the people so they sit in the scene. **Amount** sets how much.

Overlay

The show's logo or frame on top of the print.

- **Load…** a PNG (or a Photoshop .psd) that's clear where the photo shows through. **Change…** swaps it; **Remove** takes it off.
- It starts in the bottom right. **Corner** switches between Bottom right and Bottom left. **Size**, **From side** and **From bottom** fine-tune it, or drag its yellow box (inside to move; the vertical arm or a corner to resize). AI Optimize keeps it clear of faces (see *AI Optimize + Verify*).
- Group Photos has no Overlay tool: the show's frame goes in **Frame** (see *Group Photos*).
- The overlay is saved inside the template.

Text

Add Text puts a caption on the print. `{date}` fills in the show date (from the photo's camera date). **Remove Text** takes it off.

In Group Photos, **Group Name** at the top of Text shows this photo's group name; fix a typo there and the printed name and the export name follow. Its **Style**, **Across**, **Down**, **Size** and **Max width** set how and where the name prints (see *Group name style*).

SECTION 08

AI Optimize + Verify

One click makes a photo ready to print: the AI fixes brightness, places the people, puts them on the background, keeps the overlay clear, then checks its own work and retries up to 3 times. What it decides becomes that photo's settings, so the preview shows exactly what will export.

To run it: open the **AI** tool. **Optimize Photo** does the photo on screen; **Optimize All Photos** does the whole batch. Or tick *AI Optimize every photo when prep finishes* on the Prep page. When it's done, **Go to Export** stays pinned at the bottom of the AI panel. In Group Photos the AI only fixes colour and brightness; the frame and the group's place stay put.

Each step can be ticked off:

STEP	WHAT IT DOES
Fix brightness	Brightens dark shots and darkens bright ones, measured on the people's faces. Also sets white balance.
Center the people	Sizes and centres the group the X-treme way (Canvas › People Placement). On an *as shot* photo, the photo is kept as shot instead.
Put the background behind them	Uses the background picked in Import.
Keep the overlay clear	Keeps it off faces and upper bodies; moves it to the other corner if it has to.
Verify, and redo until clean	Scans each finished photo, fixes what it finds (up to 3 tries) and flags anything still wrong for a person.

When a photo is flagged

A flagged photo gets the ⚠ **check** tag and its reason in the status line. It's held out of Export until someone edits it.

THE AI SAYS	WHAT TO DO
no people found in the photo	Check it's the right photo. If people are there, mask them in (Masks › Retain Alpha) or place them by hand.

THE AI SAYS	WHAT TO DO
no background loaded	Import › Background, pick one.
someone cut off at the ... edge of the original shot doesn't reach the print's edge	The camera cut someone off. Press **Auto-fit**, or drag the people so the cut sits on the print's edge.
people run off the ... edge of the print	Press **Auto-fit**, or make them smaller (Position › Scale).
the overlay covers someone	Move the overlay (drag its box or switch the Corner), or make it smaller.
a face is too dark / too bright	Filters › Brightness, or Levels.
green fringe left on the edges	Key › Spill Suppression at 100, or Matte › Erode/Expand a little negative.

After fixing by hand, the tag changes to **edited** and the photo goes into Export.

Re-running the AI on a photo replaces its position and brightness with the AI's choices; masks, layers and manual red-eye fixes are kept.

SECTION 09

Templates

A template is one show's whole setup in a single `.pptemplate` file. Templates replace venues: set a show up once, save it, and any PC can open it.

What a template holds: print size, People Placement numbers, backgrounds (the images are packed inside), the overlay (packed inside), caption, layers, effects, and the shared key and filter settings. A Group Photos template also holds its Oval Window, Group Placement, the theatre-seat setting and the group name's style and spot. It doesn't hold photos. Each mode has its own templates (see *Door Mode, Meet and Greet or Group Photos*).

Build one:

1. Click **New** to start blank.
2. Set Canvas, load backgrounds (Import › Background), load the overlay, add a caption and any layers or effects. You can do all of this before any photos are open; the preview shows the template on its own.
3. Key, people filters, people position and masks need a photo, since they work on the people. Open a few test photos to tune them.
4. Type the show's name in the **Template** box and click **Save**. Templates save to the mode's own folder in *Documents › Photo Prep Templates*: **Door Mode**, **Meet and Greet** or **Group Photos**. Photo Prep makes the three folders itself, and **Open...** starts in the folder for the mode you're in. Templates saved loose in *Photo Prep Templates* by an older version are moved into the right folder the first time Photo Prep starts.

Open one:

- **Double-click** the `.pptemplate` file in File Explorer. Template files show the Photo Prep template icon. If Photo Prep is already open, the template loads into the open window.
- Or click **Open...** in Edit.
- Opening a template resets photo edits to the template's look, so it asks first if any photos have edits.

Share between PCs: the template is one file with every image inside it, so it works the same from Dropbox, a shared drive or a USB stick. Edit it on one PC, save, and copy the file to the others.

New clears everything back to blank. The app always opens blank; nothing is tied to a location or a person.

SECTION 10

Step 3: Export

Export renders every finished photo at full print size. By default the prints go into a **Ready to Print** folder, made next to the **Prepped** folder inside the night's photo folder:

```
Card folder (the night's photos, never changed)
├── Prepped          ← Prep's copies, what Edit works on
└── Ready to Print   ← finished prints from Export
```

1. Check the top lines: the **Template** in use, how many photos will export, and any held back.
2. Under **Save to**, leave **Save to a "Ready to Print" folder next to Prepped** ticked. To send prints somewhere else, like the printer's hot folder, untick it and pick the folder with **Browse...**. Photo Prep remembers your choice.
3. Click **Batch Export**. **Stop** halts it; photos already written stay.

The log ends with the night's total (*Tonight so far: 212 exported*), counted across every export this show night; it's written to the print log too. If the drive is getting full, Prep and Export say so before they start, so it can't run out halfway.

SETTING	DEFAULT	WHAT IT DOES
Print size	From Canvas	Shown for checking; change it in Edit › Canvas.
Format	JPG	JPG, TIFF or PNG.
Quality	100	JPG quality. Leave at 100 for prints.
Prefix / Suffix	Blank	Added before and after the file name. The *Example* line shows the result.
Embed color profile (sRGB)	On	Keeps colours consistent on the printer.
Keep the camera's photo info (EXIF)	On	Keeps the camera date and settings in the file.

SETTING	DEFAULT	WHAT IT DOES
Use Batched Backgrounds	Off	Exports every photo on **each** background in the library; the background's name is added to the file name.
Also save screen-size copies for a sales display	Off	Writes smaller copies for showing on a screen.
Save to a "Ready to Print" folder next to Prepped	On	Prints go in that night's photo folder. Untick to choose another folder.
Open the print folder when done	On	Opens the folder in File Explorer at the end.

Held-back photos. Photos tagged **⚠ check** don't export. The orange line under the count says how many. Fix or edit them in Edit, then click Batch Export again.

Start New Card. When a card is done, click **Start New Card** (above Batch Export). After you confirm, the photo list and the Prep and Export logs clear and Photo Prep goes back to **1 Prep** with an empty folder box, ready for the next card. The template stays loaded: backgrounds, overlay, canvas, text and look. Nothing is deleted: the finished card's prepped photos, edits and prints stay on disk, and opening its folder again brings it all back. Wait for an export to finish, and stop Prep if it's watching a folder, before starting a new card.

SECTION 11

Meet and Greet

For meet and greets: the camera sends each shot to the PC (over its own Wi-Fi or a USB cable), the shot comes straight into Edit already finished, and you print it on the spot. Entering Meet and Greet loads the AI in the background straight away, so the first customer doesn't wait for it. Meet and Greet has its own templates (*Documents › Photo Prep Templates › Meet and Greet*) and always prints **8×10**. For full-length shows like SIX, tick **Canvas › Keep the real floor** in the show's template (see *Canvas*). A Door Mode template opened here opens as a new 8×10 Meet and Greet template (the Door file isn't changed); **Save** it to keep it for meet and greets.

Step 1: Camera (Nikon D5300 over Wi-Fi or USB)

Pick how the shots come in at the top of the Camera page:

CHOICE	WHEN
D5300 over Wi-Fi	No cable: the PC joins the camera's own Wi-Fi (steps below).
D5300 over USB	The camera's USB cable plugged into the PC. Faster than Wi-Fi for full-size JPEGs, and nothing to join. Plug in, turn the camera on, close the Windows Photos import or Nikon Transfer if they pop up, and click **Connect to Camera**. Everything else (settings, test shot, the connection box) works the same as over Wi-Fi.

CHOICE	WHEN
Camera software folder	Another program (digiCamControl) saves the shots into a folder and Photo Prep watches it.

Once per camera: on the D5300, **MENU › Setup › Wi-Fi › Network connection › Enable**. The camera makes its own Wi-Fi network, named like *Nikon_WU2_0090B5....*

Each event:

1. Turn the camera on with Wi-Fi enabled.
2. On the PC, join the camera's Wi-Fi network (Windows' Wi-Fi menu, bottom right). The connection box shows which Wi-Fi the PC is on, and warns if it isn't the camera's.
3. Open the show's Meet and Greet template in Edit first if it isn't loaded, so each shot is finished with it.
4. On **1 Camera**, click **Connect to Camera**. That's it.

The connection box shows where things stand:

DOT	MEANS
Green: *Connected to D5300*	Ready. Battery level is shown, and a picture of the D5300 appears in the bottom-left corner of the Camera page. Every shot taken on the camera comes in by itself.
Amber: *Connecting...*	Looking for the camera.
Red: *Can't reach the camera / Connection lost – reconnecting*	The PC isn't on the camera's Wi-Fi, the camera's Wi-Fi went to sleep, or the signal dropped. Photo Prep keeps trying by itself; shots taken meanwhile come in once it's back.

The same dot shows next to **Camera** at the top of the window, so the printer can see it from Edit. Edit also has a **Photo Transfer** box in its lower-left corner: the connection, the shot coming over from the camera with a progress bar, and when the last one reached Edit with the count so far. Click it to go to the Camera step.

Camera battery. Under Photo Transfer, the **Camera Battery** tile shows the camera's charge as a bar (green, then amber from 35%, red from 15%) and about how long it has left at tonight's rate, for example *About 2 h 10 min left*. The time left needs about 8 minutes and a few percent of drain to work out (*Working out the time left...* until then; *Holding steady* if the level isn't moving). At 15% it turns red: *Low - swap the battery soon*. A fresh battery starts the estimate again. It works over Wi-Fi or USB; watching a folder (Camera software), Photo Prep can't ask the camera.

Each new shot is copied from the camera into the shots folder (a folder per show night, in *Pictures › Photo Prep Camera* unless you pick another), keyed (the green removed, nothing painted over), finished by the AI with the template's background, placement and brightness, and shown in Edit. Only shots taken after connecting come in, unless *Also bring in shots taken before connecting* is ticked. Edit follows the new shots while you're on the latest one; if you've gone back to fix an earlier photo (or are drawing a mask), you stay put and the new shot waits at the top of the list. **Print** waits until the AI has finished the shot you're on. **Closed eyes:** with *Warn if eyes look closed* ticked (on by default), a shot where someone may have blinked gets an orange band on the preview, *Eyes may be closed: 2nd from right*, while the people are still there to

retake it. The check runs in the background, so the shot never waits for it; the warning appears within a second or so, by the time the AI has finished the shot. The shot is also marked ⚠ eyes in the list. It's a warning only; Print still works. Over Wi-Fi a full-size JPEG takes a few seconds to come across; set **Image size** to M and **Image quality** to JPEG normal for faster transfers (still plenty for an 8×10).

Changing the shots folder. Click **Browse...** under *Shots folder* to pick where shots are saved, connected or not. While connected, the camera stays connected: new shots go to the folder you picked (in a folder for the show night) and Edit switches to that folder's shots. The shots already taken stay in the old folder with their edits and prints. Use this to keep each show or group in its own folder.

Camera settings. Once connected, the **Camera settings** panel shows the camera's mode, shutter speed, aperture, ISO, exposure compensation, white balance, image quality, image size and battery. Pick a new value and it goes straight to the camera. Settings the mode dial controls are greyed out: on Auto or a scene mode the camera sets them itself, so turn the dial to **M**, **A**, **S** or **P** to change them from the PC. **Take a Test Shot** fires the shutter from the PC to check the settings.

The photographer keeps their own preview. Connected or not, the camera works as normal: every shot is saved to its memory card and shown on its screen. Photo Prep never starts live view, never takes over the shutter (except **Take a Test Shot**) and never deletes anything from the card; it only copies each shot after it's taken. If another program left the camera set to save shots to a computer instead of its card (digiCamControl can, which is why the preview disappears there), Photo Prep puts it back to the card when it connects and says so in the log. If shots still don't show on the camera's screen, check the camera's **Playback menu › Image review** is **On**.

Disconnect stops the connection. Shots already in stay in Edit; connecting again picks up where you left off.

If it won't connect. The red box says which step the camera stopped at. *Can't reach the camera* with "is this PC on the camera's Wi-Fi?" means the PC isn't on the camera's network (or the camera's Wi-Fi is off or asleep). *It stopped answering while...* means the PC reached the camera but it went quiet: turn the camera's Wi-Fi off and on (MENU › Setup › Wi-Fi › Network connection), close anything else that might be connected to it (Nikon's phone app, digiCamControl), and click **Connect to Camera** again. If it still won't connect, click **Connection log** and send that file to the owner: it records every step with the camera.

Show nights and folders. A show night runs until 5 AM: a show that goes past midnight, or a reconnect at 12:30, stays in the same folder. **Drive space** is checked when you connect and as shots come in; a warning shows in the log (and in the Photo Transfer box when it's nearly full) before it can run out mid-show.

If Photo Prep closes unexpectedly (a crash or a power cut) while Meet and Greet is connected, the next time it opens it asks to carry on: one click brings back the template, Meet and Greet, the camera connection and the same shots folder, and brings in the shots taken while it was down (not ones from earlier nights still on the card).

Camera software folder instead? Pick **Camera software folder**, point it at the folder digiCamControl (free, digicamcontrol.com) saves into, and click **Start Watching**. Camera settings are changed in digiCamControl in that case.

Step 2: Edit and Print

Edit works exactly as in Door Mode; the newest shot is at the top of the list and selected. Fix anything that needs it, then click **Print** at the top right (or press **Ctrl+P**). Photo Prep makes the full-size print and opens the **Print Preview**: the print on the chosen paper exactly as it will come out. Pick the **Printer**, **Paper**, **Orientation** (Automatic matches the photo) and **Copies**; **Printer Settings...** opens the full Windows print options (the printer's own preferences, such as borderless). The note under them says whether the print fills the paper edge to edge, or warns about white edges (paper that doesn't match the print) or a margin (turn on borderless). Click **Print** to send it, or **Cancel**. The printer and paper are remembered for next time. A flagged photo asks before printing. Leave **Orientation** on **Automatic**: it lays the print the right way round whichever way the printer's driver lists the paper (some list 8×10 as "10 × 8").

Smaller prints. Every printer remembers its own paper. For a 5×7 or 4×6 off the 8×10 printer, pick it under **Print size**. Photo Prep picks the smallest paper the printer offers that holds it, centres the print on it with corner marks to cut along, and the canvas doesn't change. **Scale to fit** (on by default) keeps the whole photo, with thin white edges because an 8×10 is a slightly different shape from a 5×7. Untick it to fill the 5×7 exactly; that trims a little off the photo's edges, so check that nothing important (text, the overlay) sits right at the edge.

Two on one sheet. *Two 5 × 7 on one sheet* puts two 5×7s side by side on one 8×10 sheet (half the media per 5×7), and *Two 4 × 6 on one sheet* puts two 4×6s on a 6×8 sheet; cut along the marks (or in half). Both are the same photo, so set Copies for how many pairs. Print size goes back to Full paper for the next print.

A preview that looks wrong on one of the printers: send the owner the file *printer-papers.txt*: type `%LOCALAPPDATA%\Photo Prep` in File Explorer's address bar to find it. It lists every paper that printer's driver offers, exactly as the driver describes it.

Reprint. Reprint... next to Print lists tonight's prints, newest first, with a look at each. Pick one and it goes through the Print Preview again from the same print file, at the same size (a 5×7, or two on one sheet), so it comes out exactly as before.

The Photo Transfer box (bottom left in Edit) also shows the printer and what Windows says about it: *Ready*, *Printing* with how many are waiting, or a problem in orange (*Offline*, *Out of paper or ribbon*, *Paper jam*, *Needs attention*). Under it, **Printed tonight** counts the prints made this show night.

The print log. Every print (and every Door Mode export) is written to *print-log.csv* next to the other logs: the show night, time, photo, size, copies, prints and printer. It opens in Excel for the end-of-night count. If it's open in Excel during the show, prints are still counted (and Reprint still works); they're written to the file once it's closed.

Where things go, all inside the shots folder:

FOLDER	WHAT'S IN IT
(the shots folder)	The shots as they came off the camera. Never changed.
Meet and Greet	Edit's copies and their settings.
Printed	Every print file sent to the printer, at 300 dpi.

SECTION 12

Group Photos

For big groups shot as they are: no green screen, no green fill, no red eye. Each photo goes into the template's frame (the show's art with a window cut for the group), gets auto color and brightness, and has the group's name printed under the title.

Step 1: Prep (load and name)

1. Click **Browse...** and pick the folder of group photos, or drag the folder (or just some photos) onto the window. Copies go in a **Prepped** folder inside it; the originals are never changed.
2. Every photo is listed with its thumbnail. Type the group's name in the box under it. **Enter** (or ↓) goes to the next box, ↑ to the one before.
3. Click **Next: Edit**.

Loading the same folder again only adds photos that are new; names already typed stay. A photo with no name keeps its file name and prints with no label.

Test shots. Click the **×** in the top right corner of a photo's thumbnail to take it out of the batch. It won't be edited or exported, and loading the folder again doesn't bring it back. The file itself stays on disk. Changed your mind? Click **Undo** next to the message at the bottom.

Step 2: Edit

Open the template for the show. Each photo is placed in the frame's window automatically, the way X-treme's staff place them by hand: as wide as the print, zoomed in for a smaller group (up to the template's *Max zoom*), centred on the faces, with the front row at the same height every time. The frame trims what's outside the window. Auto color and auto brightness are on by default (Filters); there's nothing to key. The photo list shows each group's name. To fix a name, use **Text › Group Name**. To nudge one photo, use **Position** as usual.

Clay Cooper or King's Castle

The two theatres are shot differently, and the templates know it: open the show's template and everything below comes with it. Nothing else to pick.

	CLAY COOPER	KING'S CASTLE
Group width (faces fill this much of the window)	88%	92%
Front row (lowest faces, down the window)	64%	47%
Max zoom for a small group	107%	145%

	CLAY COOPER	KING'S CASTLE
Theatre seats along the bottom	—	painted over with carpet
Group name	bold white, under the title	red or black serif, a word per line, beside the year

These were measured on X-treme's own finished prints. They're under **Canvas › Group Placement** (*Like* sets all three at once) and saved in the template. A supervisor can retrain Group width and Front row from photos placed by hand (see *Train* under Canvas).

Theatre seats (King's Castle). Photos taken from the house show the front-row seats along the bottom. **Frame › Theatre Seats** paints carpet over them: the stage's front edge is found from the carpet, the seats below it (and up the sides) are replaced with carpet in the same colour and texture. People are never painted over. It takes a few seconds per photo the first time. Turn it on in the template (Apply to All, then Save) so every photo gets it; untick it on a photo that wasn't taken from the house.

Group name style. Text › Group Name › Style: *Bold white, black outline* (Clay Cooper), *Red serif* or *Black serif* (King's Castle: red on Christmas Wonderland and Spirit of America, black on the Irish Tenors' orange). The serif styles put a word per line, up to three lines (*Cullman / Senior / Center*); more words are shared out over three. A long name goes onto more lines first (up to five; the white style, two), then shrinks to fit **Max width**. If it would print at under 60% of its size, step 1, Edit and Export say so: shorten it. Style, Across, Down, Size and Max width change every photo at once, so the name is in the same place on every print.

Making a Group Photos template from a PSD

1. Start **Group Photos**, load a few photos, go to **Edit** and click **New** (Template) for a blank template.
2. **Canvas:** pick the print size (6×8 for X-treme's Clay Cooper and King's Castle frames), and under **Group Placement** set *Like* to the theatre.
3. **Frame › Load:** pick the show's **.psd** (or a PNG). Photo Prep uses the picture as Photoshop shows it, transparency included; hidden layers don't show. The see-through window in the middle is where the group goes: Photo Prep finds it on its own, words inside it and all.
4. **Text › Group Name:** pick the **Style**; if the name runs into the art, move it with **Across** / **Down** and set its **Size**. For King's Castle, also tick **Frame › Theatre Seats**. Then click **Apply to All**.
5. **Save** the template with the show's name.

The PSD must be RGB, 8 or 16 bit, saved with *Maximize Compatibility* on (Photoshop's default). If Photo Prep says the file can't be read, open it in Photoshop and save it again with that setting.

A frame from any picture (Oval Window)

No PSD? Any full-size picture works: a flag, a starry background, a photo of the stage. In Group Photos, load it with **Frame › Load**. A picture with no see-through parts gets an oval window cut out of it automatically. Under **Oval Window**:

- **Shape like** sets the window exactly as cut in one of the Clay Cooper PSDs: *Clay Cooper Theatre* (with its thin black outline), *Christmas*, *Hot Rods* (soft edge), *Matt Gumm*, *60s*.

- **Width**, **Height**, **Across**, **Down** fine-tune it; **Soft edge** fades the edge; **Outline** draws a black line round it.
- Untick **Cut an oval window** to use the picture as loaded.

The group goes in the window just as with a PSD. Add the show's title with the Text tool, or design it into the picture. Save the template when it looks right.

Step 3: Export

Same as Door Mode, except no background is needed. Each print file is named for its group, as typed (*Smith & Sons.jpg*; only characters Windows can't use in a file name, like / : ? ", become _). Before exporting, Export lists any photo with no group name and asks first: those print with no name and keep the photo's own file name. Two photos of the same group become *Smith Family Reunion.jpg* and *Smith Family Reunion_2.jpg*. Prints never overwrite each other: names that differ only in capitals, or a group named like another photo's file, get _2, _3 too.

SECTION 13

Installing, updating and uninstalling

Photo Prep needs Windows 10 or 11, 64-bit. It installs for the signed-in Windows user, so no administrator password is needed.

JOB	HOW
New PC	Run **Photo Prep [version] Setup.exe** once (about a minute). It adds a *Photo Prep* icon to the desktop and Start menu; use that icon from then on.
Update	Automatic from version 2.3.9 on (below). By hand if ever needed: close Photo Prep, then run **Photo Prep [version] update.exe** once. It keeps Python and the AI models already on the PC and only swaps in the new app (a few seconds).
Uninstall	Settings › Apps › Installed apps › Photo Prep › Uninstall. It removes the app and shortcuts, asks before deleting saved templates, and never touches photos.

Automatic updates

Photo Prep updates itself. Staff don't need to do anything.

1. **When you open Photo Prep**, it takes a quick look for a newer version first. If there is one, an **Updating Photo Prep** box shows the download bar, then *Installing...*, and Photo Prep opens on the new version with a **You're updated** window showing what's new. Click **OK** and carry on. It takes under a minute; don't switch the PC off while the box is up. No internet? Photo Prep just opens as normal.
2. **While Photo Prep is open**, it checks again every 4 hours. A newer version found then downloads in the background, and the footer shows **Update [version] ready - installs when you close Photo Prep**. Nothing installs during Prep, AI or Export.

3. Close Photo Prep when you're finished. The update installs in a few seconds and Photo Prep reopens by itself with the **You're updated** window. Close it again if you're done for the night (it won't reopen a second time).
4. Every download is checked against its fingerprint, so a damaged download is thrown away and Photo Prep opens on the version it already had.
5. If a new version fails to open three times in a row, the previous version is put back automatically and that update is skipped.

FOOTER SAYS	MEANING
Update [version] ready - installs when you close Photo Prep	Nothing to do. Close Photo Prep when you're finished.
Updated to [version]	The update installed.
Update [version] was blocked by Windows Security	Windows quarantined the download. Follow *Windows security warnings* below, then click the footer message to check again.
Photo Prep [version] is out and needs the full installer	That release changes the AI models or Python. Tell the owner; it needs the full Setup.exe.
Graphics-card support ready - installs when you close Photo Prep	Nothing to do. See *The graphics card* below.
Updates refused by GitHub (the update password) - tell the owner	The password built into Photo Prep for downloading updates was turned down. Photo Prep keeps working on the version it has; the owner needs to fix it.

No internet? Photo Prep works normally and checks again later.

After an update to the person rules, Prep redoes previously prepped batches the next time it runs on them, even with *Skip photos already in output* ticked. That's deliberate.

The graphics card

On a PC with a graphics card, Photo Prep runs the AI (the cut-out in Prep and Edit, and the person finding for groups and theatre seats) on the card, which is several times faster. Nothing to set up:

1. Photo Prep downloads graphics-card support by itself (about 25 MB). The footer says **Graphics-card support ready - installs when you close Photo Prep**.
2. Close Photo Prep. It adds the support, then checks the card: both AI models run on a test picture on the CPU and on the card. The card is used only if it gives the same answer and is faster. That takes about a minute, then Photo Prep reopens by itself.
3. Every time Photo Prep opens, the card is checked again against the CPU's answer. If it ever disagrees, or errors during a night, that part of the AI goes back to the CPU and the photo is redone there. Results are the same either way; only the speed changes.

The footer shows **AI: graphics card** or **AI: CPU**. Click it to see why, or to switch the graphics card off (from the next time Photo Prep opens). A PC with only built-in graphics usually stays on the CPU because the card isn't faster. Red eye, filters, theatre-seat painting and saving the prints always run on the CPU.

Windows security warnings

Photo Prep isn't digitally signed yet, so Windows may warn about it. These warnings are false alarms.

- **"Windows protected your PC"** (blue box): click **More info**, then **Run anyway**.
- **Windows Security quarantines it** (*Trojan:Win32/Wacatac...!ml*): the `!ml` means Defender's machine-learning guess, not a known virus. Open **Windows Security › Virus & threat protection › Protection history**, click the entry, then **Actions › Restore** (or **Allow on device**).
- To stop it recurring on a PC: **Virus & threat protection › Manage settings › Exclusions › Add an exclusion › Folder**, and add the folder you keep the installers in plus `%LOCALAPPDATA%\Photo Prep`.

> Only do this for files that came from the owner. If a warning names a specific threat without `!ml`, don't restore it; tell the owner.

SECTION 14

Troubleshooting and FAQ

PROBLEM	FIX
Green showing between arms or legs	Switch the view to **Alpha** to see it. Mask it out (Masks › Remove Alpha) and tell the owner which photo; it helps tune the AI.
Part of someone is missing (a dark shirt, a hand)	Mask it back in with **Retain Alpha**, and report the photo.
A sign, poster or light touching someone's head stays in the photo	The AI reads anything touching a head as part of that person. Draw round it with **Masks › Remove Alpha**. Better still, keep guests a step away from wall signs at the edge of the curtain.
Green tint on hair or edges	Key › Spill Suppression at 100; or Matte › Erode/Expand slightly negative.
A photo won't export	It's tagged ⚠ **check**. Read its reason, fix it, and export again.
Preview looks soft	You're probably on Quarter Sample. Switch back to **Half Sample** (the default), or zoom in with the mouse wheel (the preview goes full size by itself). The export is always full size.
Photo with no green screen	Import it from Edit (it comes in *as shot*) instead of running Prep.
Red eye missed	Key › Red Eye › **Select Eyes**, drag ovals, **Remove Red Eye**. Red eye is found automatically only when the whole face is in the shot.
⚠ eyes on a photo that looks fine	Usually a big squinting smile or glare on glasses. Ignore it; nothing is held back. If it keeps happening, send logs (and the photo) to the owner so the check can be tuned. To turn it off: untick *Warn if eyes look closed* on the Prep screen (Door Mode) or the Camera screen (Meet and Greet).

PROBLEM	FIX
"Photo Prep is already open"	It's running already; check the taskbar.
Something went wrong and the app restarted	Photo Prep reopens the photos that were open (or brings the template back) in the same mode; edits are saved as you go.
Footer says **AI: CPU** on a PC with a graphics card	Click it to see why. If the card failed its check, click **Send logs**.
Windows Security deleted it	See *Windows security warnings* above.

Does the preview show the AI's changes, or are they only applied on export? The preview shows them. Everything the AI decides is saved as that photo's settings, and Export renders the same settings at full size.

Does Photo Prep change my original photos? Never. Prep writes copies, and Edit and Export work from those.

Where's the error log? Click **Send logs** at the bottom of the window: every log Photo Prep keeps (errors, the camera connection, the printers, the print log, settings, and a note about this PC, including what the AI runs on) is zipped and **sent straight to the owner**. A box confirms it and gives the PC's name: tell the owner *"logs sent from"* that name, and they can read them without any email. A copy is saved on the Desktop too. If the PC has no internet, the logs wait and go by themselves the next time Photo Prep opens online. Nothing else is ever sent: only when someone clicks Send logs. The logs live in `%LOCALAPPDATA%\Photo Prep`.

SECTION 15

Keyboard shortcuts and glossary

KEYS	DOES
F1	Open this user guide
↓ / ↑ (arrow keys)	Next / previous photo, from anywhere in Edit (not while drawing a mask or selecting eyes: finish or press Esc first). Page Down / Page Up do the same.
← / → on a slider	Nudge that slider by one step
Ctrl+P	Meet and Greet: print the photo on screen
Mouse wheel (over the preview)	Zoom in / out on the pointer
Drag (zoomed in)	Move the photo around the view
Ctrl+0	Show the whole print again
Enter / ↓ / ↑ (Group Photos, step 1)	Next / previous group-name box

KEYS	DOES
Enter	Close the mask you're drawing
Esc	Stop drawing a mask, stop selecting eyes, or cancel the eyedropper
Right-click (while selecting eyes)	Take back the last oval

TERM	MEANING
Door Mode	Photos from a memory card: Prep, Edit, Export.
Meet and Greet	Photos straight from the camera (Wi-Fi or USB): Camera, Edit, Print.
Group Photos	Big groups shot as they are, in the show's frame: load and name, Edit, Export.
Photo folder	The photo backup folder picked on the dashboard; the photo-picking windows open there.
Window	The see-through oval in a Group Photos frame where the group goes.
digiCamControl	Free Windows software that saves each shot from a USB camera into a folder (Meet and Greet's *Camera software folder* choice).
Prep	Step 1: makes clean copies with red eye fixed and off-screen areas painted green.
Prepped folder	Where Prep's copies go, inside the card's folder.
Key / keying	Removing the green screen so the background can go behind people.
Alpha	The cut-out: white is kept, black is removed.
Spill	Green light from the screen bounced onto people's edges and hair.
As shot	A photo imported with no green screen; used whole, not keyed.
Template	One show's setup saved as a `.pptemplate` file.
Overlay	The show's logo or frame (PNG or PSD) on top of every print.
Layer	An extra PNG (a prop or sign) placed behind or in front of the people.
Ready to Print	The folder Export saves prints into by default, next to Prepped.
Hot folder	The folder a printer watches; Export can write there instead. Edit's *Use Hot Folder* is a different thing: it shows photos as Prep finishes them.
Train	Canvas: a supervisor (with the PIN) teaches the template its margins from photos placed by hand.
⚠ check	A photo the AI couldn't fix; held out of Export until edited.