
Product tour and user guide

Screens, controls, indicators and everyday use

A step-by-step guide from the dashboard to wallet setup, rewards, licensing and troubleshooting. Screen samples use demo wallets and amounts. Android-specific differences have their own section.



Sample data

Contents

01 First run
02 Dashboard and live indicators
03 ACCEPT and TAP average
04 Network reward chart
05 ROOT and PROOF timing
06 Top toolbar controls
07 Reading a wallet card
08 Wallet states and AUTO
09 ACCEPT borders and flip-flop
10 Late-result palette and ACCEPT meter
11 Adding and reconnecting wallets
12 Wallet backup and restore
13 Menu, language and window
14 Engine settings and live load
15 Daily pause and timing preferences
16 Logs and troubleshooting
17 Eagle and light reflection
18 Cobra tail and claw threshold
19 Licensing and wallet selection
20 Automatic payment steps
21 Invoice status and license refresh
22 Android interface and use

First run

Eagle follows multiple wallets in one window. Run through the full workflow with one wallet first.



Illustration · Sample data · First run

1. 1. Check the version

Check the version in the menu to match these screens to your build. Android also shows its version in the header.

2. 2. Choose a language

Open the main menu and choose a language. This guide is available in Turkish, English, Russian, Arabic, Simplified Chinese and Indonesian.

3. 3. Connect a wallet

Use Add wallet to begin. Review the QR or link request in your Acki Nacki Wallet and approve it. Check the name on the resulting card.

4. 4. License and start

If the card shows Unlicensed, use the licensing panel first. Then click Start on the card. Follow its status and tap count. The counter may wait for an epoch transition.

5. 5. Read the first result

The ACCEPT counter, latest reward and daily EPOCH amount describe different events or windows. The dashboard and wallet chapters explain them.

Dashboard and live indicators

The header shows computer, network and wallet activity together. Hover over a tile to see its details.



Illustration · Sample data · Dashboard and live indicators

1. Network health

Shows the BeeScan health score, sample time and source. Low scores appear red and high scores trend green. Stale data is muted. ACCEPTs and pending messages have their own indicators.

2. CPU and RAM

These are measured system usage percentages. Below 70% is green, 70-90% is yellow and above 90% is red. At exactly 100%, the indicator blinks until usage drops.

3. TPS and difficulty

TPS is the Acki Nacki mainnet transaction rate over the latest 180 blocks. E and H show the two observed session difficulty values. VARIES appears when reports differ. Dashes indicate missing observations.

4. Two epoch clocks

The upper clock estimates time left in the daily epoch. The lower clock estimates time left in the 1,000-block mining epoch. Time varies with block speed. A blank clock waits for verified network data.

5. TOTAL NACKL and DAILY REWARD

Total NACKL sums the tracked wallet balances. Daily Reward sums mining payments found in history since the verified daily boundary. An asterisk marks a partial total. A dash indicates that the total is still unavailable.

6. ROW QUOTA

Compares the license service's shared daily row reads with its 5,000,000 limit. The day is based on UTC. The tooltip shows the last check time and whether the reading is stale.

ACCEPT and TAP average

These indicators show confirmations and tap timing from different angles. Read results together with the wallet count and sample coverage.




Illustration · Sample data · ACCEPT and TAP average

1. Accept rate

SDK accepts arriving in the current mining epoch are divided by the number of AUTO wallets below the 12,000 daily tap cap. The small fraction displays the underlying counts.

2. Late confirmations

An accept counts in the epoch when it arrives. Delayed accepts can add to the current epoch, and the rate can exceed 100%.

3. Last 20 epochs

Use ⋮ by the rate to open completed epochs. Each row shows the epoch number, percentage and accepts/wallets fraction. An empty list means no completed record is available yet.

4. Over 30 minutes

The small warning count in the ACCEPT tile adds pending ROOT and PROOF messages older than 30 minutes. A dash means no usable engine report. Zero means no such pending messages in the report.

5. TAP AVG.

Measures consecutive tap intervals for wallets that completed at least 30 taps in the last verified completed mining epoch. The value is in seconds. The wallet count shows how many accounts entered the measurement.

6. Measurement coverage

Hover over TAP AVG. to see the epoch ID, measured taps and consecutive interval count. An asterisk marks partial coverage. A dash appears while a verified result is pending.

Network reward chart

Click 5m AVG. to open network reward and recipient history. The selected period's details appear above the chart.



Illustration · Sample data · Network reward chart

1. NACKL on the badge

Shows average NACKL per wallet with a positive payment in the latest complete, verified 1,000-block period. When the panel is labelled by payment time, the chart uses that time reference too.

2. 5 min, 15 min, 1 hour

5 min shows one period. 15 min summarizes three consecutive periods, and 1 hour summarizes twelve. Labels are nominal. Read the actual start and end times in the selected period card.

3. Last 24 hours and series

The gold line tracks average reward and the teal line tracks wallets with positive payments. Both start at 0% in the same period. The vertical axis shows percentage change from that period.

4. Inspecting the chart

Hover over a period to see the actual reward, recipient count and Istanbul time. The details also show the count including zero-payment records. A missing period leaves a gap.

5. Badge color and reference

The badge compares with the verified-period average of the previous completed daily epoch. Between 85% and 115% of the reference is yellow, below is red, above is green. Partial coverage of 262 periods is provisional. Missing reference data keeps the badge neutral.

ROOT and PROOF timing

Click ROOT or PROOF for aggregate timing. Click the small clock icon for individual wallet details.




Illustration · Sample data · ROOT and PROOF timing

1. Average time

Timing runs from the first send to processing on chain. A retry keeps the initial start time. Windows 1.1.3 averages messages processed in the last 5 minutes with a measured duration.

2. Samples and finalized

Samples count messages with a valid duration. Finalized is the subset with a reported finalization. The finalized count can be zero even when measured samples exist.

3. Pending and over 30 min

Pending counts messages whose result is unresolved. Over 30 min is the subset older than half an hour since first send. Pending ages are excluded from the processed-message average.

4. Processing time unavailable

Some resolved messages lack a usable chain processing timestamp. They are counted separately and left out of the average. A ROOT or PROOF tile stays blank when no usable sample exists.

5. Per-wallet clock

The clock opens the last processed ROOT and PROOF duration for each wallet, plus the age of any pending message. The pending column shows messages that are still within their validity window.

6. Color and engine data

Timing colors run from green for faster results toward red for slower ones. Waiting for engine data means a live report is still pending. Last processed, pending and daily rewards can refer to different times.

Top toolbar controls

The upper two rows control the wallet list and the Eagle window. Hover over a control to see its name.



Illustration · Sample data · Top toolbar controls

1. CAPPA emblem and eagle

The round CAPPA emblem opens the main menu. On Windows the eagle body opens the price list. See the animation chapter for the head control.

2. Green orb and RUNNING

The green orb requests Start all for eligible wallets. Preparation may show ready/total counts or a countdown. RUNNING 8/10 means eight of ten shown wallets are counted as running.

3. Red orb and LEVEL

The red orb requests Stop all and interrupts queued bulk startup. The small LEVEL button toggles level sorting for wallet cards.

4. Wallet +, LOG and BACKUP

Wallet + opens the connection panel. The three-line LOG button opens activity logs. BACKUP opens encrypted export and restoration. A log and a backup are separate files.

5. Theme ◈ and window controls

◈ opens the theme panel. The dash minimizes, the square toggles maximization, and the down arrow hides to the tray. Close can ask for confirmation. Exit from the tray ends the app session.

6. ROOT, PROOF, clock and charts

ROOT and PROOF open their timing panels. The nearby clock opens wallet-level times. ACCEPT and 5m AVG open history and network reward details. A dash indicates that a value is still unavailable.

Reading a wallet card

Each card represents a saved wallet. It combines chain data, local session counters and four action buttons. Hover over a field to see more detail.




Illustration · Sample data · Reading a wallet card

1. Name, balance and L level

Long names are shortened. Hover to see the full name. The card shows only the whole part of the NACKL balance. L42 means MamaBoard level 42. An ellipsis indicates loading and a dash indicates an unavailable level.

2. EPOCH and latest reward

EPOCH totals mining rewards read since the verified daily boundary. An asterisk marks a partial total. A dash means the total is still unknown. The amount and time below are for the latest reward, which updates separately.

3. Green and red result counts

Green and red numbers count ACCEPT and REJECT sessions. A green border marks a current-epoch accept. Blue and other hues mark older accepts and red marks rejection. A mixed border includes a current-epoch accept.

4. Tap counters and progress bar

The large EPOCH TAP number is the on-chain daily counter. The smaller number next to it belongs to the local session. If a different positive confirmed count is available, it appears as a second value. The bottom bar tracks local progress toward the session target.

5. ▶, ■, ↻ and ×

▶ starts this wallet and ■ stops it. After stopping, use ↻ to reconnect or × to remove the profile. After confirmation, removal deletes the saved profile from Eagle only.

6. Selection and ordering

Click a card to select it. LEVEL below RUNNING switches to MamaBoard ordering. In the default Windows order, AUTO-enabled wallets come first, followed by running state and higher balance. The menu lets you set wallets per column.

Wallet states and AUTO

The short label on a card shows the wallet's current stage. Hover over it for the full status. A wallet counted as running can be waiting on the network or a new epoch.




Illustration · Sample data · Wallet states and AUTO

1. AUTO, START and HOLD

AUTO controls inclusion in Start all. Use ▶ to start a single wallet. HOLD can appear on a paused wallet or one excluded from AUTO. To resume it, use ▶ when available.

2. QUEUED, READ and SDK WAIT

QUEUED means the wallet is waiting its turn. READ checks wallet and connection data. SDK WAIT means the app is waiting for an SDK operation or a previous session to close. READ ERR or RETRY can appear while the software retries.

3. PRE CHECK, PREMINE and TAP READY

PRE CHECK is a preparation check. During PREMINE the tap counter may advance. TAP READY means the taps are ready and the wallet is waiting for the appropriate stage. Reward confirmation is shown separately.

4. MINING, ROOT, PROOF and RESULT

MINING indicates the tap stage. ROOT and PROOF mark stages in submission. FINAL or RESULT means the session is being finalized or is waiting for a result. CHECK can appear when the outcome is uncertain.

5. EPOCH, WAIT and DAY CAP

EPOCH appears while waiting for a new mini-epoch. WAIT is a general waiting state. DAY CAP indicates the daily tap cap was reached and the next daily epoch is pending. Check the header clocks for timing.

6. Results, connection and licensing

ACCEPT is an accepted result, REJECT a rejected one, and ERR an error. REC indicates recovery, NEEDS RECONNECT requires renewed authorization, and BLOCKED marks a restriction. UNLICENSED means the wallet lacks mining access. Check the card and logs together.

ACCEPT borders and flip-flop

A wallet's colored border shows SDK receipt evidence. The bottom tap line shows local progress. The header ACCEPT bar shows the app-wide rate.



Illustration · Sample data · ACCEPT borders and flip-flop

1. Green border

An ACCEPT for the verified mini-epoch at the time the event arrives gives a steady green border. If a late ACCEPT also exists, green can alternate with its older-result color.

2. Late ACCEPT color

The palette follows the difference between the session mini-epoch and the verified mini-epoch when the receipt arrives. The previous epoch is sky blue. Sky blue can also mark a known older session whose exact lag is unavailable.

3. Flip-flop · two results, two colors

When the display interval contains both a current and an older ACCEPT, the green and late colors show for one second each. The cycle takes two seconds. A late receipt preserves the current green marker.

4. Red and neutral borders

The last observed SDK result being REJECT gives red in the verified mini-epoch. A later accept can update the frame. A new verified mini-epoch clears the stored frame markers. Neutral cards use their usual styling.

5. Pulse and celebration

For accepts five or more mini-epochs late, the border can pulse in brightness when reduced motion is off. The acceptance flash and celebration shown with animations enabled are temporary effects.

Late-result palette and ACCEPT meter

Lag is the difference between the verified mini-epoch when the receipt arrives and the session mini-epoch. Receipt lag and the overall ACCEPT rate measure different quantities.



Illustration · Sample data · Late-result palette and ACCEPT meter

1. Lag of 1-4 mini-epochs

1 sky blue, 2 light lavender, 3 yellow, 4 amber. The reward amount has no effect on the hue.

2. Lag of 5-10 mini-epochs or more

5 bright turquoise, 6 periwinkle, 7 lime, 8 violet, 9 ice blue, 10 or more deep teal. Borders in this group can pulse in brightness.

3. Example · two accepts

If an ACCEPT for epoch 100 and an ACCEPT for epoch 98 both arrive in epoch 100, the card alternates green and light lavender. The rate meter counts both in arrival epoch 100.

4. Header meter color and fill

The header ACCEPT meter moves from red through yellow to green as the rate rises. Fill stops at 100%. The numeric rate can exceed 100% when arrivals outnumber eligible AUTO wallets.

5. Epoch colors in history

The three dots on the meter open the last 20 completed mini-epochs. Colored epoch numbers mark position relative to the newest row. The percentage and count/wallet ratio appear next to each one.

Adding and reconnecting wallets

Mining authorization approved in the official Acki Nacki Wallet is linked to the intended Eagle profile.




Illustration · Sample data · Adding and reconnecting wallets

1. 1 · Choose the wallet

Open the add-wallet icon in the header. Enter the AN Wallet account name and select ADD WALLET QR. For a saved wallet, use ↻ on its card.

2. 2 · QR or link

Check the displayed name. Scan in AN Wallet with the intended wallet selected. Copy link lets you open that same request on the correct device.

3. 3 · Approval and on-chain check

Review the request in Wallet and approve the mining key. Eagle waits for the address and for the key to appear on-chain. The card can first appear as waiting.

4. Reconnect and verify

Stop the wallet and open the connection panel with ↻. With Verify mining key enabled, Eagle checks the connection on-chain. Complete the new request with the intended wallet.

5. Starting and licensing

Once connected, the card enables Start. Use ▶ on a wallet with valid mining access. Enable AUTO on eligible cards for bulk start. The first tap may wait for a new mini-epoch.

6. If approval is still pending

Check that the intended wallet is selected in AN Wallet and the request was approved. Look at the Eagle card and the AUTH/WAITING entries in Logs.

Wallet backup and restore

The BACKUP panel exports saved wallets to an encrypted .cappacki file and imports existing Miner backups.




Illustration · Sample data · Wallet backup and restore

1. 1 · Wait for all wallets to load

Wait for the cards to load. If some credentials are unavailable, Eagle blocks incomplete backup export. Retry when all wallets have loaded.

2. 2 · Export an encrypted copy

Open BACKUP and choose Export .cappacki backup. Enter a password of 8-1024 characters twice and select Save backup.

3. 3 · Save and verify the file

Choose a location and a new filename. The success message shows the verified file's path. Existing backups are preserved. Store the password separately.

4. 4 · Import a backup

Stop mining, wait for the engines to finish their work and close any QR authorization. Choose Import wallet backup, select the .cappacki file and enter its password.

5. Merging and duplicate names

Eagle updates matching Miner addresses or public keys. A different wallet with the same name may get a suffix. Logs report how many records were added and updated.

6. Backup type and password

Use a Miner backup containing Eagle's mining keys. CAPPA Boost backups omit these keys. A forgotten password cannot be recovered. Check the cards and licenses after import.

Menu, language and window

Open the app menu with the CAPPA logo at top left. The window controls, theme button and backup shortcut sit at top right.



Illustration · Sample data · Menu, language and window

1. Version and contacts

Read the version on the top row. The contact card lists CAPPA's Telegram account, Acki Nacki wallet name, website and GitHub link.

2. License card and price list

The license card shows access, wallet count and any expiry date. Its management button opens licensing, and the eagle artwork opens the price list.

3. Network wallet count

The Acki Nacki network card shows the network-wide wallet count. Your saved and running wallets have separate counts.

4. Columns and language

Choose 1-25 cards per column. Cards fill top to bottom, with overflow continuing in the fifth column. The language selector changes interface text.

5. Theme and window controls

◈ opens eight themes. Minimize and maximize change the window. ▾ hides it to the tray. X asks to close. F11 toggles full screen.

Engine settings and live load

The engine count sets how many separate processes Eagle runs. An engine can serve multiple wallets.




Illustration · Sample data · Engine settings and live load

1. MANUAL / Engine count

This release offers 1-8 engines in manual mode, with 4 as the default. Wallet licensing and eligibility determine which wallets can mine.

2. Running engines / Target

The first number is the running engine count, and 8 is the cap. A transition notice appears when the target differs. Engines may become ready in stages.

3. E1, E2 and load details

An E1 label shows computing wallets first and assigned wallets second. Hover for open sessions, queued reads, pending work and slow responses.

4. Apply and restart

A changed value stays as a draft. Apply, then confirm to close and reopen Eagle. Cancel discards the draft. A failed restart displays an alert.

5. Comparing engine counts

With the same wallets, compare CPU, RAM, TAP average and running count across several mini epochs.

Daily pause and timing preferences

The daily pause takes effect at a verified daily epoch change. During a pause, the menu shows when work will resume.




Illustration · Sample data · Daily pause and timing preferences

1. On / Off

Switching on schedules the next daily transition. Switching off an active pause prompts Eagle to resume eligible wallets.

2. Delay

Waits 2-12 hours after the pause starts. A 2-hour delay beginning at 06:20 targets 08:20.

3. Local time

The chosen time follows the computer's local clock. If it already passed today, the target is tomorrow. The type and time fields are locked during the pause.

4. ROOT and PROOF retry interval

Choose a shared interval of 1, 2, 3, 4, 5 or 10 seconds. It applies to new sessions. Network checks can delay a retry.

5. Hidden setting

☺

Logs and troubleshooting

☰ opens Logs. Event times let you match what the engines and wallet reported at the moment of an issue.




Illustration · Sample data · Logs and troubleshooting

1. Timestamps and entry count

The counter is the number of entries in the panel. Each entry has a time and message. Note the wallet and the time of the issue for support.

2. Save log

Exports diagnostics from the current app run and available engine logs to a dated CAPPA-Eagle-Diagnostics-Log text file. Older entries may have rolled out.

3. Open log folder / Clear log

The folder button opens Downloads. Clear resets the in-app log buffer. Export first when you need to keep a failure for review.

4. If ENGINE QUEUED persists

Check the running and target engine counts, then the wallet license and connection. If the condition persists, save the ENGINE records from that period.

5. EPOCH WAIT, HOLD and UNLICENSED

For EPOCH WAIT, check the mini-epoch clock. For HOLD, check manual stop and daily pause. For UNLICENSED, check current wallet entitlement.

6. If the daily reward is blank

A dash in EPOCH indicates the daily total is still unavailable. The latest reward can appear separately. Save DAILY REWARD entries if the delay persists.

Eagle and light reflection

The eagle in the Windows header opens the price list. Rapid clicks on its head change its appearance. Rapid clicks on the cobra's head control the light.




Illustration · Sample data · Eagle and light reflection

1. Wings and body

Click a wing or the body once to open the license price list. The head has its own click area. Transparent space around the artwork does not open the list.

2. Eagle head: 5 clicks

Click the head five times within three seconds. The gold eagle switches to the dark, white-headed eagle. Repeat to switch the manually selected variant. An incomplete sequence starts over after the time window.

3. Pointer and click area

The pointer stays an arrow over the head. A single head click leaves the price list closed. Clicking a wing or the body interrupts the head sequence and opens the price list.

4. Cobra head: 5 clicks

Click the visible cobra face five times within three seconds. This toggles the shared light sweep on the eagle and CAPPA Eagle wordmark. The preference is saved for the next launch. Windows 1.1.3 enables general effects. These clicks control only the reflection. The system's reduced-motion preference can hide the light effect.

5. Why the reflection slows

The sweep slows logarithmically as BeeScan health drops. At a valid 100% it takes about 2.4 s, and at 0% about 26.4 s. Missing, stale or failed readings use the 4.8 s fallback.

6. Appearance precedence

The eagle can remain dark while the tail is near its claw. If five clicks do not return it to gold, wait for the tail to retreat. Manual eagle and tail colors are window state. The light preference is stored separately.

Cobra tail and claw threshold

The tail combines the times in the ROOT and PROOF tiles into one visual. Its length changes when the measurements change.




Illustration · Sample data · Cobra tail and claw threshold

1. What lengthens the tail?

ROOT and PROOF averages are rounded to seconds as shown in the tiles, then added. For example, 00:42 + 01:04 gives 01:46 on the tail scale. If one is missing, the known time draws the tail and the tooltip flags the missing measurement. With neither, the extension is absent.

2. Six minutes and coiling

As the sum approaches 6 minutes, the tail extends toward the claw. At 6 minutes it reaches the claw. Beyond that, the path starts coiling around the eagle and growth eases. The wallet count or pending-message count alone does not determine its length.

3. Automatic appearance change

The dark, white-headed eagle appears when the tip reaches roughly 6.5 mm of on-screen distance from the claw. Resizing the window realigns the path to the claw's new position.

4. Beşiktaş crest

When the tail contacts the claw, a glass-style crest appears on a red collar around the dark eagle's neck. It remains visible while the tail extends farther and coils around it.

5. Retreating tail

The crest remains when the tail first starts shrinking. It disappears once the tip retreats beyond the proximity boundary. The automatic dark appearance ends there too. A manually selected dark eagle stays dark.

6. Cobra neck: 5 clicks

Click the neck just below the cobra's head five times within three seconds. The pattern cycles yellow/black, yellow/red, yellow/navy and then back to yellow/black. The pointer remains an arrow. This click changes only the pattern.

Licensing and wallet selection

Open Subscription / payment from the License card in the main menu. An automatic order covers the selected wallet names.




Illustration · Sample data · Licensing and wallet selection

30-day base price per wallet

L 0-10 **8 NACKL**	L 11-20 **49 NACKL**	L 21-40 **75 NACKL**
L 41-50 **117 NACKL**	L 51-60 **188 NACKL**	L 61-72 **282 NACKL**

1. Active licenses

The License card summarizes active coverage. Wallets can expire on different dates. Other valid wallets can keep running when one expires. An existing device license may also cover its own wallets.

2. Selection boxes

Each checkbox includes or excludes one wallet. On Windows, Select all / Deselect all changes every checkbox. The counter reports the selected count.

3. Currency and term

Choose NACKL or SHELL. Automatic orders allow 30, 60 or 90 days. Remaining validity can prevent an early renewal. A created invoice has a fixed currency and term.

4. Price list and calculation

On Windows, click the eagle artwork to open the price list. Pricing depends on each wallet's MB level band and term. Selected wallet amounts are added together. Use the exact invoice amount for payment.

5. Manual licensing

Copy names for manual licensing puts the selected wallet names on your clipboard. Send that list to CAPPA. When the licenses are applied, Eagle reads their status from the server.

Automatic payment steps

Follow one invoice at a time. The amounts in the illustration are examples.




Illustration · Sample data · Automatic payment steps

1. Prepare payment

After choosing wallets, click Prepare payment. The invoice shows the recipient, exact amount, currency and countdown. Compare its wallet list with your selection.

2. Exact amount

Send the exact two-decimal amount in the displayed token before the window closes. If cappa is the recipient, pay from a different wallet.

3. I've paid

After sending the transfer, choose I've paid, activate license. The server checks the chain record. Confirmation can take several minutes, with longer waits during network delays.

4. Pending and cancelled invoices

A cancellation request can leave the invoice locked until absence of payment is verified. Once a payment signal is seen, cancellation can be disabled. The chain check can continue after the timer reaches zero.

5. Confirmation and new order

The confirmation message indicates the license was applied. Once an unpaid invoice is definitively closed, choose New order. If you sent funds on the previous invoice, check its status and transfer record before paying again.

Invoice status and license refresh

An invoice can appear as pending, then as confirmed or closed unpaid. The examples show a pending check and a successful confirmation.




Illustration · Sample data · Invoice status and license refresh

1. Existing invoice on reopening

Reopening the payment panel can restore the pending invoice. If invoice history cannot be read, retry and wait for the existing invoice status before sending funds.

2. Confirmation and validity

Payment confirmation records the outcome of that invoice. A wallet's current expiration can change later, for example through a CAPPA operator adjustment. Read the current entitlement from the wallet's license status.

3. Cache and recheck

Windows 1.1.3 caches active wallet status for up to 24 hours after a successful check. A sooner known expiration takes precedence. A payment confirmation can trigger a fresh check. This is why an external change may take time to appear on a card.

4. When access ends

An expired wallet can display UNLICENSED. When Eagle processes loss of entitlement, mining for that wallet can stop. Other licensed wallets can continue.

Android interface and use

This chapter covers the published Android 1.0.94 / 6000030 build. Mobile cards and controls are arranged for a narrow display.




Illustration · Sample data · Android interface and use

1. Home screen

The header displays the version. Network, countdown and reward indicators use the mobile layout. Use the relevant wallet card for Start, Stop or Reconnect.

2. Subscription / payment

Android requests the same level-based pricing from the server. This APK has no price-list image. The displayed 120-, 150- and 180-day choices are rejected for automatic orders. Choose 30, 60 or 90 days.

3. Discount field

The old discount code field is still visible here. Leave it blank if you have no code. Pay only the exact amount on a prepared invoice.

4. With the screen off

Use the notification and wallet card to check background activity. Force stop or manufacturer battery restrictions can interrupt a session. Reopen the app and compare the last tap and its timestamp.

5. Connection and version

Verify the wallet during QR approval and return to Eagle. Compare 1.0.94 and 6000030 with the download information. Desktop engine settings and the system tray are Windows features.