ToolServer Reference

♣ Apple Computer, Inc. © 1992, Apple Computer, Inc. All rights reserved.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, mechanical, electronic, photocopying, recording, or otherwise, without prior written permission of Apple Computer, Inc. Printed in the United States of America.

The Apple logo is a registered trademark of Apple Computer, Inc. Use of the "keyboard" Apple logo (Option-Shift-K) for commercial purposes without the prior written consent of Apple may constitute trademark infringement and unfair competition in violation of federal and state laws.

No licenses, express or implied, are granted with respect to any of the technology described in this book. Apple retains all intellectual property rights associated with the technology described in this book. This book is intended to assist application developers to develop applications only for Apple Macintosh computers.

Apple Computer, Inc. 20525 Mariani Avenue Cupertino, CA 95014-6299 408-996-1010

Apple, the Apple logo, AppleShare, A/UX, LaserWriter, Macintosh, MPW, and Projector are trademarks of Apple Computer, Inc., registered in the United States and other countries.

Finder is a trademark of Apple Computer, Inc.

Adobe Illustrator and PostScript are trademarks of Adobe Systems Incorporated, which may be registered in certain jurisdictions.

FrameMaker is a registered trademark of Frame Technology Corporation.

Helvetica and Palatino are registered trademarks of Linotype Company.

HyperCard is a trademark of Apple Computer, Inc., licensed to Claris Corporation.

ITC Zapf Dingbats is a registered trademark of International Typeface Corporation.

Varityper is a registered trademark of Varityper, Inc.

Simultaneously published in the United States and Canada.

LIMITED WARRANTY ON MEDIA AND REPLACEMENT

If you discover physical defects in the manual or in the media on which a software product is distributed, APDA will replace the media or manual at no charge to you provided you return the item to be replaced with proof of purchase to APDA.

ALL IMPLIED WARRANTIES ON THIS MANUAL, INCLUDING IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, ARE LIMITED IN DURATION TO NINETY (90) DAYS FROM THE DATE OF THE ORIGINAL RETAIL PURCHASE OF THIS PRODUCT.

Even though Apple has reviewed this manual, APPLE MAKES NO WARRANTY OR REPRESENTATION, EITHER EXPRESS OR IMPLIED, WITH RESPECT TO THIS MANUAL, ITS QUALITY, ACCURACY, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. AS A RESULT, THIS MANUAL IS SOLD "AS IS," AND YOU, THE PURCHASER, ARE ASSUMING THE ENTIRE RISK AS TO ITS QUALITY AND ACCURACY.

IN NO EVENT WILL APPLE BE LIABLE FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES RESULTING FROM ANY DEFECT OR INACCURACY IN THIS MANUAL, even if advised of the possibility of such damages.

THE WARRANTY AND REMEDIES SET FORTH ABOVE ARE EXCLUSIVE AND IN LIEU OF ALL OTHERS, ORAL OR WRITTEN, EXPRESS OR IMPLIED. No Apple dealer, agent, or employee is authorized to make any modification, extension, or addition to this warranty.

Some states do not allow the exclusion or limitation of implied warranties or liability for incidental or consequential damages, so the above limitation or exclusion may not apply to you. This warranty gives you specific legal rights, and you may also have other rights which vary from state to state.

Contents

	Figures, Tables, and Listings v
Preface	How to Use This Manual vii
	Related Documentation viii Syntax Conventions viii Terminology viii
Chapter 1	Making ToolServer Work for You 1-1
	Why Use ToolServer? 1-2 Memory Requirements, Performance, and Compatibility 1-2 ToolServer Partition Size 1-2 Performance 1-3 Compatibility 1-3
Chapter 2	Using ToolServer 2-1
	Installing ToolServer 2-2 Launching ToolServer From the Finder 2-2 Launching ToolServer From the Finder 2-2 Launching ToolServer From the MPW Shell 2-2 Startup Scripts 2-3 Moving ToolServer or Its Startup Scripts Out of the ToolServer Folder 2-3 Combining MPW and ToolServer Startup Scripts 2-4 Quitting ToolServer 2-5 Using ToolServer in the Foreground 2-5 Script Execution 2-6 Aborting Script Execution 2-7 Limitations on Scripts That Run Under ToolServer 2-7 Input, Output, and Diagnostic Files 2-8 Using Alerts to Monitor Script Execution 2-10

Chapter 3	The RShell Command 3-1
	Communicating With ToolServer on a Remote Machine 3-2 Using Files on the Local Machine 3-6 Using the RShell Command 3-7 Command Syntax 3-7 Examples 3-8 Variable Substitution in the RShell Command Line 3-9 Transaction ID of a Request 3-9 Redirecting Output and Abnormal Termination 3-10 Sample Scripts 3-11 A Script That Compiles in the Background 3-11 A Script That Compiles on a Remote Machine 3-12 Shortcuts 3-13
Chapter 4	Using Apple Events to Communicate With ToolServer 4-1
	ToolServer as a Server Application 4-2 Executing a Script by Using Apple Events 4-5 I/O With Apple Events 4-5 Required Events 4-6 Open Application Event 4-6 Open Documents Event 4-6 Print Documents Event 4-6 Quit Event 4-7 Script Events 4-7 Script and Do Script Events 4-7 Output and Diagnostic Output Events 4-8 Abort Event 4-9 Status Event 4-9
Appendix A	Apple Event Support in the MPW Shell A-1
Appendix B	ToolServer Files and Variables B-1 ToolServer Files B-2
	ToolServer Variables B-3 Index IN-1

Figures, Tables, and Listings

Chapter 2	Using ToolSe	erver 2-1		
	Table 2-1 Table 2-2 Table 2-3	ToolServer menu selections 2-6 Valid MPW built-in commands for scripts 2-7 Files defined by BackgroundOut and BackgroundErr 2-10		
	Listing 2-1 Listing 2-2	Sample startup script 2-4 Sample script 2-11		
Chapter 3	The RShell (Command 3-1		
	Figure 3-1 Figure 3-2 Figure 3-3 Figure 3-4 Figure 3-5 Figure 3-6	Sharing Setup control panel 3-3 Users & Groups control panel 3-3 New User document 3-4 Enabling program linking to ToolServer 3-4 PPC Browser dialog 3-5 Program linking dialog 3-6		
	Listing 3-1 Listing 3-2 Listing 3-3	Output of RShell -status option 3-9 Background compile script 3-12 Remote compile script 3-13		
Chapter 4	Using Apple Events to Communicate With ToolServer 4-1			
	Figure 4-1	Apple events 4-3		
	Table 4-1 Table 4-2 Table 4-3 Table 4-4	Apple events 4-4 Parameters to Script reply 4-8 Parameters to Do Script reply 4-8 Parameters to Status event reply 4-9		
Appendix B	ToolServer F	iles and Variables B-1		
	Table B-1 Table B-2	ToolServer files B-2 ToolServer variables B-3		

How to Use This Manual

This manual explains how you install and launch ToolServer and how you use it from different environments to run Macintosh Programmer's Workshop (MPW) tools and to execute MPW scripts.

ToolServer is a complete tool and script execution environment extracted from the MPW Shell that you can use to execute time-consuming, noninteractive tools or scripts in the background or on a remote machine. Thus ToolServer can run most of the tools and scripts in the MPW tool suite and most tools and scripts which are written for MPW. The major exceptions are editor and Projector commands.

ToolServer is primarily designed to be run using Apple events. As such, it can be run from MPW 3.3 or later using the built-in MPW RShell command and from third-party applications that include support for ToolServer. You can also use ToolServer as a foreground application; you specify the scripts to be executed and obtain the status of executing scripts by choosing the appropriate File menu items.

This manual is divided into four chapters:

- Chapter 1, "Making ToolServer Work for You," describes the ways in which you can use ToolServer and discusses memory requirements, performance, and compatibility issues.
- Chapter 2, "Using ToolServer," explains how you install, launch, and quit ToolServer. It also explains how to use ToolServer as a foreground application, how scripts execute under ToolServer, and ToolServer's use of startup, input, output, and diagnostic files.
- Chapter 3, "The RShell Command," explains the syntax of the RShell command and how you use it from the MPW Shell (version 3.3 or later) to have ToolServer execute scripts in the background or on a remote machine.
- Chapter 4, "Using Apple Events to Communicate With ToolServer" describes the Apple events supported by ToolServer. By using these events and the routines of the Apple Event Manager, an application can communicate with ToolServer and use it as an execution environment that extends the application's functionality.

Note

Because of ToolServer's dependence on Apple events, ToolServer runs only on System 7 or later. ◆

Related Documentation

For detailed information on the syntax and use of MPW commands, tools, and scripts, you need to consult the MPW Command Reference. For information on writing scripts, you need to consult Volume 1 of MPW: Macintosh Programmer's Worskhop Development Environment or any third-party book describing the MPW Shell.

Syntax Conventions

The following syntax conventions are used to describe MPW and ToolServer commands in this manual.

literal	Courier text indicates a word that must appear exactly as shown. Special symbols $(\partial, \bullet, \S, \&, \text{ and so on})$ must also be entered exactly as shown.
italics	Italics indicate a parameter that you must replace with anything that matches the parameter's definition.
[]	Brackets indicate that the enclosed item is optional.
	Ellipses () indicate that the preceding item can be repeated one or more times.
	A vertical bar () indicates an either/or choice.

Terminology

Although ToolServer is independent of MPW, it does share with MPW a common set of commands, scripts, and tools. This manual refers to the commands, scripts, and tools that ToolServer can execute as MPW commands, MPW scripts, and MPW tools because most readers are familiar with these from working with MPW and because the behavior of these commands, tools, and scripts is basically the same in both environments. (Any differences in behavior are documented in this manual.) However, this does not imply that ToolServer's ability to run these commands, scripts, and tools depends upon MPW running concurrently with ToolServer.

The term **client application** refers to an application that sends an Apple event to request a service. The term **server application** refers to the application that performs that service. For example, when you use the RShell command from the MPW Shell to have ToolServer execute a script, the MPW Shell is the client application and ToolServer is the server application.

Making ToolServer Work for You

Making ToolServer Work for You

This chapter describes the circumstances under which you might use ToolServer, explains ToolServer's use of memory and overall effect on performance, and reviews compatibility requirements.

Why Use ToolServer?

How you use ToolServer depends on your needs. The possibilities include the following:

- You can run ToolServer as a foreground application that you launch from the Finder. This allows you to execute scripts in a smaller partition than that required by the MPW Shell.
- You can run ToolServer in the background while you continue to work with MPW in the foreground.
- You can run ToolServer on a remote machine and use Apple events to communicate with ToolServer and to specify which scripts are to be executed. Using this process, you can off-load time consuming build operations to another machine.

 Version 3.3 or later of the MPW Shell includes an RShell command that uses Apple events to communicate with ToolServer. Any other application or development environment can also use Apple events to communicate with ToolServer.
- You can use ToolServer to extend the functionality of an application or development environment.
 - The application or development environment that needs to make use of an MPW tool or script uses Apple events to have ToolServer execute that tool or script in the background or on a remote machine. The existence of ToolServer would be invisible to the user who would specify his needs by means of a menu command or dialog box.

Memory Requirements, Performance, and Compatibility

The following sections describe ToolServer's memory requirements, how the execution of scripts in the background or on a remote machine affects performance, and ToolServer's dependence on system software, MPW, and other client applications.

ToolServer Partition Size

The size of ToolServer's partition depends on the types of tools run. In general, the partition required by ToolServer should be 500K smaller than that required by the MPW Shell. The recommended memory requirement for ToolServer is 1536K. The minimum requirement is 512K.

If you run all your complex operations with ToolServer and use MPW primarily for editing, you can launch MPW in a smaller partition.

In the worst case, the combined memory requirements of running ToolServer in the background and MPW in the foreground might be up to twice that of the MPW Shell.

Making ToolServer Work for You

Performance

A script run in the background should not require significantly more central processing unit (CPU) time than a script run in the foreground. In fact, scripts run by ToolServer might execute faster than they would under MPW, because much of the user interface overhead has been removed from ToolServer.

Elapsed time varies depending on the amount of foreground activity and the cost of context switches. For example, if you run CPU-intensive operations from both the ToolServer and another application on the same CPU, the elapsed time could increase by a factor of 2 or more.

If you run ToolServer on a remote machine, performance is affected by network overhead—that is, whether the files required by ToolServer are available locally or are read remotely.

Compatibility

Because of ToolServer's dependence on Apple events, ToolServer runs only on System 7 or later. When ToolServer is run under A/UX, it cannot be accessed remotely, that is, by the RShell command.

MPW version 3.3 or later is required to control ToolServer using Apple events. ToolServer supports all the routines and interfaces available to tools under the MPW Shell, including facess and getenv. Tools should run without change in either the MPW or ToolServer environment. ToolServer and the MPW Shell do differ in the way they handle input, output, and standard error. These differences are described in the section "Input, Output, and Diagnostic Files" in Chapter 2.

Any client application that knows how to send the Apple events supported by ToolServer and how to handle ToolServer's replies to these events can communicate with ToolServer in the background or on a remote machine. Version 3.3 of the MPW Shell is such a client; you can use the RShell command to specify scripts to be run in the background or on a remote machine.

ToolServer has the signature 'MPSX'. Files produced by ToolServer are of type 'TEXT' and creator 'MPS' and can be viewed or edited with the MPW editor or other editors that accept text files. ToolServer also supports the RShell command. This means that commands can be sent from ToolServer to other ToolServers (possibly on remote machines), to the foreground MPW Shell (version 3.3 or later), or to itself.

Note

ToolServer takes its input from files. A window represents a file that may contain unsaved editing changes. In order to make ToolServer aware of such changes, you must save them to a file. ◆

This chapter explains how you install, launch, and quit ToolServer. It also explains script execution under ToolServer and ToolServer's use of startup, input, output, and diagnostic files.

Installing ToolServer

If you have purchased or plan to use ToolServer with the MPW Shell, please follow the instructions in the file READMEFIRST to install ToolServer. If you have bought or plan to use ToolServer with a third-party application or development environment, please read the documentation provided with that product for installation instructions.

If you plan to use ToolServer to run scripts on a remote machine, you must install and launch ToolServer on that machine. This cannot be done remotely. You must also enable communication between the local and the remote machine. For additional information see the section "Communicating With ToolServer on a Remote Machine" in Chapter 3.

Launching ToolServer

You can launch ToolServer from the Finder or from the MPW Shell. The next two sections describe each of these procedures and also explain the organization and use of ToolServer's startup scripts.

Note

If you have purchased or plan to use ToolServer with a third-party application or development environment, please consult the documentation provided with your product for instructions on how to launch ToolServer. •

Launching ToolServer From the Finder

To launch ToolServer from the Finder, double-click the ToolServer application.

You can also launch ToolServer by double-clicking on the ToolServer script to be run. To identify a script as a ToolServer document, use the SetFile command to change the creator of the script to 'MPSX', the signature of the ToolServer.

Launching ToolServer From the MPW Shell

The syntax of the command used to launch ToolServer from the MPW Shell is:

```
[pathname]ToolServer [ script...]
```

After executing the startup script or scripts, ToolServer executes each *script* specified on the ToolServer command line.

If ToolServer resides in the current directory, or if you include the directory containing ToolServer in the {Commands} variable, you can omit the *pathname* specification.

After ToolServer has finished executing the specified scripts, it remains active until you quit the application. If you want to execute additional scripts, you can bring ToolServer to the foreground and specify these by choosing the Execute Script item from the File menu.

You can launch ToolServer, execute scripts, and quit Toolserver by using the RShell command. For additional information see Chapter 3, "The RShell Command."

Startup Scripts

Once launched, ToolServer first executes the StartupTS script. The StartupTS script then executes the UserStartupTS script and then any script whose name begins with UserStartupTS•.

The StartupTS script defines variables used by ToolServer and user scripts. For additional information about the variables defined in the StartupTS script, see Appendix B, "ToolServer Files and Variables." You can write additional scripts and have these executed as part of the launch process by naming these scripts UsersStartupTS•name.

If the execution of the StartupTS script results in text written to standard output or standard error, ToolServer creates the files StartupTS.out and StartupTS.err files in the same directory as the user's StartupTS script and writes output and diagnostic information to these files.

Moving ToolServer or Its Startup Scripts Out of the ToolServer Folder

If you are using ToolServer with the MPW Shell, it is assumed that ToolServer is in the ToolServer folder and that its startup and quit scripts are either in the same folder as ToolServer or in the Preferences folder. It is recommended that you do not move ToolServer or its startup and quit scripts out of the ToolServer folder. If quick access to ToolServer is a problem, you can create an alias for it in the desired location.

If you must place the UserStartupTS and QuitTS scripts in a folder different from the ToolServer or the Preferences folder, you will need to change the value of the {PrefsFolder} variable in the StartupTS script. For example, if you place ToolServer's UserStartupTS script in a folder called MyStartups on the boot directory, you can include the following command in the StartupTS script to enable ToolServer to find its user startup scripts.

Set PrefsFolder {Boot}MyStartups:

The StartupTS script also defines the $\{MPW\}$ variable to be the same as the directory containing ToolServer. If you move ToolServer to another directory, you need to set the $\{MPW\}$ variable to the location of the ToolServer folder. For example, if you move

ToolServer to the desktop and leave the ToolServer or MPW folder on the boot volume, you would use the following command to redefine ToolServer's directory:

```
Set MPW {Boot}MPW:
```

Combining MPW and ToolServer Startup Scripts

If you find it awkward to maintain separate startup scripts for MPW and ToolServer, you might want to isolate common aspects of the startup process into one script, and to change MPW's and ToolServer's startup process to call this common script. The best way to do this would be to write a UserStartupTS• script which would call the scripts common to ToolServer and MPW; a corresponding MPW script, or an alias to the ToolServer script would also be needed. In the same way, you could also write a ToolServer startup script that would run any MPW startup script. You can include some conditional startup code in this combined file to examine the ToolServer variable {BackgroundShell} and to determine which application is running: 1 is ToolServer, 0 is MPW or any other client application.

Listing 2-1 shows a sample ToolServer startup script. This script first executes all MPW startup scripts in the ToolServer folder and then executes a script called CommonStartup, if this script exists in the ToolServer folder. The script also demonstrates the use of the {BackgroundShell} ToolServer variable: if the script is run from MPW, it executes all ToolServer startup scripts (except itself) instead of running all MPW startup scripts.

Listing 2-1 Sample startup script

```
Set myName "{command}"
if {BackgroundShell}
      set scriptHead "UserStartup•"
else
      set scriptHead "UserStartupTS•"
end
set oldExit "{exit}"
set exit 0
for file in "{MPW}{scriptHead}"≈
      if "{file}" !~ /≈{myName}/
                                     # Prevent recursive execution of this
         execute "{file}"
                                     # script
      end
end
`exists "{MPW}"CommonStartup`
                                    # Execute CommonStartup if it exists
set exit "{oldExit}"
unset myName scriptHead file oldExit# Remove local variable definitions
```

Quitting ToolServer

Once ToolServer is launched, it executes scripts or waits for additional input until one of the following happens:

- You bring ToolServer to the foreground and choose Quit from the File menu.
- You run a script containing the built-in command Quit.
- The ToolServer receives a Quit event. For additional information see Chapter 4, "Using Apple Events to Communicate With ToolServer."
- You specify the -q (quit) option to the RShell command. For additional information see Chapter 3, "The RShell Command."

ToolServer executes the QuitTS script when asked to quit. ToolServer will also execute all QuitTS •≈ scripts that exist in ToolServer's directory (or any other directory if the QuitTS script is modified).

Note

If you are using ToolServer with the MPW Shell, it is assumed that the QuitTS script is either in the same directory as ToolServer or in the Preferences folder. If you move it to a folder different from these two, you must change the value of the {PrefsFolder} variable in the StartupTS script to the new location of the QuitTS script. •

Using ToolServer in the Foreground

It is a matter of convenience whether you use ToolServer in the foreground or in the background. Using MPW's RShell command, described in Chapter 3, or the Apple events, described in Chapter 4, you can obtain status information about an executing script, have ToolServer execute additional scripts, or quit ToolServer—all without having to bring ToolServer to the foreground.

Quitting ToolServer 2-5

Whether you launch ToolServer from the MPW Shell or from the Finder, you can bring ToolServer to the foreground and use the menu items shown in Table 2-1 to execute scripts and monitor status. ToolServer supports the Apple, File, and Edit menus.

Table 2-1 ToolServer menu selections

Menu	Item	Effect
File	Open Status	Opens a status window that displays the name of the currently executing command or tool. When ToolServer is idle, the name "ToolServer" is displayed in the status window.
	Execute Script (Command-E)	Displays a standard file dialog box from which you select a script to execute.
	Close Status	Closes the status window.
	Quit	Terminates ToolServer.
Apple	About ToolServer	Displays version and copyright information.
Edit	(all)	Become active when you open a desk accessory or dialog box.

Script Execution

Most traditional Macintosh applications provide a document and one or more ways of opening that document. A ToolServer document is a script, a file of type 'TEXT' that contains one or more MPW command lines. Unlike the MPW Shell, which creates a window in which to display and edit that script, when ToolServer opens a script, it simply executes the specified script.

When using ToolServer as a foreground application or with MPW, you can tell ToolServer to execute one or more documents in the following ways:

- Double-click one or more ToolServer documents in the Finder. (A ToolServer document is a file of type 'TEXT' and creator 'MPSX'.)
- Drop the document icon or icons onto the ToolServer icon in the Finder.
- Specify the document name as a parameter when launching ToolServer from the MPW Shell.
- Choose Execute Script from ToolServer's File menu.

Whichever of these methods you use to open a document, ToolServer sets its working directory to be the directory containing the specified file. The script contained in the file is then run as if it were executed by the MPW Shell.

Note

Third-party application or development environments may provide additional ways of executing scripts. Please consult the documentation provided for additional information. ◆

Aborting Script Execution

You can abort a script running under ToolServer by bringing ToolServer to the foreground and entering Command-. (Command-period) from the keyboard. This command aborts the currently executing script. If scripts are queued waiting to run, ToolServer executes the next script in the queue.

You can also abort scripts by using the RShell command, described in Chapter 3 or the 'abrt' Apple event described in Chapter 4.

Limitations on Scripts That Run Under ToolServer

Scripts can invoke any MPW tool and can contain the MPW built-in commands listed in Table 2-2. Scripts can also include variables, command aliases, substitution characters, quotes, wildcard operators, and redirection commands. Projector and editor commands are not supported; attempts to execute such commands cause ToolServer to set the Status variable to 1. ToolServer sets the variable BackgroundShell to 1 so that scripts can determine if they are running under the ToolServer (1) or under the MPW Shell (0).

Table 2-2 Val	id MPW built-in	commands	for scripts
---------------	-----------------	----------	-------------

Alert	Directory	Exit	Newer	Shift
Alias	Duplicate	Export	NewFolder	ShutDown
Beep	Echo	Files	Parameters	Unalias
BeginEnd	Eject	Flush	Quit	Unexport
Break	Else	For	Quote	Unmount
Catenate	Equal	Help	Rename	Unset
Confirm	Erase	If	Request	Version
Continue	Evaluate	LoopEnd	RShell [*]	Volumes
Date	Execute	Move	Set	Which
Delete	Exist	Mount	SetFile	

^{*} The RShell command is part of ToolServer's command set, but is only included in version 3.3 or later of the MPW Shell.

Script Execution 2-7

It is also a good idea to make your scripts as generic as possible so that they can run in different contexts without requiring changes. In general, observe the following points in writing scripts:

- Do not use command aliases in a script unless they are also defined in that script.
- A script should not depend on variables being defined globally except for the pre-defined MPW variables.
- Place source files in their own folder; don't put them in the MPW folder.
- Don't depend on volumes being available. A script might need to include code that determines which context it is running in and mounts the required volumes if it is not running in the same location where the files are placed.
- If you plan to run a script on a remote machine, avoid commands that put up dialogs. If the command puts up dialogs, and there are options available for disabling these dialogs, use these options.
- Make sure that your script handles error returns; the script can ignore an error, but it should not abort as a result of an error, except by design.

Input, Output, and Diagnostic Files

ToolServer and the MPW Shell differ in the way they handle input, output, and standard error. This section describes these differences.

The MPW Shell provides tools and scripts with three preopened files: standard input, standard output, and standard error. The MPW command language allows you to override these defaults to redirect input/output (I/O). MPW also provides a set of pseudodevices; these include Dev:Console, Dev:Null, Dev:StdIn, Dev:StdOut, and Dev:StdErr.

When you run a tool or script in MPW without specifying I/O redirection, standard input, standard output, and standard error are initially directed to Dev:Console. The MPW Shell installs a device handler for Dev:Console that captures reads and writes, and directs them to the frontmost window. This is generally the MPW Shell's Worksheet window. ToolServer does not have a worksheet or any window, and thus cannot provide a console device in the traditional way.

If you run a tool or script under ToolServer that does not redirect output to a file, output is sent to either of two files (pseudodevices) introduced by ToolServer to handle this situation: Dev:Output and Dev:Error. Standard output is sent to Dev:Output, and standard error is sent to Dev:Error. What ToolServer does next depends on the method used to execute scripts:

■ If the script is executed by using one of the methods described in "Script Execution" on page 2-6, ToolServer creates files to hold output and error text. The name and location of these files depend on the value of the variables BackgroundOut and BackgroundErr. These variables are not set when ToolServer starts; you can set them in the UserStartup• script.

ToolServer evaluates the BackgroundOut and BackgroundErr variables and creates the necessary files when the tool or script first writes to Dev:Output or Dev:Error. Table 2-3 shows the effect of various settings for these variables on the files created by ToolServer.

If BackgroundOut and BackgroundErr are not set, the output files are created in the directory containing the script and are the name of the script with .out and .err appended respectively. For example, if the script Test in the folder HD:TestScripts: is executed, the output and error files would be Test.out and Test.err in the folder HD:TestScripts:.

Files produced by ToolServer are of type 'TEXT' and creator 'MPS '. You can use the MPW editor or any text editor to view and edit these files.

■ If the script is executed by using Apple events, ToolServer sends the output back to the client application via an Apple event. Whether the output is buffered or sent immediately depends on the Apple event used to execute the script. For additional information see the section "I/O With Apple Events" in Chapter 4. Please note that the RShell command is an instance of executing a script by using the script ('scpt') Apple event.

WARNING

ToolServer does not support reading from standard input unless it is redirected from a file or a pipe. Attempts by tools and scripts to read from Dev:Console, Dev:StdIn, Dev:Output, or Dev:Error will return an End of File (EOF) error. ▲

Script Execution 2-9

Table 2-3 Files defined by BackgroundOut and BackgroundErr

Variable	Setting	Effect
BackgroundOut	none	ToolServer creates a file named <i>script</i> .out, where <i>script</i> is the name of the input script. The file is created in the directory containing the executing script.
	filename	ToolServer creates a file named filename.
	DEV:NULL	ToolServer does not create an output file.
BackgroundErr	none	ToolServer creates a file named <i>script.err</i> , where <i>script</i> is the name of the input script. The file is created in the directory containing the executing script.
	filename	ToolServer creates a file named filename.
	DEV: NULL	ToolServer does not create an error file.

If ToolServer cannot open the specified output files because they are in use (locked or already open), it opens a new file and generates a new, unique name by appending an ordinal number (0,1,2,...) to the specified output filename.

If ToolServer is unable to write to standard error, it will write errors to the log file ToolServer.Log. This log includes messages about errors that occur during the processing of Apple events or the creation of the output or error files.

The log file is overwritten each time you launch ToolServer. If you want to save a copy of the file, you can rename it in your QuitTS script.

WARNING

Tools and scripts can use the I/O redirection facilities of the MPW Shell language and I/O libraries to read and write files. There is one important difference between running scripts under the MPW Shell and running them under ToolServer: The MPW Shell allows tools and scripts to read the contents of files that have been changed by the editor but have not yet been saved to disk. ToolServer does not intercept file system calls and does not allow tools to read from MPW windows. You must save any changed files before running a tool or script that accesses these files. \blacktriangle

Using Alerts to Monitor Script Execution

If you use ToolServer to execute a script locally, you can use the MPW Alert command to send messages about script execution.

As the sample script in Listing 2-2 shows, you can include the MPW Alert command (which uses the Notification Manager) to display a message. Otherwise, ToolServer runs unobtrusively in the background, directing diagnostic information to standard error. If an error occurs while attempting to open the standard error file or during initialization, ToolServer writes error information to the file ToolServer.log.

Listing 2-2 shows a sample script used to do a build. The build commands output by the Make tool are written to the file domake.cmd and executed. Note that the sample script includes some error handling.

- If any of the build commands fail to execute, the script displays an alert box specifying that the make failed and gives the name of the file containing diagnostic information.
- If the build succeeds, standard output and standard error are written to the file domake.results, and the script displays an alert box specifying the name of the file containing this information.

Listing 2-2 Sample script

```
Directory 'HD:MPW:Demo:'
Begin
               echo "Beginning Build"
               date
               make -f Demo.make > domake.cmd
               set done 1
               set echo 1
               domake.cmd || begin; alert 'Make failed!!!'; unset done;end;
               set echo 0
               date
End \Sigma 'HD:MPW:Demo:domake.results'
               If {done}
                  Alert "Build is complete.∂nSee HD:MPW:Demo:domake.results"
   Else
                  Alert "Build had errors.∂nSee HD:MPW:Demo:domake.results"
   End
   Ouit
```

Note

If you are using version 3.3 or later of MPW, you can use the TraceFailures variable to obtain more detailed information about the execution of a script. Setting this variable to TRUE, causes a message to be sent to standard error, which identifies the location of the failure when a script terminates abnormally. This message is similar in form to compiler diagnostic messages. •

Script Execution 2-11

This chapter explains how you enable communication between ToolServer and the MPW Shell residing on different machines, describes the syntax of the RShell command, which is used to send a command line to be executed by ToolServer in the background or on a remote machine, includes two sample scripts, and discusses the limitations on scripts that are run on remote machines.

You need to read this chapter if

- you are using version 3.3 of the MPW Shell, and want to use the RShell command to have the MPW Shell on a local machine send a script to be executed by ToolServer in the background on your local machine or on a remote machine
- you need to make use of Apple events to have ToolServer run a tool or script from a development system other than MPW and are interested in an example of a command-line interface to the Apple event mechanism


Version 3.2 of MPW does not support the RShell command.

Communicating With ToolServer on a Remote Machine

Before you can use the RShell command to execute a script on a remote machine, you must enable ToolServer or MPW on a local machine to communicate with ToolServer on a remote machine. The following tutorial describes the procedure you need to follow to do this. For additional information about remote linking and file sharing, see the user documentation provided for System 7.


- 1. Install ToolServer on the remote machine.
- 2. Open the Sharing Setup control panel on the remote machine and turn program linking on. Figure 3-1 shows the Sharing Setup control panel. The status panel for program linking indicates that it is turned on. The status panel for File Sharing also shows that File Sharing is on, which you may also want to enable.

Figure 3-1 Sharing Setup control panel




3. Open the Users & Groups control panel on the remote machine and choose New User from the File menu. A New User icon is added to the Users & Groups control panel as shown in Figure 3-2.

Figure 3-2 Users & Groups control panel




4. Double click the New User icon. When the New User document appears, enter a user password and enable program linking by clicking the Program Linking check box. See Figure 3-3 for an example of an open New User document.

Figure 3-3 New User document



5. Select the ToolServer application and choose Sharing from the File menu. A dialog like the one shown in Figure 3-4 is displayed. Make sure the check box "Allow Remote Program Linking" is checked.

Figure 3-4 Enabling program linking to ToolServer



6. Launch ToolServer on the remote machine by double-clicking the ToolServer icon.

If you have followed the preceding steps, you are now ready to send a script from the local machine to be executed by ToolServer on the remote machine.

7. Return to the local machine. Launch MPW if you have not already done so and create a new file called RemoteScript. Type the following commands into the new file and save the file.

```
beep
beep
beep
echo "done"
```

8. Enter the following command to send the contents of RemoteScript to be executed by ToolServer on the remote machine.

```
RShell < RemoteScript
```

9. Because no target was specified with the RShell command, the PPC Browser dialog shown in Figure 3-5 is displayed. When invoked by the RShell command, the PPC Browser displays all items that respond to ToolServer Apple events and that have been launched. Select the zone, machine, and application to which the script is to be sent and click OK.

Choose a program to link to: Macintoshes **Programs** Cat O'NineTails む Too1Server Hornbout Lucky7 mk's other mac 亞 AppleTalk Zones De Anza 3/4-North む De Anza 3/4-South De Anza 3/Token Ring De Anza 6/3rd De Anza 7 Dev Support Center (DTS) Ū Cancel 0K

Figure 3-5 PPC Browser dialog

Note that the PPC Browser dialog only displays the ToolServer on a specific machine, not all ToolServers in the zone. If you want to install multiple ToolServers on one machine, you must rename them so that they have unique names; for example, ToolServer1, ToolServer 2, and so on.

10. When the dialog box shown in Figure 3-6 is displayed, click Registered User, specify your password, and then click OK.

Figure 3-6 Program linking dialog



11. The script is now executed on the remote machine. If you are close enough to the remote machine, you should hear three beeps. You should also see the "done" message echoed back to the currently active MPW window on your local machine.

Using Files on the Local Machine

The preceding tutorial assumes that any source files needed by the executing script are located on the remote machine. If the source files are located on the local machine, you will also need to do the following.

- 1. Use the Users & Groups control panel to turn file sharing on for the local machine.
- 2. Use the Sharing item in the Finder File menu on the local machine and specify the appropriate privileges for the folder(s) containing the files you need to access.
- 3. Include the Choose command in the executing script to log on to these folders (treated as AppleShare volumes). The Choose command must precede any command that access these files. For example,

Choose LocalZone:LocalMachine:Volume -u Joanna Bujes -pw boo The -u option makes the remote user a registered user of your local machine. The -pw option specifies the user's password.

If it is possible for you to respond to user dialogs on the remote machine because the two machines are physically close, you can also use the Chooser to log on to the folders on the local machine.

Using the RShell Command

This section describes the syntax and use of the RShell command.

Command Syntax

The syntax of the RShell command is:

```
RShell[[-f|-b|-r target][-q][command | < script]] | [-status|-c id | -k id][> output][ \ge error]
```

_ f

This option sends the Script event to the MPW Shell (version 3.3 or later) running on the same machine where the RShell command is executed. If the RShell command is included in a script that is executed by ToolServer, and the MPW Shell has not been launched, this option launches it.

-b

This option sends the Script event to be executed in the background by ToolServer running on the same machine where the RShell command is executed. If the RShell command is executed by the MPW Shell and ToolServer has not been launched, this option launches it.

```
-r [target]
```

This option sends the command to the application specified by *target*. The application must already be running. The *target* parameter takes the form [[zone:] server:] ApplicationName. The application is either ToolServer or the MPW Shell. The application name is case sensitive.

-q

This option quits ToolServer. If command follows, the specified command is executed first.

command

This parameter is a string specifying the command to be executed. The command you specify is syntactically equivalent to an MPW command line. If you omit this parameter, RShell reads from standard input.

If you use the -r option, the specified script or tool is assumed to reside on the remote machine. Note that ToolServer does not support all MPW built-in commands; see Table 2-3, in Chapter 2 for a list of valid commands.

script

This parameter specifies the name of a script on the local machine whose contents are redirected to ToolServer. If the script name contains a space, it must be quoted.

```
-status
```

This option displays information about scripts that are currently running or about pending RShell requests—scripts waiting to be run. Only those RShell requests that you have initiated are displayed in the status report. Standard input is ignored.

```
-c id
```

This option closes the files associated with the request whose transaction ID is *id*. Standard input is ignored. See "Transaction ID of a Request" on page 3-9 and "Redirecting Output and Abnormal Termination" on page 3-10 for more information.

```
-k id
```

This option aborts the script whose transaction ID is *id*. Standard input is ignored. See "Transaction ID of a Request" on page 3-9 and "Redirecting Output and Abnormal Termination" on page 3-10 for more information.

output

This parameter is the name of the file to which standard output is redirected. See "Input, Output, and Diagnostic Files" in Chapter 2 and "Redirecting Output and Abnormal Termination" on page 3-10 for additional information.

error

This parameter is the name of the file to which standard error is redirected. See "Input, Output, and Diagnostic Files" in Chapter 2 and "Redirecting Output and Abnormal Termination" on page 3-10 for additional information.

Note

The RShell command reads from standard input if neither *command*, -k, -c, -status, nor -q is specified.

If you don't specify any of the -f, -b, or -r options to select a target application, an interactive window called the PPC Browser is opened to allow you to select the application to receive the command. Figure 3-5 shows a sample PPC Browser. ◆

Examples

The following examples illustrate the use of the RShell command:

```
RShell -q # quit ToolServer

RShell "beep" # execute the beep command

RShell "beep" -q # execute the beep command and quit

RShell < myscript # execute the contents of the file

myscript

The command

RShell < myscript

or

RShell < "my script"
```

redirects the contents of a file named myscript, to be found in the current directory for the local (sending) machine, to the RShell command. The command

```
RShell MyScript
or
RShell "My Script"
```

sends the specified script name to ToolServer, which locates the script in ToolServer's current directory.

Variable Substitution in the RShell Command Line

The type of quotes (single or double) you use to delimit the command string you specify for the RShell command determines where variable substitution occurs.

If you specify the command

```
RShell -b "echo {BackgroundShell}"
```

the sending application (usually the MPW Shell) evaluates {BackgroundShell} and sends the resulting command to ToolServer. If you specify the command, because of the hard quotes ('), the command line is sent as is to ToolServer, which evaluates {BackgroundShell} and performs variable substitution.

```
RShell -b 'echo {BackgroundShell}'
```

Transaction ID of a Request

When you specify a script, tool, or command to be sent by the RShell command, the command assigns each request a transaction ID and places it in a queue. Multiple requests to one or more applications might be outstanding at any time. If you use the -status option to the RShell command, it displays information about requests still in the queue that were issued by your application. Listing 3-1 shows the output of the -status option.

Listing 3-1 Output of RShell -status option

rshell -	status		
ID	Request	Current Command	Server
1	makescript	link	ToolServer
2	BuildScript	duplicate	AZone:AMachine:ToolServer
3	TestScript		ToolServer

In the status shown in Listing 3-1, two requests are active on two different ToolServers. The current command column is empty for request 3; a blank current command field usually indicates that the script is queued, waiting for ToolServer to complete a previous script.

The transaction ID of a script appears in the first column of the status display. You can use this ID with the RShell -k or -c option as described in the next section.

Redirecting Output and Abnormal Termination

When you use the RShell command to send a command or script, the RShell command keeps open its standard output and standard error files in case the command or script directs output to Dev:Output or Dev:Error respectively. Thus files are kept open for each outstanding RShell request. For example, the following command opens outputfile and errfile, and then writes output and diagnostic output to these files. The sending application (ToolServer or the MPW Shell) closes these files when the script completes.

RShell 'myScript > dev:output ≥ dev:error' > outputfile ≥ errfile

- If you do not specify output redirection with the RShell command, and the sending application is ToolServer, output is sent to wherever the issuing ToolServer's Dev:Output and Dev:Error are currently directed.
- If you do not specify output redirection with the RShell command, and the sending application is the MPW Shell, output is sent to the window in which the RShell command (or the script containing it) was executed.

This can cause a problem when more than one process attempts to write to the same window or file. For example, you execute an RShell command from the Worksheet and do not specify redirection. You then choose the Check Out item from the Projector menu and find that you are not able to. The following error message is displayed:

```
###ExperShell-a15 - Unable to open "Athena:MPW:Worksheet"
# The read/write permission of only one access path to a file
can allow writing (OS error -49)
```

The cause of the error message is that both the RShell command and the Check Out item from the Projector menu redirect output to the same window, in this case the Worksheet window. If this happens to you, you can either choose the menu item from another window or you can use the -k id option of the RShell command to kill the process. The same situation can arise if you execute a number of RShell commands from the same window without specifying redirection. If you find yourself in this situation, you can use the -k id option to kill the contending processes. Best of all, you can avoid trouble by always redirecting RShell command output to a file.

If a script terminates abnormally—due, for example, to a broken network connection or to a tool that crashes—RShell's standard output and standard error files might remain open. In this case, you need to close the standard output and standard error files associated with the request by using the -c *id* option of the RShell command, where *id* specifies the transaction ID of the request.

The -c id option is not intended for use with an executing script; it is provided to allow you to cleanup output files when the connection between the client (the MPW Shell or the ToolServer that ran the RShell command) and the server (the MPW Shell or the ToolServer that received and processed the command) has been broken. If a script is running, do not use the -c id option. Kill the process instead with the -k id option.

▲ WARNING

It is strongly recommended that you do not use the -c *id* option on a running ToolServer process or on a ToolServer process awaiting execution. Doing so makes it impossible to kill the process from the sending application; it can only be stopped (it must start executing) from the ToolServer executing it by aborting the process with a Command-period. **\(\)**

Sample Scripts

This section describes the use of the RShell command to execute scripts. It describes two scripts: one that sends compilations to ToolServer running in the background and one that sends compilations to ToolServer running on a remote machine.

A Script That Compiles in the Background

The script shown in Listing 3-2 sets the current directory, searches the directory for files terminating in .c, and compiles each such file.

If the compile does not terminate normally, an RShell command within the script sends MPW an Alert command that specifies the name of the file that did not compile successfully. When the script is done, another RShell command sends MPW an Alert command that displays the message "Done."

The RShell command used to send the script shown in Listing 3-2 to ToolServer is

RShell -b "Background Compile"

▲ WARNING

Under low memory conditions, using the ¬b option to the RShell command may launch ToolServer in a partition smaller than the one requested in ToolServer's size resource. Subsequent operations performed within ToolServer might then fail because of insufficient memory. The notification given varies with the particular tool that has failed. In extreme cases the Apple events mechanism might not have enough memory to reply to the MPW Shell. In that case the ¬status option to the RShell command will show that operations are still pending. ▲

Sample Scripts 3-11

Listing 3-2 Background compile script

```
Set Exit 0

Directory "hd:ToolServer Demo"

For file In ≈.c

    (Evaluate "{file}" =~ /(≈)®1.c/) > Dev:Null  # set {®1} to the  # part of the name  # that is to the  # left of ".c"

    c "{file}" -o "{®1}".o ≥ "{®1}".err

    If {status} != 0

        RShell -f "Alert 'Errors in ∂"{file}∂"'"

    End

RShell -f "Alert Done"

Set Exit 1
```

A Script That Compiles on a Remote Machine

Before you can use the RShell command to communicate with ToolServer on a remote machine, you need to configure the local and remote machines according to the instructions given in "Communicating With ToolServer on a Remote Machine" on page 3-2.

Like the script shown in Listing 3-2, the script shown in Listing 3-3 sets the current directory, searches the directory for files ending in . c, and compiles them.

The RShell command used to send the script shown in Listing 3-3 to ToolServer is

```
rShell -r "TSZone:TSServer:ToolServer" < "Remote Compile" ∑ MyOut
```

where Remote Compile is the script to be executed. TSZone and TSServer are respectively the zone and server where ToolServer resides.

If you compare the scripts shown in Listing 3-2 and Listing 3-3, you will notice that the RShell commands in Listing 3-2 have been replaced with Echo commands in Listing 3-3. This is because RShell commands in a remote script will cause program linking dialogs to be generated on the remote machine. This will cause problems if the user cannot see the screen of the remote machine and cannot respond to the dialogs. In such a case, you must pass all status information back to the local machine using standard output or standard error.

The RShell Command

Listing 3-3 Remote compile script

The output of the RShell command used to send the script to the remote machine can be directed to a window on the local machine as follows:

```
RShell -r "TSZone:TSServer:ToolServer" < "Remote Compile" \partial \Sigma Remote.log
```

▲ WARNING

If you are issuing several RShell commands at the same time, it is best to redirect output from these commands to separate log files or windows. The problems that can arise if you do not are described in "Redirecting Output and Abnormal Termination" on page 3-10. ▲

Shortcuts

Though the RShell command provides a great deal of power and flexibility to script writers, it can be somewhat complicated to use. An MPW Shell startup file named Userstartup•ToolServer (in the Examples folder) simplifies using ToolServer from the MPW Shell. The startup file provides

- a command-key definition (Command-\) that sends the current line or selection to ToolServer for execution
- extensions to the build menu for doing background builds
- a sample script that synchronizes variables and aliases between the MPW Shell and ToolServer

A Quit • ToolServer script, also in the Userstartup • ToolServer file, checks for outstanding RShell requests before exiting MPW.

Shortcuts 3-13

This chapter describes ToolServer's support of Apple events. An Apple event is a high-level event that adheres to the Apple Event Interprocess Messaging Protocol (AEIMP). By using the routines of the Apple Event Manager your application can use Apple events to communicate with ToolServer in a standard way.

A transaction involving Apple events is initiated by a client application, which sends an Apple event to request a service. The application providing the service is called a server application. For complete information about sending and processing Apple events, see the Apple Event Manager chapter of *Inside Macintosh*, Volume VI.

You should read this chapter if you need to extend the functionality of your application by making use of ToolServer's execution environment. See the following examples.

- A client application has a text editor but no development environment. The client can use Apple events to send text input (like a BuildProgram or Link command) to ToolServer, which can execute the command and return output as the client directs.
- A client application consists of a development environment that has no resource compiler or decompiler. The client can use Apple events, triggered perhaps by a menu selection, to send Rez and DeRez commands to ToolServer.

Apple events can be sent locally or across a network. The Users & Groups control panel provides an interface for controlling Apple events access across the network. Multiple users can use a single ToolServer running on a remote server; the users share the ToolServer state such as shell variables, aliases, and the working directory. Complete information about the configuration required to enable remote communication is provided in the section "Communicating With ToolServer on a Remote Machine" in Chapter 3.

ToolServer as a Server Application

This section introduces the three kinds of Apple events that are understood by ToolServer. Some of these events are documented in other publications; this chapter supplies additional information about how ToolServer handles these events. Events that are specific to ToolServer and MPW are only documented in this chapter.

ToolServer supports the following kinds of events:

required events

The four events that an application must handle to support Apple events are Open Application, Open Documents, Print Documents, and Quit. These events are defined in the *Apple Event Registry: Standard Suites*.

miscellaneous events

ToolServer supports the 'dosc' (do script) event, which is defined in the Miscellaneous suite of the *Apple Event Registry: Standard Suites*.

■ MPW custom events

ToolServer uses the Script ('scpt'), Output ('outp'), Diagnostic ('diag'), Status ('diag'), and Abort ('abrt') events to control script execution.

Figure 4-1 shows the possible flow of events between a client application and ToolServer. Because you cannot use a high-level event to launch ToolServer, it must already be running when your application sends an Apple event.

The Apple Event Manager defines a standard reply that includes an error number ('errn') and an error string ('errs'). Events may also include additional parameters in the reply. These parameters are defined along with the events in the following sections.

Note

You can send Apple events to the MPW Shell as well as to ToolServer, but only ToolServer returns output. For additional information, see Appendix A, "Apple Event Support in the MPW Shell." ◆

Figure 4-1 Apple events




Table 4-1 lists the events supported by ToolServer. The sections "Required Events" on page 4-6 and "Script Events" on page 4-7 describe in detail the attributes and parameters for the events listed in Table 4-1.

Table 4-1	Apple events
-----------	--------------

ID	Class	Effect
'oapp'	'aevt'	Finder sends the Open Application ('oapp') event when ToolServer is launched and no documents are selected to be executed or printed. The reply contains 'errn' == noErr. This event is included because it is a required event. It would normally be used by an application that opens an untitled document in response to the user's double-clicking the application. Because ToolServer does not create new documents, it is not affected by this event.
'odoc'	'aevt'	The Open Documents ('odoc') event contains a list of files that ToolServer is to open. ToolServer treats these documents as scripts and executes them. Because the client application does not expect parameters in the reply beyond an error number and error string, scripts executed by using this event do not use Apple events to return output. All input and output must be through files. For additional information see the section "I/O With Apple Events" on page 4-5.
'pdoc'	'aevt'	The Print Documents ('pdoc') event causes ToolServer to execute the print tool to print the specified documents. As in the Open Documents case, the event returns no output to the client application.
'quit'	'aevt'	The Quit ('quit') event terminates ToolServer. If ToolServer is executing a tool or script, the Quit event is queued until the script or tool completes. As required by the Apple Event Manager, ToolServer replies to the event and then proceeds with the Quit event. Because quitting involves a number of steps, including the execution of a script, it is possible for the Quit event to fail even though a good status has been returned.
'dosc'	'misc'	The Do Script ('dosc') event sends an MPW command line to be executed by ToolServer. This event causes ToolServer to buffer script output and return it as the direct parameter of the reply. For additional information see the section "I/O With Apple Events" on page 4-5.
'scpt '	'MPS'	The Script ('scpt') event sends an MPW command line to be executed by ToolServer. This event returns a series of events containing the text written to Dev:Output, Dev:Error, or Dev:Console. See "I/O With Apple Events" on page 4-5 for additional information.
'outp'	'MPS'	The Output ('outp') event returns standard output to the client application.
'diag'	'MPS'	The Diagnostic ('diag') event returns diagnostic output (standard error) to the client application.
'stat'	'MPS'	The Status ('stat') event is used by the client application to determine the current status of ToolServer.
'abrt'	'MPS'	The client application uses the Abort ('abrt') event to abort the currently executing script.

Executing a Script by Using Apple Events

In general there are two ways to execute a script by using Apple events:

- by sending the Open Documents event to ToolServer
 If you use this method, ToolServer sets the working directory to the one containing the script.
- by sending ToolServer either the Script event or the Do Script event

 These events are designed so that development environments such as the MPW Shell or other applications can send MPW commands or scripts to ToolServer and receive the output back. ToolServer's working directory is not changed before running the script in this case.

Rather than receiving a specific file or document, ToolServer gets a buffer of text to be interpreted as an MPW Shell command line or script. ToolServer interprets the text as if it had been entered interactively to the MPW Shell. Since the MPW Shell is designed to "read" scripts to execute them, ToolServer creates a temporary file to contain the text and saves this file in the folder specified by the {TempFolder} variable, which is set to the system's temporary folder by default. You can have ToolServer save the file elsewhere by resetting the value of this variable in your UserstartupTS file.

ToolServer responds to one script event at a time. 'odoc', 'pdoc', 'quit', 'dosc', and 'scpt' events received while ToolServer is running a script are queued until that script completes. ToolServer responds to 'stat', 'abrt', and 'oapp' events even if it is handling a script or print event.

I/O With Apple Events

If you use the Script event or the Do Script event, you can have the output returned via the Apple event mechanism by directing output to the pseudofilename Dev:Output and diagnostic messages to Dev:Error. ToolServer treats anything directed to Dev:Console (specifically or by default) as if it were written to Dev:Output. The pseudofilenames Dev:Output and Dev:Error are used exclusively by ToolServer.

How ToolServer returns output to an application by using an Apple event *and* directing output to Dev:Output and Dev.Error depends on the event used to execute a script:

- If the application uses the Script event ('MPS ''scpt'), the sender should use the send mode kAEQueueReply. The sender is then able to receive events while waiting for the ToolServer reply. ToolServer generates a series of output and diagnostic output (error) events. These events contain the characters written to Dev:Output and Dev:Error respectively. The reply to the Script event itself contains the final MPW status (value of the MPW {status} variable).
- If the application uses the Do Script event ('misc' 'dosc'), ToolServer buffers output and diagnostic output. When the event is completed, ToolServer returns

these buffers as part of the reply to the event. Output is placed in the direct object parameter of the reply, and diagnostic output is placed in the 'diag' parameter of the reply.

Because Apple event messages are currently limited to 64 KB bytes, the combined total of these buffers must be slightly less than this. The reply to the 'dosc' event also contains the final MPW status value and a system error value. If the message buffer overflows, ToolServer returns the first 64 KB bytes of data and the system error message indicates bufferIsSmall (osErr = -607).

Required Events

The *Apple Event Registry: Standard Suites* defines four required events: Open Application, Open Documents, Print Documents, and Quit. This section describes the attributes and parameters used by these events.

Open Application Event

Message class:	'aevt'
Message ID:	'oapp'
Parameter Keyword:	no parameters

The reply contains 'errn' == noErr. You cannot use this event to launch ToolServer.

Open Documents Event

Message class:	'aevt'
Message ID:	'odoc'
Parameter Keyword:	11
Parameter Type:	'list'
Parameter Data:	a list of documents to open

Scripts executed via the Open Documents event do not return output via Apple events. All input and output must be through files. Refer to the section "I/O With Apple Events" on page 4-5 for additional information.

Print Documents Event

Message class:	'aevt'
Message ID:	'pdoc'
Parameter Keyword:	11
Parameter Type:	'list'
Parameter Data:	a list of documents to print

As in the Open Documents case, no output is returned to the sender.

Quit Event

```
Message class: 'aevt'
Message ID: 'quit'
Parameter Keyword: no parameters
```

Script Events

You use script events, which include one miscellaneous event and four MPW events, to execute a script, return status information, return output and diagnostic information, and abort a script. The following sections describe the attributes and parameters of these events as well as the reply returned by ToolServer.

Script and Do Script Events

The Script and Do Script events are used to execute scripts. The Do Script event is defined in the *Apple Event Registry: Standard Suites*; the Script event is an MPW-specific event. Both events are shown below:

Message class:	'misc'		
Message ID:	'dosc'		
Parameter Keyword:	11		
Parameter Type:	'TEXT'		
Parameter Data:	string containing command line		
Message class:	'MPS '		
Message ID:	'scpt'		
Parameter Keyword:	11		
Parameter Type:	'TEXT'		
Parameter Type: Parameter Data:	'TEXT' string containing command line		

Both events contain a single parameter of type 'TEXT' that is a string containing a command line to be executed. This line can specify a single tool or script, or it can contain a series of command lines separated by semicolons or return characters.

When sending the 'scpt' or 'dosc' event, the sender can specify an optional transaction ID to identify the event. The sender can use the transaction ID later to obtain the status of this script event, or to abort it.

The Script event ('MPS', 'scpt') can return 'diag' and 'outp' events containing the text written to Dev:Output, Dev:Error, or Dev:Console. These events are defined in the next section, "Output and Diagnostic Output Events." The Do Script event ('misc', 'dosc') will buffer this data, and return it in the Apple event reply.

Script Events 4-7

The Apple event reply contains the parameters shown in Table 4-2 and Table 4-3. The 'errn' parameter contains any system errors reported while handling the event or constructing the reply. The 'stat' value contains the MPW status variable set as a result of running the script. The direct ('----') and 'diag' parameters are set in the Do Script event to contain standard output and standard error (diagnostic output) respectively. If no output or error data is produced, these parameters are not set.

Table 4-2 Parameters to Script reply

Parameter	Туре	Description
'errn'	typeLongInteger	system errors
'stat'	typeLongInteger	MPW status value

Table 4-3 Parameters to Do Script reply

Parameter	Туре	Description
'errn'	typeLongInteger	system errors
'stat'	typeLongInteger	MPW status value
' '	typeChar	standard output
'diag'	typeChar	diagnostic output

Output and Diagnostic Output Events

These events are used to return standard output ('outp') and standard error ('diag') to the sender of a Script event. The transaction ID of the event matches the transaction ID specified in the Script event that resulted in these events.

```
Message class:
                          'MPS '
Message ID:
                          'diag'
                          1 ---- 1
Parameter Keyword:
Parameter Type:
                          'TEXT'
Parameter Data:
                           a stream of characters
TransactionID:
                           same as that of scpt event
Message class:
                          'MPS '
Message ID:
                          'outp'
Parameter Keyword:
                          ' ---- '
                          'TEXT'
Parameter Type:
Parameter Data:
                           a stream of characters
TransactionID:
                           same as that of scpt event
```

The libraries and device handlers might buffer output, so these events can contain an arbitrary amount of text (up to 64 KB bytes). The C stdio library allows you to change the size of its buffers.

Abort Event

The Abort event aborts the currently executing script.

Message class: 'MPS'
Message ID: 'abrt'

Parameter Keyword: no parameters
TransactionID: optional

If the sender of the event does not specify a transaction ID, ToolServer aborts the currently executing script as if the user had entered a Command-. from the keyboard. If a transaction ID is specified, this ID and the sender of this event must match the ID and sender of the currently executing script. The script is aborted only if these two parameters match. The error number ProcNotFound is returned if no abort occurred.

Status Event

The Status event determines the current status of the ToolServer.

Message class: 'MPS '
Message ID: 'stat'

Parameter Keyword: no parameters

TransactionID: optional

If the transaction ID and sender of the status event match those of the currently executing script, or if no transaction ID is specified, the reply 'errn' is set to noErr(0), and the four additional parameters listed in Table 4-4 are returned.

Table 4-4 Parameters to Status event reply

Parameter	Туре	Description
'what'	typeChar	file name of the script in progress
'pos '	typeLongInteger	number of characters read from the file
'size'	typeLongInteger	the size of the file
'who '	typeChar	the name of the current command or tool

If the transaction ID does not match that of the currently executing script, the error number ProcNotFound is returned. If the shell is not running a script, ToolServer sets the error number to noErr, and returns no other parameters.

Script Events 4-9

Apple Event Support in the MPW Shell

Version 3.3 or later of the MPW Shell supports the Apple events described in Chapter 4 of this manual. However, due to the interactive nature of the MPW Shell and the design of the MPW Shell and the editor, this support is somewhat limited compared to the support provided by ToolServer. The differences and limitations are:

- The MPW Shell's reply to an Apple event is merely an acknowledgment that the event was received properly; it does not indicate the success or failure of the request. The reason for this is that the MPW Shell replies to the event before it processes the event.
- Because the MPW Shell replies immediately to script events, the Abort and Status events function only when the transaction ID is not set (specified as kAnyTransactionID). The MPW Shell does not match the sender of this event with the sender of the script.
- Because the MPW Shell has a console, it does not support the Dev:Output or Dev:Error devices nor return console output to the sender of a script event.
- The MPW Shell supports the four required events (Open Application, Open Documents, Print Documents, and Quit). However, the Open Documents event opens the files in the editor and does not execute a script, as is the case with ToolServer.
- The MPW Shell accepts the Script and Do Script events. However, it replies immediately and then executes the script as if the user had run the script via a user-defined menu item. Standard output and standard error default to the console, which is generally the frontmost window. The error number in the reply indicates that the script was successfully received, not the success or failure of the script itself.

Version 3.3 of MPW can also communicate with ToolServer by using the RShell command that has been added to both the MPW Shell and ToolServer. This command is described in Chapter 3, "The RShell Command."

This appendix provides summary information about the files created by ToolServer and the variables used by ToolServer.

ToolServer Files

Table B-1 describes the files included with ToolServer and the files ToolServer creates during execution.

Table B-1	ToolServer files
I able b-1	IOOOEIVEI IIIES

File	Use
StartupTS	The contents of this script are executed at launch time. The script sets the default value of ToolServer variables, calls the script UserstartupTS, and then calls any additional user-defined startup scripts named UserStartupTS•name.
UserStartupTS	User-defined script that specifies commands to be executed after the StartupTS script is executed. This script can be used to set new default variables or to change the values of variables set in the StartupTS script.
Scriptname.err	File created by ToolServer when a script is executed using the Execute Script menu item and the execution of the script results in text written to standard error.
Scriptname.out	File created by ToolServer when a script is executed using the Execute Script menu item and the execution of the script results in text written to standard ouput.
QuitTS	File executed as part of the quit process. Commands included in this file search for additional scripts to be run at quit time. Such scripts must be named QuitTS•name and be located either in the ToolServer folder or in the MPW Preferences folder.
	By default, ToolServer overwrites the ToolServer.log file each time it runs, the QuitTS script includes a command which you can uncomment to save a copy of this file.
ToolServer.log	File created by ToolServer to which messages are directed about errors that occur during the creation of the output or error files or the processing of Apple events.
	By default, ToolServer overwrites the ToolServer.log file each time it runs, the QuitTS script includes a command which you can uncomment to save a copy of this file.
Userstartup•ToolServer	File containing scripts that provide shortcuts in the use of ToolServer from MPW 3.3.
Dev:Output	ToolServer pseudodevice to which standard output is sent if a script does not specify a file to which standard output is redirected.
Dev:Error	ToolServer pseudodevice to which standard error is sent if a script does not specify a file to which diagnostic output is redirected.
Dev:Null	ToolServer pseudodevice to which standard output or standard error may be redirected. Standard output or standard error information redirected to this device is then discarded.

ToolServer Variables

The following variables are set in ToolServer's ${\tt StartupTS}$ file.

 Table B-2
 ToolServer variables

Variable	Use and default value
BackgroundShell	True for ToolServer.
Boot	The boot disk.
SystemFolder	The directory that contains the System and the Finder.
ShellDirectory	The directory that contains ToolServer.
Status	The result of the last command executed.
User	Automatically defined to the name that appears in the Chooser.
MPW	The volume or folder containing ToolServer. If you place ToolServer outside this folder, you should redefine this variable to the location of the ToolServer folder.
Commands	Directories to search for commands. The default setting is ":{MPW} Tools:, {MPW}Scripts:".
PrefsFolder	The directory to search for UserStartupTS and QuitTS scripts: by default {SystemFolder}Preferences:MPW. You can change the value in the Startup file or create an alias named MPW in the preferences folder to reference the folder where you keep your scripts.
TempFolder	The directory for temporary items. ToolServer may create some temporary items here. The default value is "{Boot}Temporary Items".
AIncludes	The directories to search for assembly language include files. The default value is "{MPW}Interfaces:AIncludes: ".
Libraries	The directory that contains shared libraries. The default value is "{MPW}Libraries:Libraries ".
CIncludes	The directories to search for C include files. The default value is "{MPW}Interfaces:CIncludes ".
CLibraries	The directory that contains C libraries. The default value is "{MPW}Libraries:CLibraries ".
PInterfaces	The directories to search for Pascal interface files. The default value is "{MPW}Interfaces:PInterfaces ".
PLibraries	The directory that contains Pascal libraries. The default value is "{MPW}Libraries:PLibraries ".
RIncludes	The directory that contains Rez include files. The default value is "{MPW}Interfaces:RIncludes ".

ToolServer Variables B-3

 Table B-2
 ToolServer variables (continued)

Variable	Use and default value
WordSet	Character set that defines words for searches and double-clicks. The default value is $\ 'a-zA-Z_0-9'$.
PrintOptions	Determines the options used by the print tool. The default -h setting, prints headers containing the name of the file, the page, and the time.
Exit	Determines whether command files terminate after first error: 0 not to terminate; non-zero to terminate. The default value is 1 .
Echo	Determines whether commands are echoed before execution: 0 not to echo; 0 to echo. The default value is 0 .
Test	Determines whether tools and applications are executed: 0 to execute; non-zero not to execute. The default value is 0.

Index

BackgroundShell variable B-3

A	Backup command 1-3 Boot variable B-3
Abort event 4-4, 4-9 aborting script execution 2-7, 4-9 'abrt' event 4-4 'abrt' Apple event 4-4, 4-9	C
AIncludes variable B-3 Alert command 2-10 alerts example of use in scripts 3-11 to monitor script execution 2-10 aliases synchronizing 3-13 Apple events 'abrt' event 4-4, 4-9	CIncludes variable B-3 CLibraries variable B-3 client application 4-2 command aliases in scripts 2-8 Commands variable B-3 compatibility 1-3
can't launch ToolServer 4-4 client application 4-2	D
current directory 4-5 'diag' event 4-4, 4-8 'dosc' event 4-4, 4-8 examples of use 4-2 handled by ToolServer 4-2 I/O with 4-5 messages, limitations on 4-6 MPW support for A-1 'oapp' event 4-4, 4-6 'odoc' event 4-4, 4-6 'outp' event 4-4, 4-6 'pdoc' event 4-4, 4-7 required events 4-6 'scpt' event 4-4, 4-7 required events 4-6 'scpt' event 4-4, 4-7 sending across network 4-2 sending to MPW Shell 4-3 send mode 4-5 server application 4-2 'stat' event 4-4, 4-9 uniquely identifying 4-7	determining context of 2-7 Dev:Error 2-9 using Apple events 4-5 Dev:Error pseudodevice B-2 Dev:Null pseudodevice B-2 Dev:Output 2-9 using Apple events 4-5 Dev:Output pseudodevice B-2 'diag' Apple event 4-4, 4-8 Diagnostic event 4-4, 4-8 diagnostic output differences between MPW and ToolServer 2-8 'dosc' Apple event 4-4, 4-8 Do Script event 4-4, 4-8
	Echo variable B-4 error handling in scripts 2-10
В	F, G, H
BackgroundErr variable 2-9 BackgroundOut variable 2-9 BackgroundShell variable 2-3	files as windows 1-3

changed but not saved 1-3

creator of ToolServer 1-3

files (continued) diagnostic 2-8 input 2-8 Log.out 2-10 output 2-8 standard error 2-9 standard output 2-9 StartupTS.err 2-3 StartupTS.out 2-3	output 1-3 differences between MPW and ToolServer 2-8 'outp' Apple event 4-4 redirection 3-10 Output event 4-4, 4-8
synchronizing 1-3 ToolServer.Log 2-10 type of ToolServer 1-3 viewing ToolServer 1-3	'pdoc' Apple event 4-4, 4-6 performance impact on 1-2 running ToolServer on a remote machine 1-3 PInterfaces variable B-3 PLibraries variable B-3
I, J, K	PrefsFolder variable B-3
input 1-3 differences between MPW and ToolServer 2-8 installing ToolServer 2-2 I/O redirection 2-9	Print documents event 4-4, 4-6 PrintOptions variable B-4 pseudodevices 2-9 Dev:Error 2-9 Dev:Output 2-9
<u>L</u>	Q
launching ToolServer from MPW 2-3 from the Finder 2-3 methods of 2-2 Libraries variable B-3	'quit' Apple event 4-4, 4-7 Quit event 4-4 quitting ToolServer 2-5, 4-7 from File menu 2-6 'quit' event 4-4 QuitTS file B-2 QuitTS script 2-10
M, N	
memory required by ToolServer 1-2	R
size of ToolServer partition 1-2 MPW launching in smaller partition 1-2 support for Apple events A-1 MPW variable B-3	RIncludes variable B-3 RShell command variable substitution in 3-9
	S
O 'oapp' Apple event 4-4, 4-6 'odoc' Apple event 4-4, 4-6 Open Application event 4-4, 4-6 Open Documents event 4-4, 4-6 'outp' Apple event 4-4, 4-8	'scpt' Apple event 4-4, 4-7 Script event 4-4, 4-7 script execution aborting 4-9 'dosc' event 4-4 'odoc' event 4-4 'scpt' event 4-4 status 4-9

TempFolder variable B-3 Test variable B-4

scripts	ToolServer
abnormal termination 3-10	Apple events. See Apple events
aborting execution of 2-7	file type and creator 1-3
command aliases in 2-8	in different directory than MPW 2-4
error handling in 2-8, 2-10	partition for 1-2
executing by using Apple events 4-5	signature 1-3
executing from File menu 2-6	use of on a remote machine 3-12
executing using command key 3-13	ToolServer document
identifying as ToolServer document 2-2	defined 2-6
limitation on contents of 2-7	identifying a script as 2-2
monitoring execution of 2-10	ToolServer.log file B-2
no I/O redirection 2-9	ToolServer menus 2-6
QuitTS 2-10	ToolServer version 2-6
running under MPW vs ToolServer 2-10	TraceFailures variable 2-11
run under ToolServer 1-3	transaction ID 3-9
sample using alerts 2-10	
startup 2-3	
that execute in the background 3-11	
that execute on a remote machine 3-12	U
use of CPU by 1-3	
ways of executing 2-6	Userstartup•ToolServer file B-2
writing generic 2-8	UserStartupTS file B-2
server application 4-2	UserStartupTS script 2-3
ShellDirectory variable B-3	User variable B-3
standard error 2-9	
unable to write to 2-10	
standard input	
reading from 2-9	V
standard output 2-9	
startup scripts 2-3	variables
StartupTS.err file 2-3	BackgroundErr 2-9
StartupTS file B-2, B-3	BackgroundOut 2-9
StartupTS.out file 2-3	synchronizing 3-13
StartupTS script 2-3,2-4	
'stat' Apple event 4-4, 4-9	
status	W V V 7
Close Status from File menu 2-6	W, X, Y, Z
interpreting status information 3-10	
Open status from File menu 2-6	WordSet variable B-4
'stat' Apple event 4-4	working directory 2-6
Status event 4-4, 4-9	Apple events 4-5
Status variable B-3	how it's set 2-2
status window	
accessing from File menu 2-6	
syntax conventions viii	
System 7, dependence of ToolServer on 1-3	
SystemFolder variable B-3	
-	
1	

This Apple manual was written, edited, and composed on a desktop publishing system using Apple Macintosh computers and FrameMaker software. Proof pages and final pages were created on an Apple LaserWriter IINTX printer. Line art was created using Adobe™ Illustrator. PostScript™, the page-description language for the LaserWriter, was developed by Adobe Systems Incorporated.

Text type is Palatino[®] and display type is Helvetica[®]. Bullets are ITC Zapf Dingbats[®]. Some elements, such as program listings, are set in Apple Courier.

WRITER
Joanna A. Bujes

EDITORS
Loralee Windsor and Wendy Krafft
ILLUSTRATOR
Dave Olmos
PRODUCTION EDITOR
Teresa Lujan

Special thanks to Judy Ketenhoffen, Mark Cleveland, Brian Strull, Keithen Hayenga, and Herb Kanner.