



IBM ECM System Monitor Field Guides

Upgrade to Version 5.8.0.0-000

July 30th, 2026
CENIT AG
Frank Larisch

Content

Introduction	3
Overview	3
Prerequisites	3
Updating to IBM Enterprise Content Management System Monitor ESM 5.8.0.0-000.....	3
Backup and Fall-back scenario.....	4
Installation steps	4
Advanced options.....	5
Update from version 5.6.0.0.x to 5.7.0.0-000 – Windows Section	6
Update to 5.8.0.0-000 - Windows Section	16
Update of Windows 5.7.0.0.x Server to 5.8.0.0-000 Server	16
ESM GUI Update of Windows 5.6.0.0x Agent to 5.8.0.0-000	25
If you are not already on 5.7.0.0-000 UNIX Section	29
Update from version 5.6.0.0.x Server to 5.7.0.0-000 – UNIX Section	29
Update to 5.8.0.0-000 UNIX section	39
Update of UNIX 5.7.0.0-000 Server to 5.8.0.0-000	39
ESM GUI Update of UNIX 5.6.0.0.x Agent to 5.8.0.0-000.....	47
Contact Information	51

Introduction

There is no substitute for a reliable and stable environment. IBM ESM is one of the most comprehensive tools for achieving precisely this high level of availability of your IBM Business Automation platform. Through precise system and application monitoring, administrators receive a comprehensive overview of their systems.

Overview

This guide describes in detail how IBM ECM System Monitor (ESM) On-Premise-Installation can be updated.

All steps are just an example. The installation described in the guide is very basic and does not include any custom settings. The focus is entirely on the actual update process.

The setup is described exemplarily for Windows Server/Agent and UNIX Server/Agent

The entire update process needs a user with local admin rights on Windows, please be aware that a rotating password change can lead to a non-functional condition.

We recommend using the option “password never expires”.

A UNIX user should have read, write and execute rights on the ESM Server and Agent install folder.

A UNIX user with root rights is not necessary. In case you want the ESM Server and Agent to start at every system start the upgrade process needs a user with root rights !

ESM 5.8.0.0 is a full installer variation. If you want to skip an update installation you can install the product from scratch up. Be aware that in this case no data from previous installations can be used or will be overtaken.

Prerequisites

Updating to IBM Enterprise Content Management System Monitor ESM 5.8.0.0-000

Requires at least a working installation of version 5.7.0.0-000.

If you are on an older version, please refer to the chapter

[Update from version 5.6.0.0.x to 5.7.0.0-000 – Windows Section](#)

[Update from version 5.6.0.0.x Server to 5.7.0.0-000 – UNIX Section](#)

This guide is based on an ESM installation which uses H2 as monitoring and configuration Database.
According to the manufacturer, the database H2 is not recommended for production use.

For all environments running on MSSQL or IBM DB2 as ESM Database, no special adjustments are required for the update process. The procedure remains the same.

In case you plan to update from 5.6.0.0.x straight to 5.8.0.0 – you just need to insert a small intermediate step to update ESM Server to version 5.7.0.0-000, the agents can remain in their 5.6.0.0.x version before the update. It is possible to update all agents later via the ESM 5.8.0.0-000 GUI.

Backup and Fall-back scenario

As a fall-back plan we recommend taking snapshots of your virtual systems. It is strongly recommended to stop the ESM Server and Agent processes (UNIX) or services (Windows) before you start to take a snapshot.

In case you work on a physical installation, stop ESM Server process and backup configuration.mv.db and monitoring.mv.db from {ESM-Install-Dir}/karaf directory. If the upgrade fails, uninstall all components of FixPack and install the last known working version.

Stop ESM Server process/service and restore backup of configuration.mv.db and monitoring.mv.db. Start ESM Server process/service.

Installation steps

Distribute IA installer binaries to your environment or put it on a share where you have access from all affected systems. Distributed installer binaries on UNIX Systems may lose execution rights during distribution process – adjust umask of installer binary, e.g. to 755.

For the update of Linux or Windows Agents you can use alternatively the ESM web Interface instead of the execution of installer binary – see chapter

[ESM GUI Update of Windows 5.6.0.0x Agent to 5.8.0.0-000](#) or

The following steps are an example of how to walk through your update process.

Advanced options

We recommend using our help for these activities. If you need further information about implementation services and ESM training, please contact CENIT at

<mailto:ECM.SystemMonitor@cenit.com>

You can find helpful videos and IBM ESM Field Guides on

[ECM System Monitor - YouTube](#)

[cenit-ag/ESM-FieldGuides: Field Guides for IBM ECM System Monitor](#)


The following chapter is intended only for users on a version earlier than 5.7.0.0.

If you are already on version 5.7.0.0 you can skip this chapter.


Update from version 5.6.0.0.x to 5.7.0.0-000 – **Windows Section**

In our example, we demonstrate a step-by-step update from version 5.6.0.0-000 to version 5.7.0.0-000. All versions from 5.6.0.0.x onwards follow the same procedure.


This is our system – it has only one agent, which runs on our ESM 5.6.0.0-000 server.




We copied our ESM binaries to a local directory, and this is exactly where we will start the update procedure. Mouse right-click on the ESM Server installer binary and choose **“Run as Administrator”**




Install Anywhere starts:




Install Anywhere found an updateable version of ESM – confirm with click on “**Update**”



Software License Agreement



Welcome Screen – click on **Next** to continue



Installation Folder – take over installation path and continue with **Next**

The screenshot shows the 'Installation Folder' window of the ESM Server Installer. The window has a title bar with 'ESM Server Installer' and standard window controls. On the left is a sidebar with the IBM logo and 'Enterprise Content Management System Monitor'. The main area contains the text 'Select installation folder for ESM Server.' and 'Where Would You Like to Install ESM Server?'. Below this is a text input field containing 'E:\IBM\ESM\Server'. To the right of the input field are two buttons: 'Restore Default Folder' and 'Choose...'. At the bottom of the window are four buttons: 'Cancel', 'Help', 'Previous', and 'Next'. The 'Next' button is highlighted with a blue border.

ESM Server Installer

Installation Folder

Select installation folder for ESM Server.

Where Would You Like to Install ESM Server?

E:\IBM\ESM\Server

Restore Default Folder Choose...

Cancel Help Previous Next

ESM Server Settings

The screenshot shows the 'ESM Server Settings' window of the ESM Server Installer. The window has a title bar with 'ESM Server Installer' and standard window controls. On the left is a sidebar with the IBM logo and 'Enterprise Content Management System Monitor'. The main area contains the text 'Please enter ESM Server hostname and port numbers.' and 'Adjust parameters according to the ESM Server environment. The port numbers must be within the range from 1 to 65535.' Below this are several input fields: 'Hostname' (w2k19snv3), 'IP Address' (192.168.154.129), 'MQTT Port' (1883), 'HTTP Port' (80), 'HTTPS' (Enabled radio button selected), 'HTTPS Port' (443), and 'RMI Registry Port' (1099). At the bottom of the window are four buttons: 'Cancel', 'Help', 'Previous', and 'Next'. The 'Next' button is highlighted with a blue border.

ESM Server Installer

ESM Server Settings

Please enter ESM Server hostname and port numbers.

Adjust parameters according to the ESM Server environment.
The port numbers must be within the range from 1 to 65535.

Hostname
w2k19snv3

IP Address
192.168.154.129

MQTT Port
1883

HTTP Port
80

HTTPS
☒ Enabled ☐ Disabled

HTTPS Port
443

RMI Registry Port
1099

Cancel Help Previous Next

Configuration Database Settings – take over settings and continue with **Next**

ESM Server Installer

Configuration Database Settings

Optionally change the JDBC URL, driver class and credentials for the configuration DB.

- jdbc:db2://[serverName[:portNumber]][/instanceName]][:property=value]
- jdbc:sqlserver://[serverName[:portNumber]][/instanceName]][:property=value]
- com.ibm.db2.jcc.DB2Driver | com.microsoft.sqlserver.jdbc.SQLServerDriver

The driver for the default embedded H2 database is already included.

Supported external databases: DB2, MSSQL

WARNING: Existing data will not be migrated to a different database!

JDBC URL

jdbc:h2:./configuration;AUTO_SERVER=TRUE;AUTO_RECONNECT=TRUE;LOCK_T

JDBC Driver Class Name

org.h2.Driver

Database User Name

db

Database User Password

Make sure to copy the external driver to the karaf/deploy folder after installation!

InstallAnywhere

Cancel Help Previous Next

Monitoring Database Settings – take over settings and continue with **Next**

ESM Server Installer

Monitoring Database Settings

Optionally change the JDBC URL, driver class and credentials for the monitoring DB.

- jdbc:db2://[serverName[:portNumber]][/instanceName]][:property=value]
- jdbc:sqlserver://[serverName[:portNumber]][/instanceName]][:property=value]
- com.ibm.db2.jcc.DB2Driver | com.microsoft.sqlserver.jdbc.SQLServerDriver

The driver for the default embedded H2 database is already included.

Supported external databases: DB2, MSSQL

WARNING: Existing data will not be migrated to a different database!

JDBC URL

VER=TRUE;AUTO_RECONNECT=TRUE;LOCK_TIMEOUT=10000;MODE=LEGACY

JDBC Driver Class Name

org.h2.Driver

Database User Name

db


Database User Password

Make sure to copy the external driver to the karaf/deploy folder after installation!


InstallAnywhere

Cancel Help Previous Next


StartUp Settings – It is strongly recommended to re-install the ESM Server service. Click on **Next** to continue.




ESM Server Service install options




Summary – click on **Install** to continue




Installer starts




Uninstall previous version



Install 5.7.0.0



Completion




Delete or rename the installer.properties file in the folder where you executed the ESM Server installer binary. This is necessary if you intend to launch the agent installer as an executable from the same directory.


Update to 5.8.0.0-000 - Windows Section

Update of Windows 5.7.0.0.x Server to 5.8.0.0-000 Server


This procedure is similar to all update paths of 5.7.0.0-000 and higher




InstallAnywhere starts :




A previous version of ESM Server was found -> click on **Update** to continue




Mark, I accept the terms in the license agreement and continue with **Next**.



Installation of ESM Server – click on **next** to continue.



Installation Folder – take over installation path and continue with **Next**.



Take over **ESM Server Settings** and continue with **Next**.

The screenshot shows the 'ESM Server Settings' window of the ESM Server Installer. The window has a title bar with 'ESM Server Installer' and standard window controls. On the left is a sidebar with the IBM logo and 'Enterprise Content Management System Monitor'. The main area contains instructions: 'Please enter ESM Server hostname and port numbers. Adjust parameters according to the ESM Server environment. The port numbers must be within the range from 1 to 65535.' Below this are input fields for 'Hostname' (smcw2k22srv5), 'IP Address' (192.168.154.130), 'MQTT Port' (1883), 'HTTP Port' (80), 'HTTPS' (Enabled), 'HTTPS Port' (443), and 'RMI Registry Port' (1099). At the bottom are 'Cancel', 'Help', 'Previous', and 'Next' buttons.

ESM Server Installer

ESM Server Settings

Please enter ESM Server hostname and port numbers.
Adjust parameters according to the ESM Server environment.
The port numbers must be within the range from 1 to 65535.

Hostname
smcw2k22srv5

IP Address
192.168.154.130

MQTT Port
1883

HTTP Port
80

HTTPS
☒ Enabled ☐ Disabled

HTTPS Port
443

RMI Registry Port
1099

InstallAnywhere
Cancel Help Previous Next

Configuration Database Settings – take over settings and continue with click on **Next**

The screenshot shows the 'Configuration Database Settings' window of the ESM Server Installer. The window has a title bar with 'ESM Server Installer' and standard window controls. On the left is a sidebar with the IBM logo and 'Enterprise Content Management System Monitor'. The main area contains instructions: 'Optionally change the JDBC URL, driver class and credentials for the configuration DB.' followed by three lines of JDBC URL examples. Below this is a note: 'The driver for the default embedded H2 database is already included. Supported external databases: DB2, MSSQL. WARNING: Existing data will not be migrated to a different database!'. Then are input fields for 'JDBC URL' (configuration;AUTO_SERVER=TRUE;AUTO_RECONNECT=TRUE;MODE=LEGACY), 'JDBC Driver Class Name' (org.h2.Driver), 'Database User Name' (db), and 'Database User Password' (masked with asterisks). At the bottom is a note: 'Make sure to copy the external driver to the karaf/deploy folder after installation!'. At the bottom are 'Cancel', 'Help', 'Previous', and 'Next' buttons.

ESM Server Installer

Configuration Database Settings

Optionally change the JDBC URL, driver class and credentials for the configuration DB.
- jdbc:db2://[serverName[:portNumber]][/instanceName]][:property=value]
- jdbc:sqlserver://[serverName[:portNumber]][/instanceName]][:property=value]
- com.ibm.db2.jcc.DB2Driver | com.microsoft.sqlserver.jdbc.SQLServerDriver

The driver for the default embedded H2 database is already included.
Supported external databases: DB2, MSSQL
WARNING: Existing data will not be migrated to a different database!

JDBC URL
configuration;AUTO_SERVER=TRUE;AUTO_RECONNECT=TRUE;MODE=LEGACY

JDBC Driver Class Name
org.h2.Driver

Database User Name
db

Database User Password

Make sure to copy the external driver to the karaf/deploy folder after installation!

InstallAnywhere
Cancel Help Previous Next

Monitoring Database Settings

ESM Server Installer

Monitoring Database Settings

Optionally change the JDBC URL, driver class and credentials for the monitoring DB.

- jdbc:db2://[serverName[:portNumber]][/instanceName]][:property=value]
- jdbc:sqlserver://[serverName[:portNumber]][/instanceName]][:property=value]
- com.ibm.db2.jcc.DB2Driver | com.microsoft.sqlserver.jdbc.SQLServerDriver

The driver for the default embedded H2 database is already included.

Supported external databases: DB2, MSSQL

WARNING: Existing data will not be migrated to a different database!

JDBC URL

./monitoring;AUTO_SERVER=TRUE;AUTO_RECONNECT=TRUE;MODE=LEGACY

JDBC Driver Class Name

org.h2.Driver

Database User Name

db

Database User Password

Make sure to copy the external driver to the karaf/deploy folder after installation!

InstallAnywhere

Cancel Help Previous Next

Start Up Settings

ESM Server Installer

Start Up Settings

Choose if you want ESM Server to start up after installation has finished and at each system start-up.

Start up ESM Server after installation

☒ Yes ☐ No

Start up ESM Server at system start-up


☒ Yes ☐ No

InstallAnywhere


Cancel Help Previous Next

Start Up Settings – It is strongly recommended to Re-Install ESM Server Service


Click on **Next** to continue




Pre-Installation **Summary** – click on **Install**.




Uninstallation of previous version



Installing ESM Server - Install procedure starts.




Installation complete – Click on **Done**.




Delete or rename the installer.properties file in the folder where you executed the ESM installer binary. This is necessary if you intend to launch the agent installer as an executable from the same directory.

ESM GUI Update of Windows 5.6.0.0x Agent to 5.8.0.0-000



Copy **ESM_Agent_Installer.exe** to E:\IBM\ESM\Server\karaf\agent\installers\5.8.0.0-000\Windows




Start the your browser and login to ESM web interface – Go to **Operating Dashboard**
Status of Agent is “outdated” – click on “Show Agents”.



The Agent is still on version 5.6.0.0.0-000 – this information is shown if you click on the Agent label in the sidebar.




Go back to the Agent Overview and select **Update All**.




The advantage of this built-in function is that you do not need to run a separate update procedure for the agent binary, instead, you can handle everything conveniently via the ESM console.


Confirm the security prompt that appears by clicking OK.




Agent status changes to “Updating”.



While the update procedure on the Agent starts the Agent status is “Timed Out”.



It takes about 4 minutes for the agent to come back online.




If you have an environment with perhaps 10, 20, or even more agents, this procedure offers a significant advantage.

If you are not already on 5.7.0.0-000 **UNIX Section**

Update from version 5.6.0.0.x Server to 5.7.0.0-000 – UNIX Section

In our example, we demonstrate a step-by-step update from version 5.6.0.0-000 to version 5.7.0.0-000. All versions from 5.6.0.0.x onwards follow the same procedure. This is our CentOS ESM 5.6.0.0-000 Server – this is a non-root installation ! The process and the install directory are owned by the esm-user.



After the transfer of the ESM binaries may have no execution rights

```
drwxr-xr-x. 2 esm-user esm-user      69 Jul 31 15:40 .
drwxr-xr-x. 8 esm-user esm-user     155 Jul 31 15:39 ..
-rw-r--r--. 1 esm-user esm-user 206294550 Jul 14 2025 ESM_Agent_Installer.bin
-rw-r--r--. 1 esm-user esm-user 257538924 Jul 14 2025 ESM_Server_Installer.bin
[esm-user@centosrv2 ESM-5.7.0.0-000]$
```

Chmod 770 *.bin solves the issue


Execute ESM Server 5.7.0.0-000 installer binary.

```
[esm-user@centosrv2 ESM-5.7.0.0-000]$ chmod 770 *.bin
[esm-user@centosrv2 ESM-5.7.0.0-000]$ ls -la
total 452964
drwxr-xr-x. 2 esm-user esm-user      69 Jul 31 15:40 .
drwxr-xr-x. 8 esm-user esm-user     155 Jul 31 15:39 ..
-rwxrwx---. 1 esm-user esm-user 206294550 Jul 14 2025 ESM_Agent_Installer.bin
-rwxrwx---. 1 esm-user esm-user 257538924 Jul 14 2025 ESM_Server_Installer.bin
[esm-user@centosrv2 ESM-5.7.0.0-000]$ ./ESM_Server_Installer.bin
```

Install Anywhere starts...



A previous version of ESM Server was found - Click on **Update** to continue



Accept Software License Agreement – continue with **Next**



Welcome to ESM Server – continue with **Next**.



Take over **installation folder** - continue with **Next**.



ESM Server settings – take over settings – **all ports should be higher than 1024**, because this is a non-root installation. Continue with **Next**.

The screenshot shows the 'ESM Server Installer' window with the 'ESM Server Settings' tab selected. The window has a title bar with 'ESM Server Installer' and a close button. The main content area is titled 'ESM Server Settings' and contains the following text: 'Please enter ESM Server hostname and port numbers. Adjust parameters according to the ESM Server environment. The port numbers must be within the range from 1 to 65535.' Below this text are several input fields: 'Hostname' (containing 'centosrv2'), 'IP Address' (containing '192.168.154.148'), 'MQTT Port' (containing '1883'), 'HTTP Port' (containing '8080'), 'HTTPS' (with 'Enabled' selected via a radio button), 'HTTPS Port' (containing '1443'), 'RMI Registry Port' (containing '1099'), and 'RMI Server Port' (empty). At the bottom left, there is an 'InstallAnywhere' logo and 'Cancel' and 'Help' buttons. At the bottom right, there are 'Previous' and 'Next' buttons.

Configuration Database Settings – take over – continue with **Next**.

The screenshot shows the 'ESM Server Installer' window with the 'Configuration Database Settings' tab selected. The window has a title bar with 'ESM Server Installer' and a close button. The main content area is titled 'Configuration Database Settings' and contains the following text: 'Optionally change the JDBC URL, driver class and credentials for the configuration DB.' followed by three lines of JDBC URL examples: '- jdbc:db2://[serverName][:portNumber][/instanceName][:property=value]', '- jdbc:sqlserver://[serverName][:portNumber][/instanceName][:property=value]', and '- com.ibm.db2.jcc.DB2Driver | com.microsoft.sqlserver.jdbc.SQLServerDriver'. Below this is a note: 'The driver for the default embedded H2 database is already included.' followed by 'Supported external databases: DB2, MSSQL' and a 'WARNING: Existing data will not be migrated to a different database!'. There are four input fields: 'JDBC URL' (containing 'onfiguration;AUTO_SERVER=TRUE;AUTO_RECONNECT=TRUE;MODE=LEGACY'), 'JDBC Driver Class Name' (containing 'org.h2.Driver'), 'Database User Name' (containing 'db'), and 'Database User Password' (containing a series of asterisks). At the bottom left, there is an 'InstallAnywhere' logo and 'Cancel' and 'Help' buttons. At the bottom right, there are 'Previous' and 'Next' buttons.

Monitoring Database Settings – take over – continue with Next.

The screenshot shows the 'Monitoring Database Settings' window of the ESM Server Installer. On the left is the IBM Enterprise Content Management System Monitor logo. The main area contains the following text:

Optionally change the JDBC URL, driver class and credentials for the monitoring DB.

- jdbc:db2://[serverName][:portNumber][/instanceName][:property=value]
- jdbc:sqlserver://[serverName][:portNumber][/instanceName][:property=value]
- com.ibm.db2.jcc.DB2Driver | com.microsoft.sqlserver.jdbc.SQLServerDriver

The driver for the default embedded H2 database is already included.

Supported external databases: DB2, MSSQL

WARNING: Existing data will not be migrated to a different database!

JDBC URL
./monitoring;AUTO_SERVER=TRUE;AUTO_RECONNECT=TRUE;MODE=LEGACY

JDBC Driver Class Name
org.h2.Driver

Database User Name
db

Database User Password

Make sure to copy the external driver to the karaf/deploy folder after installation!

At the bottom, there are buttons for 'Cancel', 'Help', 'Previous', and 'Next'. The 'InstallAnywhere' logo is also visible in the bottom left corner.

Start Up Settings – take over – continue with Next.

The screenshot shows the 'Start Up Settings' window of the ESM Server Installer. On the left is the IBM Enterprise Content Management System Monitor logo. The main area contains the following text:

Choose if you want ESM Server to start up after installation has finished and at each system start-up.

Note: you need Administrator privileges to make ESM Server do this!

Start up ESM Server after installation
☒ Yes ☐ No



Start up ESM Server at system start-up
☐ Yes ☒ No

At the bottom, there are buttons for 'Cancel', 'Help', 'Previous', and 'Next'. The 'InstallAnywhere' logo is also visible in the bottom left corner.


Installation **Summary** – click on **Install** to start Update.



Installing ESM Server



A warning notice comes up – confirm with OK.



Completion - Installation completed – click on **Done** to finish.



Rename or delete installer.properties – Example :

```
[esm-user@centosrv2 ESM-5.7.0.0-000]$ mv installer.properties server.installer.properties
[esm-user@centosrv2 ESM-5.7.0.0-000]$ ls -la
total 452968
drwxr-xr-x. 2 esm-user esm-user      104 Jul 31 16:06 .
drwxr-xr-x. 8 esm-user esm-user      155 Jul 31 15:39 ..
-rwxrwx---. 1 esm-user esm-user 206294550 Jul 14  2025 ESM_Agent_Installer.bin
-rwxrwx---. 1 esm-user esm-user 257538924 Jul 14  2025 ESM_Server_Installer.bin
-rw-rw-r--. 1 esm-user esm-user      1612 Jul 31 16:05 server.installer.properties
[esm-user@centosrv2 ESM-5.7.0.0-000]$
```

This is necessary if you intend to launch the agent installer as an executable from the same directory.


Update to 5.8.0.0-000 **UNIX** section

Update of UNIX 5.7.0.0-000 Server to 5.8.0.0-000


Execute ESM 5.8.0.0-000 Server installer binary.

```
drwxr-xr-x. 2 esm-user esm-user      69 Aug  4 16:44 .
drwxr-xr-x. 9 esm-user esm-user     178 Aug  4 16:44 ..
-rwxrwx---. 1 esm-user esm-user 224549321 Jul  3 14:26 ESM_Agent_Installer.bin
-rwxrwx---. 1 esm-user esm-user 280359695 Jul  3 14:26 ESM_Server_Installer.bin
[esm-user@centosrv2 ESM-5.8.0.0-000]$ ./ESM_Server_Installer.bin
```


InstallAnywhere starts.



A previous version of ESM Server was found – Click on **Update** to continue.




Accept **Software License Agreement** – continue with **Next**.



Welcome to ESM Server – continue with **Next**.



Take over **Installation Folder** – continue with **Next**.



ESM Server Settings – take over settings – continue with **Next**.

ESM Server Installer [Close]

ESM Server Settings

Please enter ESM Server hostname and port numbers.
Adjust parameters according to the ESM Server environment.
The port numbers must be within the range from 1 to 65535.

Hostname
centosrv2

IP Address
192.168.154.148

MQTT Port
1883

HTTP Port
8080

HTTPS
☒ Enabled ☐ Disabled


HTTPS Port
1443

RMI Registry Port
1099

RMI Server Port

InstallAnywhere
[Cancel] [Help] [Previous] [Next]

Configuration Database Settings – take over settings – continue with Next.



The screenshot shows the 'Configuration Database Settings' window of the ESM Server Installer. On the left is the IBM Enterprise Content Management System Monitor logo. The main area contains instructions for configuring the JDBC URL, driver class, and credentials for the configuration database. It lists supported external databases (DB2, MSSQL) and includes a warning that existing data will not be migrated. The JDBC URL is pre-filled with a default value. The driver class name is 'org.h2.Driver', the database user name is 'db', and the password is masked with asterisks. At the bottom, there are buttons for 'Cancel', 'Help', 'Previous', and 'Next'.

ESM Server Installer

Configuration Database Settings

Optionally change the JDBC URL, driver class and credentials for the configuration DB.

- jdbc:db2://[serverName[:portNumber]][/instanceName]][:property=value]
- jdbc:sqlserver://[serverName[:portNumber]][/instanceName]][:property=value]
- com.ibm.db2.jcc.DB2Driver | com.microsoft.sqlserver.jdbc.SQLServerDriver

The driver for the default embedded H2 database is already included.

Supported external databases: DB2, MSSQL

WARNING: Existing data will not be migrated to a different database!

JDBC URL
jdbc:db2://configuration;AUTO_SERVER=TRUE;AUTO_RECONNECT=TRUE;MODE=LEGACY

JDBC Driver Class Name
org.h2.Driver

Database User Name
db

Database User Password

Make sure to copy the external driver to the karaf/deploy folder after installation!

InstallAnywhere
Cancel Help Previous Next

Monitoring Database Settings - take over settings – continue with Next.



The screenshot shows the 'Monitoring Database Settings' window of the ESM Server Installer. It has the same layout as the Configuration Database Settings window, but the JDBC URL is pre-filled with a default value for monitoring. The driver class name is 'org.h2.Driver', the database user name is 'db', and the password is masked with asterisks. At the bottom, there are buttons for 'Cancel', 'Help', 'Previous', and 'Next'.

ESM Server Installer

Monitoring Database Settings

Optionally change the JDBC URL, driver class and credentials for the monitoring DB.

- jdbc:db2://[serverName[:portNumber]][/instanceName]][:property=value]
- jdbc:sqlserver://[serverName[:portNumber]][/instanceName]][:property=value]
- com.ibm.db2.jcc.DB2Driver | com.microsoft.sqlserver.jdbc.SQLServerDriver

The driver for the default embedded H2 database is already included.

Supported external databases: DB2, MSSQL

WARNING: Existing data will not be migrated to a different database!

JDBC URL
jdbc:db2://monitoring;AUTO_SERVER=TRUE;AUTO_RECONNECT=TRUE;MODE=LEGACY

JDBC Driver Class Name
org.h2.Driver

Database User Name
db

Database User Password

Make sure to copy the external driver to the karaf/deploy folder after installation!

InstallAnywhere
Cancel Help Previous Next


Start Up Settings – take over settings – continue with **Next**.




Installation Summary – click on **Install** to start Update.



Installation ESM Server




A warning notice comes up – confirm with click on OK.



Completion

Update of UNIX 5.6.0.0.x




ESM GUI Update of UNIX 5.6.0.0.x Agent to 5.8.0.0-000

Copy **ESM_AGENT_Installer.bin** to



/opt/IBM/ESM/Server/karaf/agent/installers/5.8.0.0-000/Linux-x86_64

```
drwxrwxr-x. 2 esm-user esm-user      37 Aug  4 17:17 .
drwxrwxr-x. 7 esm-user esm-user      88 Aug  4 16:52 ..
-rwxrwx---. 1 esm-user esm-user 224549321 Jul  3 14:26 ESM_Agent_Installer.bin
[esm-user@centosrv2 Linux-x86_64]$ pwd
/opt/IBM/ESM/Server/karaf/agent/installers/5.8.0.0-000/Linux-x86_64
[esm-user@centosrv2 Linux-x86_64]$
```


Start your browser and login to ESM web interface. Go to **Operating Dashboard**
Status of Agent is “outdated” – click on “Show Agents”



The Agent is still on version 5.6.0.0-000 – this information is shown if you click on the Agent label in the sidebar.




Go back to the Agent Overview and select **Update All**.




The advantage of this built-in function is that you do not need to run a separate update procedure for the agent binary, instead, you can handle everything conveniently via the ESM console.


Confirm the security prompt that appears by clicking OK.




Agent Status changes to “Updating”.



While the update procedure on the Agent starts, the Agent status is “Timed Out”.



It takes about 4 minutes for the Agent to come back online.



If you have an environment with perhaps 10, 20, or even more agents, this procedure offers a significant advantage.

Contact Information

If you have any questions, please contact us at ECM.SystemMonitor@cenit.com