

APPENDIX A: MSGID MESSAGE SET

Note: The “Use” column refers to whether the field is Mandatory or Optional. Also, the “Size/Type” column defines the data type and size. The allowable types are:

- Alphabetic (A): Upper case A through Z
- Numeric (N): 0 through 9
- Space (B): Space (ASCII 040 octal code)
- Special (S): Period (.), comma (,), colon (:), percent (%), pound (#), asterisk (*), hyphen (-), carriage return (CR), and line feed (LF).

For example, 2-6AN means the field can be from 2 to 6 alphanumeric characters, while 4N means the field must be a four digit number.

Field	Field Name	Use	Size/ Type	Description
0	Set Type	M	5AN	This field contains the literal string MSGID
1	Command	M	1-14ANBS	Enter the command originating the message, e.g., CTF 70, COMTHIRDFLT, KITTY HAWK
2	Message ID	M	3-9AN	Enter the message identifier: CIX
3	Message Serial Number	M	4-5N	Enter the message serial number (MSN) (0001-9999), e.g., 0001, 0445, 9999. The MSN will always consist of 4 digits; the fifth is reserved for future use.
4	Month	M	3A	Enter the first three letters of the month, e.g., JAN, FEB, MAR.
5	Operation/ Exercise Name	O	1-20ANBS	Enter the operation or exercise name, or a brief description of the mission, as directed, e.g., PACEX 89. <i>Note: This field is not currently implemented.</i>
6	Qualifier	O	3A	Enter the qualifier which further defines this message from the following list: AMP Amplifies a previously sent message. DEV Used to indicate a deviation from a previously sent message. PER Signifies a message that is standing order for a lengthy period. REQ Used to request a particular message, such as a tasking message, from another commander. <i>Note: This field is not currently implemented..</i>
7	Qualifier Serial Number	O	3N	Enter the serial number of the qualifier in Field 6. This number is used to uniquely identify qualifiers of a basic message, e.g., 001, 005, 999. <i>Note: This field is not currently implemented.</i>

THIS PAGE INTENTIONALLY LEFT BLANK

APPENDIX B: LCTC MESSAGE SET

Note: The “Use” column refers to whether the field is Mandatory or Optional. Also, the “Size/Type” column defines the data type and size. The allowable types are:

- Alphabetic (A): Upper case A through Z
- Numeric (N): 0 through 9
- Space (B): Space (ASCII 040 octal code)
- Special (S): Period (.), comma (,), colon (:), percent (%), pound (#), asterisk (*), hyphen (-), carriage return (CR), and line feed (LF).

For example, 2-6AN means the field can be from 2 to 6 alphanumeric characters, while 4N means the field must be a four digit number.

Field	Field Name	Use	Size/ Type	Description																
0	Set Type	M	4AN	This field contains the literal string LCTC																
1	Unique ID	O	12AN	A unique identifier for the track, which will be present on tracks received from the GCCS-COP, but should be left NULL on transmission to the GCCS-COP.																
2	Link Track Display Name	O	1-10ANBS	Enter the name to be displayed for the link track, e.g., F14, Yorktown.																
3	Link Type	M	3-4AN	Enter the link type using the list below, e.g., L11, L16. L11: Link-11 (TADIL A) L11B: Link-11B (TADIL B) L16: Link-16 (TADIL J) L4A: Link-4A (TADIL C) L22: Link-22 (NATO) <i>Note: Currently only L11 and L16 are implemented</i>																
4	Link Name	O	1-20ANBS	Enter the name to identify the link, e.g. COMAIRSOUTH STANDING. <i>Note: This field is not currently implemented.</i>																
5	Link Track Number	M	4-5AN	Enter the link track number for the track being reported, e.g., 1234, 01012.																
6	Link Report Type	M	3-10ANBS	Enter the link track report type, e.g. AIR, SUB.																
7	Exercise/ Simulation Indicators	M	2N	Enter the exercise indicator (0 or 1) immediately followed by the simulation indicator (0 or 1) as provided in the link report, e.g., 10, 11, 00. The exercise indicator is set to 1 for an exercise track and is 0 otherwise. The simulation indicator is set to 1 for a simulated track and is zero otherwise.																
8	Threat	M	3A	Enter the treat code from the list below, e.g. FRD, AFD, SUS. <table><tr><td><u>Code</u></td><td><u>Description</u></td></tr><tr><td>PND</td><td>Pending</td></tr><tr><td>UNK</td><td>Unknown (Evaluated)</td></tr><tr><td>FRD</td><td>Friend</td></tr><tr><td>AFD</td><td>Assumed Friend</td></tr><tr><td>NEU</td><td>Neutral</td></tr><tr><td>SUS</td><td>Suspect</td></tr><tr><td>HOS</td><td>Hostile</td></tr></table>	<u>Code</u>	<u>Description</u>	PND	Pending	UNK	Unknown (Evaluated)	FRD	Friend	AFD	Assumed Friend	NEU	Neutral	SUS	Suspect	HOS	Hostile
<u>Code</u>	<u>Description</u>																			
PND	Pending																			
UNK	Unknown (Evaluated)																			
FRD	Friend																			
AFD	Assumed Friend																			
NEU	Neutral																			
SUS	Suspect																			
HOS	Hostile																			

9	RU (Reporting Unit)	O	1-2N	Enter the RU (Reporting Unit), 4-5 octal digits, e.g. 1235, 4526, 11453.
10	Track Quality	O	3-5N	Enter the track quality reported on the Link, (0-15), e.g. 5, 8.
11	Mode 1 IFF	O	2N	Enter the Mode 1 IFF reported on the Link 01-73 octal (least significant digit cannot be greater than 3), e.g., 03 ,21, 42.
12	Mode 2 IFF	O	4N	Enter the Mode 2 IFF reported on the Link, 4 octal digits (0001-7777), e.g., 1235, 5647, 1115.
13	Mode 3 IFF	O	4N	Enter the Mode3 IFF reported on the Link, 4 octal digits (0001-7777), e.g., 1235, 5647, 1115.
14	Mode 4 IFF	O	1N	Enter the Mode 4 IFF reported on the Link, (0-3), e.g., 1,3.
15	Discrete Identifier (DI)	O	4N	Enter the DI for the track reported on the Link, 4 octal digits (0001-7777), e.g. 1234,5345.
16	CTSL	O	3-5N	Enter the combat system local track number, e.g., 547, 1223.
17	Misc. Status	O	3N	Enter, in sequence, the value of each of the following miscellaneous indicators reported on the link: Force Tell Indicator, Emergency Indicator, Special Processing Indicator, e.g., 100, 010, 011. Each indicator is reported as a value of 0 or 1. <i>Note: This field is not currently implemented.</i>

APPENDIX C: XPOS MESSAGE SET

Note: The “Use” column refers to whether the field is Mandatory or Optional. Also, the “Size/Type” column defines the data type and size. The allowable types are:

- Alphabetic (A): Upper case A through Z
- Numeric (N): 0 through 9
- Space (B): Space (ASCII 040 octal code)
- Special (S): Period (.), comma (,), colon (:), percent (%), pound (#), asterisk (*), hyphen (-), carriage return (CR), and line feed (LF).

For example, 2-6AN means the field can be from 2 to 6 alphanumeric characters, while 4N means the field must be a four digit number.

Field	Field Name	Use	Size/ Type	Description								
0	Set Type	M	4AN	This field contains the literal string XPOS								
1	Date-Time Group	M	8-12ANS	Enter the date-time group of the position report in days (01-31), hours (00-23), minutes (00-59), and optional seconds (00-59) and tenths of seconds followed by the timezone (Z), and checksum (0-9). E.g., 01211534.5Z2, 212359Z3.								
2	Month-Year	M	5AN	Enter the first three letters of the month and last two digits of the year of the position report. e.g., JUN95, JAN01.								
3	Position	M	7-27ANS	Enter the position of the report in its original format and precision if possible. Use one of the alternate field contents provided below. Enter the designated field descriptor followed by the data. Data can be expressed in: <table><tr><td><u>Coordinate System</u></td><td><u>Field Descriptor</u></td></tr><tr><td>Latitude/Longitude</td><td>LL:</td></tr><tr><td>UTM (Universal Transverse Mercator)</td><td></td></tr><tr><td>GEOREF (World Geographic Reference System)</td><td>GR:</td></tr></table> The precision reported in this field should reflect the original known precision. The only boundary or restriction placed on the reported precision of data in this field is the field length range. An optional floating decimal is allowed as appropriate, e.g., LL:304055.55N7-1304055.55E8, UT:45FDK0474, GR:DIQA. Note: Link tracks from the GCCS-COP will be transmitted in Lat/Long (LL:) format.	<u>Coordinate System</u>	<u>Field Descriptor</u>	Latitude/Longitude	LL:	UTM (Universal Transverse Mercator)		GEOREF (World Geographic Reference System)	GR:
<u>Coordinate System</u>	<u>Field Descriptor</u>											
Latitude/Longitude	LL:											
UTM (Universal Transverse Mercator)												
GEOREF (World Geographic Reference System)	GR:											
4	Sensor Code	O	2-6AN	Enter the sensor code of the detecting sensor, e.g., RADAR, VISUAL. See the <i>Operational Specification for Over-The-Horizon Targeting Gold, Rev. C, Ch. 1, Navy Center for Tactical Systems Interoperability, 01 August 1998</i> , Entry list 1104 (Sensor Codes) for more information.								
5	Bearing of Major Axis	O	4-6ANS	Enter the true bearing (000-360 or 000.0-360.0) of the semi-major axis followed by “T” (true), e.g., 5T, 135.5T. This field is mandatory if field 7 is used and is not equal to field 6.								
6	Length of Semi-Major Axis	O	2-7ANS	Enter the semi-major axis, in nautical miles (NM), kilometers (KM), meters (M), kiloyards (KY), yards (YD) or feet (FT). Use up to 5 characters with optional floating decimal (.0001-99999) followed by the appropriate alpha suffix as provided in parenthesis following each unit of measure, e.g. 12.5NM, .045YD, 345KM. Note: Link tracks								

				<i>from the GCCS-COP will be transmitted using Nautical Miles (NM).</i>
7	Length of Semi-Minor Axis	O	2-7ANS	Enter the semi-minor axis, in nautical miles (NM), kilometers (KM), meters (M), kiloyards (KY), yards (YD) or feet (FT). Use up to 5 characters with optional floating decimal (.0001-99999) followed by the appropriate alpha suffix as provided in parenthesis following each unit of measure, e.g. 12.5NM, .045YD, 345KM. <i>Note: Link tracks from the GCCS-COP will be transmitted using Nautical Miles (NM).</i>
8	Course	O	4-6ANS	Enter the true course (000-360 or 000.0-360.0) of the track followed by "T" (true). e.g. 5T, 10.3T.
9	Speed	O	4-8ANS	Enter the speed of the track in knots (KTS) or kilometers per hour (KPH). Use up to 5 characters with optional floating decimal (.0001-99999) followed by the appropriate alpha suffix as provided in parenthesis following each unit of measure. e.g., 15KTS, 2.34KPH. <i>Note: Link tracks from the GCCS-COP will be transmitted using Knots (KTS).</i>
10	Altitude	O	2-8ANS	Enter the altitude in hundreds of feet (ALT prefix), feet (FT suffix), kilometers (KM suffix), or meters (M suffix). Use up to 5 characters with optional floating decimal preceded or followed by appropriate prefix or suffix as provided in parenthesis following each unit of measure. e.g. ALT99 (for 9900 feet), 45.6M, 87FT. <i>Note: Link tracks from the GCCS-COP will be transmitted using feet (FT).</i>
11	Depth	O	2-7ANS	Enter the depth in feet (FT), meters (M), kilometers (KM), or fathoms (FH). Use up to 5 characters with optional floating decimal followed by the appropriate suffix as provided in parenthesis following each unit of measure. e.g. .45FN, 12KM, 23FH. <i>Note: Link tracks from the GCCS-COP will be transmitted using feet (FT).</i>
12	RDF-RF	O	3-10ANS	Enter the radio frequency of the intercept used to develop the XPOS in hertz (HZ), kilohertz (KHZ), or megahertz (MHZ). An optional floating decimal point is allowed, e.g., 5040.550HZ, 10050.5KHZ, 232.555MHZ.
13	Source Code	O	2-6AN	Enter the source which most recently originated, passed or amplified data on the position being reported, e.g., OSIS, SELOR. See the <i>Operational Specification for Over-The-Horizon Targeting Gold, Rev. C, Ch. 1, Navy Center for Tactical Systems Interoperability, 01 August 1998</i> , Entry list 1104 (Source Codes) for more information.

APPENDIX D: LEXT MESSAGE SET

Note: The “Use” column refers to whether the field is Mandatory or Optional. Also, the “Size/Type” column defines the data type and size. The allowable types are:

- Alphabetic (A): Upper case A through Z
- Numeric (N): 0 through 9
- Space (B): Space (ASCII 040 octal code)
- Special (S): Period (.), comma (,), colon (:), percent (%), pound (#), asterisk (*), hyphen (-), carriage return (CR), and line feed (LF).

For example, 2-6AN means the field can be from 2 to 6 alphanumeric characters, while 4N means the field must be a four digit number.

Field	Field Name	Use	Size/ Type	Description
0	Set Type	M	4AN	This field contains the literal string LEXT
1	FOTC Track Number	O	5N	Enter the track number used by correlation when operating in FOTC correlation mode.
2	CTSX Track Number	O	4N	Enter the unique local link track number, assigned when a track enters the link.
3	System Track Number	O	5N	Enter the System Track Number. This is also known as the Naval Tactical Display System (NTDS) number.
4	Tadil J Track Number	O	5N	Enter the Tadil J Track Number.
5	Parent	O	5N	Enter the local track number of a Platform track (if the Link track is associated with a Platform track).
6	AOU Type	O	10ANS	Enter the Area of Uncertainty Type. Default type is an ELLIPSE with a semi-major and semi-minor axes of 9NM each.
7	AOU Bearing	O	4ANS	Enter the AOU bearing for the track in degrees true.
8	XREF Code	O	4AN	Enter the cross-reference code for the Command originating the track report.
9	Transmit Enabled	O	1N	Enter the code indicating whether the track has been selected for transmission (enabled=1, disabled=0).
10	Received from Link	O	1N	Enter the code indicating whether the track has been received from the Link (enabled--from the Link=1, disabled--not from the Link=0).
11	Emergency Status	O	1N	Enter the code indicating whether the track has emergency status enabled (ON—overrides display filters; the track always displays and is transmitted at every opportunity=1. OFF—obeys display filters=0).
12	Force Tell Status	O	1N	Enter the code indicating whether the track has Force Tell Status enabled (ON—overrides display filters=1. OFF—obeys display filters=0).

THIS PAGE INTENTIONALLY LEFT BLANK

APPENDIX E: BMISL MESSAGE SET

Note: The “Use” column refers to whether the field is Mandatory or Optional. Also, the “Size/Type” column defines the data type and size. The allowable types are:

- Alphabetic (A): Upper case A through Z
- Numeric (N): 0 through 9
- Space (B): Space (ASCII 040 octal code)
- Special (S): Period (.), comma (,), colon (:), percent (%), pound (#), asterisk (*), hyphen (-), carriage return (CR), and line feed (LF).

For example, 2-6AN means the field can be from 2 to 6 alphanumeric characters, while 4N means the field must be a four digit number.

Field	Field Name	Use	Size/ Type	Description
0	Set Type	M	5AN	This field contains the literal string BMISL
1	Unique ID	M	12AN	A unique identifier for the track. <i>Note: This field is not currently implemented.</i>
2	Missile Type/ Generic Key	O	4-20ANBS	Enter the missile type/ generic key. For missile reports received via TDDS in the TACELINT format, report the AEN in this field. For missile reports received via TDDS in the SENSOREP format, report the MIDB equipment code/ generic key in this field. For TIBS inputs report the character string which was decoded from the TDIMF mnemonic. For reports received over TADIL J, report the Space Specific Type. This information is not contained in reports received over CSI at this time. Field format is broad to accommodate TIBS literal. <i>Note: This field is not currently implemented.</i>
3	Track Type	M	1N	Enter the track type code using the list below, e.g. 1, 2. <u>Code</u> <u>Description</u> 1 Live Tactical 2 Live Training 3 Simulated Training
4	Threat	M	3A	Enter the threat code from the list below, e.g. FRD, AFD, SUS. <u>Code</u> <u>Description</u> PND Pending UNK Unknown (Evaluated) FRD Friend AFD Assumed Friend NEU Neutral SUS Suspect HOS Hostile
5	Sensor	O	2-6AN	Enter the sensor code of the detecting sensor from Entry list 1104 (Sensor Codes), e.g., ANSPY1, DSPIR (Enter DSPIR for IR sensors on Defense Support Program (DSP) satellites. Enter ANSPY1 for radar detections off the AEGIS AN/SPY1 radar.) <i>Note: This field is not currently implemented.</i>
6	Source	O	2-6AN	Enter the source which most recently originated, passed or amplified data on the missile event being reported from Entry List 1136 (Source Codes), e.g. XO, CD. (For DSP detections enter the appropriate Correlation Index (CI). For

				AEGIS detections enter CD for AEGIS C&D/ACDS)														
7	Source Track Number	O	1-5AN	Enter the identifier or track number assigned by the source reported in field 6, e.g. 6032, 7132. For example, this could be the number assigned by the CI or the CTSX used by AEGIS. This field is optional and should be left blank if no identifier is assigned by the source. <i>Note: This field is not currently implemented.</i>														
8	Network/Format Received On	O	4-6AN	Enter the code from the list below which represents the network and/or format in which the data was received. <table><tr><td><u>Code</u></td><td><u>Description</u></td></tr><tr><td>TRAPTE</td><td>TRAP/TACELINT</td></tr><tr><td>TRAPS</td><td>TRAP/SENSOREP</td></tr><tr><td>TIBS</td><td>TIBS/TDIMF</td></tr><tr><td>CSIMT</td><td>CSI/MT messages</td></tr><tr><td>TADILJ</td><td>TADILJ</td></tr><tr><td>IBSNET</td><td>INTEGRATED BROADCAST SERVICE NETWORK</td></tr></table> <i>Note: This field is not currently implemented.</i>	<u>Code</u>	<u>Description</u>	TRAPTE	TRAP/TACELINT	TRAPS	TRAP/SENSOREP	TIBS	TIBS/TDIMF	CSIMT	CSI/MT messages	TADILJ	TADILJ	IBSNET	INTEGRATED BROADCAST SERVICE NETWORK
<u>Code</u>	<u>Description</u>																	
TRAPTE	TRAP/TACELINT																	
TRAPS	TRAP/SENSOREP																	
TIBS	TIBS/TDIMF																	
CSIMT	CSI/MT messages																	
TADILJ	TADILJ																	
IBSNET	INTEGRATED BROADCAST SERVICE NETWORK																	
9	Network ID/Track Number	O	4-12AN	Enter the identifier or track number assigned by the network reported in field 8, e.g. 00123, 07001. For example enter the JTN for missile data received over TADIL J. If IBS decides to provide an identifier it could be reported in this field. This field is optional and should be left blank if no identifier is assigned by the network. <i>Note: This field is not currently implemented.</i>														
10	MSC Status	O	1N	Enter the Multi-Source Correlator (MSC) status from the list below, e.g. 1,3. <table><tr><td><u>Code</u></td><td><u>Description</u></td></tr><tr><td>0</td><td>Unprocessed</td></tr><tr><td>1</td><td>Processed</td></tr><tr><td>2</td><td>Correlated</td></tr><tr><td>3</td><td>Redundant</td></tr><tr><td>4</td><td>Fused</td></tr></table> <i>Note: This field is not currently implemented. All BMISL messages transmitted will be for fused tracks.</i>	<u>Code</u>	<u>Description</u>	0	Unprocessed	1	Processed	2	Correlated	3	Redundant	4	Fused		
<u>Code</u>	<u>Description</u>																	
0	Unprocessed																	
1	Processed																	
2	Correlated																	
3	Redundant																	
4	Fused																	
11	Time of Report or Event Seq. Number	O	8-12ANS or 1-3N	Enter the date-time group of report if known; otherwise enter the internal system sequencing number associated with this event. When entering the date-time group of the report, enter days (01-31), hours (00-23), minutes (00-59), and optional seconds (00-59) and optional tenths of seconds followed by the timezone (Z), and checksum (0-9), e.g. 01120345Z6, 6. <i>Note: This field is not currently implemented.</i>														
12	Type of Event	M	1A	Enter the type of missile event from the list below, e.g. 1,3. <table><tr><td><u>Code</u></td><td><u>Description</u></td></tr><tr><td>1</td><td>Launch</td></tr><tr><td>2</td><td>Launch Update</td></tr><tr><td>3</td><td>Observation</td></tr><tr><td>4</td><td>Burn-out</td></tr><tr><td>5</td><td>Impact</td></tr></table>	<u>Code</u>	<u>Description</u>	1	Launch	2	Launch Update	3	Observation	4	Burn-out	5	Impact		
<u>Code</u>	<u>Description</u>																	
1	Launch																	
2	Launch Update																	
3	Observation																	
4	Burn-out																	
5	Impact																	

13	Event Date-Time Group	M	8-12ANS	Enter the date-time group of the missile event in days (01-31), hours (00-23), minutes (00-59), and optional seconds (00-59) and optional tenths of seconds followed by the timezone (Z), and checksum (0-9). e.g., 01211534.5Z2, 212359Z3.								
14	Event Month-Year	M	5AN	Enter the first three letters of the month and last two digits of the year of the missile event. e.g., JUN95, JAN01.								
15	Position	M	7-27ANS	Enter the position of the missile event in its original format and precision if possible. Use one of the alternate field contents provided below. Enter the designated field descriptor followed by the data. Data can be expressed in: <table><tr><td><u>Coordinate System</u></td><td><u>Field Descriptor</u></td></tr><tr><td>Latitude/Longitude</td><td>LL:</td></tr><tr><td>UTM (Universal Transverse Mercator)</td><td></td></tr><tr><td>GEOREF (World Geographic Reference System)</td><td>GR:</td></tr></table> The precision reported in this field should reflect the original known precision. The only boundary or restriction placed on the reported precision of data in this field is the field length range. An optional floating decimal is allowed as appropriate, e.g., LL:304055.55N7-1304055.55E8, UT:45FDK0474, GR:DIQA. <i>Note: Link tracks from the GCCS-COP will be transmitted in Lat/Long (LL:) format.</i>	<u>Coordinate System</u>	<u>Field Descriptor</u>	Latitude/Longitude	LL:	UTM (Universal Transverse Mercator)		GEOREF (World Geographic Reference System)	GR:
<u>Coordinate System</u>	<u>Field Descriptor</u>											
Latitude/Longitude	LL:											
UTM (Universal Transverse Mercator)												
GEOREF (World Geographic Reference System)	GR:											
16	Bearing of Major Axis	O	4-6ANS	Enter the true bearing (000-360 or 000.0-360.0) of the semi-major axis followed by “T” (true), e.g., 005T, 135.5T. This field is mandatory if field 18 is used and is not equal to field 17.								
17	Length of Semi-Major Axis	O	2-7ANS	Enter the semi-major axis, in nautical miles (NM), data miles (DM), kilometers (KM), meters (M), kiloyards (KY), yards (YD) or feet (FT). Use up to 5 characters with optional floating decimal (.0001-99999) followed by the appropriate alpha suffix as provided in parenthesis following each unit of measure, e.g. 12.5NM, .045YD, 345KM. <i>Note: Link tracks from the GCCS-COP will be transmitted using Nautical Miles (NM).</i>								
18	Length Of Semi-Minor Axis	O	2-7ANS	Enter the semi-minor axis, in nautical miles (NM), data miles (DM), kilometers (KM), meters (M), kiloyards (KY), yards (YD) or feet (FT). Use up to 5 characters with optional floating decimal (.0001-99999) followed by the appropriate alpha suffix as provided in parenthesis following each unit of measure, e.g. 12.5NM, .045YD, 345KM. <i>Note: Link tracks from the GCCS-COP will be transmitted using Nautical Miles (NM).</i>								
19	Course	O	4-6ANS	Enter the true course (000-360 or 000.0-360.0) of the missile followed by “T” (true). e.g. 005T, 010.3T.								
20	Speed	O	4-8ANS	Enter the speed of the missile in knots (KTS), kilometers per hour (KPH), or kilometers per second (KPS). Use up to 5 characters with optional floating decimal (.0001-99999) followed by the appropriate alpha suffix as provided in parenthesis following each unit of measure. e.g., 15KTS, 2.34KPH. <i>Note: Link tracks from the GCCS-COP will be</i>								

				<i>transmitted using knots (KTS).</i>
21	Angle of Elevation	O	1-4NS	Enter the angle of elevation (0-90 or 0.0-90.0) of the missile. e.g. 5, 010.3.
22	Altitude	O	2-8NS	Enter the altitude in hundreds of feet (ALT prefix), feet (FT suffix), kilometers (KM suffix), or meters (M suffix). Use up to 5 characters with optional floating decimal preceded or followed by appropriate prefix or suffix as provided in parenthesis following each unit of measure. e.g. ALT99 (for 9900 feet), 45.6M, 87FT. <i>Note: Link tracks from the GCCS-COP will be transmitted using feet (FT).</i>

APPENDIX F: CSITE MESSAGE SET

Note: The “Use” column refers to whether the field is Mandatory or Optional. Also, the “Size/Type” column defines the data type and size. The allowable types are:

- Alphabetic (A): Upper case A through Z
- Numeric (N): 0 through 9
- Space (B): Space (ASCII 040 octal code)
- Special (S): Period (.), comma (,), colon (:), percent (%), pound (#), asterisk (*), hyphen (-), carriage return (CR), and line feed (LF).

For example, 2-6AN means the field can be from 2 to 6 alphanumeric characters, while 4N means the field must be a four digit number.

Field	Field Name	Use	Size/ Type	Description
0	Set Type	M	4AN	This field contains the literal string CSITE
1	Site Name	M	1-30ANBS	Enter the name of the site (e.g., LANGLEY AFB). If unknown, then enter as “UNKNOWN.”
2	Flag	O	2A	Enter the flag of the site being reported from the OS-OTG Country Codes Entry List (e.g., US, UR).
3	Force Code	M	2N	Enter the force code (01-39) of the site being reported as specified in the OS-OTG (REV-C) Change 1.
4	UID	M	5-15AN	Enter a unique identifier (UID). Enter the identifier uniquely assigned by the system that introduces the site to the WAN.

THIS PAGE INTENTIONALLY LEFT BLANK

APPENDIX G: CSEA MESSAGE SET

Note: The “Use” column refers to whether the field is Mandatory or Optional. Also, the “Size/Type” column defines the data type and size. The allowable types are:

- Alphabetic (A): Upper case A through Z
- Numeric (N): 0 through 9
- Space (B): Space (ASCII 040 octal code)
- Special (S): Period (.), comma (,), colon (:), percent (%), pound (#), asterisk (*), hyphen (-), carriage return (CR), and line feed (LF).

For example, 2-6AN means the field can be from 2 to 6 alphanumeric characters, while 4N means the field must be a four digit number.

Field	Field Name	Use	Size/ Type	Description
0	Set Type	M	4AN	This field contains the literal string CSEA
1	MILSEA Code	O	4A	Enter the four-character alphanumeric code representing the military-assigned MILSTAMP identifier or other host nation identifier for a seaport.
2	GEOLOC Code	O	4A	Enter the four-character alphanumeric Geographic Location Code (e.g., FJXT, PYCT) as assigned by the Joint Chiefs of Staff (JCS).
3	Size	O	1N	Enter the code (as recorded in Table 7) indicating whether the harbor is large, medium, small, very small, or unknown.
4	Max Vessel	O	1N	Enter the code (as recorded in Table 8) indicating the maximum vessel size for the seaport.
5	Channel Depth	O	1-2N	Enter the code (as recorded in Table 9) indicating the channel depth range in feet of the seaport.
6	Pier Depth	O	1-2N	Enter the code (as recorded in Table 10) indicating the pier depth in feet at the pier or piers.
7	Tide	O	1-5N	Enter the mean tide range in feet.

THIS PAGE INTENTIONALLY LEFT BLANK

APPENDIX H: CIX XML MESSAGING

The following table maps each CIX message field, grouped by message set, to its corresponding XML tag.

Field	Field Name	XML Tag
LCTC MESSAGE SET		
0	Set Type	<LCTC>
1	Unique ID	<UID>
2	Link Track Display Name	<LTDNAME>
3	Link Type	<LTYPE>
4	Link Name	<NAME>
5	Link Track Number	<LTN>
6	Link Report Type	<LREPTYPE>
7	Exercise/ Simulation Indicators	<EXSIM>
8	Threat	<THREAT>
9	RU (Reporting Unit)	<RU>
10	Track Quality	<TQ>
11	Mode 1 IFF	<MODE1>
12	Mode 2 IFF	<MODE2>
13	Mode 3 IFF	<MODE3>
14	Mode 4 IFF	<MODE4>
15	Discrete Identifier (DI)	<DI>
16	CTSL	<CTSL>
17	Misc. Status	<STATUS>
XPOS MESSAGE SET		
0	Set Type	<XPOS>
1	Date-Time Group	<DTG>
2	Month-Year	<MOYR>
3	Position	<POSIT>
4	Sensor Code	<SENSOR>
5	Bearing of Major Axis	<BSMAJ>
6	Length of Semi-Major Axis	<LSMAJ>
7	Length of Semi-Minor Axis	<LSMIN>
8	Course	<CSE>
9	Speed	<SPD>
10	Altitude	<ALT>
11	Depth	<DPTH>
12	RDF-RF	<RDFRF>
13	Source Code	<SOURCE>

Field	Field Name	XML Tag
BMISL MESSAGE SET		
0	Set Type	<BMISL>
1	Unique ID	<UID>
2	Missile Type/ Generic Key	<MSLTP>
3	Track Type	<TTYP>
4	Threat	<THREAT>
5	Sensor	<SENSOR>
6	Source	<SOURCE>
7	Source Track Number	<SRCTN>
8	Network/ Format Received On	<NETFMT>
9	Network ID/Track Number	<NETID>
10	MSC Status	<MSC>
11	Time of Report or Event Seq. Number	<REPTME>
12	Type of Event	<REPTYP>
13	Event Date-Time Group	<EDTG>
14	Event Month- Year	<EMOYR>
15	Position	<POSIT>
16	Bearing of Major Axis	<BSMAJ>
17	Length of Semi-Major Axis	<LSMAJ>
18	Length Of Semi-Minor Axis	<LSMIN>
19	Course	<CSE>
20	Speed	<SPD>
21	Angle of Elevation	<AOE>
22	Altitude	<ALT>
LEXT MESSAGE SET		
0	Set Type	<LEXT>
1	Range	<RNG>
2	FOTC Track Number	<FTN>
3	CTSX Track Number	<CTSXTN>
4	System Track Number	<STN>
5	Tadil J Track Number	<TJTN>
6	Parent	<PRNT>
7	AOU Type	<AOUTYP>
8	AOU Bearing	<AOUBRG>
9	XREF Code	<XREF>
10	Transmit Enabled	<XMITENBL>
11	Received from Link	<RFL>
12	Emergency Status	<EMERSTAT>
13	Force Tell Status	<FTS>

APPENDIX I: WXOBS STRUCTURE

The structure of the USMTF WXOBS message as defined by the Joint User Handbook is provided here.

SEG OCC RPT SETID

C
EXER/_____/.....//
1 EXERCISE NICKNAME 2 EXERCISE MESSAGE ADDITIONAL IDENTIFIER
M [1-56 ANBS] 0 [1-16 ANBS]

Set 1 Purpose: THE EXER SET PROVIDES THE DESIGNATED
CODE NAME OR NICKNAME, IF THE MESSAGE

SUPPORTS AN EXERCISE.

Note: THE EXER SET IS PROHIBITED IF THE OPER SET IS USED.

0
OPER/_____/.....//
1 OPERATION CODEWORD 2 PLAN ORIGINATOR AND NUMBER 3 OPTION
NICKNAME 4 SECONDARY OPTION NICKNAME
M [1-32 ANBS] 0 [5-36 ANBS] 0 [1-23
ANBS] 0 [1-23 ANBS]

Set 2 Purpose: THE OPER SET PROVIDES THE DESIGNATED
CODE NAME OR NICKNAME, IF THE MESSAGE
SUPPORTS AN OPERATION.

Note: THE OPER SET IS PROHIBITED IF THE EXER SET IS USED.

M
MSGID/_____/.....//
1 MESSAGE TEXT FORMAT IDENTIFIER 2 ORIGINATOR 3 MESSAGE
SERIAL NUMBER 4 MONTH NAME 5 QUALIFIER 6 SERIAL NUMBER OF QUALIFIER
M [2-20 ANBS] M [1-30 ANBS] 0 [1-7 ANBS]
0 [3 A] 0 [3 A] 0 [1-3 N]

Set 3 Purpose: THE MSGID SET PROVIDES THE MESSAGE
IDENTIFICATION AND ORIGINATOR.

Note: FIELD 1 OF THE MSGID SET MUST EQUAL "WXOBS".

0 R
REF/_____/.....//
R.....//
1 SERIAL LETTER 2 TYPE OF REFERENCE 3 ORIGINATOR 4 DATE
AND/OR TIME OF REFERENCE 5 SERIAL NUMBER OF REFERENCE 6 SPECIAL NOTATION 7
SIC CODE OR FILING NUMBER
M [1 A] M [2/20 ANBS] M [1-30 ANBS] M
[6/15 AN] 0 [1-10 ANBS] 0 [5 A]
0 [1/10 ANBS]

Set 4 Purpose: THE REF SET PROVIDES BOTH USMTF AND
NON-USMTF REFERENCES.

C AMPN/_____/..
1 FREE TEXT

Set 5 Purpose: THE AMPN SET PROVIDES ADDITIONAL INFORMATION ON THE PRECEDING REF SET. ADDITIONALLY, THE AMPN SET PROVIDES IDENTIFYING INFORMATION FOR A NON-USMTF REFERENCE.

C NARR/_____/

1 FREE TEXT

M [1-U XEL]

```

M      WEATHLOC/_____/
|      1 LOCATION OF WEATHER
|      M [1/38 ANBS]

```

```

M      OBSTIME/_____/
          1 OBSERVATION DAY-TIME
          M [ 7 AN]

```

0			
CLDLYR/	/	R	/ R /
R	//		
1 MINIMUM CEILING		2 CLOUD COVER IN EIGHTHS	3 CLOUD TYPE
4 ALTITUDE IN HUNDREDS OF FEET			
M [1-3 N]		M [1 N]	M [2 A]

```

0      VISBY/_____/.....R.....//
      1 VISIBILITY      2 WEATHER, STATE OF
      M [2-7 ANS]      0 [3-10 ABS]

```

TEMP/_____/_____/_____//
//
 1 MAXIMUM TEMPERATURE, CELSIUS 2 MINIMUM TEMPERATURE, IN DEGREES
 CELSIUS 3 MINIMUM FREEZING LEVEL IN THOUSANDS OF FEET

|
 0 [4-7 AN] M [1-4 NS] M [1-4 NS]

|
 Set 11 Purpose: THE TEMP SET PROVIDES THE OBSERVED TEMPERATURE.

|
 0
 WIND/.....
//
 | 1 WIND DIRECTION IN DEGREES RELATIVE TO TRUE NORTH 2 VARIABLE
 WIND DIRECTION IN DEGREES 3 SPEED OF WIND IN KNOTS 4 PEAK GUSTS, IN KNOTS

| M [1-3 N] M [3 N] 0 [1-3 N] 0 [3 N]

|
 Set 12 Purpose: THE WIND SET PROVIDES THE OBSERVED WIND INFORMATION.

|
 0 ALTSTG/.....//
 | 1 ALTIMETER SETTING IN HUNDREDTHS OF INCHES OF MERCURY

|
 M [4 N]

|
 Set 13 Purpose: THE ALTSTG SET PROVIDES THE OBSERVED ATMOSPHERIC PRESSURE INFORMATION.

|
 0 SUPERAIR
 /ALT /TMPC /SPD /DEWTEMP
 /WINDIR
 //

|
 /.....//
//
 | 1 ALTITUDE 2 REPORTED TEMPERATURE, CELSIUS 3 DEWPOINT
 TEMPERATURE IN DEGREES CELSIUS 4 WIND DIRECTION IN DEGREES RELATIVE TO TRUE NORTH
 5 SPEED IN KNOTS, DECIMAL PT PERMITTED

| M [3-7 AN] M [1-4 NS] M [1-4 NS]
 0 [3 N] 0 [1-4 NS]

|
 Set 14 Purpose: THE SUPERAIR SET PROVIDES THE OBSERVED UPPER LEVEL WINDS.

|
 0
 DECL/.....R.
R.....//
 | 1 SOURCE FOR CLASSIFICATION 2 REASON FOR CLASSIFICATION 3
 DOWNGRADE INSTRUCTIONS/DATE 4 DOWNGRADING OR DECLASSIFICATION EXEMPTION CODE

|
 [1/38 ANBS] M [1/55 ANBS] C [3 AN] C
 C [2 AN]

|
 Set 15 Purpose: THE DECL SET PROVIDES DECLASSIFICATION OR DOWNGRADING INSTRUCTIONS, IF THE MESSAGE IS CLASSIFIED.

THIS PAGE INTENTIONALLY LEFT BLANK