

config firewall ippool

Configure IPv4 IP pools.

```
config firewall ippool
  Description: Configure IPv4 IP pools.
  edit <name>
    set add-nat64-route [disable|enable]
    set arp-intf {string}
    set arp-reply [disable|enable]
    set associated-interface {string}
    set block-size {integer}
    set cgn-block-size {integer}
    set cgn-client-endip {var-string}
    set cgn-client-ipv6shift {integer}
    set cgn-client-startip {var-string}
    set cgn-fixedalloc [disable|enable]
    set cgn-overload [disable|enable]
    set cgn-port-end {integer}
    set cgn-port-start {integer}
    set cgn-spa [disable|enable]
    set comments {var-string}
    set endip {ipv4-address-any}
    set endpoint {integer}
    set exclude-ip <ip1>, <ip2>, ...
    set nat64 [disable|enable]
    set num-blocks-per-user {integer}
    set pba-interim-log {integer}
    set pba-timeout {integer}
    set permit-any-host [disable|enable]
    set port-per-user {integer}
    set source-endip {ipv4-address-any}
    set source-startip {ipv4-address-any}
    set startip {ipv4-address-any}
    set startport {integer}
    set subnet-broadcast-in-ippool [disable|enable]
    set type [overload|one-to-one|...]
    set utilization-alarm-clear {integer}
    set utilization-alarm-raise {integer}
  next
end
```

config firewall ippool

Parameter	Description	Type	Size	Default						
add-nat64-route	Enable/disable adding NAT64 route.	option	-	enable						
	<table><tr><th>Option</th><th>Description</th></tr><tr><td><i>disable</i></td><td>Disable adding NAT64 route.</td></tr><tr><td><i>enable</i></td><td>Enable adding NAT64 route.</td></tr></table>				Option	Description	<i>disable</i>	Disable adding NAT64 route.	<i>enable</i>	Enable adding NAT64 route.
Option	Description									
<i>disable</i>	Disable adding NAT64 route.									
<i>enable</i>	Enable adding NAT64 route.									

Parameter	Description	Type	Size	Default
arp-intf	Select an interface from available options that will reply to ARP requests. (If blank, any is selected).	string	Maximum length: 15	
arp-reply	Enable/disable replying to ARP requests when an IP Pool is added to a policy.	option	-	enable
	Option	Description		
	disable	Disable ARP reply.		
	enable	Enable ARP reply.		
associated-interface	Associated interface name.	string	Maximum length: 15	
block-size	Number of addresses in a block.	integer	Minimum value: 64 Maximum value: 4096	128
cgn-block-size *	Number of ports in a block.	integer	Minimum value: 64 Maximum value: 4096	128
cgn-client-endip *	Final client IPv4 address (inclusive) (format xxx.xxx.xxx.xxx, Default: 0.0.0.0).	var-string	Maximum length: 255	
cgn-client-ipv6shift *	IPv6 shift for fixed-allocation.	integer	Minimum value: 0 Maximum value: 127	0
cgn-client-startip *	First client IPv4 address (inclusive) (format xxx.xxx.xxx.xxx, Default: 0.0.0.0).	var-string	Maximum length: 255	
cgn-fixedalloc *	Enable/disable fixed-allocation mode.	option	-	disable
	Option	Description		
	disable	Disable fixed-allocation mode.		
	enable	Enable fixed-allocation mode.		
cgn-overload *	Enable/disable overload mode.	option	-	disable
	Option	Description		
	disable	Disable overload mode.		
	enable	Enable overload mode.		

Parameter	Description	Type	Size	Default						
cg-n-port-end *	Ending public port can be allocated.	integer	Minimum value: 1024 Maximum value: 65535	65530						
cg-n-port-start *	Starting public port can be allocated.	integer	Minimum value: 1024 Maximum value: 65535	5117						
cg-n-spa *	Enable/disable single port allocation mode.	option	-	disable						
	<table><tr><th>Option</th><th>Description</th></tr><tr><td>disable</td><td>Disable SPA mode.</td></tr><tr><td>enable</td><td>Enable SPA mode.</td></tr></table>	Option	Description	disable	Disable SPA mode.	enable	Enable SPA mode.			
Option	Description									
disable	Disable SPA mode.									
enable	Enable SPA mode.									
comments	Comment.	var-string	Maximum length: 255							
endip	Final IPv4 address (inclusive) in the range for the address pool (format xxx.xxx.xxx.xxx, Default: 0.0.0.0).	ipv4-address-any	Not Specified	0.0.0.0						
endport	Final port number (inclusive) in the range for the address pool (Default: 65533).	integer	Minimum value: 5117 Maximum value: 65533	65533						
exclude-ip <ip> *	Exclude IPs x.x.x.x. Exclude IPs (xxx.xxx.xxx.xxx)	string	Maximum length: 79							
name	IP pool name.	string	Maximum length: 79							
nat64	Enable/disable NAT64.	option	-	disable						
	<table><tr><th>Option</th><th>Description</th></tr><tr><td>disable</td><td>Disable DNAT64.</td></tr><tr><td>enable</td><td>Enable DNAT64.</td></tr></table>	Option	Description	disable	Disable DNAT64.	enable	Enable DNAT64.			
Option	Description									
disable	Disable DNAT64.									
enable	Enable DNAT64.									
num-blocks-per-user	Number of addresses blocks that can be used by a user.	integer	Minimum value: 1 Maximum value: 128	8						

Parameter	Description	Type	Size	Default
pba-interim-log	Port block allocation interim logging interval.	integer	Minimum value: 600 Maximum value: 86400	0
pba-timeout	Port block allocation timeout (seconds).	integer	Minimum value: 3 Maximum value: 86400	30
permit-any-host	Enable/disable full cone NAT.	option	-	disable
	Option	Description		
	disable	Disable full cone NAT.		
	enable	Enable full cone NAT.		
port-per-user	Number of port for each user.	integer	Minimum value: 32 Maximum value: 60417	0
source-endip	Final IPv4 address (inclusive) in the range of the source addresses to be translated (format xxx.xxx.xxx.xxx, Default: 0.0.0.0).	ipv4-address-any	Not Specified	0.0.0.0
source-startip	First IPv4 address.	ipv4-address-any	Not Specified	0.0.0.0
startip	First IPv4 address (inclusive) in the range for the address pool (format xxx.xxx.xxx.xxx, Default: 0.0.0.0).	ipv4-address-any	Not Specified	0.0.0.0
startport	First port number (inclusive) in the range for the address pool (Default: 5117).	integer	Minimum value: 5117 Maximum value: 65533	5117
subnet-broadcast-in-ippool	Enable/disable inclusion of the subnetwork address and broadcast IP address in the NAT64 IP pool.	option	-	enable

Parameter	Description	Type	Size	Default										
	<table><tr><th>Option</th><th>Description</th></tr><tr><td><i>disable</i></td><td>Do not include the subnetwork address and broadcast IP address in the NAT64 IP pool.</td></tr><tr><td><i>enable</i></td><td>Include the subnetwork address and broadcast IP address in the NAT64 IP pool.</td></tr></table>	Option	Description	<i>disable</i>	Do not include the subnetwork address and broadcast IP address in the NAT64 IP pool.	<i>enable</i>	Include the subnetwork address and broadcast IP address in the NAT64 IP pool.							
	Option	Description												
	<i>disable</i>	Do not include the subnetwork address and broadcast IP address in the NAT64 IP pool.												
<i>enable</i>	Include the subnetwork address and broadcast IP address in the NAT64 IP pool.													
type	IP pool type: overload, one-to-one, fixed-port-range, port-block-allocation, cgn-resource-allocation (hyperscale vdom only)	option	-	overload										
	<table><tr><th>Option</th><th>Description</th></tr><tr><td><i>overload</i></td><td>IP addresses in the IP pool can be shared by clients.</td></tr><tr><td><i>one-to-one</i></td><td>One to one mapping.</td></tr><tr><td><i>fixed-port-range</i></td><td>Fixed port range.</td></tr><tr><td><i>port-block-allocation</i></td><td>Port block allocation.</td></tr></table>	Option	Description	<i>overload</i>	IP addresses in the IP pool can be shared by clients.	<i>one-to-one</i>	One to one mapping.	<i>fixed-port-range</i>	Fixed port range.	<i>port-block-allocation</i>	Port block allocation.			
	Option	Description												
	<i>overload</i>	IP addresses in the IP pool can be shared by clients.												
	<i>one-to-one</i>	One to one mapping.												
	<i>fixed-port-range</i>	Fixed port range.												
<i>port-block-allocation</i>	Port block allocation.													
utilization-alarm-clear *	Pool utilization alarm clear threshold.	integer	Minimum value: 40 Maximum value: 100	80										
utilization-alarm-raise *	Pool utilization alarm raise threshold.	integer	Minimum value: 50 Maximum value: 100	100										

* This parameter may not exist in some models.

config firewall ippool6

Configure IPv6 IP pools.

```
config firewall ippool6
  Description: Configure IPv6 IP pools.
  edit <name>
    set add-nat46-route [disable|enable]
    set comments {var-string}
    set endip {ipv6-address}
    set nat46 [disable|enable]
    set startip {ipv6-address}
  next
end
```