

Parameter	Description	Type	Size	Default
email	Account email.	string	Maximum length: 255	
id	Account id.	string	Maximum length: 255	
privatekey	Account Private Key.	string	Maximum length: 8191	
status	Account status.	string	Maximum length: 127	
url	Account url.	string	Maximum length: 511	

config system admin

Configure admin users.

```
config system admin
  Description: Configure admin users.
  edit <name>
    set accprofile {string}
    set accprofile-override [enable|disable]
    set allow-remove-admin-session [enable|disable]
    set comments {var-string}
    set email-to {string}
    set force-password-change [enable|disable]
    set fortitoken {string}
    set guest-auth [disable|enable]
    set guest-lang {string}
    set guest-usergroups <name1>, <name2>, ...
    set ip6-trusthost1 {ipv6-prefix}
    set ip6-trusthost10 {ipv6-prefix}
    set ip6-trusthost2 {ipv6-prefix}
    set ip6-trusthost3 {ipv6-prefix}
    set ip6-trusthost4 {ipv6-prefix}
    set ip6-trusthost5 {ipv6-prefix}
    set ip6-trusthost6 {ipv6-prefix}
    set ip6-trusthost7 {ipv6-prefix}
    set ip6-trusthost8 {ipv6-prefix}
    set ip6-trusthost9 {ipv6-prefix}
    set password {password-2}
    set password-expire {user}
    set peer-auth [enable|disable]
    set peer-group {string}
    set remote-auth [enable|disable]
    set remote-group {string}
    set schedule {string}
    set sms-custom-server {string}
    set sms-phone {string}
    set sms-server [fortiguard|custom]
    set ssh-certificate {string}
```

```

set ssh-public-key1 {user}
set ssh-public-key2 {user}
set ssh-public-key3 {user}
set trusthost1 {ipv4-classnet}
set trusthost10 {ipv4-classnet}
set trusthost2 {ipv4-classnet}
set trusthost3 {ipv4-classnet}
set trusthost4 {ipv4-classnet}
set trusthost5 {ipv4-classnet}
set trusthost6 {ipv4-classnet}
set trusthost7 {ipv4-classnet}
set trusthost8 {ipv4-classnet}
set trusthost9 {ipv4-classnet}
set two-factor [disable|fortitoken|...]
set two-factor-authentication [fortitoken|email|...]
set two-factor-notification [email|sms]
set vdom <name1>, <name2>, ...
set vdom-override [enable|disable]
set wildcard [enable|disable]
next
end

```

config system admin

Parameter	Description	Type	Size	Default						
accprofile	Access profile for this administrator. Access profiles control administrator access to FortiGate features.	string	Maximum length: 35							
accprofile-override	Enable to use the name of an access profile provided by the remote authentication server to control the FortiGate features that this administrator can access.	option	-	disable						
	<table><tr><th>Option</th><th>Description</th></tr><tr><td>enable</td><td>Enable access profile override.</td></tr><tr><td>disable</td><td>Disable access profile override.</td></tr></table>				Option	Description	enable	Enable access profile override.	disable	Disable access profile override.
Option	Description									
enable	Enable access profile override.									
disable	Disable access profile override.									
allow-remove-admin-session	Enable/disable allow admin session to be removed by privileged admin users.	option	-	enable						
	<table><tr><th>Option</th><th>Description</th></tr><tr><td>enable</td><td>Enable allow-remove option.</td></tr><tr><td>disable</td><td>Disable allow-remove option.</td></tr></table>				Option	Description	enable	Enable allow-remove option.	disable	Disable allow-remove option.
Option	Description									
enable	Enable allow-remove option.									
disable	Disable allow-remove option.									
comments	Comment.	var-string	Maximum length: 255							
email-to	This administrator's email address.	string	Maximum length: 63							

Parameter	Description	Type	Size	Default
force-password-change	Enable/disable force password change on next login.	option	-	disable
	Option	Description		
	enable	Enable force password change on next login.		
	disable	Disable force password change on next login.		
fortitoken	This administrator's FortiToken serial number.	string	Maximum length: 16	
guest-auth	Enable/disable guest authentication.	option	-	disable
	Option	Description		
	disable	Disable guest authentication.		
	enable	Enable guest authentication.		
guest-lang	Guest management portal language.	string	Maximum length: 35	
guest-usergroups <name>	Select guest user groups. Select guest user groups.	string	Maximum length: 79	
ip6-trusthost1	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0
ip6-trusthost10	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0
ip6-trusthost2	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0
ip6-trusthost3	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0
ip6-trusthost4	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0
ip6-trusthost5	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0

Parameter	Description	Type	Size	Default						
ip6-trusthost6	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0						
ip6-trusthost7	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0						
ip6-trusthost8	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0						
ip6-trusthost9	Any IPv6 address from which the administrator can connect to the FortiGate unit. Default allows access from any IPv6 address.	ipv6-prefix	Not Specified	::/0						
name	User name.	string	Maximum length: 64							
password	Admin user password.	password-2	Not Specified							
password-expire	Password expire time.	user	Not Specified							
peer-auth	Set to enable peer certificate authentication (for HTTPS admin access).	option	-	disable						
	<table><tr><th>Option</th><th>Description</th></tr><tr><td><i>enable</i></td><td>Enable peer.</td></tr><tr><td><i>disable</i></td><td>Disable peer.</td></tr></table>				Option	Description	<i>enable</i>	Enable peer.	<i>disable</i>	Disable peer.
Option	Description									
<i>enable</i>	Enable peer.									
<i>disable</i>	Disable peer.									
peer-group	Name of peer group defined under config user group which has PKI members. Used for peer certificate authentication (for HTTPS admin access).	string	Maximum length: 35							
remote-auth	Enable/disable authentication using a remote RADIUS, LDAP, or TACACS+ server.	option	-	disable						
	<table><tr><th>Option</th><th>Description</th></tr><tr><td><i>enable</i></td><td>Enable remote authentication.</td></tr><tr><td><i>disable</i></td><td>Disable remote authentication.</td></tr></table>				Option	Description	<i>enable</i>	Enable remote authentication.	<i>disable</i>	Disable remote authentication.
Option	Description									
<i>enable</i>	Enable remote authentication.									
<i>disable</i>	Disable remote authentication.									
remote-group	User group name used for remote auth.	string	Maximum length: 35							
schedule	Firewall schedule used to restrict when the administrator can log in. No schedule means no restrictions.	string	Maximum length: 35							

Parameter	Description	Type	Size	Default						
sms-custom-server	Custom SMS server to send SMS messages to.	string	Maximum length: 35							
sms-phone	Phone number on which the administrator receives SMS messages.	string	Maximum length: 15							
sms-server	Send SMS messages using the FortiGuard SMS server or a custom server.	option	-	fortiguard						
	<table><tr><th>Option</th><th>Description</th></tr><tr><td>fortiguard</td><td>Send SMS by FortiGuard.</td></tr><tr><td>custom</td><td>Send SMS by custom server.</td></tr></table>				Option	Description	fortiguard	Send SMS by FortiGuard.	custom	Send SMS by custom server.
Option	Description									
fortiguard	Send SMS by FortiGuard.									
custom	Send SMS by custom server.									
ssh-certificate	Select the certificate to be used by the FortiGate for authentication with an SSH client.	string	Maximum length: 35							
ssh-public-key1	Public key of an SSH client. The client is authenticated without being asked for credentials. Create the public-private key pair in the SSH client application.	user	Not Specified							
ssh-public-key2	Public key of an SSH client. The client is authenticated without being asked for credentials. Create the public-private key pair in the SSH client application.	user	Not Specified							
ssh-public-key3	Public key of an SSH client. The client is authenticated without being asked for credentials. Create the public-private key pair in the SSH client application.	user	Not Specified							
trusthost1	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0						
trusthost10	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0						
trusthost2	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0						
trusthost3	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0						

Parameter	Description	Type	Size	Default												
trusthost4	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0												
trusthost5	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0												
trusthost6	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0												
trusthost7	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0												
trusthost8	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0												
trusthost9	Any IPv4 address or subnet address and netmask from which the administrator can connect to the FortiGate unit. Default allows access from any IPv4 address.	ipv4-classnet	Not Specified	0.0.0.0 0.0.0.0												
two-factor	Enable/disable two-factor authentication.	option	-	disable												
	<table><tr><th>Option</th><th>Description</th></tr><tr><td>disable</td><td>Disable two-factor authentication.</td></tr><tr><td>fortitoken</td><td>Use FortiToken or FortiToken mobile two-factor authentication.</td></tr><tr><td>fortitoken-cloud</td><td>FortiToken Cloud Service.</td></tr><tr><td>email</td><td>Send a two-factor authentication code to the configured email-to email address.</td></tr><tr><td>sms</td><td>Send a two-factor authentication code to the configured sms-server and sms-phone.</td></tr></table>				Option	Description	disable	Disable two-factor authentication.	fortitoken	Use FortiToken or FortiToken mobile two-factor authentication.	fortitoken-cloud	FortiToken Cloud Service.	email	Send a two-factor authentication code to the configured email-to email address.	sms	Send a two-factor authentication code to the configured sms-server and sms-phone.
Option	Description															
disable	Disable two-factor authentication.															
fortitoken	Use FortiToken or FortiToken mobile two-factor authentication.															
fortitoken-cloud	FortiToken Cloud Service.															
email	Send a two-factor authentication code to the configured email-to email address.															
sms	Send a two-factor authentication code to the configured sms-server and sms-phone.															
two-factor-authentication	Authentication method by FortiToken Cloud.	option	-													

Parameter	Description	Type	Size	Default
	Option	Description		
	<i>fortitoken</i>	FortiToken authentication.		
	<i>email</i>	Email one time password.		
	<i>sms</i>	SMS one time password.		
two-factor-notification	Notification method for user activation by FortiToken Cloud.	option	-	
	Option	Description		
	<i>email</i>	Email notification for activation code.		
	<i>sms</i>	SMS notification for activation code.		
vdom <name>	Virtual domain(s) that the administrator can access. Virtual domain name.	string	Maximum length: 79	
vdom-override	Enable to use the names of VDOMs provided by the remote authentication server to control the VDOMs that this administrator can access.	option	-	disable
	Option	Description		
	<i>enable</i>	Enable VDOM override.		
	<i>disable</i>	Disable VDOM override.		
wildcard	Enable/disable wildcard RADIUS authentication.	option	-	disable
	Option	Description		
	<i>enable</i>	Enable username wildcard.		
	<i>disable</i>	Disable username wildcard.		

config system affinity-interrupt



This command is available for model(s): FortiGate 100F, FortiGate 101F, FortiGate 120G, FortiGate 121G, FortiGate 200F, FortiGate 201F, FortiGate 4200F, FortiGate 4201F, FortiGate 4400F, FortiGate 4401F, FortiGate 80F DSL, FortiGate 90G, FortiGate 91G, FortiGate-VM for Aliyun, FortiGate-VM for AWS, FortiGate-VM for Azure, FortiGate-VM for GCP, FortiGate-VM for OPC, FortiGate-VM64, FortiWiFi 80F 2R 3G4G DSL, FortiWiFi 81F 2R 3G4G DSL.

It is not available for: FortiGate 1000D, FortiGate 1000F, FortiGate 1001F, FortiGate 1100E, FortiGate 1101E, FortiGate 140E-POE, FortiGate 140E, FortiGate 1800F, FortiGate 1801F, FortiGate 2000E, FortiGate 200E, FortiGate 201E, FortiGate 2200E, FortiGate 2201E, FortiGate 2500E, FortiGate 2600F, FortiGate 2601F, FortiGate 3000D, FortiGate 3000F, FortiGate 3001F, FortiGate 300E, FortiGate 301E, FortiGate 3100D, FortiGate 3200D, FortiGate 3200F, FortiGate 3201F, FortiGate 3300E, FortiGate 3301E, FortiGate 3400E, FortiGate 3401E, FortiGate 3500F, FortiGate 3501F, FortiGate 3600E, FortiGate 3601E, FortiGate 3700D, FortiGate 3700F, FortiGate 3701F, FortiGate 3960E, FortiGate 3980E, FortiGate 400E Bypass, FortiGate 400E, FortiGate 400F, FortiGate 401E, FortiGate 401F, FortiGate 5001E1, FortiGate 5001E, FortiGate 500E, FortiGate 501E, FortiGate 600E, FortiGate 600F, FortiGate 601E, FortiGate 601F, FortiGate 60E DSLJ, FortiGate 60E DSL, FortiGate 60E-POE, FortiGate 60E, FortiGate 61E, FortiGate 800D, FortiGate 80E-POE, FortiGate 80E, FortiGate 81E-POE, FortiGate 81E, FortiGate 900D, FortiGate 900G, FortiGate 901G, FortiGate 90E, FortiGate 91E, FortiGateRugged 70F, FortiWiFi 60E DSLJ, FortiWiFi 60E DSL, FortiWiFi 60E, FortiWiFi 61E.

Configure interrupt affinity.

```
config system affinity-interrupt
  Description: Configure interrupt affinity.
  edit <id>
    set affinity-cpumask {string}
    set default-affinity-cpumask {string}
    set interrupt {string}
  next
end
```

config system affinity-interrupt

Parameter	Description	Type	Size	Default
affinity-cpumask	Affinity setting (64-bit hexadecimal value in the format of 0xxxxxxxxxxxxxxxxx).	string	Maximum length: 127	
default-affinity-cpumask	Default affinity setting (64-bit hexadecimal value in the format of 0xxxxxxxxxxxxxxxxx). Read-only.	string	Maximum length: 127	