Lab 7.1 Dynamic DNS IN715 Networks Administration

September 1, 2015

Introduction

DHCP presents a problem for DNS services, since we can't always be sure what IP address a particular machine will be assigned. For servers we can get around this using static IP configuration or reserved addresses in DHCP, but once we have a large number of machines involved this process becomes more difficult. Dynamic DNS updating can solve this problem.

With dynamic DNS we configure our DNS server to receive zone updates from other machines. This opens up a significant security risk, since a malicious attacker could "update" the address of a critical server. We reduce the risk by using a secuity mechanism called *TSIG* to allow only our DHCP servers to submit DDNS updates.

You must have properly functioning DHCP and DNS servers running before attempting this lab.

1 Generate the TSIG key

We will use TSIG to authenticate DNS updates from our DHCP server. TSIG uses a symmetric encryption key that we generate with the command

```
dnssec-keygen -a HMAC-MD5 -b 128 -r /dev/urandom -n USER DDNS_UPDATE
```

This will produce two files: Kddns_update.*.key and and Kddns_update.*.private. Copy the key from the private file. Look for a line like

```
Key: 8aEQAk+HBZVFUaZ+Bk.yQ==
Everything after the Key: is the key value.
Create a file called ddns.key containing the following:
   key DDNS_UPDATE {
      algorithm HMAC-MD5.SIG-ALG.REG.INT;
      secret "<your key value>";
   };
Set the permissions on the new file
chmod 640 ddns.key
and then copy the file to the appropriate locations and set the ownership appropriately
   cp ddns.key /var/named/etc/
   chown root:named /var/named/etc/ddns.key
   cp ddns.key /etc/
```

2 Modify DNS configuration

The DNS configuration is very simple. In the zone sections of /var/named/etc/named.conf, add the following line:

```
allow-update { key DDNS_UPDATE; };
```

This should go in your foo.org.nz zone and in the reverse zones you have set up on your network.

You will also need to include the key file in your config by adding the line

```
include "etc/ddns.key";
```

to your named.conf file, right above the zone sections.

3 Modify DHCP configuration

Add the following global options to your /etc/dhcpd.conf file:

```
ddns-updates on;
ddns-update-style interim;
include "/etc/ddns.key";
```

Finally, create blocks for the zones for which you will perform dynamic updates like the following:

```
zone foo.org.nz. {
  primary 127.0.0.1;
  key DDNS_UPDATE;
}
zone 5.16.172.in-addr.arpa. {
  primary 127.0.0.1;
  key DDNS_UPDATE;
}
```

Note that, since our DHCP server and our DNS server run on the same machine, we can use the loopback addresses for our primary DNS server. If this were not the case, we would need to supply the DNS server's address.

4 Test your setup

Once your configuration is complete, restart your DNS and DHCP servers. Then obtain a DHCP lease for one or more of your client machines, then use dig to lookup the corresponding A record. The name in the A record should match the hostname of the client machine.