



GigaCloud

PowerShell Module Guide

July 2019

Table of Contents

<i>Introduction.....</i>	<i>2</i>
<i>Silent Installation/Uninstall</i>	<i>3</i>
<i>GTEP Module.....</i>	<i>4</i>

Introduction

GigaCloud (GTEP) can now be configured using PowerShell using our custom **GTEP** module. In addition, GTEP now supports silent installation and removal from PowerShell.

The GigaCloud PowerShell module allows you to:

- 🌀 Manage and edit many GTEP configuration settings from PowerShell.
- 🌀 Allows remote PowerShell Administration of GTEP which is especially valuable in clustered configurations.
- 🌀 Seamlessly upgrade GTEP remotely via uninstall and install PowerShell scripts (without the GTEP Module.)

Silent Installation/Uninstall

To install GigaCloud silently open PowerShell and modify the following script for your environment:

```
Start-Process msixexec.exe -ArgumentList "/i ""[File Path]\GTEP Installer x64.9.1.43.116040.msi""  
/!*v bar.log /q RMSACCOUNTNAME=[AD RMS Username] RMSPASSWORD=[AD RMS User  
Password] RMSUSERDOMAIN=[Domain Name] RMSUSERNAME=[Domain name\Username]  
GTEPADMINGROUP=[Admin Group, example: GTEnterpriseAdmins]" -wait
```

Example:

```
Start-Process msixexec.exe -ArgumentList "/i ""C:\Users\administrator\Desktop\GTEP Installer  
x64.9.1.43.116040.msi"" /!*v bar.log /q RMSACCOUNTNAME=adrms  
RMSPASSWORD=Password RMSUSERDOMAIN=gtcloud9 RMSUSERNAME=gtcloud9\adrms  
GTEPADMINGROUP=GTEnterpriseAdmins" -wait
```

To uninstall with PowerShell enter the following script:

```
Start-Process msixexec.exe -ArgumentList "/x {[Application ID]} /q" -wait
```

Example:

```
Start-Process msixexec.exe -ArgumentList "/x {F5ED8702-5288-4F2A-8544-7E84E2D5B542} /q" -  
wait
```

GTEP Module

After GTEP installation open PowerShell and enter the following after the prompt:

Import-Module GTEP

To view a list all of the available commands (Cmdlet's) enter:

Get-Module GTEP -ListAvailable | % { \$_.ExportedCommands.Values }

The following list of Cmdlet's will be displayed:

```

Administrator: Windows PowerShell
PS C:\Users\administrator.21VIA> get-module gtep -ListAvailable | % { $_.ExportedCommands.Values }

CommandType      Name                                     ModuleName
-----
Cmdlet            Add-GTEPLoggingForwarders              GTEP
Cmdlet            Add-GTEPSoftwareTypes                 GTEP
Cmdlet            Get-GTEPAdminGroup                    GTEP
Cmdlet            Get-GTEPApplicationSettings           GTEP
Cmdlet            Get-GTEPCluster                       GTEP
Cmdlet            Get-GTEPDBConfigured                  GTEP
Cmdlet            Get-GTEPDBExists                      GTEP
Cmdlet            Get-GTEPDBSettings                    GTEP
Cmdlet            Get-GTEPDBVersion                     GTEP
Cmdlet            Get-GTEPHostingGroup                  GTEP
Cmdlet            Get-GTEPHostingOU                     GTEP
Cmdlet            Get-GTEPLoggingAlertSettings          GTEP
Cmdlet            Get-GTEPLoggingClusterName            GTEP
Cmdlet            Get-GTEPLoggingFirewall               GTEP
Cmdlet            Get-GTEPLoggingForwarders             GTEP
Cmdlet            Get-GTEPLoggingSMTPSettings           GTEP
Cmdlet            Get-GTEPRMSDBSettings                 GTEP
Cmdlet            Get-GTEPServerStatus                  GTEP
Cmdlet            Get-GTEPSMTPSettings                  GTEP
Cmdlet            Get-GTEPSoftwareTypes                 GTEP
Cmdlet            Get-GTEPUpgrade                       GTEP
Cmdlet            Remove-GTEPLoggingForwarders           GTEP
Cmdlet            Set-GTEPAdminGroup                    GTEP
Cmdlet            Set-GTEPApplicationSettings           GTEP
Cmdlet            Set-GTEPCluster                       GTEP
Cmdlet            Set-GTEPDBCreate                      GTEP
Cmdlet            Set-GTEPDBSettings                    GTEP
Cmdlet            Set-GTEPDBUpgrade                     GTEP
Cmdlet            Set-GTEPHostingGroup                  GTEP
Cmdlet            Set-GTEPHostingOU                     GTEP
Cmdlet            Set-GTEPLoggingAlertSettings          GTEP
Cmdlet            Set-GTEPLoggingClusterName            GTEP
Cmdlet            Set-GTEPLoggingFirewall               GTEP
Cmdlet            Set-GTEPLoggingSMTPSettings           GTEP
Cmdlet            Set-GTEPRMSDB                         GTEP
Cmdlet            Set-GTEPRMSDBSettings                 GTEP
Cmdlet            Set-GTEPServerStatus                  GTEP
Cmdlet            Set-GTEPSMTPSettings                  GTEP
Cmdlet            Set-GTEPSoftwareTypes                 GTEP
  
```

Example: Set-GTEPApplicationSettings Cmdlet -

```

Set-GTEPApplicationSettings -Name PollingIntervalOnFailure -Value 30Set-
GTEPRMSDBSettings -DataSource sqlclustmain -FailoverPartner sqlbackup -
InitialCatalog GTEP -IntegratedSecurity $True -MultiSubnetFailover $True -Password
Password -Username adrms
  
```

Each Cmdlet is listed below with any required Parameters or Commands and a usage description.

Name	Parameters	Description
Add-GTEPLoggingForwarders	Server	Select one AD RMS server in the cluster to forward all other server events to so they are all displayed on one Log Client.
Add-GTEPSoftwareTypes	AndroidUrl Default - (\$True/\$False) IOSUrl SwType	Add User default and other software types.
Get-GTEPAdminGroup	None	Set the default GTEP Administrators group.
Get-GTEPApplicationSettings	None	List all GTEP Application settings as displayed on the GTEP Administration > Settings page.
Get-GTEPCluster	None	Returns GTEP Cluster information.
Get-GTEPDBConfigured	DataSource InitialCatalog IntegratedSecurity - (\$True/\$False) Password Username	Returns GTEP database configuration status: True/False
Get-GTEPDBExists	DataSource InitialCatalog IntegratedSecurity - (\$True/\$False) Password Username	Returns GTEP database exists: True/False
Get-GTEPDBSettings	None	Returns GTEP database settings.
Get-GTEPDBVersion	DataSource InitialCatalog IntegratedSecurity - (\$True/\$False)	Returns current GTEP DB version.

	Password Username	
Get-GTEPHostingGroup	None	Returns GTEP Hosting Group.
Get-GTEPLoggingAlertSettings	None	Returns GTEP Logging Alert settings.
Get-GTEPLoggingClusterName	None	Returns GTEP Logging Cluster name.
Get-GTEPLoggingFirewall	None	Returns Firewall status for Port 10483: True/False
Get-GTEPLoggingForwarders	None	Returns a list of all servers forwarding Events to another server.
Get-GTEPLoggingSMTPSettings	None	Returns logging SMTP settings.
Get-GTEPRMSDBSettings	None	Returns RMS DRM database settings.
Get-GTEPServerStatus	None	Returns current GTEP server/cluster status.
Get-GTEPSMTPSettings	None	Returns GTEP SMTP settings.
Get-GTEPSoftwareTypes	None	Returns list of current Software Types.
Get-GTEPUpgrade	None	Returns if GTEP has been upgraded: True/False
Remove-GTEPLoggingForwarders	Instanceid	Removes all server instance Event forwarding.
Set-GTEPAdminGroup	SamAccountName	Sets the GTEP Administrator group. Suggested: GTEPEnterpriseAdmins
Set-GTEPApplicationSettings	Name Value See the next chart for all possible values.	Sets Name/Value pairs for GTEP Application settings as displayed on the GTEP Administration > Settings page.
Set-GTEPCluster	<u>Command (Choose 1)</u> Start - Create first instance in a Cluster Join – Join another instance to a Cluster	Create and manage GTEP Clusters.

	Sync – Resync ALL instances in a Cluster Leave - Remove an instance from the Cluster Password (Required)	
Set-GTEPDBCreate	DataSizeMB DataSource FailoverPartner GTEPGroup InitialCatalog IntegratedSecurity - (\$True/\$False) LogSizeMB MultiSubnetFailover - (\$True/\$False) Overwrite - (\$True/\$False) Password Username	Create the GTEP DB.
Set-GTEPDBSettings	DataSource FailoverPartner InitialCatalog IntegratedSecurity - (\$True/\$False) MultiSubnetFailover - (\$True/\$False) Password Username	Set GTEP DB settings.
Set-GTEPDBUpgrade	DataSource FailoverPartner InitialCatalog IntegratedSecurity - (\$True/\$False) MultiSubnetFailover - (\$True/\$False)	Upgrade the GTEP DB.

	Password Username	
Set-GTEPHostingGroup	AdminPassword AdminUsername SamAccountName SetPerms - (\$True/\$False)	Set the default Hosting Group.
Set-GTEPHostingOU	AdminPassword AdminUsername DistinguishedName SetPerms - (\$True/\$False)	Set the default Hosting OU.
Set-GTEPLoggingAlertSettings	Enabled - (\$True/\$False) IncludeWarnings - (\$True/\$False) IntervalMins MaxEntries Priority - (\$True/\$False) Recipients Subject	Set Logging Alert settings including Emails parameters.
Set-GTEPLoggingClusterName	ClusterName	Set the name of the Logging Cluster name that will be displayed in the GTEP Log Client.
Set-GTEPLoggingFirewall	Enabled - (\$True/\$False)	Open or Close Port 10483 for the GTEP Log Client to connect to the Log Server.
Set-GTEPLoggingSMTPSettings	FromAddress Password Port Server TLS - (\$True/\$False) Username	Set Logging SMTP settings.
Set-GTEPRMSDB	DataSource FailoverPartner	Set the RMS DRM Database.

	InitialCatalog IntegratedSecurity - (\$True/\$False) MultiSubnetFailover - (\$True/\$False) Password Username	
Set-GTEPRMSDBSettings	DataSource FailoverPartner InitialCatalog IntegratedSecurity - (\$True/\$False) MultiSubnetFailover - (\$True/\$False) Password Username	Set the RMS DRM Database settings.
Set-GTEPServerStatus	Start - (\$True/\$False)	Start/Stop the GTEPService.
Set-GTEPSMTPSettings	AuthenticationType – None, Machine, UsernamePassword FromAddress Hostname Password Port TLS - (\$True/\$False) Username	Set GTEP SMTP settings.
Set-GTEPSoftwareTypes	AndroidUrl Default - (\$True/\$False) IOSUrl SwType	Add new Software Types to GTEP.

Application Settings

Name and value pairs for Cmdlet: **Set-GTEPApplicationSettings**.

Example:

```
Set-GTEPApplicationSettings -Name PollingIntervalOnFailure -value 30
```

<u>Name</u>	<u>Value</u> (Type/Default)	<u>Setting Description</u>
PollingInterval	Policy Polling Interval (seconds)	Default: 30 The number of seconds a User's software will contact GTEP to check for policy updates.
PollingIntervalOnFailure	Policy Polling Interval on Failure (seconds)	Default: 30 The number of seconds a User's software will wait before retrying to check for policy updates on failure.
MaxPasswordAttempts	Maximum Password Attempts	Default: 3 The number of incorrect passwords a User can enter before they are automatically locked out of their account.
LockoutDuration(minutes)	Lockout Duration (minutes)	Default: 30 The time duration a user is locked out after too many incorrect login attempts.
NotifyPasswordChange(days)	GTDC - Notify Password Change (days)	Default: 14 The number of days that a reminder will be displayed before a User is required to change their password.
AlertRetentionPeriod	Alert Retention Period (days)	Default: 90 Number of days a server Alert will be retained in the database before being purged.
AuditRetentionPeriod	Audit Retention Period (days)	Default: 90 Number of days an Audit entry will be retained in the database before being purged.
EventRetentionPeriod	Event Retention Period (days)	Default: 90 Number of days an Event will be retained in the database before being purged.
LogRetentionPeriod	Activity Log Retention Period (months)	Default: 24 Number of months any Activity Log entries will be retained in the database before being automatically purged.

Alert.Subject	Alert Email Subject	Default: GTEP Alert The subject of the Alert emails.
Server.Address	GTEP Server Address	FQDN: http://adrms.trustedoffice.com/GTEP
MaxConcurrentPolicy	Maximum Concurrent Policy Updates (clients)	Default: 20 The maximum number of concurrent User connections for policy updates.
ReportPageSize	Report Page Size	Default: 2000 Maximum GTEP Report page size.
OverwatchRetentionPeriod	Overwatch Retention Period (days)	Default: 90 Number of days to retain Overwatch events in the database before purging.
DisableAllowMacrosAutoSet	Disable auto set of Allow Macros checkbox in template editor	Default: 0 This setting determines if the default for Allow Macros in the User software is set to on or off. Macros are required for Overwatch to work.
MachinePollingInterval	Machine Polling Interval (seconds)	Default: 300 - Not currently used.
MachinePollingIntervalOnFailure	Machine Polling Interval on Failure (seconds)	Default: 120 - Not currently used.
ContentClassificationPropertyName	Content Classification Property Name	Default: Classification Customize this if necessary.
SoftwareDirectory	Software Download Directory	Default: null This setting needs to point to a folder or share folder on your server(s) where the GigaTrust Desktop software will reside. This setting must be defined for the Upload Software Version feature to work. i.e. \\Yourserver\Software

ADFS.Address	ADFS Server Address	Default: If detected in DNS this setting is pre-populated. If your GigaCloud cluster is using the Microsoft Mobile Device Extension with Active Directory Federated Services, this is the FQDN of your AD FS server or cluster. On installation of GTEP the installer attempts to find the cluster FQDN. Verify this setting is correct.
FriendlyName	Cluster Friendly Name	Default: GigaCloud This is the friendly AD RMS Cluster name that will be presented to Users.
SendConfirmationEmails	Send Confirmation Emails for Synced Users	Default: 0 Define if Users synced from local Active Directory using the AD Sync Agent will receive Confirmation Emails when they are added to the cloud.
MobileAutoConfig	Enable Mobil Auto Configuration Button	Default: 0 Turns on displaying of the Mobile Auto-configure button in GTEPEXT.
TrialDays	Trial Expiration (days)	Default: 30 Number of days before trial expiration.
TenantUserLimit	Default Tenant User Limit	Default: 20 Maximum number of trial Users a trial Tenant can have in their tenancy.
TrialsEnabled	Enable Trials	Default: 0 Turn trials on/off.
CaptchaPublicKey	Captcha Public Key	Default: null Configure and enter the public key obtained from Google Captcha if you are using the trial page.
CaptchaPrivateKey	Captcha Private Key	Default: null Configure and enter the private key obtained from Google Captcha if you are using the trial page.