



GigaCloud RMS Connector

Installation and Upgrade Guide

July 2019


Table of Contents

Introduction.....	2
Prerequisites	3
Installation	4
Upgrading.....	11
Troubleshooting	15
Appendix	18

Introduction

The GigaCloud RMS Connector provides a method to communicate to your tenancy's AD RMS instance in GigaCloud. Used in conjunction with the GigaCloud AD Sync Agent, your environment will seamlessly synchronize any Active Directory Users, Groups and Organizational Units you need in your tenant to access protected content.

In essence, the RMS Connector is a proxy whereby Windows Authentication credentials that are used in your Enterprise are used to impersonate credentials in your GigaCloud tenancy. An AD RMS (Service Connection Point) SCP is added to your active directory server(s) and traffic to it is relayed to your GigaCloud Tenant. This allows the user to obtain content licenses and policies to protect and consume AD RMS protected documents with other users in your organization without needing to leave your Enterprise.



Prerequisites


- 🔗 An activated GigaCloud account
- 🔗 A server running Windows Server 2012 R2 / 2016 / 2019 (Domain Controller NOT recommended)
- 🔗 Microsoft .NET v4.6.2 Installed
- 🔗 IIS installed and configured ([See Installation section for more details](#))
- 🔗 **[Required]** GigaCloud AD Sync Agent installed in the same Enterprise environment

Installation

The GigaCloud RMS Connector tool can be installed on any server in your forest, as long as it is joined to the domain. Ensure that Microsoft .NET v4.6.2 and the following server prerequisites are installed:

- Web Server (IIS) and the following features installed:
 - Asp.net 4.5
 - .NET Extensibility 4.5
 - Security ➤ Windows Authentication

Also in Server Manager, under the server Roles screen, go to Web Server (IIS) ➤ Web Server ➤ Application Development and make sure ASP.NET 4.5 is installed.




During installation Domain Admin credentials must be provided and this account must have permissions to run the RMS Connector service locally. You must also have an activated GigaCloud account.




Important: GigaCloud RMS Connector requires the GigaCloud AD Sync Agent to be installed in the same Enterprise environment to work as designed.




Important: A Domain User account must be created and/or provided during installation with 'logon as a service' permissions and also needs to be a local Administrator.




1. Click on the GigaCloud RMS Connector to start installation. Click **Next**.




2. Accept the End User Software License Agreement and select **Next**.




3. Leave default features selected and click **Next**.




4. Enter a Domain User and password with permission to logon as a service and select **Next**.




5. Click **Install**.




6. Click **Finish**. The following window is displayed:



7. Click **Yes** and the following dialog is displayed:



- a. Enter the URL for the GigaCloud server cluster. (**Exclude** http:// or https://)
 - b. Enter the Email address of your activated GigaCloud Tenant Administrator account.
 - c. Enter the account password.
8. The GigaCloud RMS Connector Tool window prompts you to Activate the server. Select **Yes** if you would like to configure it now, **No** if you plan on configuring it later.




9. If you selected **Yes** on the previous step the window above is displayed. Select **http://** OR **https://** from the dropdown and enter your RMS Connector server's **FQDN**:

Example: "yourserver.yourdomain.com"



Important: It is highly recommended you use a SSL binding for your SCP with a valid SSL certificate.



10. Allow **SCP Access to Group** and **Deny Access to Group** allow you to filter what groups can access the SCP. Start typing in the appropriate box and matching groups will be listed. Select the group you need to allow or deny to the SCP.
11. If you are finished click on **Update SCP**.

12. Click on **Delete SCP** if you need to remove it.
13. Click on **Test RMS** and the following dialog will be displayed:

Test RMS Connector

Enter a Username and Password and click Run Test to test your RMS Connector configuration. Open the Log Client to see detailed test results.

User Name: administrator@bigcompany.local

Password:

Services

Certification Service: http://ad10.bigcompany.local/_wmcs/certification/certification.asmx ?

Licensing Service: http://ad10.bigcompany.local/_wmcs/licensing/license.asmx ?

Client Service: http://ad10.bigcompany.local/_wmcs/gigatruster/client.asmx ?

Policy Service: http://ad10.bigcompany.local/_wmcs/gigatruster/policy.asmx ?

Run Test Close

Using this tool you can verify connectivity to your SCP. There are four main web services used during the test. Enter a valid GigaCloud User email and password and click the **Run Test** button. Open the Log Client for more detailed results.

Test RMS Connector

Enter a Username and Password and click Run Test to test your RMS Connector configuration. Open the Log Client to see detailed test results.

User Name: testera@bigcompany.local

Password:

Services

Certification Service: http://ad10.bigcompany.local/_wmcs/certification/certification.asmx ✓

Licensing Service: http://ad10.bigcompany.local/_wmcs/licensing/license.asmx ✓


Client Service: http://ad10.bigcompany.local/_wmcs/gigatruster/client.asmx ✓

Policy Service: http://ad10.bigcompany.local/_wmcs/gigatruster/policy.asmx ✓

Test complete!

Run Test Close

The tool will indicate on the right-hand side success or failure for each web service test.



If there are errors a red error icon will be displayed. If you hover over the icon the error will be shown in detail in the tool tip. The errors will also be listed in the GigaTrust Log Client.


Select **Close** when you are finished.




Note: The certificate from your GigaCloud cluster may need to be imported into your RMS Connector server to develop a trust between the environments. [See appendix for more details.](#)

Upgrading


GigaCloud RMS Connector Agent does not need to be uninstalled prior to upgrading. Follow the steps below to update your GigaCloud RMS Connector software:




1. Click on the GigaCloud RMS Connector to start installation. Click **Next**.




2. Accept the End User Software License Agreement and select **Next**.




3. Leave default features selected and click **Next**.



4. Enter a Domain User and password with permission to logon as a service and select **Next**.



5. Click **Install**.



6. Click **Finish**.

Troubleshooting


It is recommended that you use the GigaTrust Log Client for any troubleshooting. It will give you real time errors and the status of the GigaCloud RMS Connector.

GigaTrust Log Client

All GTEP components send messages related to errors encountered and current status to the GigaTrust Log Server. The GigaTrust Log Server is a component of GTEP that is installed on the AD RMS Server as a service. The GTEP Log Client displays messages that are sent to the GigaTrust Log Server. You can install the GigaTrust Log Client component on its own server to isolate this component from the other GTEP components thereby allowing an administrator to delegate this process.

Access the GigaTrust Log Client via **All Programs ➤ GigaTrust ➤ GigaTrust Log Client**. Click **Connect** to view messages from the GigaTrust Log Server that is specified in the Log Server field. The default is *localhost*, but the GTEP Log Client can view messages from any accessible GigaTrust Log Server running in the network.


Click **Suspend** button to pause log messages from loading so you can view the details more closely. Click **Resume** when you are finished and the log files will continue loading from where it left off.



Click **Clear Log** to clear the messages from the display.

Click **Save** to write the currently displayed log messages to a file. A destination path and filename will be required for saving.

Export allows for saving log messages for a specific date/time range to a file. *From* and *To* dates, and time values, must be specified for the export. A destination path and filename will be required for saving.



The **Filter** drop-down list contains the different levels of messages that are displayed by the GigaTrust Log Client: *All*, *Debug*, *Info*, *Warn*, *Error*, and *Fatal*. Selecting a filter will display incoming messages received by the GigaTrust Log Server that are that level and above. (Display of existing messages is not

affected.) For example, if *Warn* is selected as the filter, only newly received messages with a status of *Warn*, *Error*, or *Fatal* will be displayed in the GTEP Log Client window.

To view the details of any message, double-click its row in the GTEP Log Client window.

The top of the details window displays all field information that displays in the GTEP Log Client window. Previous (<<) and Next (>>) buttons are available to move between messages.

For Error level messages, the trapped error message is displayed in the Exception field at the bottom of the Details window. This information is critical to troubleshooting and resolving issues with the GTEP application.



For additional features, click the menu icon at the upper right of the window.

Details

Cluster: DEFAULT

Application: ROUTER

Hostname: RMS001

Timestamp: 12/1/2011 3:06:06 PM

Level: ERROR << >>

Message: error synchronizing routes and proxies

Location: file=.line=0

Exception: mscorlib
System.ServiceModel.FaultException
unknown peer attempted to exchange routes:
CN=router.gtep.rms001.qa.ad-2k8internal.local

Server stack trace:
at System.ServiceModel.Channels.ServiceChannel.HandleReply
(ProxyOperationRuntime operation, ProxyRpc& rpc)
at System.ServiceModel.Channels.ServiceChannel.Call(String action,
Boolean oneway, ProxyOperationRuntime operation, Object[] ins,

Close

GigaTrust Log Client

Log Server: localhost Disconnect Suspend Clear Log Save Filter: ALL

Application	Hostname	Level	Timestamp	Thread	Message
GTEP	TOADRMS04	TRACE	5/28/2015 4:22:54 PM	41	<< IGTSRMSService.SubmitApplicationEvents[102ms]
GTEP	TOADRMS04	TRACE	5/28/2015 4:22:54 PM	41	>> IGTSRMSService.SubmitApplicationEvents

Search Export Archive

Search

Enter either text or a regular expression to search for matching results. Optionally, only search for Exceptions. Results are displayed with an option to **Save**.

Enter Search Criteria

Search Type

☒ Text


☐ Regular Expression

☐ Search Exceptions

OK Cancel

Export

Enter a date/time range for log messages to export. Specify the output filename and destination. The gray field shows progress as the export text file is created.




Archive

Use Archive to capture logging messages in real time. Enter a destination for what will be the archive file. Optionally define a maximum log file size.

Click **Start** when you want to start collecting log messages and **Stop** to cease collecting.

A text file labeled GTLogClient<date><start time> is created in the specified destination folder.




Appendix


Importing GigaCloud Certificate

Your Tenant's GigaCloud certificate may need to be imported into your RMS Connector server if you are having connectivity issues. You will need to request the certificate from your GigaTrust Sales Engineer. Follow these steps to import the certificate:


1. On your RMS Connector server open the MMC console as an Administrator.
2. In tool bar select **File** ➤ **Add/Remove Snap-in...**




3. Choose **Certificates** snap-in then click **Add**.




4. In the **Add or Remove Snap-ins** dialog choose **Computer** then click **Next**.




5. Click **Finish** then **OK** to close the **Add or Remove Snap-ins** dialog.




6. In the Certificates snap-in expand the **Certificates (Local Computer)** node, select **Trusted People** and click **All Tasks** then **Import**.



7. On the **Certificate Import Wizard** click **Next**.



8. Click **Browse** and select the GigaCloud certificate to import then click **Next**.



9. Click **Next** and then click **Finish** on the next window.