

JIGGLING PIG

Kiosk & Square Terminal Payment Processing User Guide

Fully structured edition with numbered subsections and continuous page flow

Prepared for Jiggling Pig Operations

Revised complete edition: August 2026

IMPORTANT

A payment is not complete until the kiosk displays the confirmation and order number. If a payment result is uncertain, check the Admin Panel and Square records before charging the customer again.

Table of Contents

1. System Overview
2. Important Payment Rules
3. Daily Opening Check
4. Starting an Order
5. Adding and Editing Cart Items
6. Combo Meals and Side Selection
7. Customer Information
8. Choosing a Payment Method
9. Paying on the Square Terminal
10. On-Screen Card Payment
11. Successful Payment
12. Canceling a Payment
13. Timeout and Decline
14. Reader Connection Failure
15. Uncertain Payment: Do Not Double-Charge
16. Payment Status Reference
17. Kiosk Activation
18. Pairing a Square Terminal
19. Refunds
20. Kitchen Queue Handoff
21. Product and Inventory Problems
22. Square Terminal Troubleshooting
23. Kiosk Troubleshooting
24. Safe Restart Procedure
25. End-of-Day Procedure
26. Payment Incident Record
27. Current Limitations
28. Quick Payment Checklist
29. Detailed Opening Test Transaction
30. Detailed Tap, Chip, and Swipe Instructions
31. Detailed Correction and Retry Procedure
32. Detailed Refund Procedure

- 33. Detailed Kiosk Activation and Security
- 34. Detailed Square Terminal Pairing
- 35. End-of-Day Reconciliation Checklist
- 36. Payment Incident Report Template
- 37. Full Pre-Payment Checklist
- 38. Full Post-Payment Checklist
- 39. Quick Troubleshooting Decision Guide
- 40. Recommended User Guide Screenshots
- 41. Complete Limitations and Verification Notice

1. System Overview

- 1.1 The Jiggling Pig payment system combines a customer touchscreen kiosk, a Square Terminal card reader, and the Jiggling Pig Admin Panel.
- 1.2 The kiosk lets customers build an order, select sides, review prices, enter a pickup name and optional phone number, and choose a payment method.
- 1.3 The Square Terminal accepts tap, chip, and swipe payments. The kiosk sends the total to the Terminal and waits for Square to report the result.
- 1.4 Authorized staff use the Admin Panel to manage kiosk devices, products, inventory, orders, payments, refunds, and the Kitchen Queue.

2. Important Payment Rules

- 2.1 Never unplug, refresh, close, or restart either device while a payment is processing.
- 2.2 The total shown on the kiosk must match the total shown on the Square Terminal.
- 2.3 A payment is not considered finished until the kiosk displays the confirmation and order number.
- 2.4 If a result is uncertain, check the order and Square payment records before charging the customer again.
- 2.5 Never ask for or record a complete card number, security code, or PIN.
- 2.6 The kiosk does not support cash, checks, split tender, partial payments, or customer-initiated refunds.

DUPLICATE-CHARGE WARNING

Never run the customer's card again until the first attempt has been checked and confirmed as failed or canceled.

3. Daily Opening Check

- 3.1 Inspect the kiosk screen, stand, power cable, and network connection. Clean the touchscreen with an approved product.
- 3.2 Inspect the Square Terminal, charging cable, card slot, battery level, and network indicator. Confirm it is not stuck on a sign-in or setup screen.
- 3.3 The kiosk should show 'Hungry? Order Here.' and 'Tap to Start.' If it shows 'Kiosk Setup,' activation is required.
- 3.4 Before opening, create a small test order, send it to the Terminal, verify the totals match, complete the approved test method, and confirm the order reaches the Admin Panel and Kitchen Queue.

4. Starting an Order

- 4.1** Tap 'Tap to Start' on the attract screen.
- 4.2** Choose a category such as Jiggling Food Menu, Sides, or Jiggling Pig Products. Food may be grouped under Combo Items, Sides, Other Items, and Drinks.
- 4.3** Only products that are in stock and enabled for kiosk sales should appear.
- 4.4** Use 'Start Over' only when the entire current order should be discarded. It clears the cart, side choices, customer details, and active order information.

5. Adding and Editing Cart Items

- 5.1** Tap a product once to add one unit. Tap it again to increase the quantity of the same selection.
- 5.2** Under 'Your Order,' use + to increase quantity and - to decrease it. Decreasing to zero removes the line.
- 5.3** Use 'Remove' to delete an unwanted product. Confirm the subtotal changes after every correction.
- 5.4** If a combo has the wrong sides, remove the combo and add it again with the correct selections.
- 5.5** Before checkout, verify every product, quantity, side, duplicate-side charge, and subtotal.

6. Combo Meals and Side Selection

- 6.1** A combo opens a window labeled 'Choose [number] sides for [product].' The counter shows how many required sides have been chosen.
- 6.2** Select the required number of sides and press 'Add to Order.' Use 'Clear' to restart the choices or 'Cancel' to leave without adding the combo.
- 6.3** Selecting some sides more than once may display 'Extra [side]?' with 'No, Go Back' and 'Yes, Add It (+\$X).' Explain and confirm the upcharge before accepting it.

7. Customer Information

- 7.1** Press 'Checkout' after the cart is correct.
- 7.2** On 'Who's this order for?', enter the required pickup name. Review the spelling because staff will use it when calling the order.
- 7.3** The phone number is optional. Enter it only with the customer's permission and verify every digit.
- 7.4** Do not promise an order-ready text until management has confirmed that texting is active and tested.
- 7.5** Use 'Back' to correct the cart. Use 'Continue to Payment' when all information is correct.

8. Choosing a Payment Method

- 8.1** The Payment screen shows the customer name, total, and available methods.
- 8.2** 'Pay on the card reader' instructs the customer to tap, insert, or swipe on the reader. If it says 'Card reader not connected yet,' do not use it.
- 8.3** 'Enter card on screen' loads a secure Square form. If it says 'Not available,' the required Square configuration is incomplete.
- 8.4** Use 'Back' if the order or customer information needs correction.

9. Paying on the Square Terminal

- 9.1** Confirm the kiosk total with the customer, then select 'Pay on the card reader' once.
- 9.2** Wait for 'Follow the card reader.' Confirm the Square Terminal wakes and displays the identical amount.
- 9.3** For contactless payment, hold the card, phone, or watch near the contactless symbol until the Terminal responds.
- 9.4** For chip payment, insert the chip end first and leave the card in place until the Terminal says to remove it.
- 9.5** Swipe only when appropriate and allowed by the Terminal. Follow every prompt shown on the Terminal.
- 9.6** Wait for both the Terminal and kiosk. The kiosk checks Square every few seconds, so a short delay is normal.

10. On-Screen Card Payment

- 10.1** Select 'Enter card on screen' and wait for the secure form. Do not refresh while it says 'Loading secure card form...'.
- 10.2** The customer should enter their own card number, expiration date, security code, and postal code when requested.
- 10.3** Review the total and press 'Pay \$X' once. Wait while the button says 'Processing...'.
- 10.4** If the form will not load, press Back, check the internet connection, try once more, or use the Square Terminal.
- 10.5** This option requires the Square application ID, location ID, access configuration, correct environment, and Square as the active payment gateway.

11. Successful Payment

- 11.1** A successful payment displays 'Thanks, [name]!', an order number, and pickup instructions.
- 11.2** Confirm the order number is visible, the payment is captured or completed, and the order appears in the Kitchen Queue.

- 11.3** Tell the customer the pickup name or number. Press 'Done,' or allow the confirmation to return to the start screen automatically after about 20 seconds.

12. Canceling a Payment

- 12.1** Cancel if the customer changes their mind, the amount is wrong, the wrong method was selected, or the Terminal cannot complete the prompts.
- 12.2** Press 'Cancel Payment,' stop interacting with the Terminal, and wait for the kiosk to return to payment choices.
- 12.3** If canceled on the reader, the kiosk should say 'Payment was canceled on the reader. Please try again.'
- 12.4** Do not begin another attempt until the first one is clearly canceled.

13. Timeout and Decline

- 13.1** A Terminal attempt may time out after about three minutes and display 'The card reader timed out. Please try again.' Verify the first attempt did not complete before retrying.
- 13.2** For a decline, say: 'The payment was not approved. You may try again or use another card.' Do not guess why the bank declined it.
- 13.3** Try a declined card only once more when appropriate. If declined again, request another card.

14. Reader Connection Failure

- 14.1** If the kiosk says 'Could not reach the card reader,' confirm the Terminal has power, internet, the correct pairing, and no other active payment.
- 14.2** Wait briefly and retry once. If the on-screen card option is available, use it instead.
- 14.3** If both methods fail, stop kiosk payments and notify a manager.

15. Uncertain Payment: Do Not Double-Charge

- 15.1** Treat the payment as uncertain if the Terminal says approved but the kiosk waits, the internet drops, the browser refreshes, or the customer receives a bank notice without kiosk confirmation.
- 15.2** Record the customer name, amount, time, and any order number. Check the kiosk, Kitchen Queue, Admin Panel order, stored payment status, and Square transaction activity.
- 15.3** Compare the amount, time, status, and order reference. If completed, fulfill the order and do not charge again. If canceled or failed, retry. If pending, ask a manager to investigate.

16. Payment Status Reference

- 16.1** Pending: started but not final; wait and verify.
- 16.2** Authorized: approved but may still require completion; do not duplicate the charge.

- 16.3** Captured or Completed: payment succeeded; fulfill the order.
- 16.4** Canceled: stopped before completion; customer may retry.
- 16.5** Failed: did not complete; verify, then retry or use another method.
- 16.6** Refunded: money was returned to the original payment method.

17. Kiosk Activation

- 17.1** If 'Kiosk Setup' appears, obtain the approved setup link or token from the Admin Panel. The token normally begins with ksk_.
- 17.2** Enter the complete token or link, press 'Activate Kiosk,' and wait while it says 'Connecting...'. Confirm the attract screen appears.
- 17.3** Treat the token like a password: never publish, photograph, or include it in a guide. Revoke the kiosk if the token may have been exposed.

18. Pairing a Square Terminal

- 18.1** In the Admin Panel, open kiosk device management, select the correct kiosk, and start Terminal pairing.
- 18.2** On the Square Terminal, open Settings, sign out if necessary, and enter the generated device code.
- 18.3** Wait for pairing confirmation, then run a test order to confirm the correct Terminal receives the correct amount.
- 18.4** Do not open the kiosk for customers until pairing and a test transaction succeed.

19. Refunds

- 19.1** Customers cannot refund from the kiosk. An authorized employee must locate the correct order or payment in the Admin Panel.
- 19.2** Verify the order number, date, customer, original amount, payment status, gateway, reason, and any required approval.
- 19.3** Submit the refund, wait for the result, and verify the record says Refunded. Refresh and check Square before retrying a refund.
- 19.4** Tell the customer the refund was submitted to the original method and that their bank determines when it appears.

20. Kitchen Queue Handoff

- 20.1** After payment, confirm the order appears in the Kitchen Queue with the correct name, number, products, quantities, and sides.
- 20.2** If payment succeeded but the order is missing, refresh the queue and search the Admin Panel. Do not charge again; notify a manager.

- 20.3** Call the pickup name or order number and use the configured notification process when the food is ready.

21. Product and Inventory Problems

- 21.1** A missing item may be deleted, out of stock, hidden from the kiosk, or assigned to the wrong category.
- 21.2** Verify stock is above zero, kiosk visibility is enabled, and the category is correct.
- 21.3** Menu changes can take several minutes to refresh. Avoid changing prices during an active checkout.

22. Square Terminal Troubleshooting

- 22.1** Blank screen: check power and charging; remove the device from service if it will not wake.
- 22.2** Offline: restore the approved network connection before retrying.
- 22.3** Wrong amount: cancel immediately, correct the cart, and restart payment.
- 22.4** No payment received: check pairing, network, power, and whether another payment is active.
- 22.5** Card will not read: try contactless, then chip, then another card. Never force a card into the slot.

23. Kiosk Troubleshooting

- 23.1** Unresponsive screen: clean and dry it, check power, and restart only when no payment is active.
- 23.2** Setup screen: reactivate with an authorized token and run a test order.
- 23.3** Secure card form missing: check internet, return to payment choices, retry once, then use the Terminal.
- 23.4** Empty menu: check internet, stock, visibility, and categories. Refresh only when no payment is active.
- 23.5** For any 'Payment failed' message, verify Square and order records before trying again.

24. Safe Restart Procedure

- 24.1** Before restarting, confirm no customer is entering payment and no payment is active or pending.
- 24.2** Record any uncertain order number, time, and amount.
- 24.3** Restart the kiosk session first. Restart the Terminal only if necessary. Wait for reconnection, verify activation and pairing, then run a test transaction.

25. End-of-Day Procedure

- 25.1** Review all kiosk orders and look for pending, failed, canceled, duplicate, and refunded payments.
- 25.2** Compare paid kiosk orders with Square completed payments and refund totals. Investigate every unclear status.
- 25.3** Return the kiosk to the attract screen, clean both devices, connect the Terminal to power, hide admin pages, and report damage.

26. Payment Incident Record

- 26.1** Record date/time, kiosk location, customer first name, order number, amount, attempted method, kiosk message, Terminal message, status, Kitchen Queue result, employee, manager, and resolution.
- 26.2** Never record a complete card number, security code, PIN, or other sensitive card information.

27. Current Limitations

- 27.1** No cash, checks, split tender, partial payments, kiosk coupons, or customer-initiated refunds.
- 27.2** No customer-facing printed, emailed, or texted receipt option is currently exposed in the kiosk.
- 27.3** A phone number is collected, but ready-text behavior must be separately verified before it is promised.
- 27.4** Menu and stock updates may take several minutes to appear.
- 27.5** A real end-to-end Square test payment must be completed before production use is considered fully verified.

28. Quick Payment Checklist

- 28.1** Before: verify items, quantities, sides, upcharges, name, total, and Terminal connection.
- 28.2** During: match the Terminal amount to the kiosk, follow prompts, leave chip cards inserted, and never press Pay repeatedly.
- 28.3** After: confirm the order number, Kitchen Queue entry, completed payment status, pickup information, and return to the start screen.

29. Detailed Opening Test Transaction

- 29.1** Wake the kiosk and verify it displays Hungry? Order Here and Tap to Start.
- 29.2** Confirm the Square Terminal is powered, charged, online, and beside the correct kiosk.

- 29.3** Tap to start, add an inexpensive test item, verify its price, and press Checkout.
- 29.4** Enter a clearly identified test pickup name and continue to payment.
- 29.5** Confirm Pay on the card reader is available. If it says Card reader not connected yet, stop and troubleshoot pairing.
- 29.6** Select the reader once. Compare the amount on the kiosk with the amount on the Terminal before presenting a card.
- 29.7** Complete the approved test method and wait for kiosk confirmation and an order number.
- 29.8** Confirm the order appears in the Admin Panel and Kitchen Queue, then refund or document it according to company policy.

30. Detailed Tap, Chip, and Swipe Instructions

- 30.1** Contactless card: hold the card flat near the contactless symbol until the Terminal responds. Do not tap repeatedly or remove it too quickly.
- 30.2** Phone or watch: unlock the device, open its wallet if required, authenticate, then hold it near the contactless symbol until confirmation.
- 30.3** Chip card: insert the chip end first, leave the card inserted, follow every prompt, and remove it only when instructed.
- 30.4** Magnetic stripe: use only when permitted. Position the stripe correctly and swipe smoothly once. Chip and contactless are preferred.
- 30.5** If a card cannot be read, try contactless, then chip, then another card. Never force a card into the slot or copy its numbers.

31. Detailed Correction and Retry Procedure

- 31.1** Wrong item or side before payment: press Back, correct the cart, and verify the new subtotal.
- 31.2** Wrong amount sent to the Terminal: do not let the customer pay. Press Cancel Payment, confirm cancellation on both devices, correct the order, and start again.
- 31.3** Canceled payment: wait until the kiosk returns to payment choices before retrying.
- 31.4** Declined payment: state only that it was not approved. Retry once when appropriate, then request another card.
- 31.5** Timeout: check the Terminal, Admin Panel, order record, and Square activity before retrying.
- 31.6** Terminal approved but kiosk did not: treat it as uncertain. Never recharge until records prove the attempt failed or was canceled.
- 31.7** Browser or network failure: record the time, amount, pickup name, and order number, then verify the payment before acting.

32. Detailed Refund Procedure

- 32.1** Obtain the order number, customer name, date, original amount, and refund reason.
- 32.2** Sign in with an authorized account and locate the exact order or payment.
- 32.3** Verify it completed through Square and is eligible for refund. Compare order and payment amounts and obtain approval when required.
- 32.4** Select the refund action, review the amount carefully, and submit once.
- 32.5** Wait for the result and verify the record changes to Refunded.
- 32.6** If the screen is slow or errors, refresh and check Square before submitting another refund.
- 32.7** Tell the customer the refund was submitted to the original method and their bank determines when it appears.

33. Detailed Kiosk Activation and Security

- 33.1** Activation is needed after initial installation, token revocation, cleared browser storage, or an invalid saved credential.
- 33.2** Use the approved setup link or token beginning with ksk_. Enter it completely and press Activate Kiosk once.
- 33.3** Wait while it says Connecting. Successful activation returns to the attract screen.
- 33.4** The token is a credential. Never publish, photograph, place it in a manual, or send it insecurely.
- 33.5** If exposed, revoke the kiosk device in the Admin Panel and issue a new activation.

34. Detailed Square Terminal Pairing

- 34.1** Verify the Terminal has power, internet, and the correct Square account and environment.
- 34.2** In Admin kiosk device management, choose the kiosk physically beside that Terminal and start pairing.
- 34.3** On the Terminal, open Settings, sign out if necessary, and enter the generated device code.
- 34.4** Wait for Square and the Admin Panel to confirm pairing.
- 34.5** Create a test order and confirm only the intended Terminal receives the correct amount.
- 34.6** Do not open the kiosk for customer payments until the pairing test succeeds.

35. End-of-Day Reconciliation Checklist

- 35.1** Review all kiosk orders and identify pending, failed, canceled, duplicate, and refunded payments.
- 35.2** Compare completed kiosk orders with completed Square transactions and refund totals.

- 35.3** Investigate every completed payment without an order and every order without a completed payment.
- 35.4** Document unresolved incidents with date, time, kiosk, customer first name, order number, amount, messages, status, employee, and resolution.
- 35.5** Return to the attract screen, hide admin pages, clean both devices, charge the Terminal, and report damage.

36. Payment Incident Report Template

- 36.1** Record the date and time, kiosk location, customer first name, order number, expected amount, and payment method.
- 36.2** Record the exact kiosk and Square Terminal messages.
- 36.3** Record whether Square shows pending, authorized, completed, canceled, failed, or refunded.
- 36.4** Record whether the order reached the Kitchen Queue, whether food was provided, who handled it, who was notified, and the resolution.
- 36.5** Never record a full card number, expiration date, security code, PIN, banking credential, or card photograph.

37. Full Pre-Payment Checklist

- 37.1** Verify products, quantities, side selections, duplicate-side charges, and subtotal.
- 37.2** Verify the pickup name and confirm the optional phone was given voluntarily.
- 37.3** Confirm the customer understands the total and payment method.
- 37.4** Confirm the Terminal is connected and idle before selecting Pay on the card reader.
- 37.5** After sending the amount, compare both screens before the card is presented.

38. Full Post-Payment Checklist

- 38.1** Confirm the kiosk displays Thanks, the customer name, and an order number.
- 38.2** Confirm payment is captured or completed and the order appears in the Kitchen Queue.
- 38.3** Tell the customer the pickup name or number and where to wait.
- 38.4** Press Done or allow the 20-second timer to return to the attract screen.
- 38.5** Before the next customer, verify no previous name, order, payment message, or card form remains visible.

39. Quick Troubleshooting Decision Guide

- 39.1** Kiosk confirmation appears: prepare the order.
- 39.2** Terminal approved but kiosk still waits: check Admin Panel and Square; do not charge again.

- 39.3** Terminal declined: retry once or use another card.
- 39.4** Payment canceled: confirm cancellation, then retry.
- 39.5** Reader timed out: verify the first attempt before retrying.
- 39.6** Reader not connected: check power, internet, pairing, and whether another payment is active.
- 39.7** Card form unavailable: use the paired Terminal or notify a manager.
- 39.8** Payment completed but kitchen order is missing: do not recharge; locate the order and notify a manager.

40. Recommended User Guide Screenshots

- 40.1** Kiosk attract screen; menu categories; product selection; combo side-selection; duplicate-side upcharge.
- 40.2** Cart quantity controls; customer details; payment-method screen; Follow the card reader screen.
- 40.3** Square Terminal tap, insert, and swipe prompts; secure card form; successful confirmation.
- 40.4** Kitchen Queue order; kiosk-device page; pairing code; payment record; refund control.
- 40.5** Failed, canceled, timeout, reader-disconnected, and Kiosk Setup messages.

41. Complete Limitations and Verification Notice

- 41.1** No cash, check, split-tender, partial-payment, kiosk coupon, or customer-initiated refund flow.
- 41.2** No customer-facing printed, emailed, or texted receipt button is exposed in the kiosk.
- 41.3** The optional phone is stored, but ready-text behavior must be tested before staff promise it.
- 41.4** Menu and stock changes may take several minutes to appear.
- 41.5** Terminal and on-screen card payments require different configuration. On-screen Square payment also requires Square as active gateway.
- 41.6** A real end-to-end Square payment must be tested before the workflow is approved for production customers.

Quick Troubleshooting Decision Guide

Kiosk shows confirmation

Prepare the order.

Terminal approved; kiosk still waiting

Check Admin Panel and Square. Do not charge again.

Terminal declined

Retry once or use another card.

Payment canceled

Confirm cancellation, then retry.

Reader timed out

Verify the first attempt before retrying.

Reader not connected

Check power, network, and pairing.

Card form unavailable

Use the paired Terminal or notify a manager.

Paid order missing from kitchen

Do not recharge; locate the order and notify a manager.