DACCESS®

COGNEXA



EXTRACTO

Smart extraction. Instantly.

User Manual

Date: 2026-08-20

Table of Contents

1. Introduction

1.1 Purpose of this document

1.2 Intended audience

1.3 Scope of this manual

2. System Overview

2.1 What Xtracto Tab does

2.2 How data flows through the app

2.3 Local processing engine

3. Getting Started

3.1 Opening the app

3.2 Reading the header bar

4. Features & How to Use Them

4.1 Choosing a capture mode

4.2 Confirming the processing engine

4.3 Capturing documents

4.4 Setting the transaction direction

4.5 Running extraction

5. Reading the Extraction Result

5.1 Status banner & document type

5.2 Document Details & Notes

5.3 Timing

5.4 Fields

5.5 Line Items

5.6 Site Entry Stamp

5.7 OCR Text & Raw JSON

5.8 Approving or rejecting a record

5.9 Manual mode

5.10 Returnable mode

6. The Xtracto Dashboard (Back-Office)

6.1 Viewing approved records on the Dashboard

6.2 Viewing extracted data in Record Details

6.3 Managing records (View, Edit, Delete)

6.4 Where captured files are stored

7. Troubleshooting (User-Level)

8. Frequently Asked Questions

9. Glossary

10. Support & Contact Information

SECTION 1

Introduction

1.1 Purpose of this document

This manual explains how to use the **Xtracto Tab** application — the gate-side terminal used to photograph and extract data from invoices, challans, security gate passes, and vehicle documents. It covers the version of the application running on the local network terminal, using the on-device (Local) extraction engine.

1.2 Intended audience

This manual is written for **gate and site operators** — staff who use the tablet or terminal stationed at the vehicle entry/exit point to capture documents. No programming or IT background is assumed.

1.3 Scope of this manual

This manual covers the Automatic capture-and-extraction workflow in full detail, including every section of the extraction result screen (Fields, Line Items, Site Entry Stamp, Raw JSON, and the Timing and Notes panels). Manual mode and Returnable mode are covered at a summary level (Sections 5.9 and 5.10), based on what the mode switch exposes. Section 6 additionally covers the Xtracto back-office Dashboard — the desktop-browser application administrative staff use to review, manage, and store the records this terminal creates.

SECTION 2

System Overview

2.1 What Xtracto Tab does

When a vehicle arrives at or leaves the site, the operator photographs the invoice/gate-pass document and the vehicle (front and body). Xtracto Tab reads the photographs using an OCR (optical character recognition) engine combined with an AI extraction model, and turns them into structured data — document type, gate pass number, vendor and buyer details, GST details, line items, and vehicle number — automatically, in seconds.

The operator then checks the extracted result on screen against the physical document and either **approves** it or **rejects** it before the vehicle proceeds.

2.2 How data flows through the app

1. **Capture.** The operator photographs or uploads the Invoice, Vehicle Front, and Vehicle Body images.
2. **Direction.** The operator confirms whether the transaction is Inward, Outward, or Returnable.
3. **Extraction.** The images are processed by the on-device Local engine. The app shows live progress and, on completion, every extracted field.
4. **Review.** The operator checks the recognized document type, the extracted fields, line items, and any warnings shown.
5. **Decision.** The operator selects **Approve** or **Reject** to finalize the record.

2.3 Local processing engine

Xtracto Tab processes every document on-device, using the Local extraction engine:

Mode	Engine	Typical use
Local	On-device combination: PaddleOCR (PP-StructureV3) + NuExtract-3 Q4	Standard operation on this terminal, with no dependency on an external processing service.

NOTE: All screenshots in this manual were captured with the app set to **Local** processing.

SECTION 3

Getting Started

3.1 Opening the app


6. On the gate terminal, open the browser tab titled **Xtracto - Tab** (it is normally left open at all times on the device).
7. If it is not open, go to the local address provided by your administrator (for example, an address in the form 192.168.x.x:3001) — this must be entered exactly as given, since it only works on your site's local network.
8. No login is required. The app opens directly to the capture screen.

3.2 Reading the header bar

The header bar is visible at all times, at the top of every screen:

Element	Meaning
Xtracto logo (left)	Confirms you are in the correct application.
● **Online**	The terminal has a working connection. If this changes to an offline indicator, see Section 7.
Automatic / Manual / Returnable	The mode switch — see Section 4.1.
D-Access logo (right)	Identifies the deployment partner; no action needed.

Figure 1


Xtracto - Tab
192.168.10.213:3001
XTRACTO
Smart extraction. Instantly.
Online
Automatic
Manual
Returnable
ACCESS®
VEHICLE INTAKE
Capture Vehicle Documents
Capture the invoice (tap again to add more pages for a multi-page invoice), vehicle front, and vehicle body to complete the extraction.
INVOICE
LOCAL OCR + LLM COMBINATION
PaddleOCR (PP-StructureV3) + NuExtract-3 Q4
Tap To Upload
Upload invoice document
Invoice
Tap To Capture
Capture vehicle image
Vehicle Front
Tap To Capture
Capture vehicle image
Vehicle Body
Captured Files
0 files captured
Invoice
Vehicle Front
Vehicle Body

SECTION 4

Features & How to Use Them

4.1 Choosing a capture mode

Purpose: The switch at the top of the screen determines how a record is created.

Mode	When to use it
Automatic	Normal operation — photograph the invoice and vehicle; the app reads the data for you. Use this for almost every transaction.
Manual	The document cannot be read automatically (damaged, illegible, or repeated extraction failure). See Section 5.9.
Returnable	Tracking or closing out items previously sent out that are expected to return. See Section 5.10.

9. Select **Automatic**, **Manual**, or **Returnable** at the top of the screen.

Expected outcome: The screen below the switch changes to match the selected mode.

4.2 Confirming the processing engine

Purpose: Confirm the on-device Local engine combination is active before capturing documents.

10. On the capture screen, locate the **Local OCR + LLM Combination** control.
11. Confirm the checkbox is selected and the combination shown — currently PaddleOCR (PP-StructureV3) + NuExtract-3 Q4 — has a checkmark confirming it is ready.

4.3 Capturing documents

Purpose: Photograph or upload the invoice and the two vehicle images required before extraction can run. This is the primary, everyday task on this terminal.


The capture screen opens with the heading **"Capture Vehicle Documents"** and shows three capture cards, each with its own colored corner marker:

Card	Empty-state label	What to photograph
Invoice	Tap To Upload	The invoice, challan, or gate pass document.
Vehicle Front	Tap To Capture	The front of the vehicle, with the number plate clearly visible.
Vehicle Body	Tap To Capture	The side/body of the vehicle, including its number plate.

12. Select the **Invoice** card and capture or upload the document. Ensure all text and all corners of the document are visible and in focus.
13. If the invoice has more than one page, tap the card again — its label changes to **Uploaded / Tap to add another page** — and capture each additional page in turn.
14. Select the **Vehicle Front** card and photograph the front of the vehicle, ensuring the number plate is readable.
15. Select the **Vehicle Body** card and photograph the side of the vehicle, again ensuring the number plate is readable.
16. Once captured, each card shows **Uploaded** with a colored checkmark, and its instruction changes to **Tap to change**.
17. Below the three cards, the **Captured Files** panel lists a thumbnail for each image with its label (Invoice / Vehicle Front / Vehicle Body). Select the trash icon on a thumbnail to delete and recapture it if needed.

Expected outcome: The panel header reads **"3 files captured"** and a progress indicator above the direction tabs reads **"3/3 Captured"**, confirming all three images are ready for extraction.

Figure 2


Xtracto - Tab
192.168.10.213:3001
XTRACTO
Smart extraction. Instantly.
Online
Automatic
Manual
Returnable
DACCESS
vehicle body to complete the extraction.
LOCAL OCR + LLM COMBINATION
PaddleOCR (PP-StructureV3) + NuExtract-3 Q4
Uploaded
Tap to add another page
Invoice
Uploaded
Tap to change
Vehicle Front
Uploaded
Tap to change
Vehicle Body
Captured Files
3 files captured
Invoice
TAX INVOICE
Vehicle Front
MH12DE1433
Vehicle Body
MH12DE1433
Please capture or upload the invoice (all pages, for a multi-page invoice), vehicle front, and vehicle body for accurate extraction.
3/3 Captured
Inward
Outward
Returnable
Extract

4.4 Setting the transaction direction

Purpose: Once all three files are captured, direction tabs appear above the Extract button.


18. Select **Inward** if the vehicle is arriving at the site, **Outward** if it is leaving, or **Returnable** if this transaction concerns previously issued returnable items.

Expected outcome: The selected tab is highlighted, and the app is ready to extract.

4.5 Running extraction

19. Once "3/3 Captured" is shown and a direction is selected, select the blue **Extract** button at the bottom of the screen.
20. The button is replaced by an **Extracting…** progress indicator. Wait for this to complete — do not navigate away or recapture images during this time.
21. When finished, a green **"✓ Extracted Successfully"** banner appears, followed by the recognized document type (for example, security_gate_pass) and the full result panel described in Section 5.

Figure 3


Xtracto - Tab
192.168.10.213:3001
XTRACTO
Smart extraction. Instantly.
Online
Automatic
Manual
Returnable
ACCESS®
vehicle body to complete the extraction.
LOCAL OCR + LLM COMBINATION
PaddleOCR (PP-StructureV3) + NuExtract-3 Q4
Uploaded
Tap to add another page
Invoice
Uploaded
Tap to change
Vehicle Front
Uploaded
Tap to change
Vehicle Body
Captured Files
3 files captured
Invoice
TAX INVOICE
ABC CONSTRUCTIONS PVT. LTD.
GSTIN : 27AABCA1254B1ZK
Vehicle Front
MH12DE1433
Vehicle Body
MH12DE1433
Please capture or upload the invoice (all pages, for a multi-page invoice), vehicle front, and vehicle body for accurate extraction.
3/3 Captured
Inward
Outward
Returnable
Extracting...

SECTION 5

Reading the Extraction Result

5.1 Status banner & document type

At the top of the result:

- A green **"✓ Extracted Successfully"** banner confirms the process completed.
- A second bar repeats **"Extracted Successfully"** alongside the "3/3 Captured" and direction tabs, for reference while scrolling.
- A green document-type chip shows what kind of document was recognized — for example security_gate_pass or cash_memo. Confirm this matches the physical document type; if it does not, treat the result with caution and consider using Manual mode instead.

5.2 Document Details & Notes

The **Document Details** panel contains a **Notes** field. Most of the time this shows — (no notes), as in the example in Figure 4 below. Occasionally it instead shows a **Partial Extraction Warning**.

Treat any warning in this panel as a signal to check the Fields, Line Items, and Site Entry Stamp panels more carefully than usual before approving — some values may be missing or misplaced even though the overall extraction "succeeded."

5.3 Timing


The **Timing** panel reports how long extraction took: **OCR Seconds** (reading the image), **LLM Seconds** (interpreting the reading into fields), and **Total Seconds**. This is informational only — no action is required — but unusually long times can indicate a network or engine issue (see Section 7). These figures are visible at the end of the **Raw JSON** panel, shown in Figure 6 below (Section 5.8) — for the example used in this manual, extraction took a total_seconds value in the range of 35–65 seconds across repeated runs.

5.4 Fields

The **Fields** panel lists every field the document type can contain, in a two-column layout. A field with a recognized value is shown in bold; a field the system could not find shows —.

For a security gate pass, this includes: Gate Pass No, Form No, SQP No, MTN No, Document Ref No, Serial No, Vendor Name/Address/GSTIN/PAN/Phone/Email, Buyer Name/Address/GSTIN/PAN, Consignee Name/Address/GSTIN, Please Allow Shri (the person authorized to carry material out), Courier Name/Contact, Reason for Removal, Material Description/Type, Contractor details, Person Taking Material details, Security Staff details, Truck/Tempo No/Date/Time, Authorised Person, and the full set of GST and financial fields (GSTIN, Place of Supply, HSN/SAC Code, Taxable Value, CGST/SGST/IGST rate and amount, Cess, TDS, Total Tax, Subtotal, Discount, Freight/Packing/Other Charges, Round Off, Grand Total, Amount in Words).

Figure 4


Xtracto - Tab
192.168.10.213:3001
XTRACTO
Smart extraction. Instantly.
Online
Automatic
Manual
Returnable
DACCESS®
security_gate_pass
DOCUMENT DETAILS
NOTES
—
FIELDS
GATE PASS NO
CITP 55
FORM NO
CITP 55
SQP NO
4/16
MTN NO
55678
DOCUMENT REF NO
—
SERIAL NO
—
VENDOR NAME
—
VENDOR ADDRESS
—
VENDOR GSTIN
—
VENDOR PAN
—
VENDOR PHONE
—
VENDOR EMAIL
—
BUYER NAME
—
BUYER ADDRESS
—
BUYER GSTIN
—
BUYER PAN
—
CONSIGNEE NAME
—
CONSIGNEE ADDRESS
—
CONSIGNEE GSTIN
—
PLEASE ALLOW SHRI
Mr. Sanjay Kulkarni
COURIER NAME
L&T Construction
COURIER CONTACT
—
REASON FOR REMOVAL
Site to Site transfer
MATERIAL DESCRIPTION
—
MATERIAL TYPE
—
CONTRACTOR NAME
—
CONTRACTOR SIGNATURE DATE
—
PERSON TAKING MATERIAL
—

5.5 Line Items

The **Line Items** panel is a horizontally scrollable table listing every item read from the document's item table: **Sr No, Description, HSN/SAC, Quantity, Unit, Rate, Discount, Taxable Amount, CGST Rate, CGST Amount, SGST Rate, SGST Amount, IGST Rate, IGST Amount,** and **Total Amount**. Scroll the table sideways to see all columns. As with Fields, columns with no value on the source document show —. The values for the example used in this manual are visible in the line_items array of the Raw JSON panel, shown in Figure 6 below (Section 5.8) — for instance, "Aluminium C-channels – 4m length", quantity 50.

5.6 Site Entry Stamp


The **Site Entry Stamp** panel shows the sign-off details printed or written at the bottom of a gate pass: Truck Tempo (vehicle description and number), Truck Date/Time, Contractor Name/Signature/Date, Authorised Person/Date, Person Taking Material (Name/Signature/Date), and Security Staff (Name/Exit Vehicle No/Date/Time). This is where to check the vehicle number and the authorizing signatory were both read correctly. For the example used in this manual, the site_entry_stamp object in the Raw JSON panel, shown in Figure 6 below (Section 5.8), shows Truck Tempo "MH03 AB No. 9988", Truck Date "10/07/2026", and Authorised Person "Priya".

5.7 OCR Text & Raw JSON

Below the Fields, Line Items, and Site Entry Stamp panels, the app also shows two technical panels, displayed as light text on a dark background. Day-to-day review does not require reading either of these — use the Fields, Line Items, and Site Entry Stamp panels instead. They are provided for cases where your administrator or support contact asks you to check or share exactly what the OCR engine read, or the exact data returned by the extraction engine.

- The **OCR Text** panel shows the raw, unstructured text the OCR engine read directly off the document image, before the AI model organized it into fields.
- The **Raw JSON** panel shows the same extracted data organized into its underlying technical format.

Figure 5


XTRACTO
Smart extraction. Instantly.
Online
Automatic
Manual
Returnable
ACCESS®
OCR TEXT
The Security
PleaseWllow Shri Mfs.Mr. Sanjay Kulkarni atM/S L&T Construction to take out the following
The material/plant& equipments beiongs to _Godrei Vikhroli site Destination of Material/ Plant& Equipments Tata Power Site, Goregaon Reasonsfortaking out Surplus/Rejected/Transfer/Repair Site to Site transfer Not for Sale
Challan Na,with dateincaseofrjectedmaterial/plant&equipment
Sr No.Description Quantity 7中Aluminium C-channels -4m length 502Bulk cement baqs-5okg 1003Welding rods - box of 10010i4Electrical conduit pipes-1-inch dia 200Goagles - pairs 156Grinding wheels -spare 05
Comnpany StatName/Signature/Date (seposn)Priya Sanjay Kulkari (Authorised person)
Persca aking out the materialName/Signature/Dae ABC ENGINEERING Eacority Staff L&T Construction eertpomName/SignatureDate
Tuck Torapol No 2023Date
TohefifeaintriplicateOrigSeutyCopcacnSite&Contractorfappiable Name andspisifthpedtositigpalibma Available with the sounty aiexi poin iSite-in-charge/GM
RAW JSON
{
"document_type": "security_gate_pass",
"fields": {
"gate_pass_no": "CITP 55",
"form_no": "CITP 55",
"sqp_no": "4/16",
"mtn_no": "55678",
"document_ref_no": null,
"serial_no": null,
"vendor_name": null,
"vendor_address": null,
"vendor_gstin": null,
"vendor_pan": null,
"vendor_phone": null,
"vendor_email": null,
"buyer_name": null,
"buyer_address": null,
"buyer_gstin": null,
"buyer_pan": null,
"consignee_name": null,
"consignee_address": null,
"consignee_gstin": null,
"please_allow_shri": "Mr. Sanjay Kulkarni",
"courier_name": "L&T Construction",
"courier_contact": null,
"reason_for_removal": "Site to Site transfer",
"material_description": null,
"material_type": null,
"contractor_name": null,
"contractor_signature_date": null,
"person_taking_material": null,
"person_taking_material_signature": null,
"person_taking_material_date": null,
"security_staff_name": null,
"security_staff_exit_vehicle_no": null,
"security_staff_exit_date": null,
"security_staff_exit_time": null,
"truck_tempo_no": "MH03 AB No. 9988",
"truck_tempo_date": "10/07/2026",


5.8 Approving or rejecting a record

Purpose: After reviewing the extraction result (Section 5), finalize the record.

22. Scroll through the result panel and compare the extracted values against the physical document.
23. Select ✓ **Approve** (blue button, bottom right) if the record is correct, or ✕ **Reject** (outlined red button, bottom left) if it is not.

After selecting Approve, a confirmation dialog appears asking **"Approve and save this extraction?"**. Select **Approve** again to confirm and save the record, or **Cancel** to return to the result screen without saving. If nothing appears to happen, wait briefly for the terminal to save the record rather than tapping the button again.

Figure 6



5.9 Manual mode

Purpose: Record a transaction by entering details directly, used when a document cannot be read automatically.

24. Select **Manual** in the header mode switch.
25. Complete the entry screen as it appears, and submit the record.

> **NOTE:** Use Manual mode as the fallback whenever a document is damaged, illegible, or has repeatedly failed automatic extraction (Section 7). Enter the same core details an Automatic capture would produce — document number, vendor, vehicle number, and item details — as accurately as possible from the physical paperwork.

5.10 Returnable mode

Purpose: View and close out items previously sent from the site that are expected to be returned.

26. Select **Returnable** in the header mode switch.
27. Locate the item using the list or search/filter tools provided, and mark it returned when it arrives back.

> **NOTE:** Use Returnable mode specifically for closing out items already logged as sent out (for example, empty pallets, crates, or drums) once they physically return to the site — not for new Inward/Outward transactions, which belong in Automatic mode (Section 4.4).

SECTION 6

The Xtracto Dashboard (Back-Office)

The screens in this section belong to the Xtracto back-office Dashboard — a separate application used by administrative staff on a desktop or laptop browser, distinct from the gate terminal covered in the rest of this manual. Once a record is approved on the terminal (Section 5.8), it is sent here automatically for review and record-keeping.


6.1 Viewing approved records on the Dashboard

Purpose: Confirm that a record approved at the gate terminal has arrived at the back office, and see it listed alongside all other records.

28. On a desktop or laptop browser, open the Xtracto Dashboard and sign in.
29. The stat cards at the top of the screen — Total Records, Inward, Outward, Returnable, Manual, and Today — update to reflect the new record.
30. The Data Status table below lists the record, showing its Project Site, Vendor Name, Document No., Date, Status, Direction, and Doc Type.

Expected outcome: The record captured at the gate appears in the Dashboard within moments of being approved, tagged with the same Direction (Inward, Outward, or Returnable) selected on the terminal — in the example below, an Outward security_gate_pass record.

Figure 7



6.2 Viewing extracted data in Record Details

Purpose: Open a record from the Dashboard to review the full set of data extracted at the gate.


31. On the Dashboard's Data Status table, select the record's row.

The Record Details window opens, showing the Approved Date and Approved Time, followed by the Document Details (Notes) and Fields panels — the same categories

32. captured on the terminal, such as Gate Pass No, Form No, SQP No, MTN No, Document Ref No, and Serial No.
33. Select Close to return to the Dashboard.

Expected outcome: Every field extracted at the gate is available for review from the back office, without needing access to the terminal itself.

Figure 8




6.3 Managing records (View, Edit, Delete)

Purpose: Perform administrative actions on a record directly from the Dashboard.

34. On the Data Status table, select the ⋮ (more options) icon on the record's row.
35. Choose View to reopen its Record Details (Section 6.2), Edit to correct a field, or Delete to permanently remove the record.

Figure 9




6.4 Where captured files are stored

Purpose: Understand where the invoice and vehicle images captured at the gate are kept after a record is approved.

Each approved record's Invoice, Vehicle Front, and Vehicle Body images are saved automatically into a folder organized by capture date and Direction (for example, a folder named for the capture date, then Inward or Outward, then a unique record ID). This filing happens automatically — no manual saving or renaming is required.

Figure 10



SECTION 7

Troubleshooting (User-Level)

The result shows a "Partial Extraction Warning"

- This means the extraction engine had trouble structuring the data it read — some fields, line items, or the Site Entry Stamp section may be missing or incorrectly grouped even though the overall status says "Extracted Successfully."
- Check the Fields, Line Items, and Site Entry Stamp panels carefully against the physical document before deciding.
- If key fields (gate pass number, vendor, vehicle number) are missing or wrong, select **Reject** and recapture, or switch to **Manual** mode (Section 5.9).

Extraction reads the wrong document type

- Check the document-type chip (Section 5.1) — if it does not match the physical document (for example it shows cash_memo for what is actually a gate pass), the fields shown may not correspond to what is on the page.
- Reject and recapture with a clearer, fully-visible photo of the document.

Extraction did not read the document correctly

- Confirm the original photo is in focus, well lit, and shows the full document with no corners cut off.
- Recapture rather than approving a poor result — select the card again to retake or re-upload before extracting.
- If the document is genuinely damaged or illegible, switch to **Manual** mode and enter the details by hand.

Extract button is not responding, or extraction is stuck on "Extracting…"

- Confirm the header still shows ● **Online**.
- Wait — extraction can take up to a minute or more, particularly on the Local engine and for multi-page invoices (Timing figures of 30–70 seconds have been observed).
- If it remains stuck well beyond that, close and reopen the browser tab, and recapture the record.

The vehicle number plate was read incorrectly

- Check the Site Entry Stamp panel's Truck Tempo / Truck Tempo Vehicle No fields against the plate photo.
- Recapture the Vehicle Front or Vehicle Body photo with the plate centered, flat, and free of glare before re-extracting.

I approved or rejected a record by mistake

> **WARNING:** Treat Approve and Reject as final once selected. Contact your administrator immediately if you select the wrong one — do not attempt to recapture the same transaction until you have confirmed with them how to proceed.

SECTION 8

Frequently Asked Questions

Q1. Do I need to type anything in for a normal transaction?

No. In Automatic mode you only capture the Invoice, Vehicle Front, and Vehicle Body images — the app reads the data for you. Typing is only needed in Manual mode.

Q2. Why does the Fields panel show so many blank ("—") values?

Every field the document type can contain is listed, whether or not the physical document has it. A blank value simply means that field was not present or not read — check it against the document before treating it as an error.

Q3. What does the "3/3 Captured" indicator mean?

It confirms all three required images — Invoice, Vehicle Front, and Vehicle Body — have been captured or uploaded and the record is ready for extraction.

Q4. What engine processes the documents?

Xtracto Tab uses an on-device Local engine — the combination of PaddleOCR (PP-StructureV3) and NuExtract-3 Q4 — so the terminal reads and extracts every document without depending on an external processing service.

Q5. What should I do if the document type shown looks wrong?

Reject the record and recapture with a clearer photo. See Section 7, "Extraction reads the wrong document type."

Q6. Do I need to read the Raw JSON panel?

No — it is provided for technical reference only. Use the Fields, Line Items, and Site Entry Stamp panels for normal review.

SECTION 9

Glossary

Term	Definition
Approve	The action that confirms an extracted record is correct and finalizes it.
Automatic mode	The default capture mode, in which photographed documents are read by the app without manual typing.
Local engine	The on-device processing engine used to extract data — the combination of PaddleOCR (PP-StructureV3) and NuExtract-3 Q4.
Direction (Inward / Outward)	Whether the vehicle is arriving at (Inward) or leaving (Outward) the site.
Document type	The category of document automatically recognized during extraction, e.g. security_gate_pass, cash_memo.
Extraction	The automated process of reading a photographed document and converting it into structured data (Fields, Line Items, Site Entry Stamp).
Fields panel	The section of the result screen listing every recognized data point as a label/value pair.
Line Items	The itemized table of goods/materials read from the document (description, quantity, tax, and amount columns).
Partial Extraction Warning	A notice shown when the extraction engine could not fully structure the result; some fields or sections may be missing or misplaced.
Reject	The action that discards the current capture attempt.
Returnable mode	The capture mode for tracking items previously sent out that are expected to be returned.
Site Entry Stamp	The sign-off section of a gate pass (vehicle, contractor, authorising person, and security staff details).
Timing panel	Reports how long OCR reading and AI interpretation each took, plus the total.

SECTION 10

Support & Contact Information

For technical support, license renewal, or installation assistance, contact:

DACCESS SECURITY SYSTEMS PVT. LTD

Pune – Corporate Office

Office No. 05, 3rd Floor, Revati Arcade-II,

Opposite to Kapil Malhar Society, Baner Road, Baner,

Pune 411045, Maharashtra, India

Phone: +91 20 4124 1256

Mobile: +91 93702 99634

Toll Free: 1800 209 7799

Email: info@daccess.co | sales@daccess.co

Website: www.daccess.co.in

When contacting support, please have the following ready:

Your installation's **Machine ID** (found on the License Activation screen or under Settings → License)

A brief description of the issue

Screenshots, if applicable

— End of Document —