Metrics

Taken from material by Michael L. Collard

Definitions

- A measure is quantitative indication of extent, amount, dimension, capacity, or size of some attribute of a product or process.
 - E.g., number of faults
- A metric is quantitative measure of degree to which a system, component or process possesses a given attribute
 - E.g., number of faults the system experiences in a year of operation

Why Measure Software?

Determine the quality of the current product or process

Predict qualities of a product/process

Improve quality of a product/process

Examples

- Estimate the cost & schedule of future projects
- Evaluate the productivity impacts of new tools and techniques
- Establish productivity trends over time
- Improve software quality
- Forecast future staffing needs
- Anticipate and reduce future maintenance needs

Metric Classification

Products

- Explicit results of software development activities
- Deliverables, documentation, products

Processes

Activities related to production of software

Resources

- Inputs into the software development activities
- hardware, knowledge, people

Product vs. Process

Process metrics

- Insights of process paradigm, software engineering tasks, work product, or milestones
- Lead to long term process improvement

Product metrics

- Assesses the state of the project
- Track potential risks
- Uncover problem areas
- Adjust workflow or tasks
- Evaluate teams ability to control quality

Types of Measures

- Direct measures (internal attributes)
 - Cost, effort, LOC, speed, memory
- Indirect measures (external attributes)
 - Functionality, quality, complexity, efficiency, reliability, maintainability



Size-oriented Metrics and Measures

Measures:

- Size of the software produced
- LOC Lines Of Code
- KLOC 1000 Lines Of Code
- SLOC Statement Lines of Code
 - Ignore whitespaces, ...

Typical metrics:

 Errors/KLOC, defects/KLOC, cost/LOC, documentation pages/KLOC

Metrics of Software Quality

- Correctness: degree to which a program operates according to specification
 - Defects/KLOC
 - Defect is a verified lack of conformance to requirements
 - Failures/hours of operation
- Maintainability: degree to which a program is open to change
 - Mean time to change
 - Cost to correct
- Integrity: degree to which a program is resilient to attacks
 - Fault tolerance, security & threats
- Usability: easiness to use
 - Training time, skill level necessary to use, increase in productivity, obtained through subjective questionnaire or controlled experiment

McCabe's Complexity Metrics

- McCabe's metrics are based on a control flow representation of the program
- A program graph is used to depict control flow
 - Nodes represent processing tasks
 - That is, one or more code statements
 - Edges represent control flow between nodes
- Cyclomatic complexity: set of independent paths through the graph

Chidamber and Kemerer Metrics

- Weighted methods per class (WMC)
- Depth of inheritance tree (DIT)
- Number of children (NOC)
- Coupling between object classes (CBO)
- Response for class (RFC)
- Lack of cohesion metric (LCOM)

WMC: Weighted Methods per Class

• WMC =
$$\sum_{i=1}^{n} C_i$$

- ..where c_i is the complexity (e.g., volume, cyclomatic complexity, etc.) of each method, n is the number of methods in a class
- The number of methods and complexity of methods is an indicator of how much time and effort is required to develop and maintain a class
- The larger the number of methods in a class, the greater the potential impact on the subclasses
- Classes with a large number of methods are likely to be more application specific, limiting the possible reuse

DIT: Depth of Inheritance Tree

- Maximum length from a node to the root
 - In Java, we only typically consider the first root developed within the project

- Lower level subclasses inherit a number of methods making behavior harder to predict
- Deeper trees indicate greater design complexity

NOC: Number of Children

- Number of subclasses immediately subordinate to a class
- As NOC grows, reuse increases...
 - ...but the abstraction may be "diluted"
- Depth is generally better than breadth in class hierarchy, since it promotes reuse of methods through inheritance
- Classes higher up in the hierarchy should have more subclasses then those lower down
- NOC gives an idea of the potential influence a class has on the design: classes with large number of children may require more testing

CBO: Coupling between Objects/Classes

- Number of collaborations between two classes
 - That is, the fan-out of a class C, which is the number of other classes that are referenced in C
 - A reference to another class A, is a reference to a method or a data member of class A
- As collaboration increases reuse decreases
- High fan-outs represent class coupling to other classes/objects and thus are undesirable
- High fan-ins represent good object designs and high level of reuse
- Not possible to maintain high fan-in and low fan-outs across the entire system

RFC: Response for a Class

- Number of methods that could be called in response to a method invocation to a class
 - -...local and remote

- As RFC increases
 - Testing effort increases
 - The greater the complexity of an object, the harder it is to understand what's going on


LCOM: Lack of Cohesion in Methods

- Number of pairs of methods in a class that don't have at least one field in common minus the number of pairs of methods in the class that do share at least one field
- When this value is negative, the metric value is set to 0
- Lower metric values represent "better" situations


Misure e metriche di stabilità

- CC: numero di classi concrete in un package P
- AC: numero di classi astratte o di interfacce in un package P
- Ca (afferent coupling): numero di package che dipendono da classi del package P
- Ce (efferent coupling): numero di package da cui dipendono le classi del package P
- A (Astrattezza): percentuale di classi astratte del package P, definita come il rapporto AC / (AC + CC)
- I (Instabilità): rapporto fra l'accoppiamento efferente e l'accoppiamento totale Ce / (Ce + Ca)
 - È un indicatore della difficoltà di modificare il package P
 - Se infatti è alto, ciò significa che molti package sarebbero interessati
- D (Distanza dalla sequenza principale): distanza del package P nel piano A,I dalla retta di equazione A + I = 1
 - E' un indicatore del compromesso raggiunto dal package fra astrattezza (A = 1, I = 0) e instabilità (A = 0, I = 1)

Diversi casi



Cosa fare?



- Giochiamo nel piano:
 - Spostare delle classi concrete in package instabili
 - Rendere astratte classi in package stabili

— ...