

Debian / Ubuntu

First you need to import the keys we use to sign packages.

```
wget -qO - https://raw.githubusercontent.com/linux-surface/linux-surface/master  
| gpg --dearmor | sudo dd of=/etc/apt/trusted.gpg.d/linux-surface.gpg
```

After this you can add the repository configuration and update APT.

```
echo "deb [arch=amd64] https://pkg.surfacelinux.com/debian release main" \  
| sudo tee /etc/apt/sources.list.d/linux-surface.list
```

```
sudo apt update
```

If you encounter any issues reading "Error 401 Unauthorized" during the update or the installation below, please have a look at [this](#).

Now you can install the linux-surface kernel and its dependencies.

```
sudo apt install linux-image-surface linux-headers-surface libwacom-surface ip
```

Ubuntu 26.04: Due to a [bug](#), don't install `libwacom-surface` .

Important: Support for `iptsd` only goes back to the latest LTS release at the time of writing (Debian 11 and Ubuntu 22.04). If you are using an older release, and the above command fails, then please remove `iptsd` from it. You will still be able to use basic singletouch through the kernel driver, but multitouch and the stylus will not work.

After that you can install our secureboot key. This will import the key that the linux-surface kernel is signed with into your bootloader, so that the kernel is bootable without disabling secureboot.

```
sudo apt install linux-surface-secureboot-mok
```

This package will print instructions to the terminal. In case you missed those, it will ask you to reboot. Then, upon reboot, a blue menu (MokManager) should pop up, asking you whether you want to enroll the key. You need to interact with the menu and select "Enroll" to

proceed. Confirm with `ok / yes` and when asked for a password enter `surface`. Note that MokManager expects a QWERTY keyboard layout, you may need to adjust your input accordingly. In case you missed the menu or accidentally chose the wrong options, you can uninstall (fully) and then reinstall the package and reboot to trigger the menu again.

Note that this will only work if your Debian derivative supports secure boot out-of-the-box. If not, please consult the wiki of your distribution and set up secure boot for distro/stock kernels first. You also want to skip installing the package for now and only install it after you have set this up.

The linux-surface kernel will be installed alongside the default kernel provided by the distribution. This way you have a backup kernel you can use if something goes wrong. The bootloader will pick up the kernel by default, but you should update its configuration to make sure it was recognized.

```
sudo update-grub
```

Finally, reboot your system and you should boot into the linux-surface kernel. Please make sure you are actually using the right kernel by checking if the output of `uname -a` contains the string `surface`. If it doesn't contain that string, you are still using the default kernel and need to configure your bootloader.