
TABLE_DIM recipe

The TABLE_DIM table I created for my data model contains the What (database TABLE?) for the model. This will allow us to meet the requirement around being able to drill to the detail of table.




Source-to-target mappings:

| Source table | Source column | Target table | Target column | Transformation / notes |
|---|---|---|---|---|
| Oracle_roles_to_tables | Owner | Table_dim | Table_owner | |
| Oracle_roles_to_tables | Table_name | Table_dim | Table_name | |


Since all the columns are coming from one table audit_src.oracle_roles_to_tables, this is an easy dimension to build.

**Load Table:**


Create a load table for oracle_roles_to_tables. Remember to use your audit_src connection for load tables.

**Stage Table:**


1) In left pane, double click "Stage Table", so stage table is the focus of middle pane.
2) In right pane, change your connection to your Data Warehouse connection.
3) In right pane, select your load_oracle_roles_to_tables table and drag to middle pane.
4) In the "Add a New Metadata Object" screen, rename object Name to "stage_table", then click add.





5) For the “Stage Table stage_table” screen, simply click OK.
6) Delete all of the columns from the middle pane, EXCEPT: owner & table_name. Right click on column, select “Delete Column”, then when asked “Coninute to delete 1 column?”, click YES.





7) Once you have deleted all but the owner and table_name columns, it should look like this:





8) In left pane, right click stage_table, then select “create(recreate)”.
9) In left pane, right click stage_table, then select “code > rebuild update procedure”.
10) For the “define stage procedure type” screen, check the “Allow modification of the Where Clause”, then click “Set”. See screenshot below.




11) For the “Select Parameters” screen, simply click OK.
12) Add the following code below the existing code in the Join Query code box:
    GROUP BY load_oracle_roles_to_tables.owner,
    load_oracle_roles_to_tables.table_name





13) Click “Finish”
14) In left pane, right click stage_table, then select “execute update procedure”.




*Notice that there are much fewer records in the stage_table versus the load table source. The Group BY code grouped by owner and table_name, so we wont have any duplicate values in our dimension table.*

**TABLE_DIM:**

1) In left pane, double click Dimension, so Dimension becomes the focus of the middle pane.
2) In right pane, click the blue sunglasses, to refresh your data warehouse connection.
3) In right pane, select stage_table and drag to middle pane.
4) In the "Add a New Metadata Object" screen change name to table_dim, then click Add.





5) For Dimension Type, select "Normal".
6) For the "Dimension table_dim" screen, simply select OK.
7) For the "Create Database Table" screen, select "Close".
8) Looking at my data model, I need to rename the owner column to table_owner. Double click the owner row, then type in the new name.


table_dim Columns

| Column Name | Display Name | Data Type | Source Table | Source Column |
|---|---|---|---|---|
| table_dim_key | table dim key | integer | | table_dim_key |
| table_owner | table owner | varchar2(40) | stage_table | owner |
| table_name | table name | varchar2(40) | stage_table | table_name |
| dss_create_time | dss create time | date | | dss_create_time |
| dss_update_time | dss update time | date | | dss_update_time |

9) Optionally you may drop the two dss_ columns.
10) In left pane, right click table_dim, then select "create(recreate)".
11) In left pane, right click table_dim, then select "code > rebuild update procedure".
12) For the Procedure Build Type, select "Set", then OK.
13) Click the box far right of "Business Key Columns". The move the two needed business key columns table_owner & table_name. finally, click OK. See screen shot below.




14) In left pane, right click table_dim, then select “execute update procedure”.




15) In left pane, right click table_dim, then select “display data”. How does it look?

