The following table explains each field of the Define PFD Specifications display.

Field Name	D Specifications display fields Description	
Printer type	Specifies the printer type you are going to use. You can use 1, 2, 3, 4, 5, 6, 7 and 9 for printer type. These values previously supported, and will continue to support, the following printer types:	
	1	4224, 4234, 4230
	2	3812, 3816, 3930
	3	3916, 4028
	4	3820, 3825, 3827, 3829, 3835, 3900
	5	3825, 3835, 3900 with the Advanced Function Image and Graphics feature
	6	3831
	7	3935
	9	Not specified
	*DEFAULT also means Not specified. If *DEFAULT or 9 is specified, the Confirm or Change Printer Attributes screen is displayed to let you specify attributes for your printer type. If you know the attributes of your printer, but the printer is not supported by the current release of, use this screen to specify the attributes. For example, if you specify that your printer supports the Bar Code Object Content Architecture (BCOCA), the printer data stream for bar codes will be created with BCOCA. However, if you specify that your printer does not support BCOCA, the bar codes will be created with the Presentation Text Object Content Architecture (PTOCA). PTOCA bar codes can be printed on any IPDS printer, but BCOCA bar codes print much faster.	
	Any valid four-digit IBM IPDS printer type may also be specified. The field level help for this parameter shows a list of the printers supported for each release after Version 3, Release 2. As new printers are added and supported, their four-digit type number will be added to the list of printers supported. Because this may occur between releases, the list may not be complete.	
	The spe	ecified value is used to:
	• Chec	k if each element is supported by the printer.
	• Crea	te the appropriate data stream for each printer.
Characters per inch	differer Specifie charact	ppendix A. Printer Characteristics" on page 417 for the nees among printers. es the number of characters per inch to print. A double-byte er is counted as two. You can choose 5.00, 10.00, 12.00, 13.30, 6.70, 18.00 and 20.00 for the CPI. The default value is 10.00.
		lue is used to decide horizontal positions when the ement method is Row/Column.
	This va	lue is used to decide the horizontal positions of the text in the

box element.