

Packet Tracer - Configure DHCPv4

Name: Danica Marie Dumalagan

Date: March 24, 2023

Addressing Table

Device	Interface	IPv4 Address	Subnet Mask	Default Gateway
R1	G0/0	192.168.10.1	255.255.255.0	N/A
	S0/0/0	10.1.1.1	255.255.255.252	N/A
R2	G0/0	192.168.20.1	255.255.255.0	N/A
	G0/1	DHCP Assigned	DHCP Assigned	N/A
	S0/0/0	10.1.1.2	255.255.255.252	N/A
	S0/0/1	10.2.2.2	255.255.255.252	N/A
R3	G0/0	192.168.30.1	255.255.255.0	N/A
	S0/0/1	10.2.2.1	255.255.255.0	N/A
PC1	NIC	DHCP Assigned	DHCP Assigned	DHCP Assigned
PC2	NIC	DHCP Assigned	DHCP Assigned	DHCP Assigned
DNS Server	NIC	192.168.20.254	255.255.255.0	192.168.20.1

Objectives

Part 1: Configure a Router as a DHCP Server

Part 2: Configure DHCP Relay

Part 3: Configure a Router as a DHCP Client

Part 4: Verify DHCP and Connectivity

Scenario

A dedicated DHCP server is scalable and relatively easy to manage but it can be costly to have one at every location in a network. However, a Cisco router can be configured to provide DHCP services without the need for a dedicated server. As the network technician for your company, you have been assigned the task of configuring a Cisco router as a DHCP server. You are also required to configure the edge router as a DHCP client so that it receives an IP address from the ISP network.

Instructions

Part 1: Configure a Router as a DHCP Server

Step 1: Configure the excluded IPv4 addresses.

Addresses that have been statically assigned to devices in the networks that will use DHCP must be excluded from the DHCP pools. This avoids errors associated with duplicate IP addresses. In this case the IP addresses of the R1 and R3

LAN interfaces must be excluded from DHCP. In addition, nine other addresses are excluded for static assignment to other devices such servers and device management interfaces.

a. Configure R2 to exclude the first 10 addresses from the R1 LAN.

```
R2(config) # ip dhcp excluded-address 192.168.10.1 192.168.10.10
```

b. Configure **R2** to exclude the first 10 addresses from R3 LAN.

Step 2: Create a DHCP pool on R2 for the R1 LAN.

a. Create a DHCP pool named R1-LAN (case-sensitive).

```
R2(config) # ip dhcp pool R1-LAN
```

b. Configure the DHCP pool to include the network address, the default gateway, and the IP address of the DNS server.

```
R2(dhcp-config) # network 192.168.10.0 255.255.255.0
R2(dhcp-config) # default-router 192.168.10.1
R2(dhcp-config) # dns-server 192.168.20.254
```

Step 3: Create a DHCP pool on R2 for the R3 LAN.

- a. Create a DHCP pool named R3-LAN (case-sensitive).
- b. Configure the DHCP pool to include the network address, the default gateway, and the IP address of the DNS server. Refer to the Addressing Table.

Part 2: Configure DHCP Relay

Step 1: Configure R1 and R3 as a DHCP relay agent.

For DHCP clients to obtain an address from a server on a different LAN segment, the interface that the clients are attached to must include a helper address pointing to the DHCP server. In this case, the hosts on the LANs that are attached to R1 and R3 will access the DHCP server that is configured on R2. The IP addresses of the R2 serial interfaces that are attached to R1 and R3 are used as the helper addresses. DHCP traffic from the hosts on the R1 and R3 LANs will be forwarded to these addresses and processed by the DHCP server that is configured on R2.

a. Configure the helper address for the LAN interface on R1.

```
R1(config) # interface g0/0
R1(config-if) # ip helper-address 10.1.1.2
```

b. Configure the helper address for the LAN interface on R3.

Step 2: Configure hosts to receive IP addressing information from DHCP.

- a. Configure hosts PC1 and PC2 to receive their IP addresses from a DHCP server.
- b. Verify that the hosts have received their addresses from the correct DHCP pools.

Part 3: Configure a Router as a DHCP Client

Just as a PC is able to receive an IPv4 address from a server, a router interface has the ability to do the same. Router R2 needs to be configured to receive addressing from the ISP.

a. Configure the Gigabit Ethernet 0/1 interface on R2 to receive IP addressing from DHCP and activate the interface.

```
R2(config) # interface g0/1
R2(config-if) # ip address dhcp
R2(config-if) # no shutdown
```

Note: Use Packet Tracer's Fast Forward Time feature to speed up the process.

b. Use the **show ip interface brief** command to verify that R2 received an IP address from DHCP.

Part 4: Verify DHCP and Connectivity

Step 1: Verify DHCP bindings.

R2# show ip dhcp binding IP address Client-ID/

IP address	Client-ID/	Lease expiration	Type
	Hardware address		
192.168.10.11	0002.4AA5.1470		Automatic
192.168.30.11	0004.9A97.2535		Automatic

Step 2: Verify configurations.

Verify that PC1 and PC2 can now ping each other and all other devices.

Part 5: Post your screenshots

On the PT Activity window, make sure that the completion grade is **100%**. Click on the **Check Results** button and select the **Assessment Items** tab. Take a screen shot of the whole window, showing the table of assessment items, and the score/item count. Own your photo by placing a watermark on your photo with your name and USC ID Number. Paste your screenshot below:

