

A Consumer Library Interface to DWARF

David Anderson

ABSTRACT

This document describes an interface to a library of functions to access DWARF debugging information entries, DWARF line number information, and other DWARF2/3/4/5 information).

There are a few sections which are SGI-specific (those are clearly identified in the document).

Starting December 2020 we rearrange the pdf that GNU groff -mm gives us (mm is not exceptionally flexible) using tools pdftotext, pdfseparate, and pdfunite from the poppler-utils package for debian/ubuntu. We hope the new arrangement with the table of contents following this page followed by the library documentation itself makes the document easier to navigate.

Rev 3.25 02 February 2021

CONTENTS

1. INTRODUCTION	16
1.1 Copyright	16
1.2 Purpose and Scope	16
1.3 Document History	17
1.4 Definitions	17
1.5 Overview	17
1.6 Items Changed	18
1.7 Items Removed	23
1.8 Revision History	23
2. Types Definitions	24
2.1 General Description	24
2.2 Scalar Types	24
2.3 Aggregate Types	25
2.3.1 Location Record	26
2.3.2 Location Description	26
2.3.3 Data Block	27
2.3.4 Frame Operation Codes: DWARF 2	28
2.3.5 Frame Regtable: DWARF 2	29
2.3.6 Frame Operation Codes: DWARF 3 (for DWARF2 and later)	29
2.3.7 Frame Regtable: DWARF 3 (for DWARF2 and later)	30
2.3.8 Macro Details Record	31
2.4 Opaque Types	32
3. UTF-8 strings	36
4. Error Handling	36
4.1 Returned values in the functional interface	39
5. Memory Management	40
5.1 Read-only Properties	41
5.2 Storage Deallocation	41
5.2.1 dwarf_dealloc()	41
5.2.2 dwarf_dealloc_die()	41
5.2.3 dwarf_dealloc_attribute()	42
5.2.4 dwarf_dealloc_error()	42
5.2.5 Errors Returned from dwarf_init* calls	43
5.2.6 Error DW_DLA error free types	46

6. Functional Interface	48
6.1 Initialization Operations	48
6.1.1 dwarf_init_path()	48
6.1.2 dwarf_init_path_dl()	50
6.1.3 dwarf_init_b()	51
6.1.4 dwarf_init()	52
6.1.5 dwarf_set_de_alloc_flag()	52
6.1.6 Dwarf_Handler function	53
6.1.7 dwarf_elf_init_b() [deprecated 2019]	53
6.1.8 dwarf_elf_init() [deprecated 2019]	54
6.1.9 dwarf_get_elf()	54
6.1.10 dwarf_set_tied_dbg()	54
6.1.11 dwarf_get_tied_dbg()	56
6.1.12 dwarf_finish()	56
6.1.13 dwarf_set_stringcheck()	56
6.1.14 dwarf_set_reloc_application()	56
6.1.15 dwarf_record_cmdline_options()	57
6.1.16 dwarf_object_init_b()	57
6.1.17 dwarf_object_init()	58
6.1.18 dwarf_get_real_section_name()	58
6.1.19 dwarf_package_version()	59
6.2 Object Type Detectors	59
6.2.1 dwarf_object_detector_path()	59
6.2.2 dwarf_object_detector_fd()	61
6.3 Section Group Operations	61
6.3.1 dwarf_sec_group_sizes()	61
6.3.2 dwarf_sec_group_map()	62
6.4 Section size operations	65
6.4.1 dwarf_get_section_max_offsets_b()	65
6.4.2 dwarf_get_section_max_offsets()	65
6.5 Printf Callbacks	66
6.5.1 dwarf_register_printf_callback	66
6.5.2 Dwarf_Printf_Callback_Info_s	67
6.5.3 dwarf_printf_callback_function_type	67
6.5.4 Example of printf callback use in a C++ application using libdwarf	68
6.6 Debugging Information Entry Delivery Operations	68
6.6.1 dwarf_get_die_section_name()	68
6.6.2 dwarf_get_die_section_name_b()	69
6.6.3 dwarf_next_cu_header_d()	69

6.6.4	dwarf_next_cu_header_c()	71
6.6.5	dwarf_next_cu_header_b()	72
6.6.6	dwarf_next_cu_header()	72
6.6.7	dwarf_siblingof_b()	72
6.6.8	dwarf_siblingof()	74
6.6.9	dwarf_child()	74
6.6.10	dwarf_offdie_b()	75
6.6.11	dwarf_offdie()	76
6.6.12	dwarf_validate_die_sibling()	76
6.7	Debugging Information Entry Query Operations	77
6.7.1	dwarf_get_die_infotypes_flag()	77
6.7.2	dwarf_cu_header_basics()	78
6.7.3	dwarf_tag()	78
6.7.4	dwarf_dieoffset()	78
6.7.5	dwarf_addr_form_is_indexed()	79
6.7.6	dwarf_debug_addr_index_to_addr()	79
6.7.7	dwarf_die_CU_offset()	79
6.7.8	dwarf_die_offsets()	80
6.7.9	dwarf_ptr_CU_offset()	80
6.7.10	dwarf_CU_dieoffset_given_die()	80
6.7.11	dwarf_die_CU_offset_range()	81
6.7.12	dwarf_diename()	82
6.7.13	dwarf_die_text()	82
6.7.14	dwarf_die_abbrev_code()	83
6.7.15	dwarf_die_abbrev_children_flag()	83
6.7.16	dwarf_die_abbrev_global_offset()	83
6.7.17	dwarf_get_version_of_die()	83
6.7.18	dwarf_attrlist()	84
6.7.19	dwarf_hasattr()	85
6.7.20	dwarf_attr()	85
6.7.21	dwarf_lowpc()	86
6.7.22	dwarf_highpc_b()	86
6.7.23	dwarf_highpc()	87
6.7.24	dwarf_dietype_offset()	87
6.7.25	dwarf_offset_list()	87
6.7.26	dwarf_bytessize()	88
6.7.27	dwarf_bitsize()	88
6.7.28	dwarf_bitoffset()	89
6.7.29	dwarf_srclang()	89
6.7.30	dwarf_arrayorder()	89

6.8	Attribute Queries	89
6.8.1	dwarf_hasform()	90
6.8.2	dwarf_whatform()	90
6.8.3	dwarf_whatform_direct()	90
6.8.4	dwarf_whatattr()	91
6.8.5	dwarf_formref()	91
6.8.6	dwarf_global_formref()	91
6.8.7	dwarf_convert_to_global_offset()	92
6.8.8	dwarf_formaddr()	92
6.8.9	dwarf_get_debug_str_index()	93
6.8.10	dwarf_formflag()	94
6.8.11	dwarf_formudata()	94
6.8.12	dwarf_formsdata()	94
6.8.13	dwarf_formblock()	95
6.8.14	dwarf_formstring()	95
6.8.15	dwarf_formsig8()	95
6.8.16	dwarf_formexprloc()	96
6.8.17	dwarf_get_form_class()	96
6.8.18	dwarf_discr_list()	97
6.8.19	dwarf_discr_entry_u()	100
6.8.20	dwarf_discr_entry_s()	100
6.9	Location List Operations, Raw .debug_loclists	100
6.9.1	dwarf_load_loclists()	103
6.9.2	dwarf_get_loclist_context_basics()	104
6.9.3	dwarf_get_loclist_offset_index_value()	105
6.9.4	dwarf_get_loclist_lle()	105
6.10	Location List operations .debug_loc & .debug_loclists	106
6.10.1	dwarf_get_loclist_c()	106
6.10.2	dwarf_get_locdesc_entry_d()	110
6.10.3	dwarf_get_locdesc_entry_c()	111
6.10.4	dwarf_get_loclist_head_kind()	112
6.10.5	dwarf_get_location_op_value_d()	112
6.10.6	dwarf_loclist_from_expr_c()	113
6.10.7	dwarf_loc_head_c_dealloc()	116
6.10.8	dwarf_loclist_n()	116
6.10.9	dwarf_loclist()	118
6.10.10	dwarf_loclist_from_expr()	119
6.10.11	dwarf_loclist_from_expr_b()	120
6.10.12	dwarf_loclist_from_expr_a()	120
6.11	Line Number Operations	121

6.11.1	Get A Set of Lines (including skeleton line tables)	122
6.11.2	dwarf_srclines_b()	122
6.11.3	dwarf_get_line_section_name_from_die()	122
6.11.4	dwarf_srclines_from_linecontext()	123
6.11.5	dwarf_srclines_two_levelfrom_linecontext()	123
6.11.6	dwarf_srclines_dealloc_b()	124
6.12	Line Context Details (DWARF5 style)	128
6.12.1	dwarf_srclines_table_offset()	128
6.12.2	dwarf_srclines_version()	128
6.12.3	dwarf_srclines_comp_dir()	128
6.12.4	dwarf_srclines_files_indexes()	129
6.12.5	dwarf_srclines_files_count()	129
6.12.6	dwarf_srclines_files_data_b()	129
6.12.7	dwarf_srclines_files_data()	130
6.12.8	dwarf_srclines_include_dir_count()	131
6.12.9	dwarf_srclines_include_dir_data()	131
6.12.10	dwarf_srclines_subprog_count()	131
6.12.11	dwarf_srclines_subprog_data()	131
6.13	Get A Set of Lines (DWARF2,3,4 style)	132
6.13.1	dwarf_srclines()	132
6.14	Get the set of Source File Names	133
6.14.1	dwarf_srcfiles()	133
6.15	Get Information About a Single Line Table Line	135
6.15.1	dwarf_linebeginstatement()	135
6.15.2	dwarf_lineendsequence()	135
6.15.3	dwarf_lineno()	136
6.15.4	dwarf_line_srcfileno()	136
6.15.5	dwarf_lineaddr()	136
6.15.6	dwarf_lineoff()	137
6.15.7	dwarf_lineoff_b()	137
6.15.8	dwarf_linesrc()	137
6.15.9	dwarf_lineblock()	138
6.15.10	dwarf_is_addr_set()	138
6.15.11	dwarf_prologue_end_etc()	139
6.16	Accelerated Access By Name operations	139
6.16.1	Fine Tuning Accelerated Access	139
6.16.1.1	dwarf_return_empty_pubnames	139
6.16.1.2	dwarf_get_globals_header	140
6.16.2	Accelerated Access Pubnames	141
6.16.2.1	dwarf_get_globals()	141

6.16.2.2	dwarf_globname()	142
6.16.2.3	dwarf_global_die_offset()	143
6.16.2.4	dwarf_global_cu_offset()	143
6.16.2.5	dwarf_get_cu_die_offset_given_cu_header_offset()	...	143
6.16.2.6	dwarf_get_cu_die_offset_given_cu_header_offset()	...	144
6.16.2.7	dwarf_global_name_offsets()	144
6.16.3	Accelerated Access Pubtypes	145
6.16.3.1	dwarf_get_pubtypes()	145
6.16.3.2	dwarf_pubtypename()	146
6.16.3.3	dwarf_pubtype_type_die_offset()	146
6.16.3.4	dwarf_pubtype_cu_offset()	147
6.16.3.5	dwarf_pubtype_name_offsets()	147
6.16.4	Accelerated Access Weaknames	147
6.16.4.1	dwarf_get_weaks()	148
6.16.4.2	dwarf_weakname()	149
6.16.4.3	dwarf_weak_cu_offset()	150
6.16.4.4	dwarf_weak_name_offsets()	150
6.16.5	Accelerated Access Funcnames	150
6.16.5.1	dwarf_get_funcs()	151
6.16.5.2	dwarf_funcname()	152
6.16.5.3	dwarf_func_die_offset()	152
6.16.5.4	dwarf_func_cu_offset()	153
6.16.5.5	dwarf_func_name_offsets()	153
6.16.6	Accelerated Access Typenames	153
6.16.6.1	dwarf_get_types()	153
6.16.6.2	dwarf_typename()	155
6.16.6.3	dwarf_type_die_offset()	155
6.16.6.4	dwarf_type_cu_offset()	156
6.16.6.5	dwarf_type_name_offsets()	156
6.16.7	Accelerated Access varnames	156
6.16.7.1	dwarf_get_vars()	157
6.16.7.2	dwarf_varname()	158
6.16.7.3	dwarf_var_die_offset()	158
6.16.7.4	dwarf_var_cu_offset()	159
6.16.7.5	dwarf_var_name_offsets()	159
6.17	Names Fast Access (DWARF5) .debug_names	159
6.17.1	dwarf_debugnames_header()	159
6.17.2	dwarf_debugnames_sizes()	160
6.17.3	dwarf_debugnames_cu_entry()	161
6.17.4	dwarf_debugnames_local_tu_entry()	161

6.17.5	dwarf_debugnames_foreign_tu_entry()	162
6.17.6	dwarf_debugnames_bucket()	162
6.17.7	dwarf_debugnames_name()	162
6.17.8	dwarf_debugnames_abbrev_by_index()	163
6.17.9	dwarf_debugnames_abbrev_by_code()	163
6.17.10	dwarf_debugnames_form_by_index()	163
6.17.11	dwarf_debugnames_entrypool()	163
6.17.12	dwarf_debugnames_entrypool_values()	164
6.18	Names Fast Access .debug_gnu_pubnames	164
6.18.1	dwarf_get_gnu_index_head()	164
6.18.2	dwarf_gnu_index_dealloc()	165
6.18.3	dwarf_get_gnu_index_block()	165
6.18.4	dwarf_get_gnu_index_block_entry()	166
6.19	Macro Information Operations (DWARF4, DWARF5)	167
6.19.1	Getting access	167
6.19.1.1	dwarf_get_macro_context()	167
6.19.1.2	dwarf_get_macro_context_by_offset()	168
6.19.1.3	dwarf_macro_context_total_length()	168
6.19.1.4	dwarf_dealloc_macro_context()	169
6.19.2	Getting Macro Unit Header Data	173
6.19.2.1	dwarf_macro_context_head()	173
6.19.2.2	dwarf_macro_operands_table()	174
6.19.3	Getting Individual Macro Operations Data	175
6.19.3.1	dwarf_get_macro_op()	175
6.19.3.2	dwarf_get_macro_defundef()	176
6.19.3.3	dwarf_get_macro_startend_file()	177
6.19.3.4	dwarf_get_macro_import()	177
6.20	Macro Information Operations (DWARF2, DWARF3, DWARF4)	178
6.20.1	General Macro Operations	178
6.20.1.1	dwarf_find_macro_value_start()	178
6.20.2	Debugger Interface Macro Operations	178
6.20.3	Low Level Macro Information Operations	178
6.20.3.1	dwarf_get_macro_details()	178
6.21	Low Level Frame Operations	181
6.21.1	dwarf_get_frame_section_name()	184
6.21.2	dwarf_get_frame_section_name_eh_gnu()	184
6.21.3	dwarf_get_fde_list()	185
6.21.4	dwarf_get_fde_list_eh()	187
6.21.5	dwarf_get_cie_of_fde()	189

6.21.6	dwarf_get_fde_for_die()	190
6.21.7	dwarf_get_fde_range()	190
6.21.8	dwarf_get_cie_info()	191
6.21.9	dwarf_get_cie_index()	192
6.21.10	dwarf_get_fde_instr_bytes()	192
6.21.11	dwarf_get_fde_info_for_reg()	193
6.21.12	dwarf_get_fde_info_for_all_regs()	193
6.21.13	dwarf_fde_section_offset()	194
6.21.14	dwarf_cie_section_offset()	194
6.21.15	dwarf_set_frame_rule_table_size()	195
6.21.16	dwarf_set_frame_rule_initial_value()	195
6.21.17	dwarf_set_frame_cfa_value()	196
6.21.18	dwarf_set_frame_same_value()	196
6.21.19	dwarf_set_frame_undefined_value()	197
6.21.20	dwarf_set_default_address_size()	197
6.21.21	dwarf_get_fde_info_for_reg3()	197
6.21.22	dwarf_get_fde_info_for_reg3_b()	199
6.21.23	dwarf_get_fde_info_for_cfa_reg3()	200
6.21.24	dwarf_get_fde_info_for_cfa_reg3_b()	200
6.21.25	dwarf_get_fde_info_for_all_regs3()	201
6.21.26	dwarf_get_fde_n()	202
6.21.27	dwarf_get_fde_at_pc()	202
6.21.28	dwarf_expand_frame_instructions()	203
6.21.29	dwarf_get_fde_exception_info()	204
6.22	Location Expression Evaluation	204
6.22.1	Location List Internal-level Interface	205
6.22.1.1	dwarf_get_loclist_entry()	205
6.23	Abbreviations access	205
6.23.1	dwarf_get_abbrev()	205
6.23.2	dwarf_get_abbrev_tag()	206
6.23.3	dwarf_get_abbrev_code()	206
6.23.4	dwarf_get_abbrev_children_flag()	207
6.23.5	dwarf_get_abbrev_entry_b()	207
6.23.6	dwarf_get_abbrev_entry()	208
6.24	String Section Operations	208
6.24.1	dwarf_get_string_section_name()	208
6.24.2	dwarf_get_str()	209
6.25	String Offsets Section Operations	209
6.25.1	dwarf_open_str_offsets_table_access()	211
6.25.2	dwarf_close_str_offsets_table_access()	211

6.25.3	dwarf_next_str_offsets_table()	212
6.25.4	dwarf_str_offsets_value_by_index()	213
6.25.5	dwarf_str_offsets_statistics()	213
6.26	Address Range Operations	214
6.26.1	dwarf_get_aranges_section_name()	214
6.26.2	dwarf_get_aranges()	214
6.26.3	dwarf_get_arange()	215
6.26.4	dwarf_get_cu_die_offset()	216
6.26.5	dwarf_get_arange_cu_header_offset()	216
6.26.6	dwarf_get_arange_info_b()	216
6.26.7	dwarf_get_arange_info()	217
6.27	General Low Level Operations	217
6.27.1	dwarf_get_offset_size()	217
6.27.2	dwarf_get_address_size()	217
6.27.3	dwarf_get_die_address_size()	218
6.27.4	dwarf_decode_leb128()	218
6.27.5	dwarf_decode_signed_leb128()	219
6.28	Ranges Operations DWARF5 (.debug_rnglists)	219
6.28.1	Getting rnglists data for a DIE	220
6.28.1.1	dwarf_rnglists_get_rle_head()	222
6.28.1.2	dwarf_get_rnglist_head_basics()	223
6.28.1.3	dwarf_get_rnglists_entry_fields_a()	223
6.28.1.4	dwarf_get_rnglists_entry_fields()	224
6.28.1.5	dwarf_dealloc_rnglists_head()	225
6.28.2	Getting raw .debug_rnglists entries	225
6.28.2.1	dwarf_load_rnglists()	227
6.28.2.2	dwarf_get_rnglist_context_basics()	228
6.28.2.3	dwarf_get_rnglist_offset_index_value()	229
6.28.2.4	dwarf_get_rnglist_rle()	229
6.29	Ranges Operations DWARF3,4 (.debug_ranges)	230
6.29.1	dwarf_get_ranges_section_name()	230
6.29.2	dwarf_get_ranges()	231
6.29.3	dwarf_get_ranges_a()	231
6.29.4	dwarf_get_ranges_b()	231
6.29.5	dwarf_ranges_dealloc()	233
6.30	Gdb Index operations	233
6.30.1	dwarf_gdbindex_header()	234
6.30.2	dwarf_gdbindex_culist_array()	237
6.30.3	dwarf_gdbindex_culist_entry()	237
6.30.4	dwarf_gdbindex_types_culist_array()	238

6.30.5	dwarf_gdbindex_types_culist_entry()	238
6.30.6	dwarf_gdbindex_addressarea()	239
6.30.7	dwarf_gdbindex_addressarea_entry()	239
6.30.8	dwarf_gdbindex_symboltable_array()	240
6.30.9	dwarf_gdbindex_symboltable_entry()	243
6.30.10	dwarf_gdbindex_cuvector_length()	243
6.30.11	dwarf_gdbindex_cuvector_inner_attributes()	244
6.30.12	dwarf_gdbindex_cuvector_instance_expand_value()	244
6.30.13	dwarf_gdbindex_string_by_offset()	245
6.31	GNU linking (.gnu_debuglink, .note.gnu.build-id) operations	245
6.31.1	dwarf_gnu_debuglink()	246
6.31.2	dwarf_add_debuglink_global_path()	249
6.31.3	dwarf_crc32()	250
6.31.4	dwarf_basic_crc32()	250
6.32	DWARF5 .debug_sup section access	250
6.32.1	dwarf_get_debug_sup()	250
6.33	Debug Fission (.debug_tu_index, .debug_cu_index) operations	251
6.33.1	Dwarf_Debug_Fission_Per CU	252
6.33.2	dwarf_die_from_hash_signature()	253
6.33.3	dwarf_get_debugfission_for_die()	253
6.33.4	dwarf_get_debugfission_for_key()	254
6.33.5	dwarf_get_xu_index_header()	254
6.33.6	dwarf_get_xu_index_section_type()	256
6.33.7	dwarf_get_xu_header_free()	257
6.33.8	dwarf_get_xu_hash_entry()	257
6.33.9	dwarf_get_xu_section_names()	258
6.33.10	dwarf_get_xu_section_offset()	259
6.34	TAG ATTR etc names as strings	261
6.34.1	dwarf_get_ACCESS_name()	263
6.34.2	dwarf_get_AT_name()	263
6.34.3	dwarf_get_ATE_name()	263
6.34.4	dwarf_get_ADDR_name()	263
6.34.5	dwarf_get_ATCF_name()	263
6.34.6	dwarf_get_CHILDREN_name()	263
6.34.7	dwarf_get_children_name()	263
6.34.8	dwarf_get_CC_name()	263
6.34.9	dwarf_get_CFA_name()	263
6.34.10	dwarf_get_DS_name()	263
6.34.11	dwarf_get_DSC_name()	263
6.34.12	dwarf_get_EH_name()	263

6.34.13 dwarf_get_END_name()	264
6.34.14 dwarf_get_FORM_name()	264
6.34.15 dwarf_get_FRAME_name()	264
6.34.16 dwarf_get_ID_name()	264
6.34.17 dwarf_get_INL_name()	264
6.34.18 dwarf_get_LANG_name()	264
6.34.19 dwarf_get_LLE_name()	264
6.34.20 dwarf_get_LNE_name()	264
6.34.21 dwarf_get_LNS_name()	264
6.34.22 dwarf_get_MACINFO_name()	264
6.34.23 dwarf_get_MACRO_name()	264
6.34.24 dwarf_get_OP_name()	264
6.34.25 dwarf_get_ORD_name()	264
6.34.26 dwarf_get_TAG_name()	264
6.34.27 dwarf_get_VIRTUALITY_name()	265
6.34.28 dwarf_get_VIS_name()	265
6.34.29 dwarf_get_FORM_CLASS_name()	265
6.35 Section Operations	265
6.35.1 dwarf_get_section_count()	265
6.35.2 dwarf_get_section_info_by_name()	266
6.35.3 dwarf_get_section_info_by_index()	266
6.36 Utility Operations	266
6.36.1 dwarf_errno()	266
6.36.2 dwarf_errmsg()	267
6.36.3 dwarf_errmsg_by_number()	267
6.36.4 dwarf_get_endian_copy_function()	267
6.36.5 dwarf_get_harmless_error_list()	268
6.36.6 dwarf_insert_harmless_error()	269
6.36.7 dwarf_set_harmless_error_list_size()	269
6.36.8 dwarf_dealloc()	272
6.36.9 dwarf_encode_leb128()	272
6.36.10 dwarf_encode_signed_leb128()	272
6.37 Finding Memory Leaks	272
6.37.1 Compiling libdwarf -DDEBUG=1	273
6.37.2 Making use of the output of -DDEBUG=1	273

LIST OF FIGURES

Figure 1.	Scalar Types	25
Figure 2.	Error Indications	39
Figure 3.	Example_dwarf_dealloc()	41
Figure 4.	Example_dwarf_dealloc_die()	42
Figure 5.	Example_dwarf_dealloc_attribute()	42
Figure 6.	Example_dwarf_dealloc_error()	42
Figure 7.	Example1 dwarf_attrlist()	43
Figure 8.	Allocation/Deallocation Identifiers	47
Figure 9.	Example2 dwarf_set_died_dbg()	55
Figure 10.	Example3 dwarf_set_tied_dbg() obsolete	55
Figure 11.	Example4 dwarf_siblingof()	73
Figure 12.	Example5 dwarf_child()	74
Figure 13.	Example6 dwarf_offdie_b()	75
Figure 14.	Example7 dwarf_CU_dieoffset_given_die()	81
Figure 15.	Example8 dwarf_attrlist() free	84
Figure 16.	Exampleoffset_list dwarf_offset_list() free	88
Figure 17.	Example Raw Loclist	101
Figure 18.	Examplea dwarf_loclist()	119
Figure 19.	Exampleb dwarf_loclist_from_expr()	120
Figure 20.	Examplec dwarf_srclines_b()	124
Figure 21.	Exampled dwarf_srclines()	132
Figure 22.	Exampled dwarf_srcfiles()	134
Figure 23.	Exampled dwarf_get_globals()	141
Figure 24.	Exampled dwarf_get_pubtypes()	145
Figure 25.	Exampleh dwarf_get_weaks()	148

Figure 26.	Examplei dwarf_get_weak()	obsolete	149
Figure 27.	Examplej dwarf_get_funcs()	151
Figure 28.	Examplek dwarf_get_funcs()	obsolete	152
Figure 29.	Examplel dwarf_get_types()	154
Figure 30.	Examplel dwarf_get_types()	obsolete	155
Figure 31.	Examplen dwarf_get_vars()	157
Figure 32.	Exampleo dwarf_get_vars()	obsolete	158
Figure 33.	Examplep5 dwarf_dealloc_macro_context()	169
Figure 34.	Examplep2 dwarf_get_macro_details()	179
Figure 35.	Frame Information Rule Assignments MIPS		183
Figure 36.	Frame Information Special Values any architecture		183
Figure 37.	Exampleq dwarf_get_fde_list()	185
Figure 38.	Exampleqb dwarf_get_fde_list()	obsolete	186
Figure 39.	Exampler dwarf_get_fde_list_eh()	188
Figure 40.	Examples dwarf_expand_frame_instructions()	203
Figure 41.	examplestringoffsets dwarf_open_str_offsets_table_access() etc	209
Figure 42.	Exampleu dwarf_get_aranges()	215
Figure 43.	Example .debug_rnglist for attribute	221
Figure 44.	Examplev dwarf_get_ranges_a()	225
Figure 45.	Examplev dwarf_get_ranges_b()	232
Figure 46.	Examplew dwarf_get_gdbindex_header()	235
Figure 47.	Examplewgdbindex dwarf_gdbindex_addressarea()	240
Figure 48.	Examplex dwarf_gdbindex_symboltable_array()	242

Figure 49.	Example debuglink ()	248
Figure 50.	Exampley dwarf_get_xu_index_header()	256
Figure 51.	Examplez dwarf_get_xu_hash_entry()	258
Figure 52.	Exampleza dwarf_get_xu_section_names()	261
Figure 53.	Examplezb dwarf_get_TAG_name()	262
Figure 54.	Dwarf Error Codes	270
Figure 55.	Dwarf 2 and later Error Codes	271

A Consumer Library Interface to DWARF

David Anderson

1. INTRODUCTION

This document describes an interface to *libdwarf*, a library of functions to provide access to DWARF debugging information records, DWARF line number information, DWARF address range and global names information, weak names information, DWARF frame description information, DWARF static function names, DWARF static variables, and DWARF type information.

The document has long mentioned the "Unix International Programming Languages Special Interest Group" (PLSIG), under whose auspices the DWARF committee was formed around 1991. "Unix International" was disbanded in the 1990s and no longer exists.

The DWARF committee published DWARF2 July 27, 1993.

In the mid 1990s this document and the library it describes (which the committee never endorsed, having decided not to endorse or approve any particular library interface) was made available on the internet by Silicon Graphics, Inc.

In 2005 the DWARF committee began an affiliation with FreeStandards.org. In 2007 FreeStandards.org merged with The Linux Foundation. The DWARF committee dropped its affiliation with FreeStandards.org in 2007 and established the dwarfstd.org website. See "<http://www.dwarfstd.org>" for current information on standardization activities and a copy of the standard.

1.1 Copyright

Copyright 1993-2006 Silicon Graphics, Inc.

Copyright 2007-2019 David Anderson.

Permission is hereby granted to copy or republish or use any or all of this document without restriction except that when publishing more than a small amount of the document please acknowledge Silicon Graphics, Inc and David Anderson.

This document is distributed in the hope that it would be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.

1.2 Purpose and Scope

The purpose of this document is to document a library of functions to access DWARF debugging information. There is no effort made in this document to address the creation

of these records as those issues are addressed separately (see "A Producer Library Interface to DWARF").

Additionally, the focus of this document is the functional interface, and as such, implementation as well as optimization issues are intentionally ignored.

1.3 Document History

A document was written about 1991 which had similar layout and interfaces. Written by people from Hal Corporation, That document described a library for reading DWARF1. The authors distributed paper copies to the committee with the clearly expressed intent to propose the document as a supported interface definition. The committee decided not to pursue a library definition.

SGI wrote the document you are now reading in 1993 with a similar layout and content and organization, but it was complete document rewrite with the intent to read DWARF2 (the DWARF version then in existence). The intent was (and is) to also cover future revisions of DWARF. All the function interfaces were changed in 1994 to uniformly return a simple integer success-code (see DW_DLV_OK etc), generally following the recommendations in the chapter titled "Candy Machine Interfaces" of "Writing Solid Code", a book by Steve Maguire (published by Microsoft Press).

1.4 Definitions

DWARF debugging information entries (DIEs) are the segments of information placed in the .debug_* sections by compilers, assemblers, and linkage editors that, in conjunction with line number entries, are necessary for symbolic source-level debugging. Refer to the latest "*DWARF Debugging Information Format*" from www.dwarfstd.org for a more complete description of these entries.

This document adopts all the terms and definitions in "*DWARF Debugging Information Format*" versions 2,3,4, and 5. It originally focused on the implementation at Silicon Graphics, Inc., but now attempts to be more generally useful.

1.5 Overview

The remaining sections of this document describe the proposed interface to libdwarf, first by describing the purpose of additional types defined by the interface, followed by descriptions of the available operations. This document assumes you are thoroughly familiar with the information contained in the *DWARF Debugging Information Format* document.

We separate the functions into several categories to emphasize that not all consumers want to use all the functions. We call the categories Debugger, Internal-level, High-level, and Miscellaneous not because one is more important than another but as a way of

making the rather large set of function calls easier to understand.

Unless otherwise specified, all functions and structures should be taken as being designed for Debugger consumers.

The Debugger Interface of this library is intended to be used by debuggers. The interface is low-level (close to dwarf) but suppresses irrelevant detail. A debugger will want to absorb all of some sections at startup and will want to see little or nothing of some sections except at need. And even then will probably want to absorb only the information in a single compilation unit at a time. A debugger does not care about implementation details of the library.

The Internal-level Interface is for a DWARF prettyprinter and checker. A thorough prettyprinter will want to know all kinds of internal things (like actual FORM numbers and actual offsets) so it can check for appropriate structure in the DWARF data and print (on request) all that internal information for human users and libdwarf authors and compiler-writers. Calls in this interface provide data a debugger does not normally care about.

The High-level Interface is for higher level access (it is not really a high level interface!). Programs such as disassemblers will want to be able to display relevant information about functions and line numbers without having to invest too much effort in looking at DWARF.

The miscellaneous interface is just what is left over: the error handler functions.

The following is a brief mention of the changes in this libdwarf from the libdwarf draft for DWARF Version 1 and recent changes.

1.6 Items Changed

Added `dwarf_get_FORM_CLASS_name()` so library users can print a form class value usefully. 2 February 2021.

Added `dwarf_decode_leb128()` and `dwarf_decode_signed_leb128()` so library users can access these library-internal functions.

Added `dwarf_macro_context_total_length()` because callers of `dwarf_get_macro_context[_by_offset]()` sometimes want to know the length of ops + header.

The description of `dwarf_srcfiles()` now reflects the difference in line table handling between DWARF5 and other line table versions. If using `dwarf_srcfiles()` do read its documentation here (Section 6.14, page 117 in this version).

Added functions `dwarf_crc32()` and `dwarf_basic_crc32()` so libdwarf can check debuglink/build-id CRC values.

Clarified the DW_DLC* value meaning here and in libdwarf.h. In the consumer/reader

case DW_DLC_READ is zero and zero is the only meaningful value to pass as the 'access' argument of dwarf_init(and the like) consumer/reader initialization functions. All this has been true for many years, it is only now being clearly (one hopes) stated. (September 28, 2020)

Added dwarf_get_ranges_b() so clients reading DWARF4 split dwarf (a GNU extension) can get the final offset of the ranges. (September 10, 2020)

All the dwarf_init*() and dwarf_elf_init*() calls have always been able to return DW_DLV_ERROR with a Dwarf_Error pointer returned too. We now update the advice on dealing with this situation, unifying with the rest of libdwarf errors. (September 9, 2020)

The documentation of dwarf_init_path() was basically correct but omitted meaningful mention of the dbg argument and a little wrongly described the error argument (July 22, 2020);

Added dwarf_get_debug_sup() to retrieved the DWARF5 section .debug_sup content. (July 13, 2020);

Added new functions for reading .debug_gnu_pubtypes and .debug_gnu_pubnames. dwarf_get_gnu_index_head() dwarf_get_gnu_index_dealloc dwarf_get_gnu_index_block() dwarf_get_gnu_index_block_entry() (July 9, 2020);

Added new functions for full .debug_loclists access: dwarf_get_locdesc_entry_d(), dwarf_get_loclist_head_basics(), dwarf_get_loclist_head_kind(), and dwarf_loc_head_c_dealloc(). For accessing certain DWARF5 new location operators (for example DW_OP_const_type) as well as all other operators we add dwarf_get_location_op_value_d(). Added functions allowing simple reporting of .debug_loclists without involving other sections: dwarf_load_loclists(), dwarf_get_loclist_context_basics(), dwarf_get_loclist_lle(), dwarf_get_loclist_offset_index_value(), and dwarf_get_loclist_raw_entry_detail(). (June 10, 2020);

Added new functions for full .debug_rnglists support and fixed issues with DWARF5 .debug_addr index FORMs. New functions for general use: dwarf_addr_form_is_indexed(), dwarf_get_rnglists_entry_fields_a(), dwarf_rnglists_get_rle_head(), dwarf_dealloc_rnglists_head(), New functions for a complete listing of the .debug_rnglists section. dwarf_load_rnglists(), dwarf_get_rnglist_offset_index_value(), dwarf_get_rnglist_context(), dwarf_get_rnglist_head_basics(), dwarf_get_rnglist_context_basics(), dwarf_get_rnglist_rle(). Also added new functions dwarf_dealloc_die(), dwarf_dealloc_error(), and dwarf_dealloc_attribute() to provide type-safe calls for deallocation of the specific data types. (May 20, 2020)

What was historically called 'length_size' in libdwarf and dwarfdump is actually the size of an offset (4 or 8 in DWARF2,3,4 and 5). For readability all instances of 'length_size' are being converted, as time permits, to 'offset_size'. (May 1, 2020)

Added a new function dwarf_set_de_alloc_flag() which allows turning-off of libdwarf-internal allocation tracking to improve libdwarf performance a few percent (which only

really matters with giant DWARF sections). The downside of turning off the flag is consumer code must do all the dwarf_dealloc() calls itself to avoid memory leaks. (March 14, 2020)

Corrected the documentation of dwarf_diename: It was never appropriate to use dwarf_dealloc on the string pointer returned but Up till now this document said such a call was required. (March 14, 2020)

Now we document here that if one uses dwarf_init() or dwarf_init_b() or dwarf_init_path() that the function dwarf_get_elf() cannot succeed as there is no longer any Elf pointer (from libelf) to return. (November 26, 2019)

New function dwarf_gnu_debuglink() allow callers to access fields that GNU compilers create and use to link an executable to its separate DWARF debugging content object file. (September 9, 2019, updated October 2019)

dwarf_next_cu_header_d() (and the other earlier versions of this) now allow a null in place of a pointer for next_cu_offset. dwarf_hipc_b() now allows a null in place of the return_form and/or return_class arguments. Unless you know a sufficiently recent libdwarf is to be used it is not safe to pass those arguments as null pointers. This allowance of null is because we've become aware that the relevant NetBSD man pages on these functions incorrectly specified that null was allowed. (April 22, 2019)

The dwarf_elf_init() and dwarf_elf_init_b() are now deprecated as they require the use of elf.h and libelf.h and libelf. Use dwarf_init_path() or dwarf_init_b() instead. The new non-libelf reader code checks elf header values more thoroughly than libelf and detects corrupted Elf earlier and in more cases than libelf. Since the reports of elf corruption from libdwarf/dwarfdump are not detailed we suggest one use an object dumper to check the object file in question. Two useful object dumpers are GNU readelf (part of GNU binutils) and readelfobj (part of the readelfobj project on sourceforge.net). readelfobj uses essentially the same algorithms as libdwarf does and should report something meaningful. (April 20, 2019)

Added support for MacOS dSYM objects and PE object files as well as an initialization function allowing a path instead of a Posix/Unix fd or a libelf Elf*. (January 2019)

Added a libdwarf interface dwarf_errmsg_by_number() so that places in the code that can have errors but do not want the Dwarf_Error complexities can report more details than just an error number. (December 19, 2018)

Now Mach-o dSYM files containing dwarf are readable by libdwarf and their DWARF dumped by dwarfdump. There are no new options or choices, libdwarf and dwarfdump notice which kind of object they are processing. New functions added to libdwarf.h.in: dwarf_init_path(), dwarf_object_detector_path(), and dwarf_object_detector_fd(). (October 24, 2018)

All references to Dwarf_Frame_Op3 have been removed as that struct was never created or available. The new function dwarf_get_fde_info_for_reg3_b() is documented. (May 12, 2018)

With DWARF5 it became harder to use `dwarf_srclines_data_b()` as DWARF5 changed each line table header file table to zero-based indexing from one-based (and made the primary file index zero). So a new function `dwarf_srclines_file_indexes()` returns values that make it easy to step through and call `dwarf_srclines_data_b()` sensibly whether the line table is DWARF2,3,4, or 5. (March 23, 2018)

Added COMDAT support. Recent compilers generate COMDAT sections (for some DWARF information) routinely so this became important recently. The new libdwarf COMDAT support extends the groupnumber idea as suggested just below. (May 17, 2017)

Adding `dwarf_init_b()` and `dwarf_elf_init_b()` and `dwarf_object_init_b()` with a groupnumber option added. DWARF5 adds split-dwarf and we call original sections like `.debug_info` group one and new sections like `.debug_info.dwo` group two. It has not escaped our attention that this numbering can be extended to deal with Elf COMDAT section groups of DWARF information, though COMDAT groups are not currently supported. (April 02, 2017)

Adding support for DWARF5 `.debug_loc.dwo` and split dwarf range tables. Added `dwarf_get_offset_size()`. (November 08, 2015)

Adding support for reading DWARF5 line tables and GNU two-level line tables. The function `dwarf_srclines()` still works but those using DWARF4 or DWARF5 are advised to switch to `dwarf_srclines_b()`. `dwarf_srclines()` cannot handle skeleton line tables sensibly and a new interface was needed for two-level line tables so the new approach satisfies both. (October 5, 2015)

Adding support for Package Files (DWARF5) to enable access of address data using `DW_FORM_addrx`. See `dwarf_set_tied_dbg()`. (September 13, 2015)

Adding some DWARF5 support and improved DWP Package File support, using `dwarf_next_cu_header_d()`.

Added a note about `dwarf_errmsg()`: the string pointer returned should be considered ephemeral, not a string which remains valid permanently. User code should print it or copy it before calling other libdwarf functions on the specific Dwarf_Debug instance. (May 15, 2014)

Added a printf-callback so libdwarf will not actually print to `stdout`. Added `dwarf_highpc_b()` so return of a DWARF4 `DW_AT_high_pc` of class constant can be returned properly. (August 15 2013)

Defined how the new operator `DW_OP_GNU_const_type` is handled. (January 26 2013)

Added `dwarf_loclist_from_expr_b()` function which adds arguments of the DWARF version (2 for DWARF2, etc) and the offset size to the `dwarf_loclist_from_expr_a()` function. Because the `DW_OP_GNU_implicit_pointer` opcode is defined differently for DWARF2 than for later versions. (November 2012)

Added new functions (some for libdwarf client code) and internal logic support for the DWARF4 `.debug_types` section. The new functions are `dwarf_next_cu_header_c()`, `dwarf_siblingof_b()`, `dwarf_offdie_b()`,

dwarf_get_cu_die_offset_given_cu_header_offset_b(), dwarf_get_die_infotypes_flag(), dwarf_get_section_max_offsets_b().

New functions and logic support additional detailed error reporting so that more compiler bugs can be reported sensibly by consumer code (as opposed to having libdwarf just assume things are ok and blindly continuing on with erroneous data). November 20, 2010

It seems impossible to default to both DW_FRAME_CFA_COL and DW_FRAME_CFA_COL3 in a single build of libdwarf, so the default is now unambiguously DW_FRAME_CFA_COL3 unless the configure option --enable-oldframecol is specified at configure time. The function dwarf_set_frame_cfa_value() may be used to override the default : using that function gives consumer applications full control (its use is highly recommended). (January 17,2010)

Added dwarf_set_reloc_application() and the default automatic application of Elf 'rela' relocations to DWARF sections (such rela sections appear in .o files, not in executables or shared objects, in general). The dwarf_set_reloc_application() routine lets a consumer turn off the automatic application of 'rela' relocations if desired (it is not clear why anyone would really want to do that, but possibly a consumer could write its own relocation application). An example application that traverses a set of DIEs was added to the new dwarfexample directory (not in this libdwarf directory, but in parallel to it). (July 10, 2009)

Added dwarf_get_TAG_name() (and the FORM AT and so on) interface functions so applications can get the string of the TAG, Attribute, etc as needed. (June 2009)

Added dwarf_get_ranges_a() and dwarf_loclist_from_expr_a() functions which add arguments allowing a correct address_size when the address_size varies by compilation unit (a varying address_size is quite rare as of May 2009). (May 2009)

Added dwarf_set_frame_same_value(), and dwarf_set_frame_undefined_value() to complete the set of frame-information functions needed to allow an application get all frame information returned correctly (meaning that it can be correctly interpreted) for all ABIs. Documented dwarf_set_frame_cfa_value(). Corrected spelling to dwarf_set_frame_rule_initial_value(). (April 2009).

Added support for various DWARF3 features, but primarily a new frame-information interface tailorable at run-time to more than a single ABI. See dwarf_set_frame_rule_initial_value(), dwarf_set_frame_rule_table_size(), dwarf_set_frame_cfa_value(). See also dwarf_get_fde_info_for_reg3() and dwarf_get_fde_info_for_cfa_reg3(). (April 2006)

Added support for DWARF3 .debug_pubtypes section. Corrected various leaks (revising dealloc() calls, adding new functions) and corrected dwarf_formstring() documentation.

Added dwarf_srclines_dealloc() as the previous deallocation method documented for data returned by dwarf_srclines() was incapable of freeing all the allocated storage (14 July 2005).

dwarf_nextglob(), dwarf_globname(), and dwarf_globdie() were all changed to operate

on the items in the .debug_pubnames section.

All functions were modified to return solely an error code. Data is returned through pointer arguments. This makes writing safe and correct library-using-code far easier. For justification for this approach, see the chapter titled "Candy Machine Interfaces" in the book "Writing Solid Code" by Steve Maguire.

1.7 Items Removed

Dwarf_Type was removed since types are no longer special.

dwarf_typeof() was removed since types are no longer special.

Dwarf_Ellist was removed since element lists no longer are a special format.

Dwarf_Bounds was removed since bounds have been generalized.

dwarf_nextdie() was replaced by dwarf_next_cu_header() to reflect the real way DWARF is organized. The dwarf_nextdie() was only useful for getting to compilation unit beginnings, so it does not seem harmful to remove it in favor of a more direct function.

dwarf_childcnt() is removed on grounds that no good use was apparent.

dwarf_prevline() and dwarf_nextline() were removed on grounds this is better left to a debugger to do. Similarly, dwarf_dieline() was removed.

dwarf_is1stline() was removed as it was not meaningful for the revised DWARF line operations.

Any libdwarf implementation might well decide to support all the removed functionality and to retain the DWARF Version 1 meanings of that functionality. This would be difficult because the original libdwarf draft specification used traditional C library interfaces which confuse the values returned by successful calls with exceptional conditions like failures and 'no more data' indications.

1.8 Revision History

September 2020 A new approach (simpler, more uniform) to deal with a failure of a dwarf_init*() or dwarf_elf_init*() call is described in Chapter 4. Improved support for split dwarf. Added dwarf_get_ranges_b().

May 2020 Adding support for DWARF5 sections .debug_rnglists and .debug_loclists.

March 2020 Added dwarf_set_de_alloc_flag() so consumers get a little better performance from libdwarf. At a price. See the description a bit later here.

January 2019 Added support for reading DWARF in PE object files.

October 2018 Added support for reading MacOS dSYM object files.

2017	Added support for nearly all of DWARF5.
July 2014	Added support for the .gdb_index section and started support for the .debug_cu_index and .debug_tu_index sections.
October 2011	DWARF4 support for reading .debug_types added.
March 93	Work on DWARF2 SGI draft begins
June 94	The function returns are changed to return an error/success code only.
April 2006	Support for DWARF3 consumer operations is close to completion.
November 2010	Added various new functions and improved error checking.
March 2017	Adding support for DWARF5 split dwarf.

2. Types Definitions

2.1 General Description

The *libdwarf.h* header file contains typedefs and preprocessor definitions of types and symbolic names used to reference objects of *libdwarf*. The types defined by typedefs contained in *libdwarf.h* all use the convention of adding `Dwarf_` as a prefix and can be placed in three categories:

- Scalar types : The scalar types defined in *libdwarf.h* are defined primarily for notational convenience and identification. Depending on the individual definition, they are interpreted as a value, a pointer, or as a flag.
- Aggregate types : Some values can not be represented by a single scalar type; they must be represented by a collection of, or as a union of, scalar and/or aggregate types.
- Opaque types : The complete definition of these types is intentionally omitted; their use is as handles for query operations, which will yield either an instance of another opaque type to be used in another query, or an instance of a scalar or aggregate type, which is the actual result.

2.2 Scalar Types

The following are the defined by *libdwarf.h*:

```

typedef int           Dwarf_Bool;
typedef unsigned long long Dwarf_Off;
typedef unsigned long long Dwarf_Unsigned;
typedef unsigned short   Dwarf_Half;
typedef unsigned char    Dwarf_Small;
typedef signed long long  Dwarf_Signed;
typedef unsigned long long  Dwarf_Addr;
typedef void            *Dwarf_Ptr;
typedef void  (*Dwarf_Handler)(Dwarf_Error error, Dwarf_Ptr errarg);

```

Dwarf_Ptr is an address for use by the host program calling the library, not for representing pc-values/addresses within the target object file. Dwarf_Addr is for pc-values within the target object file. The sample scalar type assignments above are for a *libdwarf.h* that can read and write 32-bit or 64-bit binaries on a 32-bit or 64-bit host machine. The types must be defined appropriately for each implementation of libdwarf. A description of these scalar types in the SGI/MIPS environment is given in Figure 1.

NAME	SIZE	ALIGNMENT	PURPOSE
Dwarf_Bool	4	4	Boolean states
Dwarf_Off	8	8	Unsigned file offset
Dwarf_Unsigned	8	8	Unsigned large integer
Dwarf_Half	2	2	Unsigned medium integer
Dwarf_Small	1	1	Unsigned small integer
Dwarf_Signed	8	8	Signed large integer
Dwarf_Addr	8	8	Program address (target program)
Dwarf_Ptr	4 8	4 8	Dwarf section pointer (host program)
Dwarf_Handler	4 8	4 8	Pointer to error handler function

Figure 1. Scalar Types

2.3 Aggregate Types

The following aggregate types are defined by *libdwarf.h*: Dwarf_Loc, Dwarf_Locdesc, Dwarf_Block, Dwarf_Frame_Op, Dwarf_Regtable, Dwarf_Regtable3. While most of libdwarf acts on or returns simple values or opaque pointer types, this small set of structures seems useful. Yet, at the same time, these public structures are inflexible as any change in format or content breaks binary (and possibly source in some cases) compatibility.

2.3.1 Location Record

The `Dwarf_Loc` type identifies a single atom of a location description or a location expression. This is obsolete and should not be used, though it works adequately for DWARF2.

```
typedef struct {
    Dwarf_Small      lr_atom;
    Dwarf_Unsigned   lr_number;
    Dwarf_Unsigned   lr_number2;
    Dwarf_Unsigned   lr_offset;
} Dwarf_Loc;
```

The `lr_atom` identifies the atom corresponding to the `DW_OP_*` definition in *dwarf.h* and it represents the operation to be performed in order to locate the item in question.

The `lr_number` field is the operand to be used in the calculation specified by the `lr_atom`

field; not all atoms use this field. Some atom operations imply signed numbers so it is necessary to cast this to a `Dwarf_Signed` type for those operations.

The `lr_number2` field is the second operand specified by the `lr_atom` field; only `DW_OP_BREGX` has this field. Some atom operations imply signed numbers so it may be necessary to cast this to a `Dwarf_Signed` type for those operations.

For a `DW_OP_implicit_value` operator the `lr_number2` field is a pointer to the bytes of the value. The field pointed to is `lr_number` bytes long. There is no explicit terminator. Do not attempt to `free` the bytes which `lr_number2` points at and do not alter those bytes. The pointer value remains valid till the open `Dwarf_Debug` is closed. This is a rather ugly use of a host integer to hold a pointer. You will normally have to do a 'cast' operation to use the value.

For a `DW_OP_GNU_const_type` operator the `lr_number2` field is a pointer to a block with an initial unsigned byte giving the number of bytes following, followed immediately that number of const value bytes. There is no explicit terminator. Do not attempt to `free` the bytes which `lr_number2` points at and do not alter those bytes. The pointer value remains valid till the open `Dwarf_Debug` is closed. This is a rather ugly use of a host integer to hold a pointer. You will normally have to do a 'cast' operation to use the value.

The `lr_offset` field is the byte offset (within the block the location record came from) of the atom specified by the `lr_atom` field. This is set on all atoms. This is useful for operations `DW_OP_SKIP` and `DW_OP_BRA`.

2.3.2 Location Description

This is obsolete and should not be used, though it works ok for DWARF2.. The

`Dwarf_Locdesc` type represents an ordered list of `Dwarf_Loc` records used in the calculation to locate an item. Note that in many cases, the location can only be calculated at runtime of the associated program.

```
typedef struct {
    Dwarf_Addr      ld_lopc;
    Dwarf_Addr      ld_hipc;
    Dwarf_Unsigned   ld_cents;
    Dwarf_Loc*       ld_s;
} Dwarf_Locdesc;
```

The `ld_lopc` and `ld_hipc` fields provide an address range for which this location descriptor is valid. Both of these fields are set to *zero* if the location descriptor is valid throughout the scope of the item it is associated with. These addresses are virtual memory addresses, not offsets-from-something. The virtual memory addresses do not account for dso movement (none of the pc values from libdwarf do that, it is up to the consumer to do that).

The `ld_cents` field contains a count of the number of `Dwarf_Loc` entries pointed to by the `ld_s` field.

The `ld_s` field points to an array of `Dwarf_Loc` records.

2.3.3 Data Block

This is obsolete and should not be used, though it works ok for DWARF2. The `Dwarf_Block` type is used to contain the value of an attribute whose form is either `DW_FORM_block1`, `DW_FORM_block2`, `DW_FORM_block4`, `DW_FORM_block8`, or `DW_FORM_block`. Its intended use is to deliver the value for an attribute of any of these forms.

```
typedef struct {
    Dwarf_Unsigned   bl_len;
    Dwarf_Ptr        bl_data;
    Dwarf_Small      bl_from_loclist;
    Dwarf_Unsigned   bl_section_offset;
} Dwarf_Block;
```

The `bl_len` field contains the length in bytes of the data pointed to by the `bl_data` field.

The `bl_data` field contains a pointer to the uninterpreted data. Since we use a

Dwarf_Ptr here one must copy the pointer to some other type (typically an `unsigned char *`) so one can add increments to index through the data. The data pointed to by `bl_data` is not necessarily at any useful alignment.

2.3.4 Frame Operation Codes: DWARF 2

This interface is adequate for DWARF2 but not entirely suitable for DWARF3 or later. A new (functional) interface is needed. This DWARF2 interface is not sufficient but at present is the only available interface.

See also the section "Low Level Frame Operations" below.

The DWARF2 `Dwarf_Frame_Op` type is used to contain the data of a single instruction of an instruction-sequence of low-level information from the section containing frame information. This is ordinarily used by Internal-level Consumers trying to print everything in detail.

```
typedef struct {
    Dwarf_Small  fp_base_op;
    Dwarf_Small  fp_extended_op;
    Dwarf_Half   fp_register;
    Dwarf_Signed  fp_offset;
    Dwarf_Offset fp_instr_offset;
} Dwarf_Frame_Op;
```

`fp_base_op` is the 2-bit basic op code. `fp_extended_op` is the 6-bit extended opcode (if `fp_base_op` indicated there was an extended op code) and is zero otherwise.

`fp_register` is any (or the first) register value as defined in the Call frame instruction encodings in the dwarf document (in DWARF3 see Figure 40,in DWARF5 see table 7.29). If not used with the operation it is 0.

`fp_offset` is the address, delta, offset, or second register as defined in the Call frame instruction encodings documentation. If this is an address then the value should be cast to (`Dwarf_Addr`) before being used.

In any implementation this field *must* be as large as the largest of `Dwarf_Ptr`, `Dwarf_Signed`, and `Dwarf_Addr` for this to work properly. If not used with the op it is 0. If the `fp_extended_op` is `DW_CFA_def_cfa` or `DW_CFA_val_expression` or `DW_CFA_expression` then `fp_offset` is a pointer to an expression block in the in-memory copy of the frame section.

`fp_instr_offset` is the byte_offset (within the instruction stream of the frame instructions) of this operation. It starts at 0 for a given frame descriptor.

2.3.5 Frame Regtable: DWARF 2

This interface is adequate for DWARF2 and MIPS but not for DWARF3 or later. A separate and preferred interface usable for DWARF3 and for DWARF2 is described below. See also the section "Low Level Frame Operations" below.

The `Dwarf_Regtable` type is used to contain the register-restore information for all registers at a given PC value. Normally used by debuggers. If you wish to default to this interface and to the use of `DW_FRAME_CFA_COL`, specify `--enable_oldframecol` at libdwarf configure time. Or add a call `dwarf_set_frame_cfa_value(dbg,DW_FRAME_CFA_COL)` after your `dwarf_init_b()` call, this call replaces the default libdwarf-compile-time value with `DW_FRAME_CFA_COL`.

```
/* DW_REG_TABLE_SIZE must reflect the number of registers
 * (DW_FRAME_LAST_REG_NUM) as defined in dwarf.h
 */
#define DW_REG_TABLE_SIZE <fill in size here, 66 for MIPS/IRIX>
typedef struct {
    struct {
        Dwarf_Small      dw_offset_relevant;
        Dwarf_Half       dw_regnum;
        Dwarf_Addr      dw_offset;
    }
    rules [DW_REG_TABLE_SIZE];
} Dwarf_Regtable;
```

The array is indexed by register number. The field values for each index are described next. For clarity we describe the field values for index `rules[M]` (`M` being any legal array element index).

`dw_offset_relevant` is non-zero to indicate the `dw_offset` field is meaningful. If zero then the `dw_offset` is zero and should be ignored.

`dw_regnum` is the register number applicable. If `dw_offset_relevant` is zero, then this is the register number of the register containing the value for register `M`. If `dw_offset_relevant` is non-zero, then this is the register number of the register to use as a base (`M` may be `DW_FRAME_CFA_COL`, for example) and the `dw_offset` value applies. The value of register `M` is therefore the value of register `dw_regnum`.

`dw_offset` should be ignored if `dw_offset_relevant` is zero. If `dw_offset_relevant` is non-zero, then the consumer code should add the value to the value of the register `dw_regnum` to produce the value.

2.3.6 Frame Operation Codes: DWARF 3 (for DWARF2 and later)

This interface was intended to be adequate for DWARF3 and for DWARF2 (and DWARF4) but was never implemented.

2.3.7 Frame Regtable: DWARF 3 (for DWARF2 and later)

This interface is adequate for DWARF2 and later versions. It is new in libdwarf as of April 2006. The default configure of libdwarf inserts DW_FRAME_CFA_COL3 as the default CFA column. Or add a call dwarf_set_frame_cfa_value(dbg,DW_FRAME_CFA_COL3) after your dwarf_init_b() call, this call replaces the default libdwarf-compile-time value with DW_FRAME_CFA_COL3.

The Dwarf_Regtable3 type is used to contain the register-restore information for all registers at a given PC value. Normally used by debuggers.

```
typedef struct Dwarf_Regtable_Entry3_s {
    Dwarf_Small          dw_offset_relevant;
    Dwarf_Small          dw_value_type;
    Dwarf_Half           dw_regnum;
    Dwarf_Unsigned       dw_offset_or_block_len;
    Dwarf_Ptr             dw_block_ptr;
} Dwarf_Regtable_Entry3;

typedef struct Dwarf_Regtable3_s {
    struct Dwarf_Regtable_Entry3_s    rt3_cfa_rule;
    Dwarf_Half              rt3_reg_table_size;
    struct Dwarf_Regtable_Entry3_s * rt3_rules;
} Dwarf_Regtable3;
```

The array is indexed by register number. The field values for each index are described next. For clarity we describe the field values for index rules[M] (M being any legal array element index). (DW_FRAME_CFA_COL3 DW_FRAME_SAME_VAL, DW_FRAME_UNDEFINED_VAL are not legal array indexes, nor is any index < 0 or >= rt3_reg_table_size); The caller of routines using this struct must create data space for rt3_reg_table_size entries of struct Dwarf_Regtable_Entry3_s and arrange that rt3_rules points to that space and that rt3_reg_table_size is set correctly. The caller need not (but may) initialize the contents of the rt3_cfa_rule or the rt3_rules array. The following applies to each rt3_rules rule M:

dw_regnum is the register number applicable. If dw_regnum is DW_FRAME_UNDEFINED_VAL, then the register I has undefined value. If dw_regnum is DW_FRAME_SAME_VAL, then the register I has the same value as in the previous frame.

If dw_regnum is neither of these two, then the following apply:

dw_value_type determines the meaning of the other fields. It is one of DW_EXPR_OFFSET (0), DW_EXPR_VAL_OFFSET(1), DW_EXPR_EXPRESSION(2) or DW_EXPR_VAL_EXPRESSION(3).

If dw_value_type is DW_EXPR_OFFSET (0) then this is as in DWARF2

and the offset(N) rule or the register(R) rule of the DWARF3 and DWARF2 document applies. The value is either:

If `dw_offset_relevant` is non-zero, then `dw_regnum` is effectively ignored but must be identical to `DW_FRAME_CFA_COL3` (and the `dw_offset` value applies. The value of register M is therefore the value of CFA plus the value of `dw_offset`. The result of the calculation is the address in memory where the value of register M resides. This is the offset(N) rule of the DWARF2 and DWARF3 documents.

`dw_offset_relevant` is zero it indicates the `dw_offset` field is not meaningful. The value of register M is the value currently in register `dw_regnum` (the value `DW_FRAME_CFA_COL3` must not appear, only real registers). This is the register(R) rule of the DWARF3 spec.

If `dw_value_type` is `DW_EXPR_OFFSET` (1) then this is the the val_offset(N) rule of the DWARF3 spec applies. The calculation is identical to that of `DW_EXPR_OFFSET` (0) but the value is interpreted as the value of register M (rather than the address where register M's value is stored).

If `dw_value_type` is `DW_EXPR_EXPRESSION` (2) then this is the the expression(E) rule of the DWARF3 document.

`dw_offset_or_block_len` is the length in bytes of the in-memory block pointed at by `dw_block_ptr`. `dw_block_ptr` is a DWARF expression. Evaluate that expression and the result is the address where the previous value of register M is found.

If `dw_value_type` is `DW_EXPR_VAL_EXPRESSION` (3) then this is the the val_expression(E) rule of the DWARF3 spec.

`dw_offset_or_block_len` is the length in bytes of the in-memory block pointed at by `dw_block_ptr`. `dw_block_ptr` is a DWARF expression. Evaluate that expression and the result is the previous value of register M.

The rule `rt3_cfa_rule` is the current value of the CFA. It is interpreted exactly like any register M rule (as described just above) except that `dw_regnum` cannot be `CW_FRAME_CFA_REG3` or `DW_FRAME_UNDEFINED_VAL` or `DW_FRAME_SAME_VAL` but must be a real register number.

2.3.8 Macro Details Record

The `Dwarf_Macro_Details` type gives information about a single entry in the `.debug.macinfo` section (DWARF2, DWARF3, and DWARF4). It is not useful for

DWARF 5 .debug_macro section data.

```
struct Dwarf_Macro_Details_s {
    Dwarf_Off     dmd_offset;
    Dwarf_Small   dmd_type;
    Dwarf_Signed  dmd_lineno;
    Dwarf_Signed  dmd_fileindex;
    char *        dmd_macro;
};

typedef struct Dwarf_Macro_Details_s Dwarf_Macro_Details;
```

dmd_offset is the byte offset, within the .debug_macinfo section, of this macro information.

dmd_type is the type code of this macro info entry (or 0, the type code indicating that this is the end of macro information entries for a compilation unit. See DW_MACINFO_define, etc in the DWARF document.

dmd_lineno is the line number where this entry was found, or 0 if there is no applicable line number.

dmd_fileindex is the file index of the file involved. This is only guaranteed meaningful on a DW_MACINFO_start_file dmd_type. Set to -1 if unknown (see the functional interface for more details).

dmd_macro is the applicable string. For a DW_MACINFO_define this is the macro name and value. For a DW_MACINFO_undef, or this is the macro name. For a DW_MACINFO_vendor_ext this is the vendor-defined string value. For other dmd_types this is 0.

2.4 Opaque Types

The opaque types declared in *libdwarf.h* are used as descriptors for queries against DWARF information stored in various debugging sections. Each time an instance of an opaque type is returned as a result of a *libdwarf* operation (Dwarf_Debug excepted), it should be freed, using *dwarf_dealloc()* when it is no longer of use (read the following documentation for details, as in at least one case there is a special routine provided for deallocation and *dwarf_dealloc()* is not directly called: see *dwarf_srclines()*). Some functions return a number of instances of an opaque type in a block, by means of a pointer to the block and a count of the number of opaque descriptors in the block: see the function description for deallocation rules for such functions. The list of opaque types defined in *libdwarf.h* that are pertinent to the Consumer Library, and their intended use is described below. This is not a full list of the opaque types, see *libdwarf.h* for the full list.

```
typedef struct Dwarf_Debug_s* Dwarf_Debug;
```

An instance of the Dwarf_Debug type is created as a result of a successful call to *dwarf_init_b()*, or *dwarf_elf_init_b()*, and is used as a descriptor for

subsequent access to most `libdwarf` functions on that object. The storage pointed to by this descriptor should be not be freed, using the `dwarf_dealloc()` function. Instead free it with `dwarf_finish()`.

```
typedef struct Dwarf_Die_s* Dwarf_Die;
```

An instance of a `Dwarf_Die` type is returned from a successful call to the `dwarf_siblingof()`, `dwarf_child`, or `dwarf_offdie_b()` function, and is used as a descriptor for queries about information related to that DIE. The storage pointed to by this descriptor should be freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_DIE` when no longer needed, or, preferably, call `dwarf_dealloc_die()` instead.

```
typedef struct Dwarf_Line_s* Dwarf_Line;
```

Instances of `Dwarf_Line` type are returned from a successful call to the `dwarf_srclines()` function, and are used as descriptors for queries about source lines. The storage pointed to by these descriptors should be individually freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_LINE` when no longer needed.

```
typedef struct Dwarf_Global_s* Dwarf_Global;
```

Instances of `Dwarf_Global` type are returned from a successful call to the `dwarf_get_globals()` function, and are used as descriptors for queries about global names (pubnames).

```
typedef struct Dwarf_Weak_s* Dwarf_Weak;
```

Instances of `Dwarf_Weak` type are returned from a successful call to the SGI-specific `dwarf_get_weaks()` function, and are used as descriptors for queries about weak names. The storage pointed to by these descriptors should be individually freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_WEAK_CONTEXT` (or `DW_DLA_WEAK`, an older name, supported for compatibility) when no longer needed.

```
typedef struct Dwarf_Func_s* Dwarf_Func;
```

Instances of `Dwarf_Func` type are returned from a successful call to the SGI-specific `dwarf_get_funcs()` function, and are used as descriptors for queries about static function names.

```
typedef struct Dwarf_Type_s* Dwarf_Type;
```

Instances of `Dwarf_Type` type are returned from a successful call to the SGI-specific `dwarf_get_types()` function, and are used as descriptors for queries about user defined types.

```
typedef struct Dwarf_Var_s* Dwarf_Var;
```

Instances of `Dwarf_Var` type are returned from a successful call to the SGI-specific `dwarf_get_vars()` function, and are used as descriptors for queries about static variables.

```
typedef struct Dwarf_Error_s* Dwarf_Error;
```

This descriptor points to a structure that provides detailed information about errors detected by `libdwarf`. Users typically provide a location for `libdwarf` to store this descriptor for the user to obtain more information about the error. The storage pointed to by this descriptor should be freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_ERROR` when no longer needed or, preferably, call `dwarf_dealloc_error()` instead.

```
typedef struct Dwarf_Attribute_s* Dwarf_Attribute;
```

Instances of `Dwarf_Attribute` type are returned from a successful call to the `dwarf_attrlist()`, or `dwarf_attr()` functions, and are used as descriptors for queries about attribute values. The storage pointed to by this descriptor should be individually freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_ATTR` when no longer needed, or call `dwarf_dealloc_attribute()` instead.

```
typedef struct Dwarf_Abbrev_s* Dwarf_Abbrev;
```

An instance of a `Dwarf_Abbrev` type is returned from a successful call to `dwarf_get_abbrev()`, and is used as a descriptor for queries about abbreviations in the `.debug_abbrev` section. The storage pointed to by this descriptor should be freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_ABBREV` when no longer needed.

```
typedef struct Dwarf_Fde_s* Dwarf_Fde;
```

Instances of `Dwarf_Fde` type are returned from a successful call to the `dwarf_get_fde_list()`, `dwarf_get_fde_for_die()`, or `dwarf_get_fde_at_pc()` functions, and are used as descriptors for queries about frames descriptors.

```
typedef struct Dwarf_Cie_s* Dwarf_Cie;
```

Instances of `Dwarf_Cie` type are returned from a successful call to the `dwarf_get_fde_list()` function, and are used as descriptors for queries about information that is common to several frames.

```
typedef struct Dwarf_Arange_s* Dwarf_Arange;
```

Instances of `Dwarf_Arange` type are returned from successful calls to the

`dwarf_get_aranges()`, or `dwarf_get_arange()` functions, and are used as descriptors for queries about address ranges. The storage pointed to by this descriptor should be individually freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_ARANGE` when no longer needed.

```
typedef struct Dwarf_Gdbindex_s* Dwarf_Gdbindex;
```

Instances of `Dwarf_Gdbindex` type are returned from successful calls to the `dwarf_gdbindex_header()` function and are used to extract information from a `.gdb_index` section. This section is a gcc/gdb extension and is designed to allow a debugger fast access to data in `.debug_info`. The storage pointed to by this descriptor should be freed using a call to `dwarf_gdbindex_free()` with a valid `Dwarf_Gdbindex` pointer as the argument.

```
typedef struct Dwarf_Xu_Index_Header_s* Dwarf_Xu_Index_header;
```

Instances of `Dwarf_Xu_Index_Header_s` type are returned from successful calls to the `dwarf_get_xu_index_header()` function and are used to extract information from a `.debug_cu_index` or `.debug_tu_index` section. These sections are used to make possible access to `.dwo` sections gathered into a `.dwp` object as part of the DebugFission (ie Split Dwarf) project allowing separation of an executable from most of its DWARF debugging information. As of May 2015 these sections are accepted into DWARF5 but the standard has not been released. The storage pointed to by this descriptor should be freed using a call to `dwarf_xh_header_free()` with a valid `Dwarf_XuIndexHeader` pointer as the argument.

```
typedef struct Dwarf_Line_Context_s * Dwarf_Line_Context;
```

`dwarf_srclines_b()` returns a `Dwarf_Line_Context` through an argument and the new structure pointer lets us access line header information conveniently.

```
typedef struct Dwarf_Locdesc_c_s * Dwarf_Locdesc_c;
typedef struct Dwarf_Loc_Head_c_s * Dwarf_Loc_Head_c;
```

`Dwarf_Loc*` are involved in the DWARF5 interfaces to location lists. The new interfaces are all functional and contents of the above types are not exposed.

```
typedef struct Dwarf_Macro_Context_s * Dwarf_Macro_Context;
dwarf_get_macro_context()                                         and
dwarf_get_macro_context_by_offset() return a Dwarf_Line_Context
through an argument and the new structure pointer lets us access macro data from the
.debug_macro section.
```

```
typedef struct Dwarf_Dsc_Head_s * Dwarf_Dsc_Head;
```

`dwarf_discr_list()` returns a `Dwarf_Dsc_Head` through an argument and the new structure pointer lets us access macro data from a `DW_AT_discr_list` attribute.

3. UTF-8 strings

libdwarf is defined, at various points, to return string pointers or to copy strings into string areas you define. DWARF allows the use of DW_AT_use_UTF8 (DWARF3 and later) DW_ATE_UTF (DWARF4 and later) to specify that the strings returned are actually in UTF-8 format. What this means is that if UTF-8 is specified on a particular object it is up to callers that wish to print all the characters properly to use language-appropriate functions to print Unicode strings appropriately. All ASCII characters in the strings will print properly whether printed as wide characters or not. The methods to convert UTF-8 strings so they will print correctly for all such strings is beyond the scope of this document.

If UTF-8 is not specified then one is probably safe in assuming the strings are iso_8859-15 and normal C printf() will work fine..

In either case one should be wary of corrupted (accidentally or intentionally) strings with ASCII control characters in the text. Such can cause bad effects if simply printed to a device (such as a terminal).

4. Error Handling

The method for detection and disposition of error conditions that arise during access of debugging information via *libdwarf* is consistent across all *libdwarf* functions that are capable of producing an error. This section describes the method used by *libdwarf* in notifying client programs of error conditions.

Most functions within *libdwarf* accept as an argument a pointer to a Dwarf_Error descriptor where a Dwarf_Error descriptor is stored if an error is detected by the function. Routines in the client program that provide this argument can query the Dwarf_Error descriptor to determine the nature of the error and perform appropriate processing. The intent is that clients do the appropriate processing immediately on encountering an error and then the client calls dwarf_dealloc_error to free the Dwarf_Error descriptor (at which point the client should zero that descriptor as the non-zero value is stale).

We think the following is appropriate as a general outline. See dwarfdump source for many examples of both of the following incomplete examples.

```
int example_codea{Dwarf_Debug dbg,Dwarf_Die indie,
    int is_info, Dwarf_Die *sibdie, Dwarf_Error *err)
{
    int res = 0;
    const char *secname = 0;
    res = dwarf_siblingof_b(dbg,indie,is_info,sibdie,
        err);
    if (res == DW_DLV_ERROR) {
        return res; /*let higher level decide what to do
            and it will eventually need to do
            dwarf_dealloc_error() appropriately */
    } else if (res == DW_DLV_NO_ENTRY) {
        /* No sibdie created. Nothing done. */
        return res;
    }
    /* sibdie created, caller will have to eventually
       do dwarf_dealloc_die() appropriately. */
    ...
    return DW_DLV_OK;
}
```

In a case where it is ok to suppress the error as being unimportant, this is an outline, not a useful function.

```
int example_codeb{Dwarf_Debug dbg, const char **sec_name,
    int is_info)
{
    Dwarf_Error e = 0;
    int res = 0;
    res = dwarf_get_die_section_name(dbg,is_info,
        sec_name, &e);
    if (res == DW_DLV_ERROR) {
        dwarf_dealloc_error(e);
        e = 0;
        return res; /*let higher level decide what to do,
            Nothing allocated in the call still exists. */
    } if (res == DW_DLV_NO_ENTRY) {
        ....
    }
    ...
}
```

In the rare case where the malloc arena is exhausted when trying to create a Dwarf_Error descriptor a pointer to a statically allocated descriptor will be returned. This static descriptor is new in December 2014. A call to dwarf_dealloc() to free the

statically allocated descriptor is harmless (it sets the error value in the descriptor to DW_DLE_FAILSAFE_ERRVAL). The possible conflation of errors when the arena is exhausted (and a dwarf_error descriptor is saved past the next reader call in any thread) is considered better than having *libdwarf* call `abort()` (as earlier *libdwarf* did).

We strongly suggest most applications calling *libdwarf* follow the suggestion above (passing a valid Dwarf_Error address in the last argument when calling *libdwarf* where there are such Dwarf_Error arguments) there are other approaches described just below that might be worth considering in small simple applications as they reduce the Dwarf_Error argument to just passing 0 (null pointer)..

The cases that arise when passing a null for the Dwarf_Error and where there is an error detected are A) with an error handler function *libdwarf* will call that function and on return to *libdwarf*, *libdwarf* will return DW_DLV_ERROR to the original client call.. or B) with no error handler function (see below) *libdwarf* will print an error and call `abort()`.

- A. For the error-handler case a client program can specify a function to be invoked upon detection of an error at the time the library is initialized (see `dwarf_init_b()` or `dwarf_init_path()` for example). When a *libdwarf* routine detects an error, this function is called with two arguments: a code indicating the nature of the error and a pointer provided by the client at initialization (again see `dwarf_init_b()` or `dwarf_init_path()`). This pointer argument can be used to relay information between the error handler and other routines of the client program. A client program can specify or change both the error handling function and the pointer argument after initialization using `dwarf_seterrhand()` and `dwarf_seterrarg()`. When the client error function returns *libdwarf* returns DW_DLV_ERROR.

If the client passed in a non-null `error` argument in the *libdwarf* call finding an error, the `dwarf_seterrhand()` function-invocation mentioned here does not happen.

- B. In the final case, where *libdwarf* functions are not provided a pointer to a Dwarf_Error descriptor, and no error handling function was provided at initialization, *libdwarf* functions print a short message to `stdout` and terminate execution with `abort()`.

Before March 2016 *libdwarf* gave up when there was no error handling by emitting a short message on `stderr` and calling `abort()` (3C).

The following lists the processing steps taken upon detection of an error:

1. Check the `error` argument; if not a `NULL` pointer, allocate and initialize a Dwarf_Error descriptor with information describing the error, place this descriptor in the area pointed to by `error`, and return a value indicating an error condition.

2. If an `errhand` argument was provided to `dwarf_init_b()` at initialization, call `errhand()` passing it the error descriptor and the value of the `errarg` argument provided to `dwarf_init_b()`. If the error handling function returns, return `DW_DLV_ERROR` indicating an error condition.
3. If neither the `error` argument nor an `errhand` argument was provided Terminate program execution by calling `abort` (3C).

In all cases, it is clear from the value returned from a function that an error occurred in executing the function, since `DW_DLV_ERROR` is returned.

As can be seen from the above steps, the client program can provide an error handler at initialization, and still provide an `error` argument to *libdwarf* functions when it is not desired to have the error handler invoked.

If a *libdwarf* function is called with invalid arguments, the behavior is undefined. In particular, supplying a NULL pointer to a *libdwarf* function (except where explicitly permitted), or pointers to invalid addresses or uninitialized data causes undefined behavior; the return value in such cases is undefined, and the function may fail to invoke the caller supplied error handler or to return a meaningful error number. Implementations also may abort execution for such cases.

Some errors are so inconsequential that it does not warrant rejecting an object or returning an error. Examples would be a frame length not being a multiple of an address-size, an arange in `.debug_aranges` has some padding bytes, or a relocation could not be completed. To make it possible for a client to report such errors the function `dwarf_get_harmless_error_list` returns strings with error text in them. This function may be ignored if client code does not want to bother with such error reporting.

4.1 Returned values in the functional interface

Values returned by *libdwarf* functions to indicate success and errors are enumerated in Figure 2. The `DW_DLV_NO_ENTRY` case is useful for functions need to indicate that while there was no data to return there was no error either. For example, `dwarf_siblingof()` may return `DW_DLV_NO_ENTRY` to indicate that that there was no sibling to return.

SYMBOLIC NAME	VALUE	MEANING
<code>DW_DLV_ERROR</code>	1	Error
<code>DW_DLV_OK</code>	0	Successful call
<code>DW_DLV_NO_ENTRY</code>	-1	No applicable value

Figure 2. Error Indications

Each function in the interface that returns a value returns one of the integers in the above

figure.

If DW_DLV_ERROR is returned and a pointer to a Dwarf_Error pointer is passed to the function, then a Dwarf_Error handle is returned through the pointer. No other pointer value in the interface returns a value. After the Dwarf_Error is no longer of interest, a dwarf_dealloc(dbg, dw_err, DW_DLA_ERROR) on the error pointer is appropriate to free any space used by the error information.

If DW_DLV_NO_ENTRY is returned no pointer value in the interface returns a value.

If DW_DLV_OK is returned, the Dwarf_Error pointer, if supplied, is not touched, but any other values to be returned through pointers are returned. In this case calls (depending on the exact function returning the error) to dwarf_dealloc() may be appropriate once the particular pointer returned is no longer of interest.

Pointers passed to allow values to be returned through them are uniformly the last pointers in each argument list.

All the interface functions are defined from the point of view of the writer-of-the-library (as is traditional for UN*X library documentation), not from the point of view of the user of the library. The caller might code:

```
Dwarf_Line line;
Dwarf_Signed ret_loff;
Dwarf_Error err;
int retval = dwarf_lineoff(line, &ret_loff, &err);
```

for the function defined as

```
int dwarf_lineoff(Dwarf_Line line,
                  Dwarf_Signed *return_lineoff,
                  Dwarf_Error* err);
```

and this document refers to the function as returning the value through *err or *return_lineoff or uses the phrase "returns in the location pointed to by err". Sometimes other similar phrases are used.

5. Memory Management

Several of the functions that comprise *libdwarf* return pointers (opaque descriptors) to structures that have been dynamically allocated by the library. To manage dynamic memory the function dwarf_dealloc() is provided to free storage allocated as a result of a call to a *libdwarf* function. Some additional functions (described later) are provided to free storage in particular circumstances. This section describes the general strategy that should be taken by a client program in managing dynamic storage.

By default *libdwarf* tracks its allocations and dwarf_finish() cleans up allocations where dwarf_dealloc() was not called. See dwarf_set_de_alloc_flag() below.

5.1 Read-only Properties

All pointers (opaque descriptors) returned by or as a result of a *libdwarf Consumer Library* call should be assumed to point to read-only memory. The results are undefined for *libdwarf* clients that attempt to write to a region pointed to by a value returned by a *libdwarf Consumer Library* call.

5.2 Storage Deallocation

See the section "Returned values in the functional interface", above, for the general rules where calls to `dwarf_dealloc()` are appropriate.

As of May 2020 there are additional dealloc calls which enable type-checking the calls:
`dwarf_dealloc_error()`, `dwarf_dealloc_die()`, and
`dwarf_dealloc_attribute()`.

5.2.1 `dwarf_dealloc()`

The first prototype is the generic one that can deallocate any of the libdwarf types, such as `DW_DLA_DIE` etc.. This has the disadvantages that the `space_to_dealloc` argument cannot be type checked and the `appropriate_dla_name` is a simple integer, hence not meaningfully checkable either.

Whenever possible, use a type-safe deallocation call (for several types that is the only documented deallocation call) and for `Dwarf_Die` `Dwarf_Attribute` or `Dwarf_Error` use the following dealloc functions instead of this one. The use of this form remains fully supported,

```
void dwarf_dealloc(Dwarf_Debug dbg,
                    void *space_to_dealloc,
                    int appropriate_dla_name);
```

Figure 3. Example_dwarf_dealloc()

```
void exampledealloc(Dwarf_Debug dbg, Dwarf_Die somedie)
{
    dwarf_dealloc(dbg, somedie, DW_DLA_DIE);
}
```

5.2.2 `dwarf_dealloc_die()`

The second prototype is only to deallocate a `Dwarf_Die`. Any call to this is typechecked.

```
void dwarf_dealloc_die(Dwarf_Die mydie);
```

Figure 4. Example_dwarf_dealloc_die()

```
void exampledeallocdie(Dwarf_Die somedie)
{
    dwarf_dealloc_die(somedie);
}
```

5.2.3 dwarf_dealloc_attribute()

The second prototype is only to deallocate a Dwarf_Attribute. These arise from calls from dwarf_attrlist(). Any call to this is typechecked.

```
void dwarf_dealloc_error(Dwarf_Debug dbg,
    Dwarf_Die mydie);
```

Figure 5. Example_dwarf_dealloc_attribute()

```
void exampledeallocerror(Dwarf_Attribute attr)
{
    dwarf_dealloc_attribute(attr);
}
```

5.2.4 dwarf_dealloc_error()

The second prototype is only to deallocate a Dwarf_Error. These arise when some libdwarf call returns DW_DLV_ERROR. Any call to this is typechecked.

```
void dwarf_dealloc_error(Dwarf_Debug dbg,
    Dwarf_Die mydie);
```

Figure 6. Example_dwarf_dealloc_error()

```
void exampledeallocerror(Dwarf_Debug dbg, Dwarf_Error err)
{
    dwarf_dealloc_error(dbg, err);
}
```

See also Errors Returned from dwarf_init* calls (below).

In some cases the pointers returned by a *libdwarf* call are pointers to data which is not freeable. The library knows from the allocation type provided to it whether the space is freeable or not and will not free inappropriately when dwarf_dealloc() is called. So it is vital that dwarf_dealloc() be called with the proper allocation type.

For all storage allocated by *libdwarf*, the client can free the storage for reuse by calling dwarf_dealloc(), providing it with the Dwarf_Debug descriptor specifying the

object for which the storage was allocated, a pointer to the area to be free-ed, and an identifier that specifies what the pointer points to (the allocation type). For example, to free a `Dwarf_Die` `die` belonging the the object represented by `Dwarf_Debug` `dbg`, allocated by a call to `dwarf_siblingof()`, the call to `dwarf_dealloc()` would be:

```
dwarf_dealloc(dbg, die, DW_DLA_DIE);  
or, preferably,  
dwarf_dealloc_die(die);
```

To free storage allocated in the form of a list of pointers (opaque descriptors), each member of the list should be deallocated, followed by deallocation of the actual list itself. The following code fragment uses an invocation of `dwarf_attrlist()` as an example to illustrate a technique that can be used to free storage from any *libdwarf* routine that returns a list:

Figure 7. Example1 dwarf_attrlist()

```
void example1(Dwarf_Debug dbg, Dwarf_Die somedie)  
{  
    Dwarf_Signed atcount = 0;  
    Dwarf_Attribute *atlist = 0;  
    Dwarf_Error error = 0;  
    Dwarf_Signed i = 0;  
    int errv = 0;  
  
    errv = dwarf_attrlist(somedie, &atlist, &atcount, &error);  
    if (errv == DW_DLV_OK) {  
        for (i = 0; i < atcount; ++i) {  
            /* use atlist[i] */  
            dwarf_dealloc_attribute(atlist[i]);  
            /* This original form still works.  
            dwarf_dealloc(dbg, atlist[i], DW_DLA_ATTR);  
            */  
        }  
        dwarf_dealloc(dbg, atlist, DW_DLA_LIST);  
    }  
}
```

`dwarf_finish()` will deallocate all dynamic storage associated with an instance of a `Dwarf_Debug` type. In particular, it will deallocate all dynamically allocated space associated with the `Dwarf_Debug` descriptor, and finally make the descriptor invalid.

5.2.5 Errors Returned from `dwarf_init*` calls

These errors are almost always due to fuzzing objects, injecting random values into objects. Rarely seen in any valid object file. See "<https://en.wikipedia.org/wiki/Fuzzing>"

A `Dwarf_Error` returned from any `dwarf_init*`() or `dwarf_elf_init*`() should be dealt with like any other error. We start with an example of how to deal with this class of errors. See just below the example for a further discussion.

```
void exampleinitfail(const char *path,
    char *true_pathbuf,
    unsigned tpathlen,
    unsigned access,
    unsigned groupnumber)
{
    Dwarf_Handler errhand = 0;
    Dwarf_Ptr errarg = 0;
    Dwarf_Error error = 0;
    Dwarf_Debug dbg = 0;
    const char *reserved1 = 0;
    Dwarf_Undefined reserved2 = 0;
    Dwarf_Undefined reserved3 = 0;
    int res = 0;

    res = dwarf_init_path(path,true_pathbuf,
        tpathlen,access,groupnumber,errhand,
        errarg,&dbg,reserved1,reserved2,
        &reserved3,
        &error);
    /* Preferred version */
    if (res == DW_DLV_ERROR) {
        /* Valid call even though dbg is null! */
        dwarf_dealloc(dbg,error,DW_DLA_ERROR);
        /* Simpler newer form in
           this comment, but use the
           older form above for compatibility
           with older libdwarf.
           dwarf_dealloc_error(dbg,error);
           With libdwarf before September 2020
           these dealloc calls will leave
           a few bytes allocated.
        */
        /* The orginal recommendation to call
           free(error) in this case is still
           valid though it will not necessarily
           free every byte allocated with
           September 2020 and later libdwarf. */
    }
    /* Horrible messy alternative, best effort
       if dwarf_package_version exists
       (function created in October 2019
       package version 20191106). */
    if (res == DW_DLV_ERROR) {
        const char *ver = dwarf_package_version();
        int cmpres = 0;
```

```
cmpres = strcmp(ver,"20200822");
if (cmpres > 0) {
    dwarf_dealloc_error(dbg,error);
} else {
    free(error);
}
}
```

If your application needs to be absolutely sure not even a single byte leaks from a failed libdwarf init function call the only sure approach is to ensure you use a September 2020 (version 20200908) or later libdwarf. Versions between 20191104 and 20200908 have no available function that will guarantee freeing these last few bytes.

If your application does not care if a failed libdwarf init function leaks a few bytes then the September 2020 advice of calling dwarf_dealloc(dbg,error,DW_DLA_ERROR) is best, as though leaks a few bytes with libdwarf before September 2020.

If your application is using 20191104 or earlier libdwarf the choice of free(error) will avoid a leak from a failed dwarf init call, though changing to a more recent libdwarf will then make a few bytes leak quite possible until the application is changed to use the dwarf_dealloc call.

5.2.6 Error DW_DLA error free types

The codes that identify the storage pointed to in calls to dwarf_dealloc() are described in figure 8.

IDENTIFIER	USED TO FREE
DW_DLA_STRING	char*
DW_DLA_LOC	Dwarf_Loc
DW_DLA_LOCDESC	Dwarf_Locdesc
DW_DLA_ELLIST	Dwarf_Ellist (not used)
DW_DLA_BOUNDS	Dwarf_Bounds (not used)
DW_DLA_BLOCK	Dwarf_Block
DW_DLA_DEBUG	Dwarf_Debug (do not use)
DW_DLA_DIE	Dwarf_Die
DW_DLA_LINE	Dwarf_Line
DW_DLA_ATTR	Dwarf_Attribute
DW_DLA_TYPE	Dwarf_Type (not used)
DW_DLA_SUBSCR	Dwarf_Subscr (not used)
DW_DLA_GLOBAL	Dwarf_Global
DW_DLA_ERROR	Dwarf_Error
DW_DLA_LIST	a list of opaque descriptors
DW_DLA_LINEBUF	Dwarf_Line* (not used)
DW_DLA_ARANGE	Dwarf_Arange
DW_DLA_ABBREV	Dwarf_Abbrev
DW_DLA_FRAME_OP	Dwarf_Frame_Op
DW_DLA_CIE	Dwarf_Cie
DW_DLA_FDE	Dwarf_Fde
DW_DLA_LOC_BLOCK	Dwarf_Loc_Block
DW_DLA_FRAME_BLOCK	Dwarf_Frame_Block (not used)
DW_DLA_FUNC	Dwarf_Func
DW_DLA_TYPENAME	Dwarf_Type
DW_DLA_VAR	Dwarf_Var
DW_DLA_WEAK	Dwarf_Weak
DW_DLA_ADDR	Dwarf_Addr
DW_DLA_RANGES	Dwarf_Ranges
DW_DLA_GNU_INDEX_HEAD	.debug_gnu_type/pubnames
DW_DLA_RNGLISTS_HEAD	.debug_rnglists
DW_DLA_DGBINDEX	Dwarf_Gdbindex
DW_DLA_XU_INDEX	Dwarf_Xu_Index_Header
DW_DLA_LOC_BLOCK_C	Dwarf_Loc_c
DW_DLA_LOCDESC_C	Dwarf_Locdesc_c
DW_DLA_LOC_HEAD_C	Dwarf_Loc_Head_c
DW_DLA_MACRO_CONTEXT	Dwarf_Macro_Context
DW_DLA_DSC_HEAD	Dwarf_Dsc_Head
DW_DLA_DNAMES_HEAD	Dwarf_Dnames_Head
DW_DLA_STR_OFFSETS	Dwarf_Str_Offsets_Table

Figure 8. Allocation/Deallocation Identifiers

6. Functional Interface

This section describes the functions available in the *libdwarf* library. Each function description includes its definition, followed by one or more paragraph describing the function's operation.

The following sections describe these functions.

6.1 Initialization Operations

These functions are concerned with preparing an object file for subsequent access by the functions in *libdwarf* and with releasing allocated resources when access is complete. `dwarf_init_path()` or `dwarf_init_path_dl()` are the initialization functions to use if one actually has a path (if you just have an open fd or open libelf handle you cannot use the `_path_` versions that's fine). These both allow libdwarf to attempt to follow GNU debuglink hints in a specially produced executable/shared-object to find the object file with the DWARF sections to match the executable(or shared-object). For non-debuglink executables these two functions behave identically.

GNU debuglink is completely different than and separate from Split Dwarf and MacOS dSYM. it would seem unlikely that these could be combined in any single executable/shared-object. All are intended to have DWARF fully available but not taking space in the executable/shared object. See <https://sourceware.org/gdb/onlinedocs/gdb/Separate-Debug-Files.html> for information on debuglink and the related build-id.

`dwarf_init_path()` provides no way to add extra global paths to debuglink searches. But `dwarf_init_path_dl()` has 2 extra arguments to make adding extra paths easy.

libdwarf lets one access the executable's section `.eh_frame` with frame/backtrace information by turning off recognition of GNU debuglink in the `Dwarf_Debug` being opened by passing in `true_path_out_buffer` `true_path_bufferlen` as zero.

6.1.1 `dwarf_init_path()`

```
int dwarf_init_path(
    const char *          path,
    char *                true_path_out_buffer,
    unsigned               true_path_bufferlen,
    Dwarf_Unsigned         access,
    unsigned               groupnumber,
    Dwarf_Handler          errhand,
    Dwarf_Ptr               errarg,
    Dwarf_Debug*            dbg,
    const char *           reserved1,
    Dwarf_Unsigned *        reserved2,
    Dwarf_Unsigned *        reserved3,
    Dwarf_Error*           * error);
```

On success the function returns DW_DLV_OK, and returns a pointer to an initialized Dwarf_Debug through the dbg argument. All this work identically across all supported object file types.

If DW_DLV_NO_ENTRY is returned there is no such file and nothing else is done or returned.

If DW_DLV_ERROR is returned a Dwarf_Error is returned through the error pointer. and nothing else is done or returned.

Now we turn to the arguments.

Pass in the name of the object file via the path argument.

For MacOS pass in a pointer to true_path_out_buffer big pointing to a buffer large enough to hold the passed-in path if that were doubled plus adding 100 characters. Then pass that length in the true_path_bufferlen argument. If a file is found (the dSYM path or if not that the original path) the final path is copied into true_path_out_buffer. In any case, This is harmless with non-MacOS executables, but for non-MacOS non GNU_debuglink objects true_path_out_buffer will just match path.

For Elf executables/shared-objects using GNU_debuglink The same considerations apply: pass in a pointer to true_path_out_buffer big pointing to a buffer large enough to hold the passed-in path if that were doubled plus adding 100 characters (a heuristic) (the 100 is arbitrary: GNU_debuglink paths can be long but not likely longer than this suggested size.

When you know you won't be reading MacOS executables and won't be accessing GNU_debuglink executables special treatment by passing 0 as arguments to true_path_out_buffer and true_path_bufferlen. If those are zero the MacOS/ GNU_debuglink special processing will not occur.

Pass in zero with the access argument. The DW_DLC_READ flag, which only ever applied to libelf, is zero.

The groupnumber argument indicates which group is to be accessed Group one is normal dwarf sections such as .debug_info. Group two is DWARF5 dwo split-dwarf dwarf sections such as .debug_info.dwo.

Groups three and higher are for COMDAT groups. If an object file has only sections from one of the groups then passing zero will access that group. Otherwise passing zero will access only group one.

See `dwarf_sec_group_sizes()` and `dwarf_sec_group_map()` for more group information.

Typically pass in DW_GROUPNUMBER_ANY to groupnumber. Non-elf objects do not use this field.

The errhand argument is a pointer to a function that will be invoked whenever an error is detected as a result of a *libdwarf* operation. The errarg argument is passed as an argument to the errhand function.

`dbg` is used to return an initialized `Dwarf_Debug` pointer.

`reserved1`, `reserved2`, and `reserved3` are currently unused, pass 0 in to all three.

Pass in a pointer to a `Dwarf_Error` to the `error` argument if you wish libdwarf to return an error code.

6.1.2 `dwarf_init_path_dl()`

```
int dwarf_init_path_dl(
    const char *          path,
    char *                true_path_out_buffer,
    unsigned              true_path_bufferlen,
    Dwarf_Unsigned        access,
    unsigned              groupnumber,
    Dwarf_Handler         errhand,
    Dwarf_Ptr              errarg,
    char **               global_paths,
    unsigned int           global_paths_count
    Dwarf_Debug*           dbg,
    const char *           reserved1,
    Dwarf_Unsigned *       reserved2,
    Dwarf_Unsigned *       reserved3,
    Dwarf_Error*           * error);
```

This function is identical to `dwarf_init_path()` in every respect except if you know that you must use special paths to find the GNU debuglink target file with DWARF information.

`global_paths` allows you to specify such paths. Pass in `global_paths` as a

pointer to an array of pointer-to-char, each pointing to a global path string. Pass in `global_paths_count` with the number of entries in the pointer array. Pass both as zero if there are no debuglink global paths other than the default standard `/usr/lib/debug`.

6.1.3 `dwarf_init_b()`

```
int dwarf_init_b(
int fd,
    Dwarf_Unsigned access,
    unsigned group_number,
    Dwarf_Handler errhand,
    Dwarf_Ptr errarg,
    Dwarf_Debug * dbg,
    Dwarf_Error *error)
```

When it returns `DW_DLV_OK`, the function `dwarf_init_b()` returns through `dbg` a `Dwarf_Debug` descriptor that represents a handle for accessing debugging records associated with the open file descriptor `fd`. `DW_DLV_NO_ENTRY` is returned if the object does not contain DWARF debugging information. `DW_DLV_ERROR` is returned if an error occurred.

The `access` argument indicates what access is allowed for the section. The `DW_DLC_READ` macro value is zero and valid for read access (only read access is defined or discussed in this document). No value other than zero should be passed in to these consumer/reader functions. The value passed in is ignored.

The `groupnumber` argument indicates which group is to be accessed Group one is normal dwarf sections such as `.debug_info`. Group two is DWARF5 dwo split-dwarf dwarf sections such as `.debug_info.dwo`.

Groups three and higher are for COMDAT groups. If an object file has only sections from one of the groups then passing zero will access that group. Otherwise passing zero will access only group one.

See `dwarf_sec_group_sizes()` and `dwarf_sec_group_map()` for more group information.

The `errhand` argument is a pointer to a function that will be invoked whenever an error is detected as a result of a *libdwarf* operation. The `errarg` argument is passed as an argument to the `errhand` function.

The file descriptor associated with the `fd` argument must refer to an ordinary file (i.e. not a pipe, socket, device, /proc entry, etc.), be opened with the at least as much permission as specified by the `access` argument, and cannot be closed or used as an argument to any system calls by the client until after `dwarf_finish()` is called. The seek position of the file associated with `fd` is undefined upon return of `dwarf_init()`.

Historical Note: With SGI IRIX, by default it was allowed that the app `close()` `fd` immediately after calling `dwarf_init()`, but that is not a portable approach (that it worked was an accidental side effect of the fact that SGI IRIX used `ELF_C_READ_MMAP` in its hidden internal call to `elf_begin()`). The portable approach is to consider that `fd` must be left open till after the corresponding `dwarf_finish()` call has returned.

Since `dwarf_init()` uses the same error handling processing as other *libdwarf* functions (see *Error Handling* above), client programs will generally supply an `error` parameter to bypass the default actions during initialization unless the default actions are appropriate.

6.1.4 dwarf_init()

```
int dwarf_init(
    int fd,
    Dwarf_Unsigned access,
    Dwarf_Handler errhand,
    Dwarf_Ptr errarg,
    Dwarf_Debug * dbg,
    Dwarf_Error *error)
```

`dwarf_init()` is identical to `dwarf_init_b()` except that `dwarf_init()` is missing the `groupnumber` argument so access to an object file containing both dwo and non-dwo DWARF5 object sections will access only group one (and will ignore the dwo sections).

The `dwarf_get_elf()` function cannot succeed when using `dwarf_init()` or `dwarf_init_b()` or `dwarf_init_path()` to open an object file.

6.1.5 dwarf_set_de_alloc_flag()

```
int dwarf_set_de_alloc_flag(
    int v)
```

`dwarf_set_de_alloc_flag()` sets and returns a flag value applying to the current running instance of *libdwarf*. It's action sets an internal value, and that value should be set/changed (if you wish to do that) before any other *libdwarf* calls.

By default *libdwarf* keeps track of all its internal allocations. So if the documentation here says you should do `dwarf_dealloc()` calls (or other calls documented here for specific functions) and you omit some or all of them then calling `dwarf_finish()` will clean up all those allocations left undone.

If you call `dwarf_set_de_alloc_flag(0)` then *libdwarf* will not keep track of allocations so your code must do all `dwarf_dealloc()` calls as defined below.

If you call `dwarf_set_de_alloc_flag(1)` that sets/restores the setting to its default value so from that point all new internal allocations will be tracked and `dwarf_finish()` can clean the new ones up.

The return value of `dwarf_set_de_alloc_flag()` is the previous value of the internal flag: One (1) is the default, meaning record allocations.. Zero (0) is the other possible value, meaning do not record libdwarf allocations.

It is best to ignore this call unless you have gigantic DWARF sections and you need whatever percent speed improvement from libdwarf that you can get. If you do use it then by all means use tools such as `cc --fsanitize...` or `valgrind` to ensure there are no leaks in your application (at least given your test cases).

The function name echos the spelling of a libdwarf-internal field in `struct Dwarf_Debug_s` named `de_alloc_tree`.

6.1.6 Dwarf_Handler function

This is an example of a valid error handler function. A pointer to this (or another like it) may be passed to `dwarf_elf_init_b()` or `dwarf_init_b()`.

```
static void
simple_error_handler(Dwarf_Error error, Dwarf_Ptr errarg)
{
    printf("libdwarf error: %d  %s\n",
           dwarf_errno(error), dwarf_errmsg(error));
    exit(1);
}
```

This will only be called if an error is detected inside libdwarf and the `Dwarf_Error` argument passed to libdwarf is `NULL`. A `Dwarf_Error` will be created with the error number assigned by the library and passed to the error handler.

The second argument is a copy of the value passed in to `dwarf_elf_init_b()` or `dwarf_init()` as the `errarg()` argument. Typically the init function would be passed a pointer to an application-created struct containing the data the application needs to do what it wants to do in the error handler.

In a language with exceptions or exception-like features an exception could be thrown here. Or the application could simply give up and call `exit()` as in the sample given above.

6.1.7 dwarf_elf_init_b() [deprecated 2019]

```
int dwarf_elf_init_b(
    Elf * elf_file_pointer,
    Dwarf_Unsigned access,
    unsigned groupnumber,
    Dwarf_Handler errhand,
    Dwarf_Ptr errarg,
    Dwarf_Debug * dbg,
    Dwarf_Error *error)
```

We recommend you change to calling `dwarf_init_b()` or `dwarf_init_path()`

instead. The `dwarf_elf_init()` and `dwarf_elf_init_b()` interfaces give no benefit over the other interfaces (other than allowing `dwarf_get_elf()` to succeed).

The function `dwarf_elf_init_b()` is similar to `dwarf_init_b()` but an open `Elf *` pointer is passed instead of a file descriptor so `dwarf_get_elf()` can succeed.

The client is allowed to use the `Elf *` pointer for its own purposes without restriction during the time the `Dwarf_Debug` is open, except that the client should not `elf_end()` the pointer till after `dwarf_finish` is called.

6.1.8 `dwarf_elf_init()` [deprecated 2019]

```
int dwarf_elf_init(
    Elf * elf_file_pointer,
    Dwarf_Unsigned access,
    Dwarf_Handler errhand,
    Dwarf_Ptr errarg,
    Dwarf_Debug * dbg,
    Dwarf_Error *error)
```

The function `dwarf_elf_init()` is identical to `dwarf_init[_b]()` except an open `Elf *` pointer is passed instead of a file descriptor so `dwarf_get_elf()` can succeed.

Code using `dwarf_elf_init[_b]()` should be switched to calling `dwarf_init_b()`.

6.1.9 `dwarf_get_elf()`

```
int dwarf_get_elf(
    Dwarf_Debug dbg,
    Elf ** elf,
    Dwarf_Error *error)
```

The function `dwarf_get_elf()` is only meaningful if a `dwarf_elf_init[_b]()` function was used to initialize the pointer `dbg`. None of the other `dwarf*init*()` functions here ever use `libelf`, so there is no `Elf` pointer to return through the pointer, so and the call will return `DW_DLV_NO_ENTRY`. In addition, this function is also not meaningful for an object file that is not in the `Elf` format.

When it returns `DW_DLV_OK`, the function `dwarf_get_elf()` returns through the pointer `elf` the `Elf *` handle used to access the object represented by the `Dwarf_Debug` descriptor `dbg`. It returns `DW_DLV_ERROR` on error.

6.1.10 `dwarf_set_tied_dbg()`

```
int dwarf_set_tied_dbg(
    Dwarf_Debug dbg,
    Dwarf_Debug tieddbg,
    Dwarf_Error *error)
```

The function `dwarf_set_tied_dbg()` enables cross-object access of DWARF data. If a DWARF5 Package object has `DW_FORM_addrx` or `DW_FORM_GNU_addr_index` or one of the other indexed forms in DWARF5 in an address attribute one needs both the Package file and the executable to extract the actual address with `dwarf_formaddr()`. The utility function `dwarf_addr_form_is_indexed(form)` is a handy way to know if an address form is indexed. One does a normal `dwarf_elf_init_b()` or `dwarf_init()_b` on each object and then tie the two together with a call such as:

Figure 9. Example2 `dwarf_set_died_dbg()`

```
void example2(Dwarf_Debug dbg, Dwarf_Debug tieddbg)
{
    Dwarf_Error error = 0;
    int res = 0;

    /* Do the dwarf_init_b() or dwarf_elf_init_b()
       calls to set
       dbg, tieddbg at this point. Then: */
    res = dwarf_set_tied_dbg(dbg, tieddbg, &error);
    if (res != DW_DLV_OK) {
        /* Something went wrong*/
    }
}
```

When done with both `dbg` and `tieddbg` do the normal finishing operations on both in any order.

It is possible to undo the tieing operation with

Figure 10. Example3 `dwarf_set_tied_dbg()` obsolete

```
void example3(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    int res = 0;
    res = dwarf_set_tied_dbg(dbg, NULL, &error);
    if (res != DW_DLV_OK) {
        /* Something went wrong*/
    }
}
```

It is not necessary to undo the tieing operation before finishing on the `dbg` and `tieddbg`.

6.1.11 dwarf_get_tied_dbg()

```
int dwarf_get_tied_dbg(
    Dwarf_Debug /*dbg*/,
    Dwarf_Debug * /*tieddbg_out*/,
    Dwarf_Error * /*error*/)
```

dwarf_get_tied_dbg returns DW_DLV_OK and sets tieddbg_out to the pointer to the 'tied' Dwarf_Debug. If there is no 'tied' object tieddbg_out is set to NULL.

On error it returns DW_DLV_ERROR.

It never returns DW_DLV_NO_ENTRY.

6.1.12 dwarf_finish()

```
int dwarf_finish(
    Dwarf_Debug dbg,
    Dwarf_Error *error)
```

The function dwarf_finish() releases all *Libdwarf* internal resources associated with the descriptor dbg, and invalidates dbg. It returns DW_DLV_ERROR if there is an error during the finishing operation. It returns DW_DLV_OK for a successful operation.

Because int dwarf_init() opens an Elf descriptor on its fd and dwarf_finish() does not close that descriptor, an app should use dwarf_get_elf and should call elf_end with the pointer returned through the Elf** handle created by int dwarf_init().

6.1.13 dwarf_set_stringcheck()

```
int dwarf_set_stringcheck(
    int stringcheck)
```

The function int dwarf_set_stringcheck() sets a global flag and returns the previous value of the global flag.

If the stringcheck global flag is zero (the default) libdwarf does string length validity checks (the checks do slow libdwarf down very slightly). If the stringcheck global flag is non-zero libdwarf does not do string length validity checks.

The global flag is really just 8 bits long, upperbits are not noticed or recorded.

6.1.14 dwarf_set_reloc_application()

```
int dwarf_set_reloc_application(
    int apply)
```

The function `int dwarf_set_reloc_application()` sets a global flag and returns the previous value of the global flag.

If the `reloc_application` global flag is non-zero (the default) then the applicable `.rela` section (if one exists) will be processed and applied to any DWARF section when it is read in. If the `reloc_application` global flag is zero no such relocation-application is attempted.

Not all machine types (elf header `e_machine`) or all relocations are supported, but then very few relocation types apply to DWARF debug sections.

The global flag is really just 8 bits long, upperbits are not noticed or recorded.

It seems unlikely anyone will need to call this function.

6.1.15 dwarf_record_cmdline_options()

```
int dwarf_record_cmdline_options(
    Dwarf_Cmdline_Options options)
```

The function `int dwarf_record_cmdline_options()` copies a `Dwarf_Cmdline_Options` structure from consumer code to libdwarf.

The structure is defined in `libdwarf.h`.

The initial version of this structure has a single field `check_verbose_mode` which, if non-zero, tells libdwarf to print some detailed messages to `stdout` in case certain errors are detected.

The default for this value is FALSE (0) so the extra messages are off by default.

6.1.16 dwarf_object_init_b()

```
int dwarf_object_init_b(
    Dwarf_Obj_Access_Interface* obj,
    Dwarf_Handler errhand,
    Dwarf_Ptr errarg,
    unsigned groupnumber,
    Dwarf_Debug* dbg,
    Dwarf_Error* error)
```

The function `int dwarf_object_init_b()` enables access to non-Elf object files by allowing the caller to then provide function pointers to code (user-written, not part of libdwarf) that will look, to libdwarf, as if libdwarf was reading Elf.

See `int dwarf_init_b()` for additional information on the arguments passed in (the `obj` argument here is a set of function pointers and describing how to access non-Elf

files is beyond the scope of this document.

As a hint, note that the source files with dwarf_elf_init_file_ownership() (dwarf_original_elf_init.c) and dwarf_elf_object_access_init() (dwarf_elf_access.c) are the only sources that would need replacement for a different object format. The replacement would need to emulate certain conventions of Elf objects, (mainly that section index 0 is an empty section) but the rest of libdwarf uses what these two source files set up without knowing how to operate on Elf.

Writing the functions needed to support non-Elf will require study of Elf and of the object format involved. The topic is beyond the scope of this document.

6.1.17 dwarf_object_init()

```
int dwarf_object_init(
    Dwarf_Obj_Access_Interface* obj,
    Dwarf_Handler errhand,
    Dwarf_Ptr     errarg,
    Dwarf_Debug*   dbg,
    Dwarf_Error*   error)
```

The function int dwarf_object_init() is the same as int dwarf_object_init_b() except int dwarf_object_init() is missing the groupnumber argument so DWARF5 split dwarf objects cannot be fully handled.

6.1.18 dwarf_get_real_section_name()

```
int dwarf_get_real_section_name( Dwarf_Debug dbg,
                                const char * std_section_name,
                                const char ** actual_sec_name_out,
                                Dwarf_Small * marked_compressed,
                                Dwarf_Small * marked_zlib_compressed,
                                Dwarf_Small * marked_shf_compressed,
                                Dwarf_Unsigned * compressed_length,
                                Dwarf_Unsigned * uncompressed_length,
                                Dwarf_Error * error);
```

Elf sections are sometimes compressed to reduce the disk footprint of the sections. It's sometimes interesting to library users what the real name was in the object file and whether it was compressed. Libdwarf uncompresses such sections automatically. It's not usually necessary to know the true name or anything about compression.

The caller passes in a Dwarf_Debug pointer and a standard section name such as ".debug_info". On success the function returns (through the other arguments) the true section name and a flag which, if non-zero means the section was compressed and a flag which, if non-zero means the section had the Elf section flag SHF_COMPRESSED set. The caller must ensure that the memory pointed to by actual_sec_name_out,

`marked_zcompressed`, and `marked_zlib_compressed`,
`marked_shf_compressed`, `compressed_length`, `uncompressed_length`,
is zero at the point of call.

The flag `*marked_compressed`, if non-zero, means the section name started with `.zdebug` (indicating compression was done).

The flag `marked_zlib_compressed`, if non-zero means the initial bytes of the section start with the ASCII characters ZLIB and the section was compressed.

The flag `marked_shf_compressed` if non-zero means the Elf section `sh_flag` `SHF_COMPRESSED` is set and the section was compressed.. The flag value in an elf section header is $(1 \ll 11)$ (`0x800`).

The value `compressed_length` is passed back through the pointer if and only if the section is compressed and the pointer is non-null.

The value `uncompressed_length` is passed back through the pointer if and only if the section is compressed and the pointer is non-null.

If the section name passed in is not used by libdwarf for this object file the function returns `DW_DLV_NO_ENTRY`

On error the function returns `DW_DLV_ERROR`.

The string pointed to by `*actual_sec_name_out` must not be free()'d.

6.1.19 dwarf_package_version()

```
const char * dwarf_package_version(void);
```

The package version is set in config.h (from its value in configure.ac and in CMakeLists.txt in the source tree) at the build time of the library. A pointer to a static string is returned by this function. The format is standard ISO date format. For example "20180718". It's not entirely clear how this actually helps. But there is a request for this and we provide it as of 23 October 2019.

6.2 Object Type Detectors

These are used by libdwarf and may be of use generally. They have no connection to any Dwarf_Debug data as you see from the arguments passed in.

6.2.1 dwarf_object_detector_path()

```
int dwarf_object_detector_path(const char *path,
    char *outpath,
    unsigned long outpath_len,
    unsigned *ftype,
    unsigned *endian,
    unsigned *offsetsize,
    Dwarf_Unsigned *filesize,
    int * errcode);
```

On success the function returns DW_DLV_OK, and returns various data through the arguments (described just below). This works identically across all supported object file types.

If DW_DLV_NO_ENTRY is returned there is no such file and nothing else is done or returned.

If DW_DLV_ERROR is returned a Dwarf_Error is returned through the error pointer. and nothing else is done or returned.

Now we turn to the arguments. Pass in the name of the object file via the path argument.

To outpath pass in a pointer big enough to hold the passed-in path if that were doubled plus adding 100 characters. Then pass that length in the outpath_len argument. The path will be copied to outpath. In the case of certain MacOS dSYM object files the final outpath of the dSYM file (with MacOS conventional directories added) is copied into outpath. Where the MacOS local directory tree is missing or incomplete outpath will be left as a zero-length string.

To entirely skip the MacOS special treatment pass 0 as arguments to outpath and outpath_len.

The ftype pointer argument returns DW_FTYPE_ELF, DW_FTYPE_MACH_O , DW_FTYPE_PE , DW_FTYPE_ARCHIVE or DW_FTYPE_UNKNOWN to the caller. The DW_FTYPE_ARCHIVE value says nothing whatever about the contents of the archive.

The endian pointer argument returns DW_ENDIAN_BIG, DW_ENDIAN_LITTLE , DW_ENDIAN_SAME , DW_ENDIAN_OPPOSITE or DW_ENDIAN_UNKNOWN to the caller.

The offsetsize pointer argument returns a size value from the object file. If the object file uses 32-bit offsets it returns 32, and if 64-bit offsets it returns 64. Each object type uses such values but the ways the value is used varies.

The filesize pointer argument returns the size, in bytes, of the object file. This is essentially useless for DW_FTYPE_ARCHIVE files, one thinks.

The errcode pointer argument returns (if and only if DW_DLV_ERROR is returned by the function) an integer error code. At this time there is no handy function to turn that error code into a string. In the libdwarf source you will find that code in the DW_DLE_* error list.

6.2.2 dwarf_object_detector_fd()

```
int dwarf_object_detector_fd(int fd,
    unsigned *ftype,
    unsigned *endian,
    unsigned *offsetsize,
    Dwarf_Unsigned *filesize,
    int *errcode);
```

dwarf_object_detector_fd() is the same as dwarf_object_detector_path() except that no path strings apply to dwarf_object_detector_fd().

6.3 Section Group Operations

The section group data is essential information when processing an object with COMDAT section group DWARF sections or with both split-dwarf (.dwo sections) and non-split dwarf sections.

It relies on Elf section groups, whereas some compilers rely instead on relocation information to identify section groups. These relocation-specified groupings are not understood at this time.

A standard DWARF2 or DWARF3 or DWARF4 object (Old Standard Object, or OSO) will not contain any of those new sections. The DWARF4 standard, Appendix E.1 "Using Compilation Units" offers an overview of COMDAT section groups. libdwarf assigns the group number one(1) to OSO DWARF. Any sections that are split dwarf (section name ending in .dwo or one of the two special DWP index sections) are assigned group number two(2) by libdwarf. COMDAT section groups are assigned groups numbers 3 and higher as needed.

The COMDAT section group uses are not well defined, but popular compilations systems are using such sections. There is no meaningful documentation that we can find (so far) on how the COMDAT section groups are used, so libdwarf is based on observations of what compilers generate.

6.3.1 dwarf_sec_group_sizes()

```
int dwarf_dwarf_sec_group_sizes(
    Dwarf_Debug dbg,
    Dwarf_Unsigned * section_count_out,
    Dwarf_Unsigned * group_count_out,
    Dwarf_Unsigned * selected_group_out,
    Dwarf_Unsigned * map_entry_count_out,
    Dwarf_Error * error)
```

The function dwarf_sec_group_sizes() may be called on any open Dwarf_Debug. It returns DW_DLV_OK on success and returns values via the pointer

arguments.

Once the Dwarf_Debug is open the group information is set and it will not change for the life of this Dwarf_Debug.

The *section_count_out is set to the number of sections in the object. Many of the sections will be irrelevant to libdwarf.

The *group_count_out is set to the number of groups in the object (as libdwarf counts them). An OSO will have exactly one group. A DWP object will have exactly one group. If is more than one group consumer code will likely want to open additional Dwarf_Debug objects and request relevant information to process the DWARF contents. An executable or a DWP object will always have a *group_count_out of one(1). An executable or a shared library cannot have any COMDAT section groups as the linker will have dealt with them.

The *selected_group_out is set to the group number that this Dwarf_Debug will focus on. See dwarf_sec_group_map() for additional details on how *selected_group_out is interpreted.

The *map_entry_count_out is set to the number of entries in the map. See dwarf_sec_group_map().

On failure it returns DW_DLV_ERROR and sets *error

The initial implementation never returns DW_DLV_ERROR or DW_DLV_NO_ENTRY but callers should allow for that possibility.

6.3.2 dwarf_sec_group_map()

```
int dwarf_sec_group_map(
    Dwarf_Debug         dbg,
    Dwarf_Unsigned     map_entry_count,
    Dwarf_Unsigned *   group_numbers_array,
    Dwarf_Unsigned *   section_numbers_array,
    const char        ** sec_names_array,
    Dwarf_Error       * error)
```

The function dwarf_sec_group_map() may be called on any open Dwarf_Debug.

The caller must allocate map_entry_count arrays used in the following three arguments the and pass the appropriate pointer into the function as well as passing in map_entry_count itself.

The map entries returned cover all the DWARF related sections in the object though the selected_group value will dictate which of the sections in the Dwarf_Debug will actually be accessed via the usual libdwarf functions. That is, only sections in the selected group may be directly accessed though libdwarf may indirectly access sections in section group one(1) so relevant details can be accessed, such as abbreviation tables

etc. Describing the details of this access outside the current `selected_group` goes beyond what this document covers (as of this writing).

It returns `DW_DLV_OK` on success and sets values into the user-allocated array elements (sorted by section number):

```
group_numbers_array[0]... group_numbers_array[map_entry_count-1]
section_numbers_array[0]... section_numbers_array[map_entry_count-1]
sec_names_array[0]... sec_names_array[map_entry_count-1]
```

`group_numbers_array[0]` for example is set to a group number. One(1), or two(2) or if there are COMDAT groups it will be three(3) or higher.

`section_numbers_array[0]` for example is set to a valid Elf section number relevant to DWARF (each section number shown will be greater than zero).

`sec_names_array[0]` for example is set to a pointer to a string containing the Elf section name of the Elf section number in `sections_number_array[0]`.

On error the function will return `DW_DLV_ERROR` or `DW_DLV_NO_ENTRY` which indicates a serious problem with this object.

Here is an example of use of these functions.

```
void examplesecgroup(Dwarf_Debug dbg)
{
    int res = 0;
    Dwarf_Uunsigned section_count = 0;
    Dwarf_Uunsigned group_count;
    Dwarf_Uunsigned selected_group = 0;
    Dwarf_Uunsigned group_map_entry_count = 0;
    Dwarf_Uunsigned *sec_nums = 0;
    Dwarf_Uunsigned *group_nums = 0;
    const char ** sec_names = 0;
    Dwarf_Error error = 0;
    Dwarf_Uunsigned i = 0;

    res = dwarf_sec_group_sizes(dbg, &section_count,
        &group_count, &selected_group, &group_map_entry_count,
        &error);
    if(res != DW_DLV_OK) {
        /* Something is badly wrong*/
        return;
    }
    /* In an object without split-dwarf sections
       or COMDAT sections we now have
       selected_group == 1. */
    sec_nums = calloc(group_map_entry_count, sizeof(Dwarf_Uunsigned));
    if(!sec_nums) {
        /* FAIL. out of memory */
        return;
    }
    group_nums = calloc(group_map_entry_count, sizeof(Dwarf_Uunsigned));
    if(!group_nums) {
        free(sec_nums);
        /* FAIL. out of memory */
        return;
    }
    sec_names = calloc(group_map_entry_count, sizeof(char*));
    if(!sec_names) {
        free(group_nums);
        free(sec_nums);
        /* FAIL. out of memory */
        return;
    }

    res = dwarf_sec_group_map(dbg, group_map_entry_count,
        group_nums, sec_nums, sec_names, &error);
    if(res != DW_DLV_OK) {
```

```
    /* FAIL. Something badly wrong. */
}
for( i = 0; i < group_map_entry_count; ++i) {
    /* Now do something with
       group_nums[i],sec_nums[i],sec_names[i] */
}
free(group_nums);
free(sec_nums);
/* The strings are in Elf data.
   Do not free() the strings themselves.*/
free(sec_names);
}
```

6.4 Section size operations

These operations are informative but not normally needed.

6.4.1 dwarf_get_section_max_offsets_b()

```
int dwarf_get_section_max_offsets_b(Dwarf_Debug dbg,
Dwarf_Unsigned * /*debug_info_size*/,
Dwarf_Unsigned * /*debug_abbrev_size*/,
Dwarf_Unsigned * /*debug_line_size*/,
Dwarf_Unsigned * /*debug_loc_size*/,
Dwarf_Unsigned * /*debug_aranges_size*/,
Dwarf_Unsigned * /*debug_macinfo_size*/,
Dwarf_Unsigned * /*debug_pubnames_size*/,
Dwarf_Unsigned * /*debug_str_size*/,
Dwarf_Unsigned * /*debug_frame_size*/,
Dwarf_Unsigned * /*debug_ranges_size*/,
Dwarf_Unsigned * /*debug_pubtypes_size*/,
Dwarf_Unsigned * /*debug_types_size*/);
```

The function `dwarf_get_section_max_offsets_b()` takes an open Dwarf_Db and reports on the section sizes by pushing section size values back through the pointers.

Created in October 2011.

6.4.2 dwarf_get_section_max_offsets()

```
int dwarf_get_section_max_offsets(Dwarf_Debug dbg,
    Dwarf_Uunsigned /*debug_info_size*/,
    Dwarf_Uunsigned /*debug_abbrev_size*/,
    Dwarf_Uunsigned /*debug_line_size*/,
    Dwarf_Uunsigned /*debug_loc_size*/,
    Dwarf_Uunsigned /*debug_aranges_size*/,
    Dwarf_Uunsigned /*debug_macinfo_size*/,
    Dwarf_Uunsigned /*debug_pubnames_size*/,
    Dwarf_Uunsigned /*debug_str_size*/,
    Dwarf_Uunsigned /*debug_frame_size*/,
    Dwarf_Uunsigned /*debug_ranges_size*/,
    Dwarf_Uunsigned /*debug_pubtypes_size*/);
```

The function is the same as `dwarf_get_section_max_offsets_b()` except it is missing the `debug_types_size()` argument. Though obsolete it is still supported.

6.5 Printf Callbacks

This is new in August 2013.

The `dwarf_print_lines()` function is intended as a helper to programs like `dwarfdump` and show some line internal details in a way only the internals of libdwarf can show them. But using `printf` directly in libdwarf means the caller has limited control of where the output appears. So now the 'printf' output is passed back to the caller through a callback function whose implementation is provided by the caller.

Any code calling libdwarf can ignore the functions described in this section completely. If the functions are ignored the messages (if any) from libdwarf will simply not appear anywhere.

The `libdwarf.h` header file defines `struct Dwarf_Printf_Callback_Info_s` and `dwarf_register_printf_callback` for those libdwarf callers wishing to implement the callback. In this section we describe how one uses that interface. The applications `dwarfdump` and `dwarfdump2` are examples of how these may be used.

6.5.1 `dwarf_register_printf_callback`

```
struct Dwarf_Printf_Callback_Info_s
    dwarf_register_printf_callback(Dwarf_Debug dbg,
        struct Dwarf_Printf_Callback_Info_s * newvalues);
```

The `dwarf_register_printf_callback()` function can only be called after the `Dwarf_Debug` instance has been initialized, the call makes no sense at other times. The function returns the current value of the structure. If `newvalues` is non-null then the passed-in values are used to initialize the libdwarf internal callback data (the values

returned are the values before the newvalues are recorded). If newvalues is null no change is made to the libdwarf internal callback data.

6.5.2 Dwarf_Printf_Callback_Info_s

```
struct Dwarf_Printf_Callback_Info_s {
    void *                      dp_user_pointer;
    dwarf_printf_callback_function_type dp_fptr;
    char *                      dp_buffer;
    unsigned int                 dp_buffer_len;
    int                          dp_buffer_user_provided;
    void *                      dp_reserved;
};
```

First we describe the fields as applicable in setting up for a call to `dwarf_register_printf_callback()`.

The field `dp_user_pointer` is remembered by libdwarf and passed back in any call libdwarf makes to the user's callback function. It is otherwise ignored by libdwarf.

The field `dp_fptr` is either NULL or a pointer to a user-implemented function.

If the field `dp_buffer_user_provided` is non-zero then `dp_buffer_len` and `dp_buffer` must be set by the user and libdwarf will use that buffer without doing any malloc of space. If the field `dp_buffer_user_provided` is zero then the input fields `dp_buffer_len` and `dp_buffer` are ignored by libdwarf and space is malloc'd as needed.

The field `dp_reserved` is ignored, it is reserved for future use.

When the structure is returned by `dwarf_register_printf_callback()` the values of the fields before the `dwarf_register_printf_callback()` call are returned.

6.5.3 dwarf_printf_callback_function_type

```
typedef void (* dwarf_printf_callback_function_type)(void * user_pointer,
                                                    const char * linecontent);
```

Any application using the callbacks needs to use the function `dwarf_register_printf_callback()` and supply a function matching the above function prototype from libdwarf.h.

6.5.4 Example of printf callback use in a C++ application using libdwarf

```
struct Dwarf_Printf_Callback_Info_s printfcallbackdata;
memset(&printfcallbackdata, 0, sizeof(printfcallbackdata));
printfcallbackdata.dp_fptr = printf_callback_for_libdwarf;
dwarf_register_printf_callback(dbg, &printfcallbackdata);
```

Assuming the user implements something like the following function in her application:

```
void
printf_callback_for_libdwarf(void *userdata, const char *data)
{
    cout << data;
}
```

It is crucial that the user's callback function copies or prints the data immediately. Once the user callback function returns the `data` pointer may change or become stale without warning.

6.6 Debugging Information Entry Delivery Operations

These functions are concerned with accessing debugging information entries, whether from a `.debug_info`, `.debug_types`, `.debug_info.dwo`, or `.debug_types.dwo`.

Since all such sections use similar formats, one set of functions suffices.

6.6.1 dwarf_get_die_section_name()

```
int
dwarf_get_die_section_name(Dwarf_Debug dbg,
                           Dwarf_Bool is_info,
                           const char ** sec_name,
                           Dwarf_Error * error);
```

`dwarf_get_die_section_name()` lets consumers access the object section name when no specific DIE is at hand. This is useful for applications wanting to print the name, but of course the object section name is not really a part of the DWARF information. Most applications will probably not call this function. It can be called at any time after the `Dwarf_Debug` initialization is done. See also `dwarf_get_die_section_name_b()`.

The function `dwarf_get_die_section_name()` operates on the either the `.debug_info[dwo]` section (if `is_info` is non-zero) or `.debug_types[dwo]` section (if `is_info` is zero).

If the function succeeds, `*sec_name` is set to a pointer to a string with the object section name and the function returns `DW_DLV_OK`. Do not free the string whose pointer

is returned. For non-Elf objects it is possible the string pointer returned will be NULL or will point to an empty string. It is up to the calling application to recognize this possibility and deal with it appropriately.

If the section does not exist the function returns DW_DLV_NO_ENTRY.

If there is an internal error detected the function returns DW_DLV_ERROR and sets the *error pointer.

6.6.2 dwarf_get_die_section_name_b()

```
int  
dwarf_get_die_section_name_b(Dwarf_Die die,  
    const char ** sec_name,  
    Dwarf_Error * error);
```

`dwarf_get_die_section_name_b()` lets consumers access the object section name when one has a DIE. This is useful for applications wanting to print the name, but of course the object section name is not really a part of the DWARF information. Most applications will probably not call this function. It can be called at any time after the Dwarf_Debug initialization is done. See also `dwarf_get_die_section_name()`.

If the function succeeds, `*sec_name` is set to a pointer to a string with the object section name and the function returns DW_DLV_OK. Do not free the string whose pointer is returned. For non-Elf objects it is possible the string pointer returned will be NULL or will point to an empty string. It is up to the calling application to recognize this possibility and deal with it appropriately.

If the section does not exist the function returns DW_DLV_NO_ENTRY.

If there is an internal error detected the function returns DW_DLV_ERROR and sets the *error pointer.

6.6.3 dwarf_next_cu_header_d()

```
int dwarf_next_cu_header_d(
    Dwarf_Debug dbg,
    Dwarf_Bool is_info,
    Dwarf_Usigned *cu_header_length,
    Dwarf_Half     *version_stamp,
    Dwarf_Usigned *abbrev_offset,
    Dwarf_Half     *address_size,
    Dwarf_Half     *offset_size,
    Dwarf_Half     *extension_size,
    Dwarf_Sig8     *signature,
    Dwarf_Usigned *typeoffset
    Dwarf_Usigned *next_cu_header,
    Dwarf_Half     *header_cu_type,
    Dwarf_Error    *error);
```

The function `dwarf_next_cu_header_d()` operates on either the `.debug_info` section (if `is_info` is non-zero) or `.debug_types` section (if `is_info` is zero). It returns `DW_DLV_ERROR` if it fails, and `DW_DLV_OK` if it succeeds.

If it succeeds, `*next_cu_header` is set to the offset in the `.debug_info` section of the next compilation-unit header if it succeeds. On reading the last compilation-unit header in the `.debug_info` section it contains the size of the `.debug_info` or `debug_types` section. Beginning 22 April 2019 `next_cu_header` will not be used to return the offset if `next_cu_header` is null. Be cautious using a null argument unless you know that only a suitably recent version of libdwarf will be used.

The next call to `dwarf_next_cu_header_b()` returns `DW_DLV_NO_ENTRY` without reading a compilation-unit or setting `*next_cu_header`. Subsequent calls to `dwarf_next_cu_header()` repeat the cycle by reading the first compilation-unit and so on.

The other values returned through pointers are the values in the compilation-unit header. If any of `cu_header_length`, `version_stamp`, `abbrev_offset`, `address_size`, `offset_size`, `extension_size`, `signature`, or `typeoffset`, is `NULL`, the argument is ignored (meaning it is not an error to provide a `NULL` pointer for any or all of these arguments).

`cu_header_length` returns the length in bytes of the compilation unit header.

`version_stamp` returns the section version, which would be (for `.debug_info`) 2 for DWARF2, 3 for DWARF3, 4 for DWARF4, or 5 for DWARF5..

`abbrev_offset` returns the `.debug_abbrev` section offset of the abbreviations for this compilation unit.

`address_size` returns the size of an address in this compilation unit. Which is usually 4 or 8.

`offset_size` returns the size in bytes of an offset for the compilation unit. The offset size is 4 for 32bit dwarf and 8 for 64bit dwarf. This is the offset size in dwarf data, not

the address size inside the executable code. The offset size can be 4 even if embedded in a 64bit elf file (which is normal for 64bit elf), and can be 8 even in a 32bit elf file (which probably will never be seen in practice).

The `extension_size` pointer is only relevant if the `offset_size` pointer returns 8. The value is not normally useful but is returned through the pointer for completeness. The pointer `extension_size` returns 0 if the CU is MIPS/IRIX non-standard 64bit dwarf (MIPS/IRIX 64bit dwarf was created years before DWARF3 defined 64bit dwarf) and returns 4 if the dwarf uses the standard 64bit extension (the 4 is the size in bytes of the 0xffffffff in the initial length field which indicates the following 8 bytes in the `.debug_info` section are the real length). See the DWARF3 or DWARF4 standard, section 7.4.

The `signature` pointer is only relevant if the CU has a type signature, and if relevant the 8 byte type signature of the `.debug_types` CU header is assigned through the pointer.

The `typeoffset` pointer is only relevant the CU has a type signature if relevant the local offset within the CU of the the type offset the `.debug_types` entry represents is assigned through the pointer. The `typeoffset` matters because a DW_AT_type referencing the type unit may reference an inner type, such as a C++ class in a C++ namespace, but the type itself has the enclosing namespace in the `.debug_type` type_unit.

The `header_cu_type` pointer is applicable to all CU headers. The value returned through the pointer is either DW_UT_compile DW_UT_partial DW_UT_type and identifies the header type of this CU. In DWARF4 a DW_UT_type will be in `.debug_types`, but in DWARF5 these compilation units are in `.debug_info` and the Debug Fission (ie Split Dwarf) `.debug_info.dwo` sections .

6.6.4 `dwarf_next_cu_header_c()`

```
int dwarf_next_cu_header_c(
    Dwarf_debug dbg,
    Dwarf_Bool is_info,
    Dwarf_Unsigned *cu_header_length,
    Dwarf_Half     *version_stamp,
    Dwarf_Unsigned *abbrev_offset,
    Dwarf_Half     *address_size,
    Dwarf_Half     *offset_size,
    Dwarf_Half     *extension_size,
    Dwarf_Sig8     *signature,
    Dwarf_Unsigned *typeoffset
    Dwarf_Unsigned *next_cu_header,
    Dwarf_Error    *error);
```

The function `dwarf_next_cu_header_c()` operates on the either the `.debug_info` section (if `is_info` is non-zero) or `.debug_types` section (if `is_info` is zero).

It operates exactly like `dwarf_next_cu_header_d()` but is missing the

header_type field. This is kept for compatibility. All code using this should be changed to use dwarf_next_cu_header_d()

6.6.5 dwarf_next_cu_header_b()

```
int dwarf_next_cu_header_b(
    Dwarf_Debug dbg,
    Dwarf_Uunsigned *cu_header_length,
    Dwarf_Half      *version_stamp,
    Dwarf_Uunsigned *abbrev_offset,
    Dwarf_Half      *address_size,
    Dwarf_Half      *offset_size,
    Dwarf_Half      *extension_size,
    Dwarf_Uunsigned *next_cu_header,
    Dwarf_Error     *error);
```

This is obsolete as of October 2011 though supported.

The function dwarf_next_cu_header_b() operates on the .debug_info section. It operates exactly like dwarf_next_cu_header_c() but is missing the signature, and typeoffset fields. This is kept for compatibility. All code using this should be changed to use dwarf_next_cu_header_c()

6.6.6 dwarf_next_cu_header()

The following is the original form, missing the offset_size, extension_size, signature, and typeoffset fields in dwarf_next_cu_header_c(). This is kept for compatibility. All code using this should be changed to use dwarf_next_cu_header_c()

```
int dwarf_next_cu_header(
    Dwarf_Debug dbg,
    Dwarf_Uunsigned *cu_header_length,
    Dwarf_Half      *version_stamp,
    Dwarf_Uunsigned *abbrev_offset,
    Dwarf_Half      *address_size,
    Dwarf_Uunsigned *next_cu_header,
    Dwarf_Error     *error);
```

6.6.7 dwarf_siblingof_b()

```
int dwarf_siblingof_b(
    Dwarf_Debug dbg,
    Dwarf_Die die,
    Dwarf_Bool is_info,
    Dwarf_Die *return_sib,
    Dwarf_Error *error)
```

The function `dwarf_siblingof_b()` returns `DW_DLV_ERROR` and sets the `error` pointer on error. If there is no sibling it returns `DW_DLV_NO_ENTRY`. When it succeeds, `dwarf_siblingof_b()` returns `DW_DLV_OK` and sets `*return_sib` to the `Dwarf_Die` descriptor of the sibling of `die`.

If `is_info` is non-zero then the `die` is assumed to refer to a `.debug_info` DIE. If `is_info` is zero then the `die` is assumed to refer to a `.debug_types` DIE. Note that the first call (the call that gets the compilation-unit DIE in a compilation unit) passes in a `NULL` `die` so having the caller pass in `is_info` is essential. And if `die` is non-`NULL` it is still essential for the call to pass in `is_info` set properly to reflect the section the DIE came from. The function `dwarf_get_die_infotypes_flag()` is of interest as it returns the proper `is_info` value from any non-`NULL` `die` pointer.

If `die` is `NULL`, the `Dwarf_Die` descriptor of the first die in the compilation-unit is returned. This die has the `DW_TAG_compile_unit`, `DW_TAG_partial_unit`, or `DW_TAG_type_unit` tag.

Figure 11. Example4 `dwarf_siblingof()`

```
void example4(Dwarf_Debug dbg,Dwarf_Die in_die,Dwarf_Bool is_info)
{
    Dwarf_Die return_sib = 0;
    Dwarf_Error error = 0;
    int res = 0;

    /* in_die might be NULL or a valid Dwarf_Die */
    res = dwarf_siblingof_b(dbg,in_die,is_info,&return_sib, &error);
    if (res == DW_DLV_OK) {
        /* Use return_sib here. */
        dwarf_dealloc_die(return_sib);
        /* This original form still works.
           dwarf_dealloc(dbg, return_sib, DW_DLA_DIE);
        */
        /* return_sib is no longer usable for anything, we
           ensure we do not use it accidentally with: */
        return_sib = 0;
    }
}
```

6.6.8 dwarf_siblingof()

```
int dwarf_siblingof(
    Dwarf_Debug dbg,
    Dwarf_Die die,
    Dwarf_Die *return_sib,
    Dwarf_Error *error)
```

int dwarf_siblingof() operates exactly the same as int dwarf_siblingof_b(), but int dwarf_siblingof() refers only to .debug_info DIEs.

6.6.9 dwarf_child()

```
int dwarf_child(
    Dwarf_Die die,
    Dwarf_Die *return_kid,
    Dwarf_Error *error)
```

The function dwarf_child() returns DW_DLV_ERROR and sets the error die on error. If there is no child it returns DW_DLV_NO_ENTRY. When it succeeds, dwarf_child() returns DW_DLV_OK and sets *return_kid to the Dwarf_Die descriptor of the first child of die. The function dwarf_siblingof() can be used with the return value of dwarf_child() to access the other children of die.

Figure 12. Example5 dwarf_child()

```
void example5(Dwarf_Die in_die)
{
    Dwarf_Die return_kid = 0;
    Dwarf_Error error = 0;
    int res = 0;

    res = dwarf_child(in_die, &return_kid, &error);
    if (res == DW_DLV_OK) {
        /* Use return_kid here. */
        dwarf_dealloc_die(return_kid);
        /* The original form of dealloc still works
           dwarf_dealloc(dbg, return_kid, DW_DLA_DIE);
        */
        /* return_die is no longer usable for anything, we
           ensure we do not use it accidentally with: */
        return_kid = 0;
    }
}
```

6.6.10 dwarf_offdie_b()

```
int dwarf_offdie_b(
    Dwarf_Debug dbg,
    Dwarf_Off offset,
    Dwarf_Bool is_info,
    Dwarf_Die *return_die,
    Dwarf_Error *error)
```

The function `dwarf_offdie_b()` returns `DW_DLV_ERROR` and sets the `error` die on error. When it succeeds, `dwarf_offdie_b()` returns `DW_DLV_OK` and sets `*return_die` to the the `Dwarf_Die` descriptor of the debugging information entry at `offset` in the section containing debugging information entries i.e the `.debug_info` section. A return of `DW_DLV_NO_ENTRY` means that the `offset` in the section is of a byte containing all 0 bits, indicating that there is no abbreviation code. Meaning this 'die offset' is not the offset of a real die, but is instead an offset of a null die, a padding die, or of some random zero byte: this should not be returned in normal use.

It is the user's responsibility to make sure that `offset` is the start of a valid debugging information entry. The result of passing it an invalid offset could be chaos.

If `is_info` is non-zero the `offset` must refer to a `.debug_info` section offset. If `is_info` zero the `offset` must refer to a `.debug_types` section offset. Error returns or misleading values may result if the `is_info` flag or the `offset` value are incorrect.

Figure 13. Example6 dwarf_offdie_b()

```
void example6(Dwarf_Debug dbg,Dwarf_Off die_offset,Dwarf_Bool is_info)
{
    Dwarf_Error error = 0;
    Dwarf_Die return_die = 0;
    int res = 0;

    res = dwarf_offdie_b(dbg,die_offset,is_info,&return_die, &error);
    if (res == DW_DLV_OK) {
        /* Use return_die here. */
        dwarf_dealloc_die(return_die);
        /* The original form still works:
           dwarf_dealloc(dbg, return_die, DW_DLA_DIE);
        */
        /* return_die is no longer usable for anything, we
           ensure we do not use it accidentally with: */
        return_die = 0;
    } else {
        /* res could be NO_ENTRY or ERROR, so no
           dealloc necessary. */
    }
}
```

6.6.11 dwarf_offdie()

```
int dwarf_offdie(
    Dwarf_Debug dbg,
    Dwarf_Off offset,
    Dwarf_Die *return_die,
    Dwarf_Error *error)
```

The function `dwarf_offdie()` is obsolete, use `dwarf_offdie_b()` instead. The function is still supported in the library, but only references the `.debug_info` section.

6.6.12 dwarf_validate_die_sibling()

```
int validate_die_sibling(
    Dwarf_Die sibling,
    Dwarf_Off *offset)
```

When used correctly in a depth-first walk of a DIE tree this function validates that any `DW_AT_sibling` attribute gives the same offset as the direct tree walk. That is the only purpose of this function.

The function `dwarf_validate_die_sibling()` returns `DW_DLV_OK` if the last die processed in a depth-first DIE tree walk was the same offset as generated by a call to

`dwarf_siblingof()`. Meaning that the DW_AT_sibling attribute value, if any, was correct.

If the conditions are not met then DW_DLV_ERROR is returned and `*offset` is set to the offset in the `.debug_info` section of the last DIE processed. If the application prints the offset a knowledgeable user may be able to figure out what the compiler did wrong.

6.7 Debugging Information Entry Query Operations

These queries return specific information about debugging information entries or a descriptor that can be used on subsequent queries when given a `Dwarf_Die` descriptor. Note that some operations are specific to debugging information entries that are represented by a `Dwarf_Die` descriptor of a specific type. For example, not all debugging information entries contain an attribute having a name, so consequently, a call to `dwarf_diename()` using a `Dwarf_Die` descriptor that does not have a name attribute will return DW_DLV_NO_ENTRY. This is not an error, i.e. calling a function that needs a specific attribute is not an error for a die that does not contain that specific attribute.

There are several methods that can be used to obtain the value of an attribute in a given die:

1. Call `dwarf_hasattr()` to determine if the debugging information entry has the attribute of interest prior to issuing the query for information about the attribute.
2. Supply an `error` argument, and check its value after the call to a query indicates an unsuccessful return, to determine the nature of the problem. The `error` argument will indicate whether an error occurred, or the specific attribute needed was missing in that die.
3. Arrange to have an error handling function invoked upon detection of an error (see `dwarf_init()`).
4. Call `dwarf_attrlist()` and iterate through the returned list of attributes, dealing with each one as appropriate.

6.7.1 `dwarf_get_die_infotypes_flag()`

```
Dwarf_Bool dwarf_get_die_infotypes_flag(Dwarf_Die die)
```

The function `dwarf_get_die_infotypes_flag()` returns the section flag indicating which section the DIE originates from. If the returned value is non-zero the DIE originates from the `.debug_info` section. If the returned value is zero the DIE originates from the `.debug_types` section.

6.7.2 dwarf_cu_header_basics()

```
int dwarf_cu_header_basics(Dwarf_Die die
    Dwarf_Half *version,
    Dwarf_Bool *is_info,
    Dwarf_Bool *is_dwo,
    Dwarf_Half *offset_size,
    Dwarf_Half *address_size,
    Dwarf_Half *extension_size,
    Dwarf_Sig8 **signature,
    Dwarf_Off *offset_of_length,
    Dwarf_Unsigned *total_byte_length,
    Dwarf_Error *error)
```

On success, the function `cu_header_basics()` various data items from the CU header and the CU die passed in. Any return-value pointer may be passed in as NULL, indicating that the value is not needed.

Summing `offset_size` and `extension_size` gives the length of the CU length field, which is immediately followed by the CU header.

`is_dwo` field will surely always be 0 as dwo/dwp .debug_info cannot be skeleton CUs.

The `signature` value is returned if there a signature in the DWARF5 CU header or the CU die.

The `offset_of_length` returned is the offset of the first byte of the length field of the CU.

The `total_byte_Length` returned is the length of data in the CU counting from the first byte at `offset_of_length`.

6.7.3 dwarf_tag()

```
int dwarf_tag(
    Dwarf_Die die,
    Dwarf_Half *tagval,
    Dwarf_Error *error)
```

The function `dwarf_tag()` returns the `tag` of `die` through the pointer `tagval` if it succeeds. It returns `DW_DLV_OK` if it succeeds. It returns `DW_DLV_ERROR` on error.

6.7.4 dwarf_dieoffset()

```
int dwarf_dieoffset(
    Dwarf_Die die,
    Dwarf_Off * return_offset,
    Dwarf_Error *error)
```

When it succeeds, the function `dwarf_dieoffset()` returns DW_DLV_OK and sets `*return_offset` to the position of `die` in the section containing debugging information entries (the `return_offset` is a section-relative offset). In other words, it sets `return_offset` to the offset of the start of the debugging information entry described by `die` in the section containing dies i.e `.debug_info`. It returns DW_DLV_ERROR on error.

6.7.5 dwarf_addr_form_is_indexed()

`dwarf_addr_form_is_indexed(form)` is a utility function to make it simple to determine if a form is one of the indexed forms (there are several such in DWARF5). See DWARF5 section 7.5.5 Classes and Forms for more information.

```
int dwarf_addr_form_is_indexed(Dwarf_Half form);
```

It returns TRUE if the form is one of the indexed address forms (such as DW_FORM_addrx1) and FALSE otherwise.

6.7.6 dwarf_debug_addr_index_to_addr()

```
int dwarf_debug_addr_index_to_addr(Dwarf_Die /*die*/,
    Dwarf_Unsigned index,
    Dwarf_Addr * return_addr,
    Dwarf_Error * error);
```

Attributes with form DW_FORM_addrx, the operation DW_OP_addrx, or certain of the split-dwarf location list entries give an index value to a machine address in the `.debug_addr` section (which is always in `.debug_addr` even when the form/operation are in a split dwarf .dwo section).

On successful return this function turns such an index into a target address value through the pointer `return_addr`.

If there is an error this may return DW_DLV_ERROR and it will have returned an error through `*error`.

If there is no available `.debug_addr` section this may return DW_DLV_NO_ENTRY.

6.7.7 dwarf_die_CU_offset()

```
int dwarf_die_CU_offset(
    Dwarf_Die die,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_die_CU_offset()` is similar to `dwarf_dieoffset()`, except that it puts the offset of the DIE represented by the `Dwarf_Die` die, from the start of the compilation-unit that it belongs to rather than the start of `.debug_info` (the `return_offset` is a CU-relative offset).

6.7.8 `dwarf_die_offsets()`

```
int dwarf_die_offsets(
    Dwarf_Die die,
    Dwarf_Off *global_off,
    Dwarf_Off *cu_off,
    Dwarf_Error *error)
```

The function `dwarf_die_offsets()` is a combination of `dwarf_dieoffset()` and `dwarf_die_cu_offset()` in that it returns both the global `.debug_info` offset and the CU-relative offset of the die in a single call.

6.7.9 `dwarf_ptr_CU_offset()`

```
int dwarf_ptr_CU_offset(
    Dwarf_CU_Context cu_context,
    Dwarf_Bit_ptr di_ptr ,
    Dwarf_Off *cu_off)
```

Given a valid CU context pointer and a pointer into that CU context, the function `dwarf_ptr_CU_offset()` returns `DW_DLV_OK` and sets `*cu_off` to the CU-relative (local) offset in that CU.

6.7.10 `dwarf_CU_dieoffset_given_die()`

```
int dwarf_CU_dieoffset_given_die(
    Dwarf_Die given_die,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_CU_dieoffset_given_die()` is similar to `dwarf_die_CU_offset()`, except that it puts the global offset of the CU DIE owning `given_die` of `.debug_info` (the `return_offset` is a global section offset).

This is useful when processing a DIE tree and encountering an error or other surprise in a DIE, as the `return_offset` can be passed to `dwarf_offdie_b()` to return a

pointer to the CU die of the CU owning the given_die passed to dwarf_CU_dieoffset_given_die(). The consumer can extract information from the CU die and the given_die (in the normal way) and print it.

An example (a snippet) of code using this function follows. It assumes that in_die is a DIE in .debug_info that, for some reason, you have decided needs CU context printed (assuming print_die_data does some reasonable printing).

Figure 14. Example7 dwarf_CU_dieoffset_given_die()

```
void example7(Dwarf_Debug dbg, Dwarf_Die in_die, Dwarf_Bool is_info)
{
    int res = 0;
    Dwarf_Off cudieoff = 0;
    Dwarf_Die cudie = 0;
    Dwarf_Error error = 0;

    res = dwarf_CU_dieoffset_given_die(in_die, &cudieoff, &error);
    if(res != DW_DLV_OK) {
        /* FAIL */
        return;
    }
    res = dwarf_offdie_b(dbg, cudieoff, is_info, &cudie, &error);
    if(res != DW_DLV_OK) {
        /* FAIL */
        return;
    }
    /* do something with cu_die */
    dwarf_dealloc_die(cudie);
    /* The original form still works.
       dwarf_dealloc(dbg, cudie, DW_DLA_DIE);
    */
}
```

y

6.7.11 dwarf_die_CU_offset_range()

```
int dwarf_die_CU_offset_range(
    Dwarf_Die die,
    Dwarf_Off *cu_global_offset,
    Dwarf_Off *cu_length,
    Dwarf_Error *error)
```

The function dwarf_die_CU_offset_range() returns the offset of the beginning

of the CU and the length of the CU. The offset and length are of the entire CU that this DIE is a part of. It is used by dwarfdump (for example) to check the validity of offsets. Most applications will have no reason to call this function.

6.7.12 dwarf_diename()

```
int dwarf_diename(
    Dwarf_Die die,
    char ** return_name,
    Dwarf_Error *error)
```

When it succeeds, the function `dwarf_diename()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string of characters that represents the name attribute (`DW_AT_name`) of `die`.

The storage pointed to by a successful return of `dwarf_diename()` should not be freed as the text is a string in static memory (for some error cases) or a string residing in a DWARF data section.

Up to March 2020 this document said that `dwarf_dealloc` with `DW_DLA_STRING` should be applied to the string returned through the pointer. That was always incorrect. However, doing the `dwarf_dealloc(dbg,xxx,DW_DLA_STRING)` that was previously called for does not result in any error (`dwarf_dealloc` avoids freeing strings like this).

It returns `DW_DLV_NO_ENTRY` if `die` does not have a name attribute. It returns `DW_DLV_ERROR` if an error occurred.

6.7.13 dwarf_die_text()

```
int dwarf_die_text(
    Dwarf_Die die,
    Dwarf_Half attrnum,
    char ** return_name,
    Dwarf_Error *error)
```

When it succeeds, the function `dwarf_die_text()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string of characters that represents a string-value attribute of `die` if an attribute `attrnum` is present.

The storage pointed to by a successful return of `dwarf_die_text()` must never be freed, the string is in the DWARF data and is not dynamically allocated.

As of March 2020 the description here has been corrected. `dwarf_dealloc()` should never have been applied to a string returned by `dwarf_die_text()`.

It returns `DW_DLV_NO_ENTRY` if `die` does not have the attribute `attrnum`. It returns `DW_DLV_ERROR` if an error occurred.

6.7.14 dwarf_die_abbrev_code()

```
int dwarf_die_abbrev_code( Dwarf_Die die)
```

The function returns the abbreviation code of the DIE. That is, it returns the abbreviation "index" into the abbreviation table for the compilation unit of which the DIE is a part. It cannot fail. No errors are possible. The pointer die() must not be NULL.

6.7.15 dwarf_die_abbrev_children_flag()

```
int dwarf_die_abbrev_children_flag( Dwarf_Die die,
                                    Dwarf_Half *has_child)
```

The function returns the has-children flag of the die passed in through the *has_child passed in and returns DW_DLV_OK on success. A non-zero value of *has_child means the die has children.

On failure it returns DW_DLV_ERROR.

The function was developed to let consumer code do better error reporting in some circumstances, it is not generally needed.

6.7.16 dwarf_die_abbrev_global_offset()

```
int dwarf_die_abbrev_global_offset(Dwarf_Die die,
                                    Dwarf_Off      * abbrev_offset,
                                    Dwarf_Unsigned * abbrev_count,
                                    Dwarf_Error*   error);
```

The function allows more detailed printing of abbreviation data. It is handy for analyzing abbreviations but is not normally needed by applications. The function first appears in March 2016.

On success the function returns DW_DLV_OK and sets *abbrev_offset to the global offset in the .debug_abbrev section of the abbreviation. It also sets *abbrev_count to the number of attribute/form pairs in the abbreviation entry. It is possible, though unusual, for the count to be zero (meaning there is abbreviation instance and a TAG instance which have no attributes).

On failure it returns DW_DLV_ERROR and sets *error

It should never return DW_DLV_NO_ENTRY, but callers should allow for that possibility..

6.7.17 dwarf_get_version_of_die()

```
int dwarf_get_version_of_die(Dwarf_Die die,
                            Dwarf_Half *version,
                            Dwarf_Half *offset_size)
```

The function returns the CU context version through *version and the CU context

offset-size through `*offset_size` and returns DW_DLV_OK on success.

In case of error, the only errors possible involve an inappropriate NULL die pointer so no Dwarf_Debug pointer is available. Therefore setting a Dwarf_Error would not be very meaningful (there is no Dwarf_Debug to attach it to). The function returns DW_DLV_ERROR on error.

The values returned through the pointers are the values two arguments to `dwarf_get_form_class()` requires.

6.7.18 dwarf_attrlist()

```
int dwarf_attrlist(
    Dwarf_Die die,
    Dwarf_Attribute** attrbuf,
    Dwarf_Signed *attrcount,
    Dwarf_Error *error)
```

When it returns DW_DLV_OK, the function `dwarf_attrlist()` sets `attrbuf` to point to an array of `Dwarf_Attribute` descriptors corresponding to each of the attributes in `die`, and returns the number of elements in the array through `attrcount`. DW_DLV_NO_ENTRY is returned if the count is zero (no `attrbuf` is allocated in this case). DW_DLV_ERROR is returned on error. On a successful return from `dwarf_attrlist()`, each of the `Dwarf_Attribute` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type DW_DLA_ATTR, followed by free-ing the list pointed to by `*attrbuf` using `dwarf_dealloc()` with the allocation type DW_DLA_LIST, when no longer of interest (see `dwarf_dealloc()`).

Freeling the attrlist:

Figure 15. Example8 dwarf_attrlist() free

```
void example8(Dwarf_Debug dbg, Dwarf_Die somedie)
{
    Dwarf_Signed atcount = 0;
    Dwarf_Attribute *atlist = 0;
    Dwarf_Error error = 0;
    int errv = 0;

    errv = dwarf_attrlist(somedie, &atlist, &atcount, &error);
    if (errv == DW_DLV_OK) {
        Dwarf_Signed i = 0;

        for (i = 0; i < atcount; ++i) {
            /* use atlist[i] */
            dwarf_dealloc_attribute(atlist[i]);
            /* The original form still works.
               dwarf_dealloc(dbg, atlist[i], DW_DLA_ATTR);
            */
        }
        dwarf_dealloc(dbg, atlist, DW_DLA_LIST);
    }
}
```

6.7.19 dwarf_hasattr()

```
int dwarf_hasattr(
    Dwarf_Die die,
    Dwarf_Half attr,
    Dwarf_Bool *return_bool,
    Dwarf_Error *error)
```

When it succeeds, the function `dwarf_hasattr()` returns `DW_DLV_OK` and sets `*return_bool` to *non-zero* if `die` has the attribute `attr` and *zero* otherwise. If it fails, it returns `DW_DLV_ERROR`.

6.7.20 dwarf_attr()

```
int dwarf_attr(
    Dwarf_Die die,
    Dwarf_Half attr,
    Dwarf_Attribute *return_attr,
    Dwarf_Error *error)
```

When it returns `DW_DLV_OK`, the function `dwarf_attr()` sets `*return_attr` to the `Dwarf_Attribute` descriptor of `die` having the attribute `attr`. When one no longer needs the attribute call `dwarf_dealloc_attribute(return_attr)`.

It returns `DW_DLV_NO_ENTRY` if `attr` is not contained in `die`.

It returns `DW_DLV_ERROR` and sets the `*error` argument if an error occurred.

6.7.21 dwarf_lowpc()

```
int dwarf_lowpc(
    Dwarf_Die      die,
    Dwarf_Addr   * return_lowpc,
    Dwarf_Error  * error)
```

The function `dwarf_lowpc()` returns `DW_DLV_OK` and sets `*return_lowpc` to the low program counter value associated with the `die` descriptor if `die` represents a debugging information entry with the `DW_AT_low_pc` attribute. It returns `DW_DLV_NO_ENTRY` if `die` does not have this attribute. It returns `DW_DLV_ERROR` if an error occurred.

6.7.22 dwarf_highpc_b()

```
int dwarf_highpc_b(
    Dwarf_Die          die,
    Dwarf_Addr        * return_highpc,
    Dwarf_Half        * return_form*/,
    enum Dwarf_Form_Class * return_class*/,
    Dwarf_Error     *error)
```

The function `dwarf_highpc_b()` returns `DW_DLV_OK` and sets `*return_highpc` to the value of the `DW_AT_high_pc` attribute.

It also sets `*return_form` to the FORM of the attribute. Beginning 22 April 2019 `return_form` will not be used to return the form class if `return_form` is null. Be cautious using a null argument unless you know that only a suitably recent version of libdwarf will be used.

It sets `*return_class` to the form class of the attribute. Beginning 22 April 2019 `return_class` will not be used to return the form class if `return_class` is null. Be cautious using a null argument unless you know that only a suitably recent version of libdwarf will be used.

If the form class returned is `DW_FORM_CLASS_ADDRESS` the `return_highpc` is an actual pc address (1 higher than the address of the last pc in the address range).. If the form class returned is `DW_FORM_CLASS_CONSTANT` the `return_highpc` is an offset from the value of the the DIE's low PC address (see DWARF4 section 2.17.2 Contiguous Address Range).

It returns `DW_DLV_NO_ENTRY` if `die` does not have the `DW_AT_high_pc` attribute.

It returns `DW_DLV_ERROR` if an error occurred.

6.7.23 dwarf_highpc()

```
int dwarf_highpc(
    Dwarf_Die die,
    Dwarf_Addr * return_highpc,
    Dwarf_Error *error)
```

The function `dwarf_highpc()` returns `DW_DLV_OK` and sets `*return_highpc` the high program counter value associated with the `die` descriptor if `die` represents a debugging information entry with the `DW_AT_high_pc` attribute and the form is `DW_FORM_addr` (meaning the form is of class address).

This function is useless for a `DW_AT_high_pc` which is encoded as a constant (which was first possible in DWARF4).

It returns `DW_DLV_NO_ENTRY` if `die` does not have this attribute.

It returns `DW_DLV_ERROR` if an error occurred or if the form is not of class address.

6.7.24 dwarf_dietype_offset()

```
int dwarf_dietype_offset(Dwarf_Die /*die*/,
    Dwarf_Off /*return_off*/,
    Dwarf_Error /*error*/);
```

On success the function `dwarf_dietype_offset()` returns the offset referred to by `DW_AT_type` attribute of `die`.

`DW_DLV_NO_ENTRY` is returned if the `die` has no `DW_AT_type` attribute.

`DW_DLV_ERROR` is returned if an error is detected.

This feature was introduced in February 2016.

6.7.25 dwarf_offset_list()

```
int dwarf_offset_list(Dwarf_Debug dbg,
    Dwarf_Off offset,
    Dwarf_Bool is_info,
    Dwarf_Off ** offbuf,
    Dwarf_Unsigned * offcnt,
    Dwarf_Error * error);
```

On success The function `dwarf_offset_list()` returns `DW_DLV_OK` and sets `*offbuf` to point to an array of the offsets of the direct children of the `die` at `offset`. It sets `*offcnt` to point to the count of entries in the `offset` array

In case of error it returns `DW_DLV_OK`.

It does not return `DW_DLV_NO_ENTRY` but callers should allow for that possibility anyway.

This feature was introduced in March 2016.

Freeing the offset_list is done as follows.:

Figure 16. Exampleoffset_list dwarf_offset_list() free

```
void exampleoffset_list(Dwarf_Debug dbg, Dwarf_Off dieoffset,
    Dwarf_Bool is_info)
{
    Dwarf_Unsigned offcnt = 0;
    Dwarf_Off *offbuf = 0;
    Dwarf_Error error = 0;
    int errv = 0;

    errv = dwarf_offset_list(dbg, dieoffset, is_info,
        &offbuf, &offcnt, &error);
    if (errv == DW_DLV_OK) {
        Dwarf_Unsigned i = 0;

        for (i = 0; i < offcnt; ++i) {
            /* use offbuf[i] */
        }
        dwarf_dealloc(dbg, offbuf, DW_DLA_LIST);
    }
}
```

6.7.26 dwarf_bytesize()

```
Dwarf_Signed dwarf_bytesize(
    Dwarf_Die die,
    Dwarf_Unsigned *return_size,
    Dwarf_Error *error)
```

When it succeeds, dwarf_bytesize() returns DW_DLV_OK and sets *return_size to the number of bytes needed to contain an instance of the aggregate debugging information entry represented by die. It returns DW_DLV_NO_ENTRY if die does not contain the byte size attribute DW_AT_byte_size. It returns DW_DLV_ERROR if an error occurred.

6.7.27 dwarf_bitsize()

```
int dwarf_bitsize(
    Dwarf_Die die,
    Dwarf_Unsigned *return_size,
    Dwarf_Error *error)
```

When it succeeds, dwarf_bitsize() returns DW_DLV_OK and sets

*`return_size` to the number of bits occupied by the bit field value that is an attribute of the given die. It returns DW_DLV_NO_ENTRY if `die` does not contain the bit size attribute DW_AT_bit_size. It returns DW_DLV_ERROR if an error occurred.

6.7.28 dwarf_bitoffset()

```
int dwarf_bitoffset(
    Dwarf_Die die,
    Dwarf_Unsigned *return_size,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_bitoffset()` returns DW_DLV_OK and sets `*return_size` to the number of bits to the left of the most significant bit of the bit field value. This bit offset is not necessarily the net bit offset within the structure or class, since DW_AT_data_member_location may give a byte offset to this DIE and the bit offset returned through the pointer does not include the bits in the byte offset. It returns DW_DLV_NO_ENTRY if `die` does not contain the bit offset attribute DW_AT_bit_offset. It returns DW_DLV_ERROR if an error occurred.

6.7.29 dwarf_srclang()

```
int dwarf_srclang(
    Dwarf_Die die,
    Dwarf_Unsigned *return_lang,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_srclang()` returns DW_DLV_OK and sets `*return_lang` to a code indicating the source language of the compilation unit represented by the descriptor `die`. It returns DW_DLV_NO_ENTRY if `die` does not represent a source file debugging information entry (i.e. contain the attribute DW_AT_language). It returns DW_DLV_ERROR if an error occurred.

6.7.30 dwarf_arrayorder()

```
int dwarf_arrayorder(
    Dwarf_Die die,
    Dwarf_Unsigned *return_order,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_arrayorder()` returns DW_DLV_OK and sets `*return_order` a code indicating the ordering of the array represented by the descriptor `die`. It returns DW_DLV_NO_ENTRY if `die` does not contain the array order attribute DW_AT_ordering. It returns DW_DLV_ERROR if an error occurred.

6.8 Attribute Queries

Based on the attributes form, these operations are concerned with returning uninterpreted

attribute data. Since it is not always obvious from the return value of these functions if an error occurred, one should always supply an `error` parameter or have arranged to have an error handling function invoked (see `dwarf_init()`) to determine the validity of the returned value and the nature of any errors that may have occurred.

A `Dwarf_Attribute` descriptor describes an attribute of a specific die. Thus, each `Dwarf_Attribute` descriptor is implicitly associated with a specific die.

6.8.1 `dwarf_hasform()`

```
int dwarf_hasform(
    Dwarf_Attribute attr,
    Dwarf_Half form,
    Dwarf_Bool *return_hasform,
    Dwarf_Error *error)
```

The function `dwarf_hasform()` returns `DW_DLV_OK` and puts a *non-zero* value in the `*return_hasform` boolean if the attribute represented by the `Dwarf_Attribute` descriptor `attr` has the attribute form `form`. If the attribute does not have that form *zero* is put into `*return_hasform`. `DW_DLV_ERROR` is returned on error.

6.8.2 `dwarf_whatform()`

```
int dwarf_whatform(
    Dwarf_Attribute attr,
    Dwarf_Half *return_form,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_whatform()` returns `DW_DLV_OK` and sets `*return_form` to the attribute form code of the attribute represented by the `Dwarf_Attribute` descriptor `attr`. It returns `DW_DLV_ERROR` on error.

An attribute using `DW_FORM_indirect` effectively has two forms. This function returns the 'final' form for `DW_FORM_indirect`, not the `DW_FORM_indirect` itself. This function is what most applications will want to call.

6.8.3 `dwarf_whatform_direct()`

```
int dwarf_whatform_direct(
    Dwarf_Attribute attr,
    Dwarf_Half *return_form,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_whatform_direct()` returns `DW_DLV_OK` and sets `*return_form` to the attribute form code of the attribute represented by the `Dwarf_Attribute` descriptor `attr`. It returns `DW_DLV_ERROR` on error. An

attribute using DW_FORM_indirect effectively has two forms. This returns the form 'directly' in the initial form field. That is, it returns the 'initial' form of the attribute.

So when the form field is DW_FORM_indirect this call returns the DW_FORM_indirect form, which is sometimes useful for dump utilities.

It is confusing that the _direct() function returns DW_FORM_indirect if an indirect form is involved. Just think of this as returning the initial form the first form value seen for the attribute, which is also the final form unless the initial form is DW_FORM_indirect.

6.8.4 dwarf_whatattr()

```
int dwarf_whatattr(
    Dwarf_Attribute attr,
    Dwarf_Half      *return_attr,
    Dwarf_Error   *error)
```

When it succeeds, dwarf_whatattr() returns DW_DLV_OK and sets *return_attr to the attribute code represented by the Dwarf_Attribute descriptor attr. It returns DW_DLV_ERROR on error.

6.8.5 dwarf_formref()

```
int dwarf_formref(
    Dwarf_Attribute attr,
    Dwarf_Off     *return_offset,
    Dwarf_Error   *error)
```

When it succeeds, dwarf_formref() returns DW_DLV_OK and sets *return_offset to the CU-relative offset represented by the descriptor attr if the form of the attribute belongs to the REFERENCE class. attr must be a CU-local reference, not form DW_FORM_ref_addr and not DW_FORM_sec_offset . It is an error for the form to not belong to the REFERENCE class. It returns DW_DLV_ERROR on error.

Beginning November 2010: All DW_DLV_ERROR returns set *return_offset. Most errors set *return_offset to zero, but for error DW_DLE_ATTR_FORM_OFFSET_BAD the function sets *return_offset to the invalid offset (which allows the caller to print a more detailed error message).

See also dwarf_global_formref below.

6.8.6 dwarf_global_formref()

```
int dwarf_global_formref(
    Dwarf_Attribute attr,
    Dwarf_Off     *return_offset,
    Dwarf_Error  *error)
```

When it succeeds, `dwarf_global_formref()` returns `DW_DLV_OK` and sets `*return_offset` to the section-relative offset represented by the descriptor `attr` if the form of the attribute belongs to the `REFERENCE` or other section-references classes.

`attr` can be any legal `REFERENCE` class form plus `DW_FORM_ref_addr` or `DW_FORM_sec_offset`. It is an error for the form to not belong to one of the reference classes. It returns `DW_DLV_ERROR` on error. See also `dwarf_formref` above.

The caller must determine which section the offset returned applies to. The function `dwarf_get_form_class()` is useful to determine the applicable section.

The function converts CU relative offsets from forms such as `DW_FORM_ref4` into global section offsets.

6.8.7 dwarf_convert_to_global_offset()

```
int dwarf_convert_to_global_offset(
    Dwarf_Attribute attr,
    Dwarf_Off     offset,
    Dwarf_Off     *return_offset,
    Dwarf_Error  *error)
```

When it succeeds, `dwarf_convert_to_global_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the section-relative offset represented by the cu-relative offset `offset` if the form of the attribute belongs to the `REFERENCE` class. `attr` must be a CU-local reference (DWARF class `REFERENCE`) or form `DW_FORM_ref_addr` and the `attr` must be directly relevant for the calculated `*return_offset` to mean anything.

The function returns `DW_DLV_ERROR` on error.

The function is not strictly necessary but may be a convenience for attribute printing in case of error.

6.8.8 dwarf_formaddr()

```
int dwarf_formaddr(
    Dwarf_Attribute attr,
    Dwarf_Addr    * return_addr,
    Dwarf_Error  *error)
```

When it succeeds, `dwarf_formaddr()` returns `DW_DLV_OK` and sets

*`return_addr` to the address represented by the descriptor `attr` if the form of the attribute belongs to the ADDRESS class. It is an error for the form to not belong to this class. It returns DW_DLV_ERROR on error.

One possible error that can arise (in a .dwo object file or a .dwp package file) is DW_DLE_MISSING_NEEDED_DEBUG_ADDR_SECTION. Such an error means that the .dwo or .dwp file is missing the .debug_addr section. When opening a .dwo object file or a .dwp package file one should also open the corresponding executable and use `dwarf_set_tied_dbg()` to associate the objects before calling `dwarf_formaddr()`.

H 3 "dwarf_get_debug_addr_index()"

```
int dwarf_get_debug_addr_index(
    Dwarf_Attribute attr,
    Dwarf_Unsigned * return_index,
    Dwarf_Error *error)
```

`dwarf_get_debug_addr_index()` is only valid on attributes with form DW_FORM_GNU_addr_index or DW_FORM_addrx.

The function makes it possible to print the index from a dwarf dumper program.

When it succeeds, `dwarf_get_debug_addr_index()` returns DW_DLV_OK and sets `*return_index` to the attribute's index (into the .debug_addr section).

It returns DW_DLV_ERROR on error.

6.8.9 dwarf_get_debug_str_index()

```
int dwarf_get_debug_str_index(
    Dwarf_Attribute attr,
    Dwarf_Unsigned * return_index,
    Dwarf_Error *error);
```

For an attribute with form DW_FORM_strx or DW_FORM_GNU_str_index this function retrieves the index (which refers to a .debug_str_offsets section in this .dwo).

If successful, the function `dwarf_get_debug_str_index()` returns DW_DLV_OK and returns the index through the `return_index()` pointer.

If the passed in attribute does not have this form or there is no valid compilation unit context for the attribute the function returns DW_DLV_ERROR.

DW_DLV_NO_ENTRY is not returned.

6.8.10 dwarf_formflag()

```
int dwarf_formflag(
    Dwarf_Attribute attr,
    Dwarf_Bool * return_bool,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_formflag()` returns DW_DLV_OK and sets `*return_bool` to the (one unsigned byte) flag value. Any non-zero value means true. A zero value means false.

Before 29 November 2012 this would only return 1 or zero through the pointer, but that was always a strange thing to do. The DWARF specification has always been clear that any non-zero value means true. The function should report the value found truthfully, and now it does.

It returns DW_DLV_ERROR on error or if the `attr` does not have form flag.

6.8.11 dwarf_formudata()

```
int dwarf_formudata(
    Dwarf_Attribute attr,
    Dwarf_Unsigned * return_uvalue,
    Dwarf_Error *error)
```

The function `dwarf_formudata()` returns DW_DLV_OK and sets `*return_uvalue` to the `Dwarf_Unsigned` value of the attribute represented by the descriptor `attr` if the form of the attribute belongs to the CONSTANT class. It is an error for the form to not belong to this class. It returns DW_DLV_ERROR on error.

Never returns DW_DLV_NO_ENTRY.

For DWARF2 and DWARF3, `DW_FORM_data4` and `DW_FORM_data8` are possibly class CONSTANT, and for DWARF4 and later they are definitely class CONSTANT.

6.8.12 dwarf_formsdata()

```
int dwarf_formsdata(
    Dwarf_Attribute attr,
    Dwarf_Signed * return_svalue,
    Dwarf_Error *error)
```

The function `dwarf_formsdata()` returns DW_DLV_OK and sets `*return_svalue` to the `Dwarf_Signed` value of the attribute represented by the descriptor `attr` if the form of the attribute belongs to the CONSTANT class. It is an

error for the form to not belong to this class. If the size of the data attribute referenced is smaller than the size of the Dwarf_Signed type, its value is sign extended. It returns DW_DLV_ERROR on error.

Never returns DW_DLV_NO_ENTRY.

For DWARF2 and DWARF3, DW_FORM_data4 and DW_FORM_data8 are possibly class CONSTANT, and for DWARF4 and later they are definitely class CONSTANT.

6.8.13 dwarf_formblock()

```
int dwarf_formblock(
    Dwarf_Attribute attr,
    Dwarf_Block ** return_block,
    Dwarf_Error * error)
```

The function `dwarf_formblock()` returns DW_DLV_OK and sets `*return_block` to a pointer to a `Dwarf_Block` structure containing the value of the attribute represented by the descriptor `attr` if the form of the attribute belongs to the BLOCK class. It is an error for the form to not belong to this class. The storage pointed to by a successful return of `dwarf_formblock()` should be freed using the allocation type DW_DLA_BLOCK, when no longer of interest (see `dwarf_dealloc()`). It returns DW_DLV_ERROR on error.

6.8.14 dwarf_formstring()

```
int dwarf_formstring(
    Dwarf_Attribute attr,
    char ** return_string,
    Dwarf_Error *error)
```

The function `dwarf_formstring()` returns DW_DLV_OK and sets `*return_string` to a pointer to a null-terminated string containing the value of the attribute represented by the descriptor `attr` if the form of the attribute belongs to the STRING class. It is an error for the form to not belong to this class.

The storage pointed to by a successful return of `dwarf_formstring()` should not be freed. The pointer points into existing DWARF memory and the pointer becomes stale/invalid after a call to `dwarf_finish`. `dwarf_formstring()` returns DW_DLV_ERROR on error.

6.8.15 dwarf_formsig8()

```
int dwarf_formsig8(
    Dwarf_Attribute attr,
    Dwarf_Sig8 * return_sig8,
    Dwarf_Error * error)
```

The function `dwarf_formsig8()` returns DW_DLV_OK and copies the 8 byte signature to a `Dwarf_Sig8` structure provided by the caller if the form of the attribute is of form DW_FORM_ref_sig8 (a member of the REFERENCE class). It is an error for the form to be anything but DW_FORM_ref_sig8. It returns DW_DLV_ERROR on error.

This form is used to refer to a type unit.

6.8.16 `dwarf_formexprloc()`

```
int dwarf_formexprloc(
    Dwarf_Attribute attr,
    Dwarf_Unsigned * return_exprlen,
    Dwarf_Ptr * block_ptr,
    Dwarf_Error * error)
```

The function `dwarf_formexprloc()` returns DW_DLV_OK and sets the two values thru the pointers to the length and bytes of the DW_FORM_exprloc entry if the form of the attribute is of form DW_FORM_exprloc. It is an error for the form to be anything but DW_FORM_exprloc. It returns DW_DLV_ERROR on error.

On success the value set through the `return_exprlen` pointer is the length of the location expression. On success the value set through the `block_ptr` pointer is a pointer to the bytes of the location expression itself.

6.8.17 `dwarf_get_form_class()`

```
enum Dwarf_Form_Class dwarf_get_form_class(
    Dwarf_Half dwversion,
    Dwarf_Half attrnum,
    Dwarf_Half offset_size,
    Dwarf_Half form)
```

The function is just for the convenience of libdwarf clients that might wish to categorize the FORM of a particular attribute. The DWARF specification divides FORMs into classes in Chapter 7 and this function figures out the correct class for a form.

The `dwversion` passed in shall be the dwarf version of the compilation unit involved (2 for DWARF2, 3 for DWARF3, 4 for DWARF 4). The `attrnum` passed in shall be the attribute number of the attribute involved (for example, DW_AT_name). The `offset_size` passed in shall be the length of an offset in the current compilation unit (4 for 32bit dwarf or 8 for 64bit dwarf). The `form` passed in shall be the attribute form number. If `form` DW_FORM_indirect is passed in DW_FORM_CLASS_UNKNOWN will be returned as this form has no defined 'class'.

When it returns DW_FORM_CLASS_UNKNOWN the function is simply saying it could not determine the correct class given the arguments presented. Some user-defined attributes might have this problem.

The function `dwarf_get_version_of_die()` may be helpful in filling out arguments for a call to `dwarf_get_form_class()`.

6.8.18 dwarf_discr_list()

```
int dwarf_discr_list(
    Dwarf_Debug dbg,
    Dwarf_Small *blockpointer,
    Dwarf_Unsigned blocklen,
    Dwarf_Dsc_Head *dsc_head_out,
    Dwarf_Unsigned *dsc_array_length_out,
    Dwarf_Error *error)
Dwarf_Error *error)
```

When it succeeds, `dwarf_discr_list()` returns DW_DLV_OK and sets `*dsc_head_out` to a pointer to the discriminant information for the discriminant list and sets `*dsc_array_length_out` to the count of discriminant entries. The only current applicability is the block value of a DW_AT_discr_list attribute.

Those values are useful for calls to `dwarf_discr_entry_u()` or `dwarf_discr_entry_s()` to get the actual discriminant values. See the example below. It returns DW_DLV_NO_ENTRY if the block is empty. It returns DW_DLV_ERROR if an error occurred.

When the call was successful and the `Dwarf_Dsc_Head` is no longer needed, call `dwarf_dealloc()` to free all the space related to this.

```
void example_discr_list(Dwarf_Debug dbg,
    Dwarf_Die die,
    Dwarf_Attribute attr,
    Dwarf_Half attrnum,
    Dwarf_Bool isunsigned,
    Dwarf_Half theform,
    Dwarf_Error *err)
{
    /* The example here assumes that
       attribute attr is a DW_AT_discr_list.
       isunsigned should be set from the signedness
       of the parent of 'die' per DWARF rules for
       DW_AT_discr_list. */
    enum Dwarf_Form_Class fc = DW_FORM_CLASS_UNKNOWN;
    Dwarf_Half version = 0;
    Dwarf_Half offset_size = 0;
    int wres = 0;

    wres = dwarf_get_version_of_die(die, &version, &offset_size);
    if (wres != DW_DLV_OK) {
        /* FAIL */
        return;
    }
    fc = dwarf_get_form_class(version, attrnum, offset_size, theform);
    if (fc == DW_FORM_CLASS_BLOCK) {
        int fres = 0;
        Dwarf_Block *tempb = 0;
        fres = dwarf_formblock(attr, &tempb, err);
        if (fres == DW_DLV_OK) {
            Dwarf_Dsc_Head h = 0;
            Dwarf_Unsigned u = 0;
            Dwarf_Unsigned arraycount = 0;
            int sres = 0;

            sres = dwarf_discr_list(dbg,
                (Dwarf_Small *)tempb->bl_data,
                tempb->bl_len,
                &h, &arraycount, err);
            if (sres == DW_DLV_NO_ENTRY) {
                /* Nothing here. */
                dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
                return;
            }
            if (sres == DW_DLV_ERROR) {
                /* FAIL . */
                dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
            }
        }
    }
}
```

```
    return;
}
for(u = 0; u < arraycount; u++) {
    int u2res = 0;
    Dwarf_Half dtype = 0;
    Dwarf_Signed dlow = 0;
    Dwarf_Signed dhigh = 0;
    Dwarf_Unsigned ulow = 0;
    Dwarf_Unsigned uhigh = 0;

    if (isunsigned) {
        u2res = dwarf_discr_entry_u(h,u,
            &dtype,&ulow,&uhigh,err);
    } else {
        u2res = dwarf_discr_entry_s(h,u,
            &dtype,&dlow,&dhigh,err);
    }
    if( u2res == DW_DLV_ERROR) {
        /* Something wrong */
        dwarf_dealloc(dbg,h,DW_DLA_DSC_HEAD);
        dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
        return;
    }
    if( u2res == DW_DLV_NO_ENTRY) {
        /* Impossible. u < arraycount. */
        dwarf_dealloc(dbg,h,DW_DLA_DSC_HEAD);
        dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
        return;
    }
    /* Do something with dtype, and whichever
       of ulow, uhigh,dlow,dhigh got set.
       Probably save the values somewhere.
       Simple casting of dlow to ulow (or vice versa)
       will not get the right value due to the nature
       of LEB values. Similarly for uhigh, dhigh.
       One must use the right call.

    */
}
dwarf_dealloc(dbg,h,DW_DLA_DSC_HEAD);
dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
}
```

6.8.19 dwarf_discr_entry_u()

```
int dwarf_discr_entry_u(
    Dwarf_Dsc_Head dsc_head,
    Dwarf_Unsigned dsc_array_index,
    Dwarf_Half *dsc_type,
    Dwarf_Unsigned *dsc_low,
    Dwarf_Unsigned *dsc_high,
    Dwarf_Error *error)
```

When it succeeds, `dwarf_discr_entry_u()` returns `DW_DLV_OK` and sets `*dsc_type`, `*dsc_low`, and `*dsc_high` to the discriminant values for that index. Valid `dsc_array_index` values are zero to (`dsc_array_length_out - 1`) from a `dwarf_discr_list()` call.

If `*dsc_type` is `DW_DSC_label` `*dsc_low` is set to the discriminant value and `*dsc_high` is set to zero.

If `*dsc_type` is `DW_DSC_range` `*dsc_low` is set to the low end of the discriminant range and `*dsc_high` is set to the high end of the discriminant range.

Due to the nature of the LEB numbers in the discriminant representation in DWARF one must call the correct one of `dwarf_discr_entry_u()` or `dwarf_discr_entry_s()` based on whether the discriminant is signed or unsigned. Casting an unsigned to signed is not always going to get the right value.

If `dsc_array_index` is outside the range of valid indexes the function returns `DW_DLV_NO_ENTRY`. On error it returns `DW_DLV_ERROR` and sets `*error` to an error pointer.

6.8.20 dwarf_discr_entry_s()

```
int dwarf_discr_entry_s(
    Dwarf_Dsc_Head dsc_head,
    Dwarf_Unsigned dsc_array_index,
    Dwarf_Half *dsc_type,
    Dwarf_Signed *dsc_low,
    Dwarf_Signed *dsc_high,
    Dwarf_Error *error)
```

This is identical to `dwarf_discr_entry_u()` except that the discriminant values are signed values in this interface. Callers must check the discriminant type and call the correct function.

6.9 Location List Operations, Raw .debug_loclists

This set of interfaces is to read the (entire) `.debug_loclists` section without reference to any DIE. As such these can only present the raw data from the file. There is

no way in these interfaces to get actual addresses. These might be of interest if you want to know exactly what the compiler output in the `.debug_loclists` section. "dwarfdump ----print-raw-loclists" (try adding `-v` or `-vvv`) makes these calls.

Here is an example using all the following calls.

Figure 17. Example Raw Loclist

```
int example_raw_loclist(Dwarf_Debug dbg,Dwarf_Error *error)
{
    Dwarf_Uunsigned count = 0;
    int res = 0;
    Dwarf_Uunsigned i = 0;

    res = dwarf_load_loclists(dbg,&count,error);
    if (res != DW_DLV_OK) {
        return res;
    }
    for(i =0 ; i < count ; ++i) {
        Dwarf_Uunsigned header_offset = 0;
        Dwarf_Small offset_size = 0;
        Dwarf_Small extension_size = 0;
        unsigned version = 0; /* 5 */
        Dwarf_Small address_size = 0;
        Dwarf_Small segment_selector_size = 0;
        Dwarf_Uunsigned offset_entry_count = 0;
        Dwarf_Uunsigned offset_of_offset_array = 0;
        Dwarf_Uunsigned offset_of_first_locentry = 0;
        Dwarf_Uunsigned offset_past_last_loceentry = 0;

        res = dwarf_get_loclist_context_basics(dbg,i,
                                                &header_offset,&offset_size,&extension_size,
                                                &version,&address_size,&segment_selector_size,
                                                &offset_entry_count,&offset_of_offset_array,
                                                &offset_of_first_locentry,
                                                &offset_past_last_locentry,error);
        if (res != DW_DLV_OK) {
            return res;
        }
        {
            Dwarf_Uunsigned e = 0;
            unsigned colmax = 4;
            unsigned col = 0;
            Dwarf_Uunsigned global_offset_of_value = 0;

            for ( ; e < offset_entry_count; ++e) {
                Dwarf_Uunsigned value = 0;
                int resc = 0;

                resc = dwarf_get_loclist_offset_index_value(dbg,
                                                i,e,&value,
                                                &global_offset_of_value,error);
                if (resc != DW_DLV_OK) {
                    return resc;
                }
            }
        }
    }
}
```

```
        }
        /* Do something */
        col++;
        if (col == colmax) {
            col = 0;
        }
    }

}

{
Dwarf_Unsigned curoffset = offset_of_first_loceentry;
Dwarf_Unsigned endoffset = offset_past_last_loceentry;
int rese = 0;
Dwarf_Unsigned ct = 0;

for ( ; curoffset < endoffset; ++ct ) {
    unsigned entrylen = 0;
    unsigned code = 0;
    Dwarf_Unsigned v1 = 0;
    Dwarf_Unsigned v2 = 0;
    rese = dwarf_get_loclist_lle(dbg,i,
        curoffset,endoffset,
        &entrylen,
        &code,&v1,&v2,error);
    if (rese != DW_DLV_OK) {
        return rese;
    }
    curoffset += entrylen;
    if (curoffset > endoffset) {
        return DW_DLV_ERROR;
    }
}
}

return DW_DLV_OK;
}
```

6.9.1 dwarf_load_loclists()

```
int dwarf_load_loclists(
    Dwarf_Debug dbg,
    Dwarf_Unsigned *loclists_count,
    Dwarf_Error *error)
```

On a successful call to `dwarf_load_loclists()` the function returns `DW_DLV_OK`,

sets *loclists_count (if and only if loclists_count is non-null) to the number of distinct section contents that exist. A small amount of data for each Location List Table (DWARF5 section 7.29) is recorded in dbg as a side effect. Normally libdwarf will have already called this, but if an application never requests any .debug_info data the section might not be loaded. If the section is loaded this returns very quickly and will set *loclists_count just as described in this paragraph.

If there is no .debug_loclists section in the object file this function returns DW_DLV_NO_ENTRY.

If something is malformed it returns DW_DLV_ERROR and sets *error to the applicable error pointer describing the problem.

There is no dealloc call. Calling dwarf_finish() releases the modest amount of memory recorded for this section as a side effect.

6.9.2 dwarf_get_loclist_context_basics()

```
int dwarf_get_loclist_context_basics(Dwarf_Debug dbg,
    Dwarf_Unsigned context_index,
    Dwarf_Unsigned * header_offset,
    Dwarf_Small     * offset_size,
    Dwarf_Small     * extension_size,
    unsigned        * version, /* 5 */
    Dwarf_Small     * address_size,
    Dwarf_Small     * segment_selector_size,
    Dwarf_Unsigned  * offset_entry_count,
    Dwarf_Unsigned  * offset_of_offset_array,
    Dwarf_Unsigned  * offset_of_first_locentry,
    Dwarf_Unsigned  * offset_past_last_locentry,
    Dwarf_Error     * /*err*/);
```

On success this returns DW_DLV_OK and returns values through the pointer arguments (other than dbg or error)

A call to dwarf_load_loclists() that succeeds gets you the count of contexts and dwarf_get_loclist_context_basics() for any "i >=0 and i < count" gets you the context values relevant to .debug_loclists.

Any of the pointer-arguments for returning context values can be passed in as 0 (in which case they will be skipped).

You will want *offset_entry_count so you can call dwarf_get_loclist_offset_index_value() usefully.

If the context_index passed in is out of range the function returns DW_DLV_NO_ENTRY

At the present time DW_DLV_ERROR is never returned.

6.9.3 dwarf_get_loclist_offset_index_value()

```
int dwarf_get_loclist_offset_index_value(Dwarf_Debug dbg,
                                         Dwarf_Unsigned context_index,
                                         Dwarf_Unsigned offsetentry_index,
                                         Dwarf_Unsigned * offset_value_out,
                                         Dwarf_Unsigned * global_offset_value_out,
                                         Dwarf_Error *error)
```

On success `dwarf_get_loclist_offset_index_value()` returns DW_DLV_OK, sets `* offset_value_out` to the value in the Range List Table offset array, and sets `* global_offset_value_out` to the section offset (in `.debug_addr`) of the offset value.

Pass in `context_index` exactly as the same field passed to `dwarf_get_loclist_context_basics()`.

Pass in `offset_entry_index` based on the return field `offset_entry_count` from `dwarf_get_loclist_context_basics()`, meaning for that `context_index` an $\text{offset_entry_index} \geq 0$ and $\text{offset_entry_index} < \text{offset_entry_count}$.

Pass in `offset_entry_count` exactly as the same field passed to `dwarf_get_loclist_context_basics()`.

If one of the indexes passed in is out of range DW_DLV_NO_ENTRY will be returned and no return arguments touched.

If there is some corruption of DWARF5 data then DW_DLV_ERROR might be returned and `*error` set to the error details.

6.9.4 dwarf_get_loclist_lle()

```
int dwarf_get_loclist_lle(
    Dwarf_Debug dbg,
    Dwarf_Unsigned contextnumber,
    Dwarf_Unsigned entry_offset,
    Dwarf_Unsigned endoffset,
    unsigned *entrylen,
    unsigned *entry_kind,
    Dwarf_Unsigned *entry_operand1,
    Dwarf_Unsigned *entry_operand2,
    Dwarf_Unsigned *expr_ops_blocksize,
    Dwarf_Unsigned *expr_ops_offset,
    Dwarf_Small **expr_opsdata,
    Dwarf_Error *error)
```

On success it returns a single DW_RLE* record (see dwarf.h) fields.

`contextnumber` is the number of the current loclist context.

`entry_offset` is the section offset (section-global offset) of the next record.

`endoffset` is one past the last entry in this rle context.

`*entrylen` returns the length in the `.debug_loclists` section of the particular record returned. It's used to increment to the next record within this loclist context.

`*entrykind` returns is the `DW_RLE*` number.

Some record kinds have 1 or 0 operands, most have two operands (the records describing ranges).

`*expr_ops_blocksize` returns the size, in bytes, of the Dwarf Expression (some operations have no Dwarf Expression and those that do can have a zero length blocksize).

`*expr_ops_offset` returns the offset (in the `.debug_loclists` section) of the first byte of the Dwarf Expression.

`*expr_opsdata` returns a pointer to the bytes of the Dwarf Expression.

If the `contextnumber` is out of range it will return `DW_DLV_NO_ENTRY`.

If the `.debug_loclists` section is malformed or the `entry_offset` is incorrect it may return `DW_DLV_ERROR`.

6.10 Location List operations `.debug_loc` & `.debug_loclists`

These operations apply to the `.debug_loc` section in DWARF2, DWARF3, DWARF4, and DWARF5 object files. Earlier versions still work as well as ever, but they only deal with, at most, DWARF2, DWARF3, and DWARF4.

6.10.1 `dwarf_get_loclist_c()`

```
int dwarf_get_loclist_c (Dwarf_Attribute attr,
    Dwarf_Loc_Head_c * loclist_head,
    Dwarf_Unsigned   * locCount,
    Dwarf_Error      * error);
```

This function returns a pointer that is, in turn, used to make possible calls to return the details of the location list.

The incoming argument `attr` should have one of the FORMs of a location expression or location list.

On success this returns `DW_DLV_OK` and sets `*loclist_head` to a pointer used in further calls (see the example and descriptions that follow it). `locCount` is set to the number of entries in the location list (or if the FORM is of a location expression the `locCount` will be set to one). At this point one cannot yet tell if it was a location list or a location expression (see `.dwarf_get_locdesc_entry_c{}`).

In case of error DW_DLV_ERROR is returned and *error is set to an error designation.
A return of DW_DLV_NO_ENTRY may be possible but is a bit odd.

```
void example_loclistcv5(Dwarf_Debug dbg,Dwarf_Attribute someattr)
{
    Dwarf_Uunsigned lcount = 0;
    Dwarf_Loc_Head_c loclist_head = 0;
    Dwarf_Error error = 0;
    int lres = 0;

    lres = dwarf_get_loclist_c(someattr,&loclist_head,&lcount,&error);
    if (lres == DW_DLV_OK) {
        Dwarf_Uunsigned i = 0;

        /* Before any return remember to call
           dwarf_loc_head_c_dealloc(loclist_head); */
        for (i = 0; i < lcount; ++i) {
            Dwarf_Small loclist_lkind = 0;
            Dwarf_Small lle_value = 0;
            Dwarf_Uunsigned rawval1 = 0;
            Dwarf_Uunsigned rawval2 = 0;
            Dwarf_Bool debug_addr_unavailable = FALSE;
            Dwarf_Addr lopc = 0;
            Dwarf_Addr hipc = 0;
            Dwarf_Uunsigned loclist_expr_op_count = 0;
            Dwarf_Locdesc_c locdesc_entry = 0;
            Dwarf_Uunsigned expression_offset = 0;
            Dwarf_Uunsigned locdesc_offset = 0;

            lres = dwarf_get_locdesc_entry_d(loclist_head,
                i,
                &lle_value,
                &rawval1,&rawval2,
                &debug_addr_unavailable,
                &lopc,&hipc,
                &loclist_expr_op_count,
                &locdesc_entry,
                &loclist_lkind,
                &expression_offset,
                &locdesc_offset,
                &error);
            if (lres == DW_DLV_OK) {
                Dwarf_Uunsigned j = 0;
                int opres = 0;
                Dwarf_Small op = 0;

                for (j = 0; j < loclist_expr_op_count; ++j) {
                    Dwarf_Uunsigned raw1 = 0;
                    Dwarf_Uunsigned raw2 = 0;
```

```
Dwarf_Unsigned raw3 = 0;
Dwarf_Unsigned opd1 = 0;
Dwarf_Unsigned opd2 = 0;
Dwarf_Unsigned opd3 = 0;
Dwarf_Unsigned offsetforbranch = 0;

opres = dwarf_get_location_op_value_d(
    locdesc_entry,
    j, &op,
    &raw1, &raw2, &raw3,
    &opd1, &opd2, &opd3, &offsetforbranch,
    &error);
if (opres == DW_DLV_OK) {
    /* Do something with the operators.
       Usually you want to use opd1,2,3
       as appropriate. Calculations
       involving base addresses etc
       have already been incorporated
       in opd1,2,3. */
} else {
    dwarf_dealloc_error(dbg, error);
    dwarf_loc_head_c_dealloc(loclist_head);
    /*Something is wrong.*/
    return;
}
}
} else {
    /* Something is wrong. Do something.*/
    dwarf_loc_head_c_dealloc(loclist_head);
    dwarf_dealloc_error(dbg, error);
    return;
}
}
}
/* Always call dwarf_loc_head_c_dealloc()
   to free all the memory associated with loclist_head. */
if (error) {
    dwarf_dealloc_error(dbg, error);
}
dwarf_loc_head_c_dealloc(loclist_head);
loclist_head = 0;
return;
}
```

6.10.2 dwarf_get_locdesc_entry_d()

Earlier versions of this work with earlier versions of DWARF. This works with all DWARF from DWARF2 on.

```
int dwarf_get_locdesc_entry_d(Dwarf_Loc_Head_c /*loclist_head*/,
    Dwarf_Unsigned index,
    Dwarf_Small *lle_value_out,
    Dwarf_Addr *rawval1_out,
    Dwarf_Addr *rawval2_out,
    Dwarf_Bool *debug_addr_unavailable,
    Dwarf_Addr *lopc_out,
    Dwarf_Addr *hipc_out,
    Dwarf_Unsigned *loc_expr_op_count_out,
    Dwarf_Locdesc_c *locentry_out,
    Dwarf_Small *loclist_kind,
    Dwarf_Unsigned *expression_offset_out,
    Dwarf_Unsigned *locdesc_offset_out,
    Dwarf_Error *error);
```

This function returns overall information about a location list or location description. Details about location operators are retrieved by a call to `dwarf_get_location_op_value_d()` (described below). In case of success `DW_DLV_OK` is returned and arguments are set through the pointers to return values to the caller. Now we describe each argument.

`*loclist_kind` returns `DW_LKIND_expression`, `DW_LKIND_loclist`, `DW_LKIND_GNU_exp_list`, or `DW_LKIND_loclists`.

`DW_LKIND_expression` means the 'list' is really just a location expression. The only entry is with index zero. In this case `*lle_value_out` will have the value `DW_LLE_start_end`.

`DW_LKIND_loclist`, means the list is from DWARF2, DWARF3, or DWARF4. The `*lle_value_out` value has been synthesized as if it were a DWARF5 expression.

`DW_LKIND_GNU_exp_list`, means the list is from a DWARF4 `.debug_loc.dwo` object section. It is an experimental version from before DWARF5 was published. The `*lle_value_out` is `DW_LLEX_start_end_entry` (or one of the other `DW_LLEX` values).

`DW_LKIND_loclists` means this is a DWARF5 loclist, so `DW_LLE_start_end` is an example of one possible `*lle_value_out` values. In addition, if `*debug_addr_unavailable` is set it means the `*lopc_out` and `*hipc_out` could not be correctly set (so are meaningless) because the `.debug_addr` section is missing. Very likely the `.debug_addr` section is in the executable and that file needs to be opened and attached to the current `Dwarf_Debug` with `dwarf_set_tied_dbg()`.

*rawval1_out returns the value of the first operand in the location list entry. Uninterpreted. Useful for reporting or for those wishing to do their own calculation of lopc.

*rawval2_out returns the value of the second operand in the location list entry. Uninterpreted. Useful for reporting or for those wishing to do their own calculation of hipc.

The argument loc_expr_op_count_out returns the number of operators in the location expression involved (which may be zero).

The argument locentry_out returns an identifier used in calls to dwarf_get_location_op_value_d().

The argument expression_offset_out returns the offset (in the .debug_loc(.dso) or .debug_info(.dwo) of the location expression itself (possibly useful for debugging).

The argument locdesc_offset_out returns the offset (in the section involved (see loclist_kind) of the location list entry itself (possibly useful for debugging).

In case of error DW_DLV_ERROR is returned and *error is set to an error designation.

A return of DW_DLV_NO_ENTRY may be possible but is a bit odd.

6.10.3 dwarf_get_locdesc_entry_c()

This is the same as dwarf_get_locdesc_entry_d() except that the debug_addr_unavailable field is missing. Earlier versions (starting with dwarf_get_locdesc_entry()) exist and work as well as they ever did, but we suggest you stop using those earlier versions. We suggest you switch to using dwarf_get_locdesc_entry_d()

```
int dwarf_get_locdesc_entry_c(Dwarf_Loc_Head_c /*loclist_head*/,
    Dwarf_Unsigned index,
    Dwarf_Small *lle_value_out,
    Dwarf_Addr *rawval1_out,
    Dwarf_Addr *rawval2_out,
    Dwarf_Addr *lopc_out,
    Dwarf_Addr *hipc_out,
    Dwarf_Unsigned *loc_expr_op_count_out,
    Dwarf_Locdesc_c *locentry_out,
    Dwarf_Small *loclist_kind,
    Dwarf_Unsigned *expression_offset_out,
    Dwarf_Unsigned *locdesc_offset_out,
    Dwarf_Error *error);
```

6.10.4 dwarf_get_loclist_head_kind()

```
int dwarf_get_loclist_head_kind(
    Dwarf_Loclists_Head head,
    unsigned int * kind,
    Dwarf_Error *error)
```

Though one should test the return code, at present this always returns DW_DLV_OK, and sets *kind to the DW_LKIND* value for this head.

At the present time neither DW_DLV_ERROR nor DW_DLV_NO_ENTRY is returned.

6.10.5 dwarf_get_location_op_value_d()

```
int dwarf_get_location_op_value_d(Dwarf_Locdesc_c locdesc,
    Dwarf_Unsigned index,
    Dwarf_Small * atom_out,
    Dwarf_Unsigned * operand1,
    Dwarf_Unsigned * operand2,
    Dwarf_Unsigned * operand3,
    Dwarf_Unsigned * rawop1,
    Dwarf_Unsigned * rawop2,
    Dwarf_Unsigned * rawop3,
    Dwarf_Unsigned * offset_for_branch,
    Dwarf_Error* error);
```

On success The function dwarf_get_location_op_value_d() returns the information for the single operator number index from the location expression locdesc. It sets the following values.

atom_out is set to the applicable operator code, for example DW_OP_reg5.

operand1, operand2, and operand3 are set to the operator operands as applicable (see DWARF documents on the operands for each operator). All additions of base fields, if any, have been done already. operand3 is new as of DWARF5.

In some cases operand3 is actually a pointer into section data in memory and operand2 has the length of the data at operand3. Callers must extract the bytes and deal with endianness issues of the extracted value.

rawop1, rawop2, and rawop3 are set to the operator operands as applicable (see DWARF documents on the operands for each operator) before any base values were added in.. As for the previous, sometimes dealing with rawop3 means interpreting it as a pointer and doing a dereference.

More on the pointer values in Dwarf_Unsigned: When a DWARF operand is not of a size fixed by dwarf or whose type is unknown, or is possibly too large for a dwarf stack entry, libdwarf will insert a pointer (to memory in the dwarf data somewhere) as the operand value. DW_OP_implicit_value operand 2, DW_OP_[GNU_]entry_value

operand 2, and DW_OP_[GNU_]const_type operand 3 are instances of this. The problem with the values is that libdwarf is unclear what the type of the value is so we pass the problem to you, the callers!

offset_for_branch is set to the offset (in bytes) in this expression of this operator. The value makes it possible for callers to implement the operator branch operators.

In case of an error, the function returns DW_DLV_ERROR and sets *error to an error value.

DW_DLV_NO_ENTRY is probably not a possible return value, but please test for it anyway.

6.10.6 dwarf_loclist_from_expr_c()

This is now obsolete, though it works as well as ever, so if it works for your object codes you may continue to use it.

```
int dwarf_loclist_from_expr_c(Dwarf_Debug dbg,
    Dwarf_Ptr           expression_in,
    Dwarf_Unsigned      expression_length,
    Dwarf_Half          address_size,
    Dwarf_Half          offset_size,
    Dwarf_Small         dwarf_version,
    Dwarf_Loc_Head_c*   loc_head,
    Dwarf_Unsigned     * listlen,
    Dwarf_Error        * error);
```

This interface is not sufficient to work properly as it fails to pass in data from the Compilation Unit. The earlier versions dwarf_loclist_from_expr(), dwarf_loclist_from_expr_a(), and dwarf_loclist_from_expr_b are all similarly deficient. These suffice for early DWARF locations but cannot work for every kind of DWARF5 location list or location.

Frame operators such as DW_CFA_def_cfa_expression have a location expression and the location_expression is accessed with this function.

On success it returns DW_DLV_OK and sets the two return arguments (explained a few lines later here).

The expression_in argument must contain a valid pointer to location expression bytes. The expression_length argument must contain the length of that location expression in bytes.

The address_size argument must contain the size of an address on the target machine for this expression (normally 4 or 8). The offset_size argument must contain the size of an offset in the expression (normally 4, sometimes 8). The version argument must contain the dwarf_version of the expression (2,3,4, or 5).

The returned value *loc_head is used to actually access the location expression details (see the example following).

The returned value `*listlen` is the number of location expressions (ie 1) in the location list (for uniformity of access we make it look like a single-entry location list).

On error the function returns `DW_DLV_ERROR` and sets `*error` to reflect the error.

A return of `DW_DLV_NO_ENTRY` is probably impossible, but callers should assume it is possible. No return arguments are set in this case.

```
void
example_locreprc(Dwarf_Debug dbg,Dwarf_Ptr expr_bytes,
    Dwarf_Unsigned expr_len,
    Dwarf_Half addr_size,
    Dwarf_Half offset_size,
    Dwarf_Half version)
{
    Dwarf_Loc_Head_c head = 0;
    Dwarf_Locdesc_c locentry = 0;
    int res2 = 0;
    Dwarf_Unsigned lopc = 0;
    Dwarf_Unsigned hipc = 0;
    Dwarf_Unsigned ulistlen = 0;
    Dwarf_Unsigned ulocentry_count = 0;
    Dwarf_Unsigned section_offset = 0;
    Dwarf_Unsigned locdesc_offset = 0;
    Dwarf_Small lle_value = 0;
    Dwarf_Small loclist_source = 0;
    Dwarf_Unsigned i = 0;
    Dwarf_Error error = 0;

    res2 = dwarf_loclist_from_expr_c(dbg,
        expr_bytes,expr_len,
        addr_size,
        offset_size,
        version,
        &head,
        &ulistlen,
        &error);
    if(res2 == DW_DLV_NO_ENTRY) {
        return;
    }
    if(res2 == DW_DLV_ERROR) {
        return;
    }
/* These are a location expression, not loclist.
   So we just need the 0th entry.*/
    res2 = dwarf_get_locdesc_entry_c(head,
        0, /* Data from 0th LocDesc */
        &lle_value,
        &lopc, &hipc,
        &ulocentry_count,
        &locentry,
        &loclist_source,
        &section_offset,
        &locdesc_offset,
```

```
&error);
if (res2 == DW_DLV_ERROR) {
    dwarf_loc_head_c_dealloc(head);
    return;
} else if (res2 == DW_DLV_NO_ENTRY) {
    dwarf_loc_head_c_dealloc(head);
    return;
}
/* ASSERT: ulistlen == 1 */
for (i = 0; i < ulocentry_count; ++i) {
    Dwarf_Small op = 0;
    Dwarf_Unsigned opd1 = 0;
    Dwarf_Unsigned opd2 = 0;
    Dwarf_Unsigned opd3 = 0;
    Dwarf_Unsigned offsetforbranch = 0;

    res2 = dwarf_get_location_op_value_c(locentry,
        i, &op, &opd1, &opd2, &opd3, &offsetforbranch,
        &error);
    /* Do something with the expression operator and operands */
    if (res2 != DW_DLV_OK) {
        dwarf_loc_head_c_dealloc(head);
        return;
    }
}
dwarf_loc_head_c_dealloc(head);
}
```

6.10.7 dwarf_loc_head_c_dealloc()

```
void dwarf_loc_head_c_dealloc(Dwarf_Loc_Head_c loclist_head);
```

This function takes care of all the details so one does not have to _dwarf_dealloc() the pieces individually, though code that continues to do the pieces individually still works.

This function frees all the memory associated with the loclist_head. There is no return value. It's good practice to set loclist_head. to zero immediately after the call, as the pointer is stale at that point.

6.10.8 dwarf_loclist_n()

```
int dwarf_loclist_n(
    Dwarf_Attribute attr,
    Dwarf_Locdesc ***llbuf,
    Dwarf_Signed *listlen,
    Dwarf_Error *error)
```

This interface cannot handle DWARF5 or Split Dwarf. Use `dwarf_get_loclist_c()` and related functions instead (as of November 2015). The function `dwarf_loclist_n()` sets `*llbuf` to point to an array of `Dwarf_Locdesc` pointers corresponding to each of the location expressions in a location list, and sets `*listlen` to the number of elements in the array and returns `DW_DLV_OK` if the attribute is appropriate.

This is the preferred function for `Dwarf_Locdesc` as it is the interface allowing access to an entire loclist. (use of `dwarf_loclist_n()` is suggested as the better interface, though `dwarf_loclist()` is still supported.)

If the attribute is a reference to a location list (DW_FORM_data4 or DW_FORM_data8) the location list entries are used to fill in all the fields of the `Dwarf_Locdesc`(s) returned.

If the attribute is a location description (DW_FORM_block2 or DW_FORM_block4) then some of the `Dwarf_Locdesc` values of the single `Dwarf_Locdesc` record are set to 'sensible' but arbitrary values. Specifically, `ld_lopc` is set to 0 and `ld_hipc` is set to all-bits-on. And `*listlen` is set to 1.

If the attribute is a reference to a location expression (DW_FORM_locrexpr) then some of the `Dwarf_Locdesc` values of the single `Dwarf_Locdesc` record are set to 'sensible' but arbitrary values. Specifically, `ld_lopc` is set to 0 and `ld_hipc` is set to all-bits-on. And `*listlen` is set to 1.

It returns `DW_DLV_ERROR` on error.

`dwarf_loclist_n()` works on DW_AT_location, DW_AT_data_member_location, DW_AT_vtable_elem_location, DW_AT_string_length, DW_AT_use_location, and DW_AT_return_addr attributes.

If the attribute is DW_AT_data_member_location the value may be of class CONSTANT. `dwarf_loclist_n()` is unable to read class CONSTANT, so you need to first determine the class using `dwarf_get_form_class()` and if it is class CONSTANT call `dwarf_formsdata()` or `dwarf_formudata()` to get the constant value (you may need to call both as DWARF4 does not define the signedness of the constant value).

Storage allocated by a successful call of `dwarf_loclist_n()` should be deallocated when no longer of interest (see `dwarf_dealloc()`). The block of `Dwarf_Loc` structs pointed to by the `ld_s` field of each `Dwarf_Locdesc` structure should be deallocated with the allocation type `DW_DLA_LOC_BLOCK`. and the `llbuf[]` space pointed to should be deallocated with allocation type `DW_DLA_LOCDESC`. This should be followed by deallocation of the `llbuf` using the allocation type `DW_DLA_LIST`.

```
void example9(Dwarf_Debug dbg, Dwarf_Attribute someattr)
{
    Dwarf_Signed lcount = 0;
    Dwarf_Locdesc **llbuf = 0;
    Dwarf_Error error = 0;
    int lres = 0;

    lres = dwarf_loclist_n(someattr, &llbuf, &lcount, &error);
    if (lres == DW_DLV_OK) {
        Dwarf_Signed i = 0;
        for (i = 0; i < lcount; ++i) {
            /* Use llbuf[i]. Both Dwarf_Locdesc and the
               array of Dwarf_Loc it points to are
               defined in libdwarf.h: they are
               not opaque structs. */
            dwarf_dealloc(dbg, llbuf[i]->ld_s, DW_DLA_LOC_BLOCK);
            dwarf_dealloc(dbg, llbuf[i], DW_DLA_LOCDESC);
        }
        dwarf_dealloc(dbg, llbuf, DW_DLA_LIST);
    }
}
```

6.10.9 dwarf_loclist()

```
int dwarf_loclist(
    Dwarf_Attribute attr,
    Dwarf_Locdesc **llbuf,
    Dwarf_Signed *listlen,
    Dwarf_Error *error)
```

Use `dwarf_get_loclist_c()` and related functions instead (as of November 2015). The function `dwarf_loclist()` sets `*llbuf` to point to a `Dwarf_Locdesc` pointer for the single location expression it can return. It sets `*listlen` to 1. and returns `DW_DLV_OK` if the attribute is appropriate.

It is less flexible than `dwarf_loclist_n()` in that `dwarf_loclist()` can handle a maximum of one location expression, not a full location list. If a location-list is present it returns only the first location-list entry location description. Use `dwarf_loclist_n()` instead.

It returns `DW_DLV_ERROR` on error. `dwarf_loclist()` works on `DW_AT_location`, `DW_AT_data_member_location`, `DW_AT_vtable_elem_location`, `DW_AT_string_length`, `DW_AT_use_location`, and `DW_AT_return_addr` attributes.

Storage allocated by a successful call of `dwarf_loclist()` should be deallocated when no longer of interest (see `dwarf_dealloc()`). The block of `Dwarf_Loc` structs pointed to by the `ld_s` field of each `Dwarf_Locdesc` structure should be

deallocated with the allocation type DW_DLA_LOC_BLOCK. This should be followed by deallocation of the llbuf using the allocation type DW_DLA_LOCDESC.

Figure 18. Examplea dwarf_loclist()

```
void examplea(Dwarf_Debug dbg,Dwarf_Attribute someattr)
{
    Dwarf_Signed lcount = 0;
    Dwarf_Locdesc *llbuf = 0;
    Dwarf_Error error = 0;
    int lres = 0;

    lres = dwarf_loclist(someattr, &llbuf,&lcount,&error);
    if (lres == DW_DLV_OK) {
        /* lcount is always 1, (and has always been 1) */
        /* Use llbuf here. */

        dwarf_dealloc(dbg, llbuf->ld_s, DW_DLA_LOC_BLOCK);
        dwarf_dealloc(dbg, llbuf, DW_DLA_LOCDESC);
    }
}
```

6.10.10 dwarf_loclist_from_expr()

```
int dwarf_loclist_from_expr(
    Dwarf_Debug dbg,
    Dwarf_Ptr bytes_in,
    Dwarf_Unsigned bytes_len,
    Dwarf_Locdesc **llbuf,
    Dwarf_Signed *listlen,
    Dwarf_Error *error)
```

Use dwarf_loclist_from_expr_b() instead. This function is obsolete.

The function dwarf_loclist_from_expr() sets *llbuf to point to a Dwarf_Locdesc pointer for the single location expression which is pointed to by *bytes_in (whose length is *bytes_len). It sets *listlen to 1. and returns DW_DLV_OK if decoding is successful. Some sources of bytes of expressions are dwarf expressions in frame operations like DW_CFA_def_cfa_expression, DW_CFA_expression, and DW_CFA_val_expression.

Any address_size data in the location expression is assumed to be the same size as the default address_size for the object being read (normally 4 or 8).

It returns DW_DLV_ERROR on error.

Storage allocated by a successful call of dwarf_loclist_from_expr() should be deallocated when no longer of interest (see dwarf_dealloc()). The block of Dwarf_Loc structs pointed to by the ld_s field of each Dwarf_Locdesc structure

should be deallocated with the allocation type DW_DLA_LOC_BLOCK. This should be followed by deallocation of the lbuf using the allocation type DW_DLA_LOCDESC.

Figure 19. Exampleb dwarf_loclist_from_expr()

```
void exampleb(Dwarf_Debug dbg, Dwarf_Ptr data, Dwarf_Unsigned len)
{
    Dwarf_Signed lcount = 0;
    Dwarf_Locdesc *lbuf = 0;
    Dwarf_Error error = 0;
    int lres = 0;

    lres = dwarf_loclist_from_expr(dbg, data, len, &lbuf, &lcount,
                                   &error);
    if (lres == DW_DLV_OK) {
        /* lcount is always 1 */
        /* Use lbuf here.*/

        dwarf_dealloc(dbg, lbuf->ld_s, DW_DLA_LOC_BLOCK);
        dwarf_dealloc(dbg, lbuf, DW_DLA_LOCDESC);
    }
}
```

6.10.11 dwarf_loclist_from_expr_b()

```
int dwarf_loclist_from_expr_a(
    Dwarf_Ptr bytes_in,
    Dwarf_Unsigned bytes_len,
    Dwarf_Half addr_size,
    Dwarf_Half offset_size,
    Dwarf_Half version_stamp,
    Dwarf_Locdesc **lbuf,
    Dwarf_Signed *listlen,
    Dwarf_Error *error)
```

This function is obsolete. The function `dwarf_loclist_from_expr_b()` is identical to `dwarf_loclist_from_expr_a()` in every way except that the caller passes an additional argument `version_stamp` containing the version stamp (2 for DWARF2, etc) of the CU using this location expression and an additional argument of the offset size of the CU using this location expression. The DW_OP_GNU_implicit_pointer operation requires this version and offset information to be correctly processed.

The `addr_size` argument (from 27April2009) is needed to correctly interpret frame information as different compilation units can have different address sizes. DWARF4 adds `address_size` to the CIE header.

6.10.12 dwarf_loclist_from_expr_a()

```
int dwarf_loclist_from_expr_a(
    Dwarf_Ptr bytes_in,
    Dwarf_Unsigned bytes_len,
    Dwarf_Half addr_size,
    Dwarf_Locdesc **llbuf,
    Dwarf_Signed *listlen,
    Dwarf_Error *error)
```

This function is obsolete. Use `dwarf_loclist_from_expr_b()` instead. This function is obsolete.

The function `dwarf_loclist_from_expr_a()` is identical to `dwarf_loclist_from_expr()` in every way except that the caller passes the additional argument `addr_size` containing the address size (normally 4 or 8) applying this location expression.

The `addr_size` argument (added 27April2009) is needed to correctly interpret frame information as different compilation units can have different address sizes. DWARF4 adds `address_size` to the CIE header.

6.11 Line Number Operations

These functions are concerned with accessing line number entries, mapping debugging information entry objects to their corresponding source lines, and providing a mechanism for obtaining information about line number entries. Although, the interface talks of "lines" what is really meant is "statements". In case there is more than one statement on the same line, there will be at least one descriptor per statement, all with the same line number. If column number is also being represented they will have the column numbers of the start of the statements also represented.

There can also be more than one `Dwarf_Line` per statement. For example, if a file is preprocessed by a language translator, this could result in translator output showing 2 or more sets of line numbers per translated line of output.

As of October 2015 there are two sets of overall access and release functions. The older set of functions is `dwarf_srclines()` with `dwarf_srclines_dealloc()`. This set does not handle line table headers with no lines.

A newer set is `dwarf_srclines_b()` with `dwarf_srclines_from_linecontext()` and `dwarf_srclines_dealloc_b()`. These functions provide for handling both DWARF2 through DWARF5 details and give access to line header information even if there are no lines in a particular compilation unit's line table.

6.11.1 Get A Set of Lines (including skeleton line tables)

This set of functions works on any DWARF version. DWARF2,3,4,5 and the DWARF4 based experimental two-level line tables are all supported. What was once done by dwarf_srclines() alone is now done with two calls as described here.

The interfaces support reading GNU two-level line tables. The format of such tables is a topic beyond the scope of this document.

6.11.2 dwarf_srclines_b()

This is the

```
int dwarf_srclines_b(
    Dwarf_Die die,
    Dwarf_Unsigned *version_out,
    Dwarf_Bool      *is_single_table,
    Dwarf_Line_Context *context_out,
    Dwarf_Error *error)
```

dwarf_srclines_b() takes a single argument as input, a pointer to a compilation-unit (CU) DIE. The other arguments are used to return values to the caller. On success DW_DLV_OK is returned and values are returned through the pointers. If there is no line table DW_DLV_NO_ENTRY is returned and no values are returned though the pointers. If DW_DLV_ERROR is returned the involved is returned through the error pointer.

The values returned on success are:

*version_out() is set to the version number from the line table header for this CU. The experimental two-level line table value is 0xf006. Standard numbers are 2,3,4 and 5.

*is_single_table() is set to non-zero if the line table is an ordinary single line table. If the line table is anything else (either a line table header with no lines or an experimental two-level line table) it is set to zero.

*context_out() is set to an opaque pointer to a Dwarf_Line_Context record which in turn is used to get other data from this line table. See below.

See *dwarf_srclines_dealloc_b() for examples showing correct use.

6.11.3 dwarf_get_line_section_name_from_die()

```
int dwarf_get_line_section_name_from_die(
    Dwarf_Die die,
    const char ** sec_name,
    Dwarf_Error *error)
```

*dwarf_get_line_section_name_from_die() retrieves the object file section name of the applicable line section. This is useful for applications wanting to print the name, but of course the object section name is not really a part of the DWARF

information. Most applications will probably not call this function. It can be called at any time after the Dwarf_Debug initialization is done.

If the function succeeds, *sec_name is set to a pointer to a string with the object section name and the function returns DW_DLV_OK. Do not free the string whose pointer is returned. For non-Elf objects it is possible the string pointer returned will be NULL or will point to an empty string. It is up to the calling application to recognize this possibility and deal with it appropriately.

If the section does not exist the function returns DW_DLV_NO_ENTRY.

If there is an internal error detected the function returns DW_DLV_ERROR and sets the *error pointer.

6.11.4 dwarf_srclines_from_linecontext()

```
int dwarf_srclines_from_linecontext(
    Dwarf_Line_Context line_context,
    Dwarf_Line ** linebuf,
    Dwarf_Signed *linecount,
    Dwarf_Error *error)
```

*dwarf_srclines_from_linecontext() gives access to the line tables. On success it returns DW_DLV_OK and passes back line tables through the pointers.

Though DW_DLV_OK will not be returned callers should assume it is possible.

On error DW_DLV_ERROR is returned and the error code set through the error pointer.

On success:

*linebuf is set to an array of Dwarf_Line pointers.

*linecount is set to the number of pointers in the array.

6.11.5 dwarf_srclines_twolevelfrom_linecontext()

```
int dwarf_srclines_twolevelfrom_linecontext(
    Dwarf_Line_Context line_context,
    Dwarf_Line ** linebuf,
    Dwarf_Signed *linecount,
    Dwarf_Line ** linebuf_actuals,
    Dwarf_Signed *linecount_actuals,
    Dwarf_Error *error)
```

*dwarf_srclines_twolevelfrom_linecontext() gives access to the line tables. On success it returns DW_DLV_OK and passes back line tables through the pointers.

Though DW_DLV_OK will not be returned callers should assume it is possible.

On error DW_DLV_ERROR is returned and the error code set through the error pointer.

On success:

*linebuf is set to an array of Dwarf_Line pointers.
*linecount is set to the number of pointers in the array.

If one is not intending that the experimental two-level line tables are of interest then pass NULL for *linebuf_actuals and *linecount_actuals. The NULL pointers notify the library that the second table is not to be passed back.

If a line table is actually a two-level tables *linebuf is set to point to an array of Logicals lines. *linecount is set to the number of Logicals. *linebuf_actuals is set to point to an array of Actuals lines. *linecount_actuals is set to the number of Actuals.

6.11.6 dwarf_srclines_dealloc_b()

```
void dwarf_srclines_dealloc_b(
    Dwarf_Line_Context line_context,
    Dwarf_Error *error)
```

This does a complete deallocation of the memory of the Dwarf_Line_Context and the Dwarf_Line array (or arrays) that came from the Dwarf_Line_Context. On return you should set any local pointers to these buffers to NULL as a reminder that any use of the local pointers would be to stale memory.

Figure 20. Examplec dwarf_srclines_b()

```
void examplec(Dwarf_Die cu_die)
{
    /* EXAMPLE: DWARF5 style access. */
    Dwarf_Line *linebuf = 0;
    Dwarf_Signed linecount = 0;
    Dwarf_Line *linebuf_actuals = 0;
    Dwarf_Signed linecount_actuals = 0;
    Dwarf_Line_Context line_context = 0;
    Dwarf_Signed linecount_total = 0;
    Dwarf_Small table_count = 0;
    Dwarf_Unsigned lineversion = 0;
    Dwarf_Error err = 0;
    int sres = 0;
    /* ... */
    /* we use 'return' here to signify we can do nothing more
       at this point in the code. */
    sres = dwarf_srclines_b(cu_die,&lineversion,
                           &table_count,&line_context,&err);
    if (sres != DW_DLV_OK) {
        /* Handle the DW_DLV_NO_ENTRY or DW_DLV_ERROR
           No memory was allocated so there nothing
           to dealloc. */
        return;
    }
    if (table_count == 0) {
        /* A line table with no actual lines.
           This occurs in a DWARF5 or DWARF5
           DW_TAG_type_unit
           as such has no lines of code
           but needs data for
           DW_AT_decl_file attributes. */
        /*...do something, see dwarf_srclines_files_count()
           etc below. */

        dwarf_srclines_dealloc_b(line_context);
        /* All the memory is released, the line_context
           and linebuf zeroed now
           as a reminder they are stale. */
        linebuf = 0;
        line_context = 0;
    } else if (table_count == 1) {
        Dwarf_Signed i = 0;
        Dwarf_Signed baseindex = 0;
        Dwarf_Signed file_count = 0;
        Dwarf_Signed endindex = 0;
        /* Standard dwarf 2,3,4, or 5 line table */
```

```
/* Do something. */

/* First let us index through all the files listed
   in the line table header. */
sres = dwarf_srclines_files_indexes(line_context,
   &baseindex,&file_count,&endindex,&err);
if (sres != DW_DLV_OK) {
    /* Something badly wrong! */
    return;
}
/* Works for DWARF2,3,4 (one-based index)
   and DWARF5 (zero-based index) */
for (i = baseindex; i < endindex; i++) {
    Dwarf_Unsigned dirindex = 0;
    Dwarf_Unsigned modtime = 0;
    Dwarf_Unsigned flength = 0;
    Dwarf_Form_Data16 *md5data = 0;
    int vres = 0;
    const char *name = 0;

    vres = dwarf_srclines_files_data_b(line_context,i,
        &name,&dirindex, &modtime,&flength,
        &md5data,&err);
    if (vres != DW_DLV_OK) {
        /* something very wrong. */
        return;
    }
    /* Do something. */
}

/* For this case where we have a line table we will likely
   wish to get the line details: */
sres = dwarf_srclines_from_linecontext(line_context,
   &linebuf,&linecount,
   &err);
if (sres != DW_DLV_OK) {
    /* Error. Clean up the context information. */
    dwarf_srclines_dealloc_b(line_context);
    return;
}
/* The lines are normal line table lines. */
for (i = 0; i < linecount; ++i) {
    /* use linebuf[i] */
}
dwarf_srclines_dealloc_b(line_context);
```

```
/* All the memory is released, the line_context
   and linebuf zeroed now as a reminder they are stale */
linebuf = 0;
line_context = 0;
linecount = 0;
} else {
    Dwarf_Signed i = 0;
    /* ASSERT: table_count == 2,
       Experimental two-level line table. Version 0xf006
       We do not define the meaning of this non-standard
       set of tables here. */

    /* For 'something C' (two-level line tables)
       one codes something like this
       Note that we do not define the meaning or use of two-level
       tables as these are experimental, not standard DWARF. */
    sres = dwarf_srclines_two_level_from_linecontext(line_context,
        &linebuf,&linecount,
        &linebuf_actuals,&linecount_actuals,
        &err);
    if (sres == DW_DLV_OK) {
        for (i = 0; i < linecount; ++i) {
            /* use linebuf[i], these are the 'logicals' entries. */
        }
        for (i = 0; i < linecount_actuals; ++i) {
            /* use linebuf_actuals[i], these are the actuals entries */
        }
        dwarf_srclines_dealloc_b(line_context);
        line_context = 0;
        linebuf = 0;
        linecount = 0;
        linebuf_actuals = 0;
        linecount_actuals = 0;
    } else if (sres == DW_DLV_NO_ENTRY) {
        /* This should be impossible, but do something. */
        /* Then Free the line_context */
        dwarf_srclines_dealloc_b(line_context);
        line_context = 0;
        linebuf = 0;
        linecount = 0;
        linebuf_actuals = 0;
        linecount_actuals = 0;
    } else {
        /* ERROR, show the error or something.
           Free the line_context. */
        dwarf_srclines_dealloc_b(line_context);
```

```
    line_context = 0;
    linebuf = 0;
    linecount = 0;
    linebuf_actuals = 0;
    linecount_actuals = 0;
}
}
}
```

6.12 Line Context Details (DWARF5 style)

New in October 2015. When a Dwarf_Line_Context has been returned by dwarf_srclines_b() that line context data's details can be retrieved with the following set of calls.

6.12.1 dwarf_srclines_table_offset()

```
int dwarf_srclines_table_offset(Dwarf_Line_Context line_context,
                                Dwarf_Unsigned * offset,
                                Dwarf_Error     * error);
```

On success, this function returns the offset (in the object file line section) of the actual line data (i.e. after the line header for this compilation unit) through the offset pointer. The offset is probably only of interest when printing detailed information about a line table header.

In case of error, DW_DLV_ERROR is returned and the error is set through the error pointer. DW_DLV_NO_ENTRY will not be returned.

6.12.2 dwarf_srclines_version()

```
int dwarf_srclines_version(Dwarf_Line_Context line_context,
                           Dwarf_Unsigned * version,
                           Dwarf_Error     * error);
```

On success DW_DLV_OK is returned and the line table version number is returned through the version pointer.

In case of error, DW_DLV_ERROR is returned and the error is set through the error pointer. DW_DLV_NO_ENTRY will not be returned.

6.12.3 dwarf_srclines_comp_dir()

```
int dwarf_srclines_comp_dir(Dwarf_Line_Context line_context,
                            const char ** compilation_directory,
                            Dwarf_Error   * error);
```

On success this returns a pointer to the compilation directory string for this line table in

*compilation_directory. That compilation string may be NULL or the empty string. The string pointer is valid until the line_context has been deallocated.

In case of error, DW_DLV_ERROR is returned and the error is set through the error pointer. DW_DLV_NO_ENTRY will not be returned.

6.12.4 dwarf_srclines_files_indexes()

```
int dwarf_srclines_files_indexes(Dwarf_Line_Context line_context,
    Dwarf_Signed * baseindex,
    Dwarf_Signed * count,
    Dwarf_Signed * endindex,
    Dwarf_Error * error);
```

With DWARF5 the base file number index in the line table changed from zero (DWARF2,3,4) to one (DWARF5). Which meant iterating through the valid source file indexes became messy if one used the older dwarf_srclines_files_count() function (zero-based and one-based indexing being incompatible). See Figure "Examplec dwarf_srclines_b()" above for use of this function in accessing file names.

The base index of files in the files list of a line table header will be returned through baseindex.

The number of files in the files list of a line table header will be returned through count.

The end index of files in the files list of a line table header will be returned through endindex.

In case of error, DW_DLV_ERROR is returned and the error is set through the error pointer. DW_DLV_NO_ENTRY will not be returned.

6.12.5 dwarf_srclines_files_count()

```
int dwarf_srclines_files_count(Dwarf_Line_Context line_context,
    Dwarf_Signed * count,
    Dwarf_Error * error);
```

On success, the number of files in the files list of a line table header will be returned through count.

In case of error, DW_DLV_ERROR is returned and the error is set through the error pointer. DW_DLV_NO_ENTRY will not be returned.

6.12.6 dwarf_srclines_files_data_b()

This supplants dwarf_srclines_files_data() as of March 2018 to allow access

to the md5 value in DWARF5. The function `dwarf_srclines_files_data()` continues to be supported.

```
int dwarf_srclines_files_data_b(Dwarf_Line_Context line_context,
    Dwarf_Signed      index,
    const char **     name,
    Dwarf_Unsigned *   directory_index,
    Dwarf_Unsigned *   last_mod_time,
    Dwarf_Unsigned *   file_length,
    Dwarf_Form_Data16 ** md5_value,
    Dwarf_Error       * error);
```

On success, data about a single file in the files list will be returned through the pointers. See DWARF documentation for the meaning of these fields. `count`. Valid `index` values are 1 through `count`, reflecting the way the table is defined by DWARF2,3,4. For a dwarf5 line table index values 0...`count`-1 are legal. This is certainly awkward.

If `md5_value` is non-null it is used to pass back a pointer to a `Dwarf_Form_Data16` md5 value if the md5 value is present. Otherwise a zero value is passed back to indicate there was no such field. The 16-byte value pointed to is inside the `line_context`, so if you want to keep the value you should probably copy it to storage you control.

This returns the raw files data from the line table header.

In case of error, `DW_DLV_ERROR` is returned and the error is set through the `error` pointer. `DW_DLV_NO_ENTRY` will not be returned.

6.12.7 `dwarf_srclines_files_data()`

This interface was created in October 2015. It cannot return the DWARF5 MD5 value. See the newer `dwarf_srclines_files_data_b()`.

```
int dwarf_srclines_files_data(Dwarf_Line_Context line_context,
    Dwarf_Signed      index,
    const char **     name,
    Dwarf_Unsigned *   directory_index,
    Dwarf_Unsigned *   last_mod_time,
    Dwarf_Unsigned *   file_length,
    Dwarf_Error       * error);
```

On success, data about a single file in the files list will be returned through the pointers. See DWARF documentation for the meaning of these fields. `count`. Valid `index` values are 1 through `count`, reflecting the way the table is defined by DWARF2,3,4. For a dwarf5 line table index values 0...`count`-1 are legal. This is certainly awkward.

This returns the raw files data from the line table header.

In case of error, `DW_DLV_ERROR` is returned and the error is set through the `error` pointer. `DW_DLV_NO_ENTRY` will not be returned.

6.12.8 dwarf_srclines_include_dir_count()

```
int dwarf_srclines_include_dir_count(Dwarf_Line_Context line_context,
                                     Dwarf_Signed * count,
                                     Dwarf_Error * error);
```

On success, the number of files in the includes list of a line table header will be returned through `count`.

Valid `index`. values are 1 through `count`, reflecting the way the table is defined by DWARF 2,3 and 4. For a dwarf5 line table index values 0...`count`-1 are legal. This is certainly awkward.

In case of error, `DW_DLV_ERROR` is returned and the error is set through the `error` pointer. `DW_DLV_NO_ENTRY` will not be returned.

6.12.9 dwarf_srclines_include_dir_data()

```
int dwarf_srclines_include_dir_data(Dwarf_Line_Context line_context,
                                    Dwarf_Signed index,
                                    const char ** name,
                                    Dwarf_Error * error);
```

On success, data about a single file in the include files list will be returned through the pointers. See DWARF documentation for the meaning of these fields.

Valid `index`. values are 1 through `count`, reflecting the way the table is defined by DWARF.

In case of error, `DW_DLV_ERROR` is returned and the error is set through the `error` pointer. `DW_DLV_NO_ENTRY` will not be returned.

6.12.10 dwarf_srclines_subprog_count()

```
int dwarf_srclines_subprog_count(Dwarf_Line_Context line_context,
                                 Dwarf_Signed * count,
                                 Dwarf_Error * error); This is only useful with experimental two-level line tables.
```

6.12.11 dwarf_srclines_subprog_data()

```
int dwarf_srclines_subprog_data(Dwarf_Line_Context line_context,
                                Dwarf_Signed index,
                                const char ** name,
                                Dwarf_Unsigned * decl_file,
                                Dwarf_Unsigned * decl_line,
                                Dwarf_Error * error); This is only useful with experimental two-level line tables.
```

6.13 Get A Set of Lines (DWARF2,3,4 style)

The function returns information about every source line for a particular compilation-unit. The compilation-unit is specified by the corresponding die. It does not support line tables with no lines very well nor does it support experimental two-level linetables.

6.13.1 dwarf_srclines()

```
int dwarf_srclines(
    Dwarf_Die die,
    Dwarf_Line **linebuf,
    Dwarf_Signed *linecount,
    Dwarf_Error *error)
```

This function is not useful for DWARF5 skeleton line tables nor for two-level line tables. It works for DWARF2,3,4,5 ordinary single line tables. The function `dwarf_srclines()` places all line number descriptors for a single compilation unit into a single block, sets `*linebuf` to point to that block, sets `*linecount` to the number of descriptors in this block and returns `DW_DLV_OK`.

To get a more detailed view of the contents of a dwarf line table header see `dwarf_srclines_b()` and the routines that use the `Dwarf_Line_Context` information, such as `dwarf_srcfiles_comp_dir()`, `dwarf_srclines_files_count()`, `dwarf_srclines_include_dir_count()` and similar functions.

The compilation-unit is indicated by the given `die` which must be a compilation-unit die. It returns `DW_DLV_ERROR` on error. On successful return, line number information should be freed using `dwarf_srclines_dealloc()` when no longer of interest.

Figure 21. Exampled dwarf_srclines()

```
void exampled(Dwarf_Debug dbg, Dwarf_Die somedie)
{
    Dwarf_Signed count = 0;
    Dwarf_Line *linebuf = 0;
    Dwarf_Signed i = 0;
    Dwarf_Error error = 0;
    int sres = 0;

    sres = dwarf_srclines(somedie, &linebuf, &count, &error);
    if (sres == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            /* use linebuf[i] */
        }
        dwarf_srclines_dealloc(dbg, linebuf, count);
    }
}
```

An alternative using `dwarf_dealloc()` directly is no longer (as of 2015) described here. It works as well as ever, but it has been obsolete since 2005. still works, but does not completely free all data allocated. The `dwarf_srclines_dealloc()` routine was created to fix the problem of incomplete deallocation.

6.14 Get the set of Source File Names

The function returns the names of the source files that have contributed to the compilation-unit represented by the given DIE. Only the source files named in the statement program prologue (which in current DWARF standards is referred to as the Line Table Header) are returned.

6.14.1 `dwarf_srcfiles()`

This works for for all line tables. However indexing is different in DWARF5 than in other versions of dwarf. To understand the DWARF5 version look at the following which explains a contradiction in the DWARF5 document and how libdwarf (and at least some compilers) resolve it. Join the next two strings together with no spaces to recreate the web reference.

If the applicable file name in the line table Statement Program Prolog does not start with a '/' character the string in `DW_AT_comp_dir` (if applicable and present) and the applicable directory name from the line Statement Program Prolog is prepended to the file name in the line table Statement Program Prolog to make a full path.

For all versions of dwarf this function and `dwarf_linesrc()` prepend the value of `DW_AT_co` prepend the value of `DW_AT_comp_dir` to the name created from the line table header file names and directory names if the line table header name(s) are not full paths.`mp_dir` to the name created from the line table header file names and directory

names if the line table header name(s) are not full paths.

http://wiki.dwarfstd.org/index.php?title=DWARF5_Line_Table_File_Numbers

It may help understand the file tables and dwarf_srcfiles() to use dwarfdump. The dwarfdump utility program now will print the dwarf_srcfiles() values in addition to the compilation unit DIE and the line table header details (and much more) if one does "dwarfdump -vvv -i -l <objfilename>" or "dwarfdump -vvv -a <objfilename>" for example. Since the output can be large, with your editor focus on lines beginning with "COMPILE_UNIT" (do not type the quotes) to quickly get to the CU die and the line table for that CU as those tend to be far apart in the output.

DWARF5: DW_MACRO_start_file, DW_LNS_set_file, DW_AT_decl_file, DW_AT_call_file, and the line table state machine file numbers begin at zero. To index srcfiles use the values directly with no subtraction.

DWARF2-4 and experimental line table: DW_MACINFO_start_file, DW_LNS_set_file, DW_AT_decl_file, and line table state machine file numbers begin at one. In all these the value of 0 means there is no source file or source file name. To index the srcfiles array subtract one from the DW_AT_decl_file (etc) file number.

```
int dwarf_srcfiles(
    Dwarf_Die die,
    char ***srcfiles,
    Dwarf_Signed *srccount,
    Dwarf_Error *error)
```

When it succeeds dwarf_srcfiles() returns DW_DLV_OK and puts the number of source files named in the statement program prologue indicated by the given die into *srccount. Source files defined in the statement program are ignored. The given die should have the tag DW_TAG_compile_unit, DW_TAG_partial_unit, or DW_TAG_type_unit. The location pointed to by srcfiles is set to point to a list of pointers to null-terminated strings that name the source files.

On a successful return from dwarf_srcfiles() each of the strings returned should be individually freed using dwarf_dealloc() with the allocation type DW_DLA_STRING when no longer of interest. This should be followed by free-ing the list using dwarf_dealloc() with the allocation type DW_DLA_LIST. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if there is no corresponding statement program (i.e., if there is no line information).

Figure 22. Exampled dwarf_srcfiles()

```
void examplee(Dwarf_Debug dbg, Dwarf_Die somedie)
{
    Dwarf_Signed count = 0;
    char **srcfiles = 0;
    Dwarf_Signed i = 0;
    Dwarf_Error error = 0;
    int res = 0;

    res = dwarf_srcfiles(somedie, &srcfiles, &count, &error);
    if (res == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            /* use srcfiles[i] */
            dwarf_dealloc(dbg, srcfiles[i], DW_DLA_STRING);
        }
        dwarf_dealloc(dbg, srcfiles, DW_DLA_LIST);
    }
}
```

6.15 Get Information About a Single Line Table Line

The following functions can be used on the Dwarf_Line descriptors returned by `dwarf_srclines()` or `dwarf_srclines_from_linecontext()` to obtain information about the source lines.

6.15.1 dwarf_linebeginstatement()

```
int dwarf_linebeginstatement(
    Dwarf_Line line,
    Dwarf_Bool *return_bool,
    Dwarf_Error *error)
```

The function `dwarf_linebeginstatement()` returns DW_DLV_OK and sets `*return_bool` to *non-zero* (if `line` represents a line number entry that is marked as beginning a statement). or *zero* ((if `line` represents a line number entry that is not marked as beginning a statement). It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

6.15.2 dwarf_lineendsequence()

```
int dwarf_lineendsequence(
    Dwarf_Line line,
    Dwarf_Bool *return_bool,
    Dwarf_Error *error)
```

The function `dwarf_lineendsequence()` returns DW_DLV_OK and sets `*return_bool` *non-zero* (in which case `line` represents a line number entry that is marked as ending a text sequence) or *zero* (in which case `line` represents a line number entry that is not marked as ending a text sequence). A line number entry that is marked

as ending a text sequence is an entry with an address one beyond the highest address used by the current sequence of line table entries (that is, the table entry is a DW_LNE_end_sequence entry (see the DWARF specification)).

The function `dwarf_lineendsequence()` returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

6.15.3 `dwarf_lineno()`

```
int dwarf_lineno(
    Dwarf_Line      line,
    Dwarf_Unsigned * returned_lineno,
    Dwarf_Error     * error)
```

The function `dwarf_lineno()` returns DW_DLV_OK and sets `*returned_lineno` to the source statement line number corresponding to the descriptor `line`. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

6.15.4 `dwarf_line_srcfileno()`

```
int dwarf_line_srcfileno(
    Dwarf_Line      line,
    Dwarf_Unsigned * returned_fileno,
    Dwarf_Error     * error)
```

The function `dwarf_line_srcfileno()` returns DW_DLV_OK and sets `*returned_fileno` to the source statement line number corresponding to the descriptor file number.

DWARF2-4 and experimental: When the number returned through `*returned_fileno` is zero it means the file name is unknown (see the DWARF2/3 line table specification). When the number returned through `*returned_fileno` is non-zero it is a file number: subtract 1 from this file number to get an index into the array of strings returned by `dwarf_srcfiles()` (verify the resulting index is in range for the array of strings before indexing into the array of strings). The file number may exceed the size of the array of strings returned by `dwarf_srcfiles()` because `dwarf_srcfiles()` does not return files names defined with the DW_DLE_define_file operator.

DWARF5: To index into the array of strings returned by `dwarf_srcfiles()` use the number returned through `*returned_fileno`.

The function `dwarf_line_srcfileno()` returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

6.15.5 `dwarf_lineaddr()`

```
int dwarf_lineaddr(
    Dwarf_Line    line,
    Dwarf_Addr   *return_lineaddr,
    Dwarf_Error  *error)
```

The function `dwarf_lineaddr()` returns `DW_DLV_OK` and sets `*return_lineaddr` to the address associated with the descriptor `line`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.15.6 dwarf_lineoff()

```
int dwarf_lineoff(
    Dwarf_Line line,
    Dwarf_Signed * return_lineoff,
    Dwarf_Error *error)
```

The function `dwarf_lineoff()` returns `DW_DLV_OK` and sets `*return_lineoff` to the column number at which the statement represented by `line` begins.

It sets `return_lineoff` to zero if the column number of the statement is not represented (meaning the producer library call was given zero as the column number). Zero is the correct value meaning "left edge" as defined in the DWARF2/3/4 specification (section 6.2.2).

Before December 2011 zero was not returned through the `return_lineoff` pointer, -1 was returned through the pointer. The reason for this oddity is unclear, lost in history. But there is no good reason for -1.

The type of `return_lineoff` is a pointer-to-signed, but there is no good reason for the value to be signed, the DWARF specification does not deal with negative column numbers. However, changing the declaration would cause compilation errors for little benefit, so the pointer-to-signed is left unchanged.

On error it returns `DW_DLV_ERROR`. It never returns `DW_DLV_NO_ENTRY`.

6.15.7 dwarf_lineoff_b()

```
int dwarf_lineoff_b(
    Dwarf_Line line,
    Dwarf_Unsigned * return_lineoff,
    Dwarf_Error *error)
```

The function `dwarf_lineoff_b()` returns exactly the same as `dwarf_lineoff()` except the line offset returned through `return_lineoff()` is an unsigned value. The signed return offset never made much sense but was harmless since line lengths are limited by most language standards.

6.15.8 dwarf_linesrc()

```
int dwarf_linesrc(
    Dwarf_Line line,
    char ** return_linesrc,
    Dwarf_Error *error)
```

The function `dwarf_linesrc()` returns DW_DLV_OK and sets `*return_linesrc` to a pointer to a null-terminated string of characters that represents the name of the source-file where `line` occurs. It returns DW_DLV_ERROR on error.

If the applicable file name in the line table Statement Program Prolog does not start with a '/' character the string in DW_AT_comp_dir (if applicable and present) or the applicable directory name from the line Statement Program Prolog is prepended to the file name in the line table Statement Program Prolog to make a full path.

The storage pointed to by a successful return of `dwarf_linesrc()` should be freed using `dwarf_dealloc()` with the allocation type DW_DLA_STRING when no longer of interest. It never returns DW_DLV_NO_ENTRY.

6.15.9 dwarf_lineblock()

```
int dwarf_lineblock(
    Dwarf_Line line,
    Dwarf_Bool *return_bool,
    Dwarf_Error *error)
```

The function `dwarf_lineblock()` returns DW_DLV_OK and sets `*return_linesrc` to non-zero (i.e. true)(if the line is marked as beginning a basic block) or zero (i.e. false) (if the line is marked as not beginning a basic block). It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

6.15.10 dwarf_is_addr_set()

```
int dwarf_line_is_addr_set (
    Dwarf_Line line,
    Dwarf_Bool *return_bool,
    Dwarf_Error *error)
```

The function `dwarf_line_is_addr_set()` returns DW_DLV_OK and sets `*return_bool` to non-zero (i.e. true)(if the line is marked as being a DW_LNE_set_address operation) or zero (i.e. false) (if the line is marked as not being a DW_LNE_set_address operation). It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

This is intended to allow consumers to do a more useful job printing and analyzing DWARF data, it is not strictly necessary.

6.15.11 dwarf_prologue_end_etc()

```
int dwarf_prologue_end_etc(Dwarf_Line  line,
    Dwarf_Bool * prologue_end,
    Dwarf_Bool * epilogue_begin,
    Dwarf_Unsigned * isa,
    Dwarf_Unsigned * discriminator,
    Dwarf_Error * error)
```

The function `dwarf_prologue_end_etc()` returns `DW_DLV_OK` and sets the returned fields to values currently set. While it is pretty safe to assume that the `isa` and `discriminator` values returned are very small integers, there is no restriction in the standard. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

This function is new in December 2011.

6.16 Accelerated Access By Name operations

These operations operate on the `.debug_pubnames` section as well as all the other sections with this specific format and purpose:

`.debug_pubtypes`,
`.debug_typerenames`,
`.debug_varnames`,
`.debug_funcnames`,

and `.debug_weaknames`. The first in the list is generic DWARF 2,3,4. The second in the list is generic DWARF 3,4. The rest are SGI specific and rarely used.

The interface types are `Dwarf_Global`, `Dwarf_Type`, `Dwarf_Weak`, `Dwarf_Func`, and `Dwarf_Var`. Only `Dwarf_Global` is a real type. The others are opaque pointers with no actual definition or instantiation and can be converted to `Dwarf_Global` with a simple cast.

In hindsight it would have been simpler to write a single set of interfaces for Accelerated Access By Name.

6.16.1 Fine Tuning Accelerated Access

By default the various `dwarf_get*`() functions here return an array of pointers to opaque records with a `.debug_info` DIE offset and a string (the fields are accessible by function calls). While the actual `.debug_pubnames` (etc) section contains CU-local DIE offsets for the named things the accelerated access functions below return a `.debug_info` (or `.debug_types`) global section offset.

6.16.1.1 dwarf_return_empty_pubnames

New March 2019. Mostly special for `dwarfdump`. If called with a flag value of one (1) it

tells libdwarf, for any pubnames/etc) section list returned to add to the list an entry with a global-DIE-offset of zero (0) for any section Compilation Unit entry with no pubnames/etc) name(ie, an empty list for the Compilation Unit).

If called with a value of zero(0) (zero is the default set by any dwarf_init*() call) it causes such empty lists to be omitted from the array of pointers returned, which is the standard behavior of libdwarf since libdwarf was first written.

Since zero is never a valid DIE offset in .debug_info (or .debug_types) consumers requesting such can detect the special Dwarf_Global entries.

For example, calling

```
dwarf_global_name_offsets() on one of the special global records sets  
*die_offset to 0, *return_name to a pointer to an empty string, and  
*cu_offset to the offset of the compilation unit die in the .debug_info (or  
.debug_types if applicable) section.
```

```
int dwarf_return_empty_pubnames(Dwarf_Debug dbg,  
                                int flag,  
                                Dwarf_Error* error)
```

Callers should pass in one (1) or zero(0), no other value. On success it returns DW_DLV_OK. On failure it returns DW_DLV_ERROR;

The assumption is that programs calling this with value one (1) will be calling dwarf_get_globals_header() to retrieve the relevant pubnames/etc) section Compilation Unit header.

6.16.1.2 dwarf_get_globals_header

New February 2019. For more complete dwarfdump printing. For each CU represented in .debug_pubnames, etc, there is a .debug_pubnames header. For any given Dwarf_Global this returns the content of the applicable header.

This allows dwarfdump, or any DWARF dumper, to print pubnames/etc) specific CU header data.

```
int dwarf_get_globals_header(Dwarf_Global global,  
                            Dwarf_Off * offset_pub_header,  
                            Dwarf_Unsigned * offset_size,  
                            Dwarf_Unsigned * length_pub,  
                            Dwarf_Unsigned * version,  
                            Dwarf_Unsigned * header_info_offset,  
                            Dwarf_Unsigned * info_length,  
                            Dwarf_Error* error)
```

On success it returns DW_DLV_OK and it returns the header data (and calculated values) through the pointers. Casting Dwarf_Type (etc) to Dwarf_Global for a call to this

function allows this to be used for any of these accelerated-access types.

6.16.2 Accelerated Access Pubnames

6.16.2.1 dwarf_get_globals()

This is .debug_pubnames and is standard DWARF2, DWARF3, and DWARF4.

```
int dwarf_get_globals(
    Dwarf_Debug dbg,
    Dwarf_Global **globals,
    Dwarf_Signed * return_count,
    Dwarf_Error *error)
```

The function `dwarf_get_globals()` returns `DW_DLV_OK` and sets `*return_count` to the count of pubnames represented in the section containing pubnames i.e. `.debug_pubnames`. It also stores at `*globals`, a pointer to a list of `Dwarf_Global` descriptors, one for each of the pubnames in the `.debug_pubnames` section. The returned results are for the entire section. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if the `.debug_pubnames` section does not exist.

On a successful return from `dwarf_get_globals()`, the `Dwarf_Global` descriptors should be freed using `dwarf_globals_dealloc()`. `dwarf_globals_dealloc()` is new as of July 15, 2005 and is the preferred approach to freeing this memory..

Global names refer exclusively to names and offsets in the `.debug_info` section. See section 6.1.1 "Lookup by Name" in the dwarf standard.

Figure 23. Exampled `dwarf_get_globals()`

```
void examplef(Dwarf_Debug dbg)
{
    Dwarf_Signed count = 0;
    Dwarf_Global *globs = 0;
    Dwarf_Signed i = 0;
    Dwarf_Error error = 0;
    int res = 0;

    res = dwarf_get_globals(dbg, &globs, &count, &error);
    if (res == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            /* use globs[i] */
        }
        dwarf_globals_dealloc(dbg, globs, count);
    }
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from `dwarf_get_globals()`, the `Dwarf_Global` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_GLOBAL_CONTEXT`, (or `DW_DLA_GLOBAL`, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type `DW_DLA_LIST` when the descriptors are no longer of interest.

```
Dwarf_Signed cnt;
Dwarf_Global *globs;
int res;

res = dwarf_get_globals(dbg, &globs, &cnt, &error);
if (res == DW_DLV_OK) {

    /* OBSOLETE: DO NOT USE to deallocate*/
    for (i = 0; i < cnt; ++i) {
        /* use globs[i] */
        dwarf_dealloc(dbg, globs[i], DW_DLA_GLOBAL_CONTEXT);
    }
    dwarf_dealloc(dbg, globs, DW_DLA_LIST);
}
```

6.16.2.2 dwarf_globname()

```
int dwarf_globname(
    Dwarf_Global global,
    char ** return_name,
    Dwarf_Error *error)
```

The function `dwarf_globname()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string that names the pubname represented by the `Dwarf_Global` descriptor, `global`. It returns `DW_DLV_ERROR` on error. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest. It never returns `DW_DLV_NO_ENTRY`.

6.16.2.3 `dwarf_global_die_offset()`

```
int dwarf_global_die_offset(
    Dwarf_Global global,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_global_die_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the pubname that is described by the `Dwarf_Global` descriptor, `glob`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.2.4 `dwarf_global_cu_offset()`

```
int dwarf_global_cu_offset(
    Dwarf_Global global,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_global_cu_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the pubname described by the `Dwarf_Global` descriptor, `global`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.2.5 `dwarf_get_cu_die_offset_given_cu_header_offset()`

```
int dwarf_get_cu_die_offset_given_cu_header_offset_b(
    Dwarf_Debug dbg,
    Dwarf_Off in_cu_header_offset,
    Dwarf_Bool is_info,
    Dwarf_Off *out_cu_die_offset,
    Dwarf_Error *error)
```

The function `dwarf_get_cu_die_offset_given_cu_header_offset()` returns `DW_DLV_OK` and sets `*out_cu_die_offset` to the offset of the compilation-unit DIE given the offset `in_cu_header_offset` of a compilation-unit header. It

returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY.

If `is_info` is non-zero the `in_cu_header_offset` must refer to a `.debug_info` section offset. If `is_info` zero the `in_cu_header_offset` must refer to a `.debug_types` section offset. Chaos may result if the `is_info` flag is incorrect.

This effectively turns a compilation-unit-header offset into a compilation-unit DIE offset (by adding the size of the applicable CU header). This function is also sometimes useful with the `dwarf_weak_cu_offset()`, `dwarf_func_cu_offset()`, `dwarf_type_cu_offset()`, and `int dwarf_var_cu_offset()` functions, though for those functions the data is only in `.debug_info` by definition.

6.16.2.6 `dwarf_get_cu_die_offset_given_cu_header_offset()`

```
int dwarf_get_cu_die_offset_given_cu_header_offset (
    Dwarf_Debug dbg,
    Dwarf_Off in_cu_header_offset,
    Dwarf_Off *out_cu_die_offset,
    Dwarf_Error *error)
```

This function is superseded by `dwarf_get_cu_die_offset_given_cu_header_offset_b()`, a function which is still supported thought it refers only to the `.debug_info` section.

`dwarf_get_cu_die_offset_given_cu_header_offset()` added Rev 1.45, June, 2001.

This function was declared as 'optional' in libdwarf.h on IRIX systems so the `_MIPS_SYMBOL_PRESENT` predicate could be used at run time to determine if the version of libdwarf linked into an application has this function.

6.16.2.7 `dwarf_global_name_offsets()`

```
int dwarf_global_name_offsets (
    Dwarf_Global global,
    char **return_name,
    Dwarf_Off *die_offset,
    Dwarf_Off *cu_die_offset,
    Dwarf_Error *error)
```

The function `dwarf_global_name_offsets()` returns DW_DLV_OK and sets `*return_name` to a pointer to a null-terminated string that gives the name of the pubname described by the `Dwarf_Global` descriptor `global`. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the global offset of the DIE representing the pubname, and the offset of the DIE representing the compilation-unit containing the pubname, respectively. On a successful return from `dwarf_global_name_offsets()` the storage pointed to by `return_name` should be freed using `dwarf_dealloc()`, with the allocation type DW_DLA_STRING

when no longer of interest.

If a portion of .debug_pubnames (or .debug_types etc) represents a compilation unit with no names there is a .debug_pubnames header there with no content. In that case a single Dwarf_Global record is created with the value of *die_offset zero and the name-pointer returned points to the empty string. A zero is never a valid DIE offset, so zero always means this is an uninteresting (Dwarf_Global).

6.16.3 Accelerated Access Pubtypes

Section ".debug_pubtypes" is in DWARF3 and DWARF4.

These functions operate on the .debug_pubtypes section of the debugging information. The .debug_pubtypes section contains the names of file-scope user-defined types, the offsets of the DIEs that represent the definitions of those types, and the offsets of the compilation-units that contain the definitions of those types.

6.16.3.1 dwarf_get_pubtypes()

This is standard DWARF3 and DWARF4.

```
int dwarf_get_pubtypes (
    Dwarf_Debug dbg,
    Dwarf_Type **types,
    Dwarf_Signed *typecount,
    Dwarf_Error *error)
```

The function `dwarf_get_pubtypes()` returns DW_DLV_OK and sets `*typecount` to the count of user-defined type names represented in the section containing user-defined type names, i.e. `.debug_pubtypes`. It also stores at `*types`, a pointer to a list of `Dwarf_Type` descriptors, one for each of the user-defined type names in the `.debug_pubtypes` section. The returned results are for the entire section. It returns DW_DLV_NOCOUNT on error. It returns DW_DLV_NO_ENTRY if the `.debug_pubtypes` section does not exist.

On a successful return from `dwarf_get_pubtypes()`, the `Dwarf_Type` descriptors should be freed using `dwarf_types_dealloc()`. `dwarf_types_dealloc()` is used for both `dwarf_get_pubtypes()` and `dwarf_get_types()` as the data types are the same.

Global type names refer exclusively to names and offsets in the `.debug_info` section. See section 6.1.1 "Lookup by Name" in the dwarf standard.

Figure 24. Exampled dwarf_get_pubtypes()

```
Avoid exampleg(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    Dwarf_Signed count = 0;
    Dwarf_Type *types = 0;
    Dwarf_Signed i = 0;
    int res = 0;

    res = dwarf_get_pubtypes(dbg, &types, &count, &error);
    if (res == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            /* use types[i] */
        }
        dwarf_types_dealloc(dbg, types, count);
    }
}
```

6.16.3.2 dwarf_pubtypename()

```
int dwarf_pubtypename(
    Dwarf_Type type,
    char **return_name,
    Dwarf_Error *error)
```

The function `dwarf_pubtypename()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string that names the user-defined type represented by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

6.16.3.3 dwarf_pubtype_type_die_offset()

```
int dwarf_pubtype_type_die_offset(
    Dwarf_Type type,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_pubtype_type_die_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the user-defined type that is described by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.3.4 dwarf_pubtype_cu_offset()

```
int dwarf_pubtype_cu_offset(
    Dwarf_Type type,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_pubtype_cu_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the user-defined type described by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.3.5 dwarf_pubtype_name_offsets()

```
int dwarf_pubtype_name_offsets(
    Dwarf_Type type,
    char ** returned_name,
    Dwarf_Off * die_offset,
    Dwarf_Off * cu_offset,
    Dwarf_Error *error)
```

The function `dwarf_pubtype_name_offsets()` returns `DW_DLV_OK` and sets `*returned_name` to a pointer to a null-terminated string that gives the name of the user-defined type described by the `Dwarf_Type` descriptor `type`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the user-defined type, and the DIE representing the compilation-unit containing the user-defined type, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_pubtype_name_offsets()` the storage pointed to by `returned_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

6.16.4 Accelerated Access Weaknames

This section is SGI specific and is not part of standard DWARF.

These functions operate on the `.debug_varnames` section of the debugging information. The `.debug_varnames` section contains the names of file-scope static variables, the offsets of the DIEs that represent the definitions of those variables, and the offsets of the compilation-units that contain the definitions of those variables.

These operations operate on the `.debug_weaknames` section of the debugging information.

6.16.4.1 dwarf_get_weaks()

```
int dwarf_get_weaks(
    Dwarf_Debug dbg,
    Dwarf_Weak **weaks,
    Dwarf_Signed *weak_count,
    Dwarf_Error *error)
```

The function `dwarf_get_weaks()` returns `DW_DLV_OK` and sets `*weak_count` to the count of weak names represented in the section containing weak names i.e. `.debug_weaknames`. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if the section does not exist. It also stores in `*weaks`, a pointer to a list of `Dwarf_Weak` descriptors, one for each of the weak names in the `.debug_weaknames` section. The returned results are for the entire section.

On a successful return from this function, the `Dwarf_Weak` descriptors should be freed using `dwarf_weaks_dealloc()` when the data is no longer of interest. `dwarf_weaks_dealloc()` is new as of July 15, 2005.

Figure 25. Exampleh dwarf_get_weaks()

```
void exampleh(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    Dwarf_Signed count = 0;
    Dwarf_Weak *weaks = 0;
    Dwarf_Signed i = 0;
    int res = 0;

    res = dwarf_get_weaks(dbg, &weaks, &count, &error);
    if (res == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            /* use weaks[i] */
        }
        dwarf_weaks_dealloc(dbg, weaks, count);
    }
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from `dwarf_get_weaks()` the `Dwarf_Weak` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_WEAK_CONTEXT`, (or `DW_DLA_WEAK`, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type `DW_DLA_LIST` when the

descriptors are no longer of interest.

Figure 26. Examplei dwarf_get_weaks() obsolete

```
void examplei(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    Dwarf_Signed count = 0;
    Dwarf_Weak *weaks = 0;
    Dwarf_Signed i = 0;
    int res = 0;

    /* Obsolete, see exampleh instead */
    res = dwarf_get_weaks(dbg, &weaks, &count, &error);
    if (res == DW_DLV_OK) {
        /* OBSOLETE: do not use dealloc for this.
           See above */
        for (i = 0; i < count; ++i) {
            /* use weaks[i] */
            dwarf_dealloc(dbg, weaks[i], DW_DLA_WEAK);
        }
        dwarf_dealloc(dbg, weaks, DW_DLA_LIST);
    }
}
```

6.16.4.2 dwarf_weakname()

```
int dwarf_weakname(
    Dwarf_Weak weak,
    char ** return_name,
    Dwarf_Error *error)
```

The function `dwarf_weakname()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string that names the weak name represented by the `Dwarf_Weak` descriptor, `weak`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

```
int dwarf_weak_die_offset(
    Dwarf_Weak weak,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_weak_die_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the

DIE representing the weak name that is described by the `Dwarf_Weak` descriptor, `weak`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.4.3 `dwarf_weak_cu_offset()`

```
int dwarf_weak_cu_offset(
    Dwarf_Weak weak,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_weak_cu_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the weak name described by the `Dwarf_Weak` descriptor, `weak`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.4.4 `dwarf_weak_name_offsets()`

```
int dwarf_weak_name_offsets(
    Dwarf_Weak weak,
    char ** weak_name,
    Dwarf_Off *die_offset,
    Dwarf_Off *cu_offset,
    Dwarf_Error *error)
```

The function `dwarf_weak_name_offsets()` returns `DW_DLV_OK` and sets `*weak_name` to a pointer to a null-terminated string that gives the name of the weak name described by the `Dwarf_Weak` descriptor `weak`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the weakname, and the DIE representing the compilation-unit containing the weakname, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_weak_name_offsets()` the storage pointed to by `weak_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

6.16.5 Accelerated Access Funcnames

This section is SGI specific and is not part of standard DWARF.

These function operate on the `.debug_funcnames` section of the debugging information. The `.debug_funcnames` section contains the names of static functions defined in the object, the offsets of the DIEs that represent the definitions of the corresponding functions, and the offsets of the start of the compilation-units that contain the definitions of those functions.

6.16.5.1 dwarf_get_funcs()

```
int dwarf_get_funcs(
    Dwarf_Debug dbg,
    Dwarf_Func **funcs,
    Dwarf_Signed *func_count,
    Dwarf_Error *error)
```

The function `dwarf_get_funcs()` returns `DW_DLV_OK` and sets `*func_count` to the count of static function names represented in the section containing static function names, i.e. `.debug_funcnames`. It also stores, at `*funcs`, a pointer to a list of `Dwarf_Func` descriptors, one for each of the static functions in the `.debug_funcnames` section. The returned results are for the entire section. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if the `.debug_funcnames` section does not exist.

On a successful return from `dwarf_get_funcs()`, the `Dwarf_Func` descriptors should be freed using `dwarf_funcs_dealloc()`. `dwarf_funcs_dealloc()` is new as of July 15, 2005.

Figure 27. Examplej dwarf_get_funcs()

```
void examplej(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    Dwarf_Signed count = 0;
    Dwarf_Func *funcs = 0;
    Dwarf_Signed i = 0;
    int fres = 0;

    fres = dwarf_get_funcs(dbg, &funcs, &count, &error);
    if (fres == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            /* use funcs[i] */
        }
        dwarf_funcs_dealloc(dbg, funcs, count);
    }
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from `dwarf_get_funcs()`, the `Dwarf_Func` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_FUNC_CONTEXT`, (or `DW_DLA_FUNC`, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type `DW_DLA_LIST` when the descriptors are no longer of interest.

Figure 28. Examplek dwarf_get_funcs() obsolete

```
void examplek(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    Dwarf_Func *funcs = 0;
    Dwarf_Signed count = 0;
    Dwarf_Signed i = 0;
    int fres = 0;

    fres = dwarf_get_funcs(dbg, &funcs, &count, &error);
    if (fres == DW_DLV_OK) {
        /* OBSOLETE: see dwarf_funcs_dealloc() above */
        for (i = 0; i < count; ++i) {
            /* use funcs[i] */
            dwarf_dealloc(dbg, funcs[i], DW_DLA_FUNC);
        }
        dwarf_dealloc(dbg, funcs, DW_DLA_LIST);
    }
}
```

6.16.5.2 dwarf_funcname()

```
int dwarf_funcname(
    Dwarf_Func func,
    char ** return_name,
    Dwarf_Error *error)
```

The function `dwarf_funcname()` returns `DW_DLV_OK` and sets `*return_name` to a pointer to a null-terminated string that names the static function represented by the `Dwarf_Func` descriptor, `func`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

6.16.5.3 dwarf_func_die_offset()

```
int dwarf_func_die_offset(
    Dwarf_Func func,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_func_die_offset()`, returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the static function that is described by the `Dwarf_Func` descriptor, `func`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.5.4 dwarf_func_cu_offset()

```
int dwarf_func_cu_offset(
    Dwarf_Func func,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_func_cu_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the static function described by the `Dwarf_Func` descriptor, `func`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.5.5 dwarf_func_name_offsets()

```
int dwarf_func_name_offsets(
    Dwarf_Func func,
    char **func_name,
    Dwarf_Off *die_offset,
    Dwarf_Off *cu_offset,
    Dwarf_Error *error)
```

The function `dwarf_func_name_offsets()` returns `DW_DLV_OK` and sets `*func_name` to a pointer to a null-terminated string that gives the name of the static function described by the `Dwarf_Func` descriptor `func`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the static function, and the DIE representing the compilation-unit containing the static function, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_func_name_offsets()` the storage pointed to by `func_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

6.16.6 Accelerated Access Typenames

Section "debug_typenames" is SGI specific and is not part of standard DWARF. (However, an identical section is part of DWARF version 3 named ".debug_pubtypes", see `dwarf_get_pubtypes()` above.)

These functions operate on the `.debug_typenames` section of the debugging information. The `.debug_typenames` section contains the names of file-scope user-defined types, the offsets of the DIEs that represent the definitions of those types, and the offsets of the compilation-units that contain the definitions of those types.

6.16.6.1 dwarf_get_types()

```
int dwarf_get_types(
    Dwarf_Debug dbg,
    Dwarf_Type **types,
    Dwarf_Signed *typecount,
    Dwarf_Error *error)
```

The function `dwarf_get_types()` returns `DW_DLV_OK` and sets `*typecount` to the count of user-defined type names represented in the section containing user-defined type names, i.e. `.debug_typenames`. It also stores at `*types`, a pointer to a list of `Dwarf_Type` descriptors, one for each of the user-defined type names in the `.debug_typenames` section. The returned results are for the entire section. It returns `DW_DLV_NOCOUNT` on error. It returns `DW_DLV_NO_ENTRY` if the `.debug_typenames` section does not exist.

On a successful return from `dwarf_get_types()`, the `Dwarf_Type` descriptors should be freed using `dwarf_types_dealloc()`. `dwarf_types_dealloc()` is new as of July 15, 2005 and frees all memory allocated by `dwarf_get_types()`.

Figure 29. Examplel dwarf_get_types()

```
void examplel(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    Dwarf_Signed count = 0;
    Dwarf_Type *types = 0;
    Dwarf_Signed i = 0;
    int res = 0;

    res = dwarf_get_types(dbg, &types, &count, &error);
    if (res == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            /* use types[i] */
        }
        dwarf_types_dealloc(dbg, types, count);
    }
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from `dwarf_get_types()`, the `Dwarf_Type` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_TYPENAME_CONTEXT`, (or `DW_DLA_TYPENAME`, an older name, supported for compatibility) followed by the

deallocation of the list itself with the allocation type DW_DLA_LIST when the descriptors are no longer of interest.

Figure 30. Examplel dwarf_get_types() obsolete

```
void example(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    Dwarf_Signed count = 0;
    Dwarf_Type *types = 0;
    Dwarf_Signed i = 0;
    int res = 0;

    /* OBSOLETE: see dwarf_types_dealloc() above */
    res = dwarf_get_types(dbg, &types, &count, &error);
    if (res == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            /* use types[i] */
            dwarf_dealloc(dbg, types[i], DW_DLA_TYPENAME);
        }
        dwarf_dealloc(dbg, types, DW_DLA_LIST);
    }
}
```

6.16.6.2 dwarf_typename()

```
int dwarf_typename(
    Dwarf_Type    type,
    char         **return_name,
    Dwarf_Error *error)
```

The function `dwarf_typename()` returns DW_DLV_OK and sets `*return_name` to a pointer to a null-terminated string that names the user-defined type represented by the `Dwarf_Type` descriptor, `type`. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type DW_DLA_STRING when no longer of interest.

6.16.6.3 dwarf_type_die_offset()

```
int dwarf_type_die_offset(
    Dwarf_Type type,
    Dwarf_Off  *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_type_die_offset()` returns DW_DLV_OK and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the

DIE representing the user-defined type that is described by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.6.4 `dwarf_type_cu_offset()`

```
int dwarf_type_cu_offset(
    Dwarf_Type type,
    Dwarf_Off *return_offset,
    Dwarf_Error *error)
```

The function `dwarf_type_cu_offset()` returns `DW_DLV_OK` and sets `*return_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the user-defined type described by the `Dwarf_Type` descriptor, `type`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.6.5 `dwarf_type_name_offsets()`

```
int dwarf_type_name_offsets(
    Dwarf_Type type,
    char ** returned_name,
    Dwarf_Off * die_offset,
    Dwarf_Off * cu_offset,
    Dwarf_Error *error)
```

The function `dwarf_type_name_offsets()` returns `DW_DLV_OK` and sets `*returned_name` to a pointer to a null-terminated string that gives the name of the user-defined type described by the `Dwarf_Type` descriptor `type`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the user-defined type, and the DIE representing the compilation-unit containing the user-defined type, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_type_name_offsets()` the storage pointed to by `returned_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

6.16.7 Accelerated Access varnames

This section is SGI specific and is not part of standard DWARF.

These functions operate on the `.debug_varnames` section of the debugging information. The `.debug_varnames` section contains the names of file-scope static variables, the offsets of the DIEs that represent the definitions of those variables, and the offsets of the compilation-units that contain the definitions of those variables.

6.16.7.1 dwarf_get_vars()

```
int dwarf_get_vars(
    Dwarf_Debug dbg,
    Dwarf_Var **vars,
    Dwarf_Signed *var_count,
    Dwarf_Error *error)
```

The function `dwarf_get_vars()` returns `DW_DLV_OK` and sets `*var_count` to the count of file-scope static variable names represented in the section containing file-scope static variable names, i.e. `.debug_varnames`. It also stores, at `*vars`, a pointer to a list of `Dwarf_Var` descriptors, one for each of the file-scope static variable names in the `.debug_varnames` section. The returned results are for the entire section. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if the `.debug_varnames` section does not exist.

The following is new as of July 15, 2005. On a successful return from `dwarf_get_vars()`, the `Dwarf_Var` descriptors should be freed using `dwarf_vars_dealloc()`.

Figure 31. Exemplen `dwarf_get_vars()`

```
void exemplen(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    Dwarf_Signed count = 0;
    Dwarf_Var *vars = 0;
    Dwarf_Signed i = 0;
    int res = 0;
    res = dwarf_get_vars(dbg, &vars, &count, &error);
    if (res == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            /* use vars[i] */
        }
        dwarf_vars_dealloc(dbg, vars, count);
    }
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did. On a successful return from `dwarf_get_vars()`, the `Dwarf_Var` descriptors should be individually freed using `dwarf_dealloc()` with the allocation type `DW_DLA_VAR_CONTEXT`, (or `DW_DLA_VAR`, an older name, supported for compatibility) followed by the deallocation of the list itself with the allocation type `DW_DLA_LIST` when the descriptors are no longer of interest.

Figure 32. Exampleo dwarf_get_vars() obsolete

```
void exampleo(Dwarf_Debug dbg)
{
    Dwarf_Error error = 0;
    Dwarf_Signed count = 0;
    Dwarf_Var *vars = 0;
    Dwarf_Signed i = 0;
    int res = 0;
    res = dwarf_get_vars(dbg, &vars, &count, &error);
    if (res == DW_DLV_OK) {
        /* DO NOT USE: see dwarf_vars_dealloc() above */
        for (i = 0; i < count; ++i) {
            /* use vars[i] */
            dwarf_dealloc(dbg, vars[i], DW_DLA_VAR);
        }
        dwarf_dealloc(dbg, vars, DW_DLA_LIST);
    }
}
```

6.16.7.2 dwarf_varname()

```
int dwarf_varname(
    Dwarf_Var var,
    char **     returned_name,
    Dwarf_Error *error)
```

The function `dwarf_varname()` returns `DW_DLV_OK` and sets `*returned_name` to a pointer to a null-terminated string that names the file-scope static variable represented by the `Dwarf_Var` descriptor, `var`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from this function, the string should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

6.16.7.3 dwarf_var_die_offset()

```
int dwarf_var_die_offset(
    Dwarf_Var      var,
    Dwarf_Off     *returned_offset,
    Dwarf_Error   *error)
```

The function `dwarf_var_die_offset()` returns `DW_DLV_OK` and sets `*returned_offset` to the offset in the section containing DIEs, i.e. `.debug_info`, of the DIE representing the file-scope static variable that is described by the `Dwarf_Var` descriptor, `var`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.7.4 dwarf_var_cu_offset()

```
int dwarf_var_cu_offset(
    Dwarf_Var var,
    Dwarf_Off *returned_offset,
    Dwarf_Error *error)
```

The function `dwarf_var_cu_offset()` returns `DW_DLV_OK` and sets `*returned_offset` to the offset in the section containing DIES, i.e. `.debug_info`, of the compilation-unit header of the compilation-unit that contains the file-scope static variable described by the `Dwarf_Var` descriptor, `var`. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.16.7.5 dwarf_var_name_offsets()

```
int dwarf_var_name_offsets(
    Dwarf_Var var,
    char **returned_name,
    Dwarf_Off *die_offset,
    Dwarf_Off *cu_offset,
    Dwarf_Error *error)
```

The function `dwarf_var_name_offsets()` returns `DW_DLV_OK` and sets `*returned_name` to a pointer to a null-terminated string that gives the name of the file-scope static variable described by the `Dwarf_Var` descriptor `var`. It also returns in the locations pointed to by `die_offset`, and `cu_offset`, the offsets of the DIE representing the

representing the compilation-unit containing the file-scope static variable, respectively. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`. On a successful return from `dwarf_var_name_offsets()` the storage pointed to by `returned_name` should be freed using `dwarf_dealloc()`, with the allocation type `DW_DLA_STRING` when no longer of interest.

6.17 Names Fast Access (DWARF5) `.debug_names`

The section `.debug_names` section is new in DWARF5 so a new set of functions is defined to access this section. This section replaces `.debug_pubnames` and `.debug_pubtypes` as those older sections were not found to be useful in practice. See also Names Fast Access `.debug_gnu_pubnames`

6.17.1 dwarf_debugnames_header()

```
int dwarf_debugnames_header(
    Dwarf_Debug           dbg,
    Dwarf_Dnames_Head   * dn_out,
    Dwarf_Unsigned      * dn_index_count_out,
    Dwarf_Error        *error)
```

The function `dwarf_debugnames_header()` allocates an opaque data structure used in all the other debugnames calls.

Many of the function calls here let one extract the entire content of the section, which is useful if one wishes to dump the section or to use its data to create one's own internal data structures.

To free space allocated when one has finished with these data structures, call

```
Debug_Dnames_Head dn /* Assume set somehow */;  
...  
dwarf_dealloc(dbg,dn,DW_DLA_DNAMES_HEAD);
```

which will free up all data allocated for `dwarf_debugnames_header()`.

On success the function returns `DW_DLV_OK` and returns a pointer to the Head structure through `dn_out`.

It also returns the count of debugnames entry in the debugnames index through the `dn_index_count_out` value.

It returns `DW_DLV_NO_ENTRY` if there is no `.debug_names` section.

It returns `DW_DLV_ERROR` if there is an internal error such as data corruption in the section.

6.17.2 `dwarf_debugnames_sizes()`

```
int dwarf_debugnames_sizes(Dwarf_Dnames_Head dn,
                           Dwarf_Unsigned index_number,
                           Dwarf_Unsigned * section_offsets,
                           Dwarf_Unsigned * version,
                           Dwarf_Unsigned * offset_size,
                           /* The counts are entry counts, not byte sizes. */
                           Dwarf_Unsigned * comp_unit_count,
                           Dwarf_Unsigned * local_type_unit_count,
                           Dwarf_Unsigned * foreign_type_unit_count,
                           Dwarf_Unsigned * bucket_count,
                           Dwarf_Unsigned * name_count,
                           /* The following are counted in bytes */
                           Dwarf_Unsigned * indextable_overall_length,
                           Dwarf_Unsigned * abbrev_table_size,
                           Dwarf_Unsigned * entry_pool_size,
                           Dwarf_Unsigned * augmentation_string_size,
                           Dwarf_Error * error*)
```

Given a properly created head dn this Allows access to fields a .debug_names DWARF5 header record index_number.

We will not describe the fields in detail here. See the DWARF5 standard and dwarfdump for the motivation of this function.

6.17.3 dwarf_debugnames_cu_entry()

```
int dwarf_debugnames_cu_entry(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned index_number,
    Dwarf_Unsigned offset_number,
    Dwarf_Unsigned * offset_count,
    Dwarf_Unsigned * offset,
    Dwarf_Error * error)
```

Given a properly created head dn this Allows access to fields in cu entry index_number from a .debug_names DWARF5 Compilation Unit entry.

We will not describe the fields in detail here. See the DWARF5 standard and dwarfdump for the motivation of this function.

6.17.4 dwarf_debugnames_local_tu_entry()

```
int dwarf_debugnames_local_tu_entry(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned      index_number,
    Dwarf_Unsigned      offset_number,
    Dwarf_Unsigned      * offset_count,
    Dwarf_Unsigned      * offset,
    Dwarf_Error *       error)
```

The same as `dwarf_debugnames_cu_entry()` but referencing type unit fields.

6.17.5 `dwarf_debugnames_foreign_tu_entry()`

```
int dwarf_debugnames_foreign_tu_entry(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned      index_number,
    Dwarf_Unsigned      sig_number,
    Dwarf_Unsigned      * sig_minimum,
    Dwarf_Unsigned      * sig_count,
    Dwarf_Sig8          * signature,
    Dwarf_Error *       error)
```

Allows retrieving the data for foreign type-unit entries.

6.17.6 `dwarf_debugnames_bucket()`

```
int dwarf_debugnames_bucket(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned      index_number,
    Dwarf_Unsigned      bucket_number,
    Dwarf_Unsigned      * bucket_count,
    Dwarf_Unsigned      * index_of_name_entry,
    Dwarf_Error *       error)
```

Allows retrieving the data for hash buckets.

6.17.7 `dwarf_debugnames_name()`

```
int dwarf_debugnames_name(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned      index_number,
    Dwarf_Unsigned      name_entry,
    Dwarf_Unsigned      * names_count,
    Dwarf_Sig8          * signature,
    Dwarf_Unsigned      * offset_to_debug_str,
    Dwarf_Unsigned      * offset_in_entrypool,
    Dwarf_Error *       error)
```

Allows retrieving the data about names and signatures.

6.17.8 dwarf_debugnames_abbrev_by_index()

```
int dwarf_debugnames_abbrev_by_index(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned     index_number,
    Dwarf_Unsigned     abbrev_entry,
    Dwarf_Unsigned     * abbrev_code,
    Dwarf_Unsigned     * tag,
    Dwarf_Unsigned     * number_of_abbrev,
    Dwarf_Unsigned     * number_of_attr_form_entries,
    Dwarf_Error *      error)
```

Allows retrieving the abbreviations from a portion of the section by index.

6.17.9 dwarf_debugnames_abbrev_by_code()

```
int dwarf_debugnames_abbrev_by_code(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned     index_number,
    Dwarf_Unsigned     abbrev_code,
    Dwarf_Unsigned     * tag,
    Dwarf_Unsigned     * index_of_abbrev,
    Dwarf_Unsigned     * index_of_attr_form_entries,
    Dwarf_Error *      error)
```

Allows retrieving the abbreviations from a portion of the section by abbrev-code.

6.17.10 dwarf_debugnames_form_by_index()

```
int dwarf_debugnames_form_by_index(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned     index_number,
    Dwarf_Unsigned     abbrev_entry_index,
    Dwarf_Unsigned     abbrev_form_index,
    Dwarf_Unsigned     * name_attr_index,
    Dwarf_Unsigned     * form,
    Dwarf_Unsigned     * number_of_attr_form_entries,
    Dwarf_Error *      error)
```

Allows retrieving the abbreviations forms from a portion of the section by index.

6.17.11 dwarf_debugnames_entryptool()

```
int dwarf_debugnames_entrypool(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned      index_number,
    Dwarf_Unsigned      offset_in_entrypool,
    Dwarf_Unsigned      * abbrev_code,
    Dwarf_Unsigned      * tag,
    Dwarf_Unsigned      * value_count,
    Dwarf_Unsigned      * index_of_abbrev,
    Dwarf_Unsigned      * offset_of_initial_value,
    Dwarf_Error          * error)
```

Allows retrieving the data from a portion of the entrypool by index and offset.

6.17.12 dwarf_debugnames_entrypool_values()

```
int dwarf_debugnames_entrypool_values(
    Dwarf_Dnames_Head dn,
    Dwarf_Unsigned      index_number,
    Dwarf_Unsigned      index_of_abbrev,
    Dwarf_Unsigned      offset_in_entrypool_of_values,
    Dwarf_Unsigned      * array_dw_idx_number,
    Dwarf_Unsigned      * array_form,
    Dwarf_Unsigned      * array_of_offsets,
    Dwarf_Sig8          * array_of_signatures,
    Dwarf_Error          * error)
```

Allows retrieving detailed data from a portion of the entrypool by index and offset.

6.18 Names Fast Access .debug_gnu_pubnames

The sections `.debug_gnu_pubnames` and `.debug_gnu_pubtypes` are non-standard sections emitted by gcc and clang with DWARF5. Typically they will be in the skeleton executable and the split dwarf section `.debug_info.dwo` will have the actual DWARF the offsets refer to. These sections would normally be read once by a program wanting them and filed in an internal format and then the program would do the cleanup `dwarf_gnu_index_dealloc()`.

Each section is divided into what we term blocks here and within each block there is an array of entries. The functions below enable access.

6.18.1 dwarf_get_gnu_index_head()

```
int dwarf_get_gnu_index_head(
    Dwarf_Debug dbg,
    /* The following arg false to select gnu_pubtypes */
    Dwarf_Bool           for_gdb_pubnames ,
    Dwarf_Gnu_Index_Head * head,
    Dwarf_Unsigned       * index_block_count,
    Dwarf_Error          * error);
```

This creates an open header to use in subsequent data access. Free the memory associated with this by calling `dwarf_gnu_index_dealloc(head)`.

The field `index_block_count` is set through the pointer to the number of blocks in the section. Call `dwarf_get_gnu_index_block()` and pass in valid block number (zero through `index_block_count`-1) to get block information.

If the section does not exist or is empty it returns `DW_DLV_NO_ENTRY` and does nothing else.

If there is data corruption or some serious error it returns `DW_DLV_ERROR` and sets the error pointer with information about the error.

6.18.2 dwarf_gnu_index_dealloc()

```
void dwarf_gnu_index_dealloc(
    Dwarf_Gnu_Index_Head index_head);
```

This frees all data associated with the section.

6.18.3 dwarf_get_gnu_index_block()

```
int dwarf_get_gnu_index_block(
    Dwarf_Gnu_Index_Head head,
    Dwarf_Unsigned      blocknumber,
    Dwarf_Unsigned      * block_length,
    Dwarf_Half          * version ,
    Dwarf_Unsigned      * offset_into_debug_info,
    Dwarf_Unsigned      * size_of_debug_info_area,
    Dwarf_Unsigned      * count_of_index_entries,
    Dwarf_Error         * error);
```

On success this returns `DW_DLV_OK` and fills in the various fields through the pointers. If the pointer to a field is null the function ignores that field.

The field `block_length` has the byte length of the block (with its entries).

The field `version` has the version number. Currently it must be 2.

The field `offsetinto_debug_info` is the offset (in some `.debug_info` or `.debug_info.owo` section) of a Compilation Unit Header.

The field `size_of_debug_info_area` is the size of the referenced compilation unit.

The field `count_of_index_entries` is the number of entries attached to the block. See `dwarf_get_gnu_index_block_entry()`.

If the block number is outside the valid range (zero through `index_block_count` -1) it returns `DW_DLV_NO_ENTRY` and does nothing.

If there is data corruption or some serious error it returns `DW_DLV_ERROR` and sets the error pointer with information about the error.

6.18.4 `dwarf_get_gnu_index_block_entry()`

```
int dwarf_get_gnu_index_block_entry(
    Dwarf_Gnu_Index_Head head,
    Dwarf_Unsigned      blocknumber,
    Dwarf_Unsigned      entrynumber,
    Dwarf_Unsigned      * offset_in_debug_info
    const char          ** name,
    unsigned char        * flagbyte,
    unsigned char        * staticorglobal,
    unsigned char        * typeofentry,
    Dwarf_Error         * error);
```

If either `blocknumber` or `entrynumber` is outside the range of valid values it returns `DW_DLV_NO_ENTRY` and does nothing.

On success it returns `DW_DLV_OK` and sets information about each entry through the pointers. Any pointers passed in as `NULL` are ignored.

The field `offset_in_debug_info` has the offset of DIE in a `.debug_info` section.

The field `name` has a pointer to the name of the variable or function that the DIE refers to.

The field `flagbyte` has the entire 8 bits of a byte that has two useful fields. The next two fields are those useful fields.

The field `staticorglobal` has an integer 0 if the DIE involved describes a global (externally-visible) name. It has an integer 1 if the name refers to a static (file-local) DIE.

The field `typeofentry` has a small integer describing the type. Zero means the type is "none". One means the type is "type". Two means the type is "variable". Three means the type is "function". Four means the type is "other". Any other value has, apparently, no assigned meaning.

If there is data corruption or some serious error it returns `DW_DLV_ERROR` and sets the error pointer with information about the error.

6.19 Macro Information Operations (DWARF4, DWARF5)

This section refers to DWARF4 and later macro information from the `.debug_macro` section (for DWARF 4 some producers generated `.debug_macro` before its formal standardization in DWARF 5). While standard operations are supported there is as yet no support for implementation-defined extensions. Once someone has defined such things it will make sense to design an interface for extensions.

6.19.1 Getting access

The opaque struct pointer `Dwarf_Macro_Context` is allocated by either `dwarf_get_macro_context()` or `dwarf_get_macro_context_by_offset()` and once the context is no longer needed one frees up all its storage by `dwarf_dealloc_macro_context()`.

6.19.1.1 `dwarf_get_macro_context()`

```
int dwarf_get_macro_context(Dwarf_Die die,
    Dwarf_Unsigned * version_out,
    Dwarf_Macro_Context * macro_context,
    Dwarf_Unsigned * macro_unit_offset_out,
    Dwarf_Unsigned * macro_ops_count_out,
    Dwarf_Unsigned * macro_ops_data_length_out,
    Dwarf_Error * error);
```

Given a Compilation Unit (CU) die, on success `dwarf_get_macro_context()` opens a `Dwarf_Macro_Context` and returns a pointer to it and some data from the macro unit for that CU. The `Dwarf_Macro_Context` is used to get at the details of the macros.

The value `version_out` is set to the DWARF version number of the macro data. Version 5 means DWARF5 version information. Version 4 means the DWARF5 format macro data is present as an extension of DWARF4.

The value `macro_unit_offset_out` is set to the offset in the `.debug_macro` section of the first byte of macro data for this CU.

Macro unit is defined in the DWARF5 standard, Section 6.3 Macro Information on page 165.

The value `macro_ops_count_out` is set to the number of macro entries in the macro data data for this CU. The count includes the final zero entry (which is not really a macro, it is a terminator, a zero byte ending the macro unit).

The value `macro_ops_data_length_out` is set to the number of bytes of data in the set of ops (not including macro_unit header bytes). See `dwarf_macro_context_total_length()` to get the macro unit total length.

If `DW_DLV_NO_ENTRY` is returned the CU has no macro data attribute or there is no `.debug_macro` section present.

On error `DW_DLV_ERROR` is returned and the error details are returned through the pointer `error`.

6.19.1.2 `dwarf_get_macro_context_by_offset()`

```
int dwarf_get_macro_context_by_offset(Dwarf_Die die,
                                      Dwarf_Unsigned          offset,
                                      Dwarf_Unsigned          * version_out,
                                      Dwarf_Macro_Context    * macro_context,
                                      Dwarf_Unsigned          * macro_ops_count_out,
                                      Dwarf_Unsigned          * macro_ops_total_byte_len,
                                      Dwarf_Error             * error);
```

Given a Compilation Unit (CU) die and the offset of an imported macro unit `dwarf_get_macro_context_by_offset()` opens a `Dwarf_Macro_Context` and returns a pointer to it and some data from the macro unit for that CU on success.

On success the function produces the same output values as `dwarf_get_macro_context()`.

If `DW_DLV_NO_ENTRY` is returned there is no `.debug_macro` section present.

On error `DW_DLV_ERROR` is returned and the error details are returned through the pointer `error`.

6.19.1.3 `dwarf_macro_context_total_length()`

```
int dwarf_macro_context_total_length(
    Dwarf_Macro_Context macro_context,
    Dwarf_Unsigned     *total_length,
    Dwarf_Error        * error);
```

New in December, 2020, `dwarf_macro_context_total_length()` because callers of `dwarf_get_macro_context[_by_offset]()` sometimes want to know the length of macro ops plus the length of the DWARF5-style header.

On success function returns `DW_DLV_OK` and sets `*total_length` to the total length of the DWARF5-style macro unit.

It never returns `DW_DLV_NO_ENTRY`.

If the macro_context argument is NULL or invalid it returns DW_DLV_ERROR. and sets *error to an appropriate error value.

6.19.1.4 dwarf_dealloc_macro_context()

```
void dwarf_dealloc_macro_context (Dwarf_Macro_Context macro_context);
```

The function dwarf_dealloc_macro_context () cleans up memory allocated by a successful call to dwarf_get_macro_context () or dwarf_get_macro_context_by_offset ().

Figure 33. Examplep5 dwarf_dealloc_macro_context()

```
/* This builds an list or some other data structure
   (not defined) to give an import somewhere to list
   the import offset and then later to enquire
   if the list has unexamined offsets.

   A candidate set of hypothetical functions that
   callers would write:
   has_unchecked_import_in_list()
   get_next_import_from_list()
   mark_this_offset_as_examined(macro_unit_offset);
   add_offset_to_list(offset);

*/
void examplep5(Dwarf_Debug dbg, Dwarf_Die cu_die)
{
    int lres = 0;
    Dwarf_Unsigned version = 0;
    Dwarf_Macro_Context macro_context = 0;
    Dwarf_Unsigned macro_unit_offset = 0;
    Dwarf_Unsigned number_of_ops = 0;
    Dwarf_Unsigned ops_total_byte_len = 0;
    Dwarf_Bool is_primary = TRUE;
    unsigned k = 0;
    Dwarf_Error err = 0;

    for(;;) {
        if (is_primary) {
            lres = dwarf_get_macro_context(cu_die,
                &version, &macro_context,
                &macro_unit_offset,
                &number_of_ops,
                &ops_total_byte_len,
                &err);
            is_primary = FALSE;
        } else {
            if (has_unchecked_import_in_list()) {
                macro_unit_offset = get_next_import_from_list();
            } else {
                /* We are done */
                break;
            }
            lres = dwarf_get_macro_context_by_offset(cu_die,
                macro_unit_offset,
                &version,
                &macro_context,
                &number_of_ops,
                &ops_total_byte_len,
                &err);
        }
    }
}
```

```
    mark_this_offset_as_examined(macro_unit_offset);
}

if (lres == DW_DLV_ERROR) {
    /* Something is wrong. */
    return;
}
if (lres == DW_DLV_NO_ENTRY) {
    /* We are done. */
    break;
}
/* lres == DW_DLV_OK */
for (k = 0; k < number_of_ops; ++k) {
    Dwarf_Unsigned section_offset = 0;
    Dwarf_Half      macro_operator = 0;
    Dwarf_Half      forms_count = 0;
    const Dwarf_Small *formcode_array = 0;
    Dwarf_Unsigned  line_number = 0;
    Dwarf_Unsigned  index = 0;
    Dwarf_Unsigned  offset = 0;
    const char      *macro_string = 0;
    int lres = 0;

    lres = dwarf_get_macro_op(macro_context,
        k, &section_offset, &macro_operator,
        &forms_count, &formcode_array, &err);
    if (lres != DW_DLV_OK) {
        print_error(dbg,
            "ERROR from dwarf_get_macro_op()",
            lres, err);
        dwarf_dealloc_macro_context(macro_context);
        return;
    }
    switch(macro_operator) {
    case 0:
        /* Nothing to do. This
           signifies it is the end-marker,
           standing in for the 0 byte
           at the end of his macro group. */
        break;
    case DW_MACRO_end_file:
        /* Do something */
        break;
    case DW_MACRO_define:
    case DW_MACRO_undef:
    case DW_MACRO_define_strp:
```

```
case DW_MACRO_undef_strp:
case DW_MACRO_define_strx:
case DW_MACRO_undef_strx:
case DW_MACRO_define_sup:
case DW_MACRO_undef_sup: {
    lres = dwarf_get_macro_defundef(macro_context,
        k,
        &line_number,
        &index,
        &offset,
        &forms_count,
        &macro_string,
        &err);
    if (lres != DW_DLV_OK) {
        print_error(dbg,
            "ERROR from sup dwarf_get_macro_defundef()", lres, err);
        dwarf_dealloc_macro_context(macro_context);
        return;
    }
    /* do something */
}
break;
case DW_MACRO_start_file: {
    lres = dwarf_get_macro_startend_file(macro_context,
        k, &line_number,
        &index,
        &macro_string, &err);
    if (lres != DW_DLV_OK) {
        print_error(dbg,
            "ERROR from dwarf_get_macro_startend_file() (sup)", lres, err);
        dwarf_dealloc_macro_context(macro_context);
        return;
    }
    /* do something */
}
break;
case DW_MACRO_import: {
    lres = dwarf_get_macro_import(macro_context,
        k, &offset, &err);
    if (lres != DW_DLV_OK) {
        print_error(dbg,
            "ERROR from dwarf_get_macro_import() (sup)", lres, err);
        dwarf_dealloc_macro_context(macro_context);
```

```
        return;
    }
    add_offset_to_list(offset);
}
break;
case DW_MACRO_import_sup: {
    lres = dwarf_get_macro_import(macro_context,
        k,&offset,&err);
    if (lres != DW_DLV_OK) {
        print_error(dbg,
            "ERROR from dwarf_get_macro_import() (sup) ",
            lres,err);
        dwarf_dealloc_macro_context(macro_context);
        return;
    }
    /* do something */
}
break;
}
dwarf_dealloc_macro_context(macro_context);
macro_context = 0;
}
}
```

6.19.2 Getting Macro Unit Header Data

6.19.2.1 dwarf_macro_context_head()

```
int dwarf_macro_context_head(Dwarf_Macro_Context macro_context,
    Dwarf_Half      * version,
    Dwarf_Unsigned * mac_offset,
    Dwarf_Unsigned * mac_len,
    Dwarf_Unsigned * mac_header_len,
    unsigned       * flags,
    Dwarf_Bool     * has_line_offset,
    Dwarf_Unsigned * line_offset,
    Dwarf_Bool     * has_offset_size_64,
    Dwarf_Bool     * has_operands_table,
    Dwarf_Half     * opcode_count,
    Dwarf_Error    * error);
```

Given a Dwarf_Macro_Context pointer this function returns the basic fields of a macro unit header (Macro Information Header) on success.

The value `version` is set to the DWARF version number of the macro unit header.

Version 5 means DWARF5 version information. Version 4 means the DWARF5 format macro data is present as an extension of DWARF4.

The value `mac_offset` is set to the offset in the `.debug_macro` section of the first byte of macro data for this CU.

The value `mac_len` is set to the number of bytes of data in the macro unit, including the macro unit header.

The value `mac_header_len` is set to the number of bytes in the macro unit header (not a field that is generally useful).

The value `flags` is set to the value of the `flags` field of the macro unit header.

The value `has_line_offset` is set to non-zero if the `debug_line_offset_flag` bit is set in the `flags` field of the macro unit header. If `has_line_offset` is set then `line_offset` is set to the value of the `debug_line_offset` field in the macro unit header. If `has_line_offset` is not set there is no `debug_line_offset` field present in the macro unit header.

The value `has_offset_size_64` is set non-zero if the `offset_size_flag` bit is set in the `flags` field of the macro unit header and in this case offset fields in this macro unit are 64 bits. If `has_offset_size_64` is not set then offset fields in this macro unit are 32 bits.

The value `has_operands_table` is set to non-zero if the `opcode_operands_table_flag` bit is set in the `flags` field of the macro unit header.

If `has_operands_table` is set non-zero then The value `opcode_count` is set to the number of opcodes in the macro unit header `opcode_operands_table`. See `dwarf_get_macro_op()`.

`DW_DLV_NO_ENTRY` is not returned.

On error `DW_DLV_ERROR` is returned and the error details are returned through the pointer `error`.

6.19.2.2 `dwarf_macro_operands_table()`

```
int dwarf_macro_operands_table(Dwarf_Macro_Context macro_context,
    Dwarf_Half      index, /* 0 to opcode_count -1 */
    Dwarf_Half    * opcode_number,
    Dwarf_Half    * operand_count,
    const Dwarf_Small ** operand_array,
    Dwarf_Error   * error);
```

`dwarf_macro_operands_table()` is used to index through the operands table in a macro unit header if the operands table exists in the macro unit header. The operands table provides the mechanism for implementations to add extensions to the macro operations while allowing clients to skip macro operations the client code does not recognize.

The `macro_context` field passed in identifies the macro unit involved. The `index` field passed in identifies which macro operand to look at. Valid index values are zero through the `opcode_count-1` (returned by `dwarf_macro_context_head()`).

The `opcode_number` value returned through the pointer is the the macro operation code. The operation code could be one of the standard codes or if there are user extensions there would be an extension code in the `DW_MACRO_lo_user` to `DW_MACRO_hi_user` range.

The `operand_count` returned is the number of form codes in the form codes array of unsigned bytes `operand_array`.

`DW_DLV_NO_ENTRY` is not returned.

On error `DW_DLV_ERROR` is returned and the error details are returned through the pointer `error`.

6.19.3 Getting Individual Macro Operations Data

6.19.3.1 `dwarf_get_macro_op()`

```
int dwarf_get_macro_op(Dwarf_Macro_Context macro_context,
                      Dwarf_Unsigned op_number,
                      Dwarf_Unsigned * op_start_section_offset,
                      Dwarf_Half      * macro_operator,
                      Dwarf_Half      * forms_count,
                      const Dwarf_Small **  formcode_array,
                      Dwarf_Error     * error);
```

Use `dwarf_get_macro_op()` to access the macro operations of this macro unit.

The `macro_context` field passed in identifies the macro unit involved. The `op_number` field passed in identifies which macro operand to look at. Valid index values are zero through `macro_ops_count_out-1` (field returned by `dwarf_get_macro_context()` or `dwarf_get_macro_context_by_offset()`)

On success the function returns values through the pointers.

If `macro_operator` returned is zero that means this is a placeholder for the null byte at the end of this array of macros. The other pointer values returned are also zero in this case.

The `op_start_section_offset` returned is useful for debugging but otherwise is not normally useful. It is the byte offset of the beginning of this macro operator's data.

The `macro_operator` returned is one of the defined macro operations such as `DW_MACRO_define`. This is the field you will use to choose what call to use to get the data for a macro operator. For example, for `DW_MACRO_undef` one would call `dwarf_get_macro_defundef()` (see below) to get the details about the undefine.

The `forms_count` returned is useful for debugging but otherwise is not normally useful. It is the number of bytes of form numbers in the `formcode_array` of this macro operator's applicable forms.

`DW_DLV_NO_ENTRY` is not returned.

On error `DW_DLV_ERROR` is returned and the error details are returned through the pointer `error`.

6.19.3.2 `dwarf_get_macro_defundef()`

```
int dwarf_get_macro_defundef(Dwarf_Macro_Context macro_context,
    Dwarf_Unsigned op_number,
    Dwarf_Unsigned * line_number,
    Dwarf_Unsigned * index,
    Dwarf_Unsigned * offset,
    Dwarf_Half     * forms_count,
    const char    ** macro_string,
    Dwarf_Error   * error);
```

Call `dwarf_get_macro_defundef` for any of the macro define/undefine operators. Which fields are set through the pointers depends on the particular operator.

The `macro_context` field passed in identifies the macro unit involved. The `op_number` field passed in identifies which macro operand to look at. Valid index values are zero through `macro_ops_count_out-1` (field returned by `dwarf_get_macro_context()` or `dwarf_get_macro_context_by_offset()`).

The `line_number` field is set with the source line number of the macro.

The `index` field only set meaningfully if the macro operator is `DW_MACRO_define_strx` or `DW_MACRO_undef_strx`. If set it is an index into an array of offsets in the `.debug_str_offsets` section.

The `offset` field only set meaningfully if the macro operator is `DW_MACRO_define_strx`, `DW_MACRO_undef_strx`, `DW_MACRO_define_strp`, or `DW_MACRO_undef_strp`. If set it is an offset of a string in the `.debug_str` section.

The `forms_count` is set to the number of forms that apply to the macro operator.

The `macro_string` pointer is used to return a pointer to the macro string. If the actual string cannot be found (as when section with the string is in a different object, see `set_tied_dbg()`) the string returned may be "`<No string available>`" or "`<.debug_str_offsets not available>`" (without the quotes).

The function returns `DW_DLV_NO_ENTRY` if the macro operation is not one of the define/undef operations.

On error `DW_DLV_ERROR` is returned and the error details are returned through the

pointer `error`.

6.19.3.3 `dwarf_get_macro_startend_file()`

```
int dwarf_get_macro_startend_file(Dwarf Macro_Context macro_context,
    Dwarf_Unsigned op_number,
    Dwarf_Unsigned * line_number,
    Dwarf_Unsigned * name_index_to_line_tab,
    const char ** src_file_name,
    Dwarf_Error * error);
```

Call `dwarf_get_macro_startend_file` for operators `DW_MACRO_start_file` or `DW_MACRO_end_file`.

The `macro_context` field passed in identifies the macro unit involved.

The `op_number` field passed in identifies which macro operand to look at. Valid index values are zero through `macro_ops_count_out-1` (field returned by `dwarf_get_macro_context()` or `dwarf_get_macro_context_by_offset()`)

For `DW_MACRO_end_file` none of the following fields are set on successful return, they are only set for `DW_MACRO_start_file`

The `line_number` field is set with the source line number of the macro.

The `name_index_to_line_tab` field is set with the index into the file name table of the line table section. For DWARF2, DWARF3, DWARF4 line tables the index value assumes DWARF2 line table header rules (identical to DWARF3, DWARF4 line table header rules). For DWARF5 the index value assumes DWARF5 line table header rules. The `src_file_name` is set with the source file name. If the index seems wrong or the line table is unavailable the name returned is "<no-source-file-name-available>");

The function returns `DW_DLV_NO_ENTRY` if the macro operation is not one of the start/end operations.

On error `DW_DLV_ERROR` is returned and the error details are returned through the pointer `error`.

6.19.3.4 `dwarf_get_macro_import()`

```
int dwarf_get_macro_import(Dwarf Macro_Context macro_context,
    Dwarf_Unsigned op_number,
    Dwarf_Unsigned * target_offset,
    Dwarf_Error * error);
```

Call `dwarf_get_macro_import` for operators `DW_MACRO_import` or `DW_MACRO_import_sup`.

The `macro_context` field passed in identifies the macro unit involved. The `op_number` field passed in identifies which macro operand to look at. Valid index values are zero through `macro_ops_count_out-1` (field returned by

```
dwarf_get_macro_context()  
dwarf_get_macro_context_by_offset())
```

or

On success the target_offset field is set to the offset in the referenced section. For DW_MACRO_import the referenced section is the same section as the macro operation referenced here. For DW_MACRO_import_sup the referenced section is in a supplementary object.

The function returns DW_DLV_NO_ENTRY if the macro operation is not one of the import operations.

On error DW_DLV_ERROR is returned and the error details are returned through the pointer error.

6.20 Macro Information Operations (DWARF2, DWARF3, DWARF4)

This section refers to DWARF2,DWARF3, and DWARF4 macro information from the .debug_macinfo section. These do not apply to DWARF5 macro data.

6.20.1 General Macro Operations

6.20.1.1 dwarf_find_macro_value_start()

```
char *dwarf_find_macro_value_start(char * macro_string);
```

Given a macro string in the standard form defined in the DWARF document ("name <space> value" or "name(args)<space>value") this returns a pointer to the first byte of the macro value. It does not alter the string pointed to by macro_string or copy the string: it returns a pointer into the string whose address was passed in.

6.20.2 Debugger Interface Macro Operations

Macro information is accessed from the .debug_info section via the DW_AT_macro_info attribute (whose value is an offset into .debug_macinfo).

No Functions yet defined.

6.20.3 Low Level Macro Information Operations

6.20.3.1 dwarf_get_macro_details()

```
int dwarf_get_macro_details(Dwarf_Debug /*dbg*/,
    Dwarf_Off             macro_offset,
    Dwarf_Unsigned        maximum_count,
    Dwarf_Signed          * entry_count,
    Dwarf_Macro_Details ** details,
    Dwarf_Error *         err);
```

dwarf_get_macro_details() returns DW_DLV_OK and sets entry_count to the number of details records returned through the details pointer. The data returned through details should be freed by a call to dwarf_dealloc() with the allocation type DW_DLA_STRING. If DW_DLV_OK is returned, the entry_count will

be at least 1, since a compilation unit with macro information but no macros will have at least one macro data byte of 0.

`dwarf_get_macro_details()` begins at the `macro_offset` offset you supply and ends at the end of a compilation unit or at `maximum_count` detail records (whichever comes first). If `maximum_count` is 0, it is treated as if it were the maximum possible unsigned integer.

`dwarf_get_macro_details()` attempts to set `dmd_fileindex` to the correct file in every `details` record. If it is unable to do so (or whenever the current file index is unknown, it sets `dmd_fileindex` to -1.

`dwarf_get_macro_details()` returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if there is no more macro information at that `macro_offset`. If `macro_offset` is passed in as 0, a `DW_DLV_NO_ENTRY` return means there is no macro information.

Figure 34. Examplep2 `dwarf_get_macro_details()`

```
void examplep2(Dwarf_Debug dbg, Dwarf_Off cur_off)
{
    Dwarf_Error error = 0;
    Dwarf_Signed count = 0;
    Dwarf_Macro_Details *maclist = 0;
    Dwarf_Signed i = 0;
    Dwarf_Unsigned max = 500000; /* sanity limit */
    int errv = 0;

    /* Given an offset from a compilation unit,
       start at that offset (from DW_AT_macroinfo)
       and get its macro details. */
    errv = dwarf_get_macro_details(dbg, cur_off, max,
        &count, &maclist, &error);
    if (errv == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            Dwarf_Macro_Details * mentry = maclist + i;
            /* example of use */
            Dwarf_Signed lineno = mentry->dmd_lineno;
            functionusingsigned(lineno);
        }
        dwarf_dealloc(dbg, maclist, DW_DLA_STRING);
    }
    /* Loop through all the compilation units macro info from zero.
       This is not guaranteed to work because DWARF does not
       guarantee every byte in the section is meaningful:
       there can be garbage between the macro info
       for CUs. But this loop will sometimes work.
    */
    cur_off = 0;
    while((errv = dwarf_get_macro_details(dbg, cur_off, max,
        &count, &maclist, &error)) == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {
            Dwarf_Macro_Details * mentry = maclist + i;
            /* example of use */
            Dwarf_Signed lineno = mentry->dmd_lineno;
            functionusingsigned(lineno);
        }
        cur_off = maclist[count-1].dmd_offset + 1;
        dwarf_dealloc(dbg, maclist, DW_DLA_STRING);
    }
}
```

6.21 Low Level Frame Operations

These functions provide information about stack frames to be used to perform stack traces. The information is an abstraction of a table with a row per instruction and a column per register and a column for the canonical frame address (CFA, which corresponds to the notion of a frame pointer), as well as a column for the return address.

From 1993-2006 the interface we'll here refer to as DWARF2 made the CFA be a column in the matrix, but left DW_FRAME_UNDEFINED_VAL, and DW_FRAME_SAME_VAL out of the matrix (giving them high numbers). As of the DWARF3 interfaces introduced in this document in April 2006, there are *two* interfaces (the original set and a new set). Several frame functions work transparently for either set, we will focus on the ones that are not equally suitable now.

The original DWARF2 interface set still exists (dwarf_get_fde_info_for_reg(), dwarf_get_fde_info_for_cfa_reg(), and dwarf_get_fde_info_for_all_regs()) and works adequately for MIPS/IRIX DWARF2 and ABI/ISA sets that are sufficiently similar to MIPS. These functions not a good choice for non-MIPS architectures nor were they a good design for MIPS either. It's better to switch entirely to the new functions mentioned in the next paragraph. This DWARF2 interface set assumes and uses DW_FRAME_CFA_COL and that is assumed when libdwarf is configured with --enable-oldframecol .

A new DWARF3 interface set of dwarf_get_fde_info_for_reg3(), dwarf_get_fde_info_for_cfa_reg3(), dwarf_set_frame_rule_table_size(), dwarf_get_fde_info_for_all_regs3(), dwarf_set_frame_cfa_value(), dwarf_set_frame_same_value(), dwarf_set_frame_undefined_value(), and dwarf_set_frame_initial_value() is more flexible and will work for many more architectures. It is also entirely suitable for use with DWARF2 and DWARF4. The setting of the 'frame cfa column number' defaults to DW_FRAME_CFA_COL3 and it can be set at runtime with dwarf_set_frame_cfa_value().

Mixing use of the DWARF2 interface set with use of the new DWARF3 interface set on a single open Dwarf_Debug instance is a mistake. Do not do it.

We will pretend, from here on unless otherwise specified, that DW_FRAME_CFA_COL3, DW_FRAME_UNDEFINED_VAL, and DW_FRAME_SAME_VAL are the synthetic column numbers. These columns may be user-chosen by calls of dwarf_set_frame_cfa_value(), dwarf_set_frame_undefined_value(), and dwarf_set_frame_same_value() respectively.

Each cell in the table contains one of the following:

1. A register + offset(a)(b)
2. A register(c)(d)

3. A marker (DW_FRAME_UNDEFINED_VAL) meaning *register value undefined*

4. A marker (DW_FRAME_SAME_VAL) meaning *register value same as in caller*

(a old DWARF2 interface) When the column is DW_FRAME_CFA_COL: the register number is a real hardware register, not a reference to DW_FRAME_CFA_COL, not DW_FRAME_UNDEFINED_VAL, and not DW_FRAME_SAME_VAL. The CFA rule value should be the stack pointer plus offset 0 when no other value makes sense. A value of DW_FRAME_SAME_VAL would be semi-logical, but since the CFA is not a real register, not really correct. A value of DW_FRAME_UNDEFINED_VAL would imply the CFA is undefined -- this seems to be a useless notion, as the CFA is a means to finding real registers, so those real registers should be marked DW_FRAME_UNDEFINED_VAL, and the CFA column content (whatever register it specifies) becomes unreferenced by anything.

(a new April 2006 DWARF2/3 interface): The CFA is separately accessible and not part of the table. The 'rule number' for the CFA is a number outside the table. So the CFA is a marker, not a register number. See DW_FRAME_CFA_COL3 in libdwarf.h and dwarf_get_fde_info_for_cfa_reg3() and dwarf_set_frame_rule_cfa_value().

(b) When the column is not DW_FRAME_CFA_COL3, the 'register' will and must be DW_FRAME_CFA_COL3(COL), implying that to get the final location for the column one must add the offset here plus the DW_FRAME_CFA_COL3 rule value.

(c) When the column is DW_FRAME_CFA_COL3, then the 'register' number is (must be) a real hardware register . (This paragraph does not apply to the April 2006 new interface). If it were DW_FRAME_UNDEFINED_VAL or DW_FRAME_SAME_VAL it would be a marker, not a register number.

(d) When the column is not DW_FRAME_CFA_COL3, the register may be a hardware register. It will not be DW_FRAME_CFA_COL3.

There is no 'column' for DW_FRAME_UNDEFINED_VAL or DW_FRAME_SAME_VAL. Nor for DW_FRAME_CFA_COL3.

Figure 8 is machine dependent and represents MIPS CPU register assignments. The DW_FRAME_CFA_COL define in dwarf.h is historical and really belongs in libdwarf.h, not dwarf.h.

NAME	value	PURPOSE
DW_FRAME_CFA_COL	0	column used for CFA
DW_FRAME_REG1	1	integer register 1
DW_FRAME_REG2	2	integer register 2
---		obvious names and values here
DW_FRAME_REG30	30	integer register 30
DW_FRAME_REG31	31	integer register 31
DW_FRAME_FREG0	32	floating point register 0
DW_FRAME_FREG1	33	floating point register 1
---		obvious names and values here
DW_FRAME_FREG30	62	floating point register 30
DW_FRAME_FREG31	63	floating point register 31
DW_FRAME_RA_COL	64	column recording ra
DW_FRAME_UNDEFINED_VAL	1034	register val undefined
DW_FRAME_SAME_VAL	1035	register same as in caller

Figure 35. Frame Information Rule Assignments MIPS

The following table shows SGI/MIPS specific special cell values: these values mean that the cell has the value *undefined* or *same value* respectively, rather than containing a *register* or *register+offset*. It assumes DW_FRAME_CFA_COL is a table rule, which is not readily accomplished or even sensible for some architectures.

NAME	value	PURPOSE
DW_FRAME_UNDEFINED_VAL	1034	means undefined value. Not a column or register value
DW_FRAME_SAME_VAL	1035	means 'same value' as caller had. Not a column or register value
DW_FRAME_CFA_COL	0	means register zero is usurped by the CFA column.

Figure 36. Frame Information Special Values any architecture

The following table shows more general special cell values. These values mean that the cell register-number refers to the *cfa-register* or *undefined-value* or *same-value* respectively, rather than referring to a *register in the table*. The generality arises from making DW_FRAME_CFA_COL3 be outside the set of registers and making the cfa rule accessible from outside the rule-table.

NAME	value	PURPOSE
DW_FRAME_UNDEFINED_VAL	1034	means undefined value. Not a column or register value
DW_FRAME_SAME_VAL	1035	means 'same value' as caller had. Not a column or register value
DW_FRAME_CFA_COL3	1436	means 'cfa register' is referred to, not a real register, not a column, but the cfa (the cfa does have a value, but in the DWARF3 libdwarf interface it does not have a 'real register number').

6.21.1 dwarf_get_frame_section_name()

```
int dwarf_get_frame_section_name(Dwarf_Debug dbg,
                                const char ** sec_name,
                                Dwarf_Error *error)
```

dwarf_get_string_section_name() lets consumers access the object string section name. This is useful for applications wanting to print the name, but of course the object section name is not really a part of the DWARF information. Most applications will probably not call this function. It can be called at any time after the Dwarf_Debug initialization is done. See also dwarf_get_frame_section_name_eh_gnu().

The function dwarf_get_frame_section_name() operates on the .debug_frame section.

If the function succeeds, *sec_name is set to a pointer to a string with the object section name and the function returns DW_DLV_OK. Do not free the string whose pointer is returned. For non-Elf objects it is possible the string pointer returned will be NULL or will point to an empty string. It is up to the calling application to recognize this possibility and deal with it appropriately.

If the section does not exist the function returns DW_DLV_NO_ENTRY.

If there is an internal error detected the function returns DW_DLV_ERROR and sets the *error pointer.

6.21.2 dwarf_get_frame_section_name_eh_gnu()

```
int dwarf_get_frame_section_name_eh_gnu(Dwarf_Debug dbg
                                         const char ** sec_name,
                                         Dwarf_Error *error)
```

dwarf_get_frame_section_name_eh_gnu() lets consumers access the object string section name. This is useful for applications wanting to print the name, but of course the object section name is not really a part of the DWARF information. Most applications will probably not call this function. It can be called at any time after the

Dwarf_Debug initialization is done. See also dwarf_get_frame_section_name().

The function dwarf_get_frame_section_name_eh_ghu() operates on the the .eh_frame section.

If the function succeeds, *sec_name is set to a pointer to a string with the object section name and the function returns DW_DLV_OK. Do not free the string whose pointer is returned. For non-Elf objects it is possible the string pointer returned will be NULL or will point to an empty string. It is up to the calling application to recognize this possibility and deal with it appropriately.

If the section does not exist the function returns DW_DLV_NO_ENTRY.

If there is an internal error detected the function returns DW_DLV_ERROR and sets the *error pointer.

6.21.3 dwarf_get_fde_list()

```
int dwarf_get_fde_list(
    Dwarf_Debug dbg,
    Dwarf_Cie **cie_data,
    Dwarf_Signed *cie_element_count,
    Dwarf_Fde **fde_data,
    Dwarf_Signed *fde_element_count,
    Dwarf_Error *error);
```

dwarf_get_fde_list() stores a pointer to a list of Dwarf_Cie descriptors in *cie_data, and the count of the number of descriptors in *cie_element_count. There is a descriptor for each CIE in the .debug_frame section. Similarly, it stores a pointer to a list of Dwarf_Fde descriptors in *fde_data, and the count of the number of descriptors in *fde_element_count. There is one descriptor per FDE in the .debug_frame section. dwarf_get_fde_list() returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if it cannot find frame entries. It returns DW_DLV_OK on a successful return.

On successful return, structures pointed to by a descriptor should be freed using dwarf_fde_cie_list_dealloc(). This dealloc approach is new as of July 15, 2005.

Figure 37. Exampleq dwarf_get_fde_list()

```
void exampleq(Dwarf_Debug dbg)
{
    Dwarf_Cie *cie_data = 0;
    Dwarf_Signed cie_count = 0;
    Dwarf_Fde *fde_data = 0;
    Dwarf_Signed fde_count = 0;
    Dwarf_Error error = 0;
    int fres = 0;

    fres = dwarf_get_fde_list(dbg, &cie_data, &cie_count,
        &fde_data, &fde_count, &error);
    if (fres == DW_DLV_OK) {
        dwarf_fde_cie_list_dealloc(dbg, cie_data, cie_count,
            fde_data, fde_count);
    }
}
```

The following code is deprecated as of July 15, 2005 as it does not free all relevant memory. This approach still works as well as it ever did.

Figure 38. Exampleqb dwarf_get_fde_list() obsolete

```
/* OBSOLETE EXAMPLE */
void exampleqb(Dwarf_Debug dbg)
{
    Dwarf_Cie *cie_data = 0;
    Dwarf_Signed cie_count = 0;
    Dwarf_Fde *fde_data = 0;
    Dwarf_Signed fde_count = 0;
    Dwarf_Error error = 0;
    Dwarf_Signed i = 0;
    int fres = 0;

    fres = dwarf_get_fde_list(dbg, &cie_data, &cie_count,
        &fde_data, &fde_count, &error);
    if (fres == DW_DLV_OK) {
        for (i = 0; i < cie_count; ++i) {
            /* use cie[i] */
            dwarf_dealloc(dbg, cie_data[i], DW_DLA_CIE);
        }
        for (i = 0; i < fde_count; ++i) {
            /* use fde[i] */
            dwarf_dealloc(dbg, fde_data[i], DW_DLA_FDE);
        }
        dwarf_dealloc(dbg, cie_data, DW_DLA_LIST);
        dwarf_dealloc(dbg, fde_data, DW_DLA_LIST);
    }
}
```

6.21.4 dwarf_get_fde_list_eh()

```
int dwarf_get_fde_list_eh(
    Dwarf_Debug dbg,
    Dwarf_Cie **cie_data,
    Dwarf_Signed *cie_element_count,
    Dwarf_Fde **fde_data,
    Dwarf_Signed *fde_element_count,
    Dwarf_Error *error);
```

dwarf_get_fde_list_eh() is identical to dwarf_get_fde_list() except that dwarf_get_fde_list_eh() reads the GNU gcc section named .eh_frame (C++ exception handling information).

dwarf_get_fde_list_eh() stores a pointer to a list of Dwarf_Cie descriptors in *cie_data, and the count of the number of descriptors in *cie_element_count. There is a descriptor for each CIE in the .debug_frame section. Similarly, it stores a pointer to a list of Dwarf_Fde descriptors in *fde_data, and the count of the number of descriptors in *fde_element_count. There is one descriptor per FDE in the

.debug_frame section. `dwarf_get_fde_list()` returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if it cannot find exception handling entries. It returns DW_DLV_OK on a successful return.

On successful return, structures pointed to by a descriptor should be freed using `dwarf_fde_cie_list_dealloc()`. This dealloc approach is new as of July 15, 2005.

Figure 39. Exampler dwarf_get_fde_list_eh()

```
void exemplar(Dwarf_Debug dbg,Dwarf_Addr mypcval)
{
    /* Given a pc value
       for a function find the FDE and CIE data for
       the function.
       Example shows basic access to FDE/CIE plus
       one way to access details given a PC value.
       dwarf_get_fde_n() allows accessing all FDE/CIE
       data so one could build up an application-specific
       table of information if that is more useful. */
Dwarf_Signed count = 0;
Dwarf_Cie *cie_data = 0;
Dwarf_Signed cie_count = 0;
Dwarf_Fde *fde_data = 0;
Dwarf_Signed fde_count = 0;
Dwarf_Error error = 0;
int fres = 0;

fres = dwarf_get_fde_list_eh(dbg,&cie_data,&cie_count,
    &fde_data,&fde_count,&error);
if (fres == DW_DLV_OK) {
    Dwarf_Fde myfde = 0;
    Dwarf_Addr low_pc = 0;
    Dwarf_Addr high_pc = 0;
    fres = dwarf_get_fde_at_pc(fde_data,mypcval,
        &myfde,&low_pc,&high_pc,
        &error);
    if (fres == DW_DLV_OK) {
        Dwarf_Cie mycie = 0;
        fres = dwarf_get_cie_of_fde(myfde,&mycie,&error);
        if (fres == DW_DLV_OK) {
            /* Now we can access a range of information
               about the fde and cie applicable. */
        }
    }
    dwarf_fde_cie_list_dealloc(dbg, cie_data, cie_count,
        fde_data,fde_count);
}
/* ERROR or NO ENTRY. Do something */
}
```

6.21.5 dwarf_get_cie_of_fde()

```
int dwarf_get_cie_of_fde(Dwarf_Fde fde,
    Dwarf_Cie *cie_returned,
    Dwarf_Error *error);
```

dwarf_get_cie_of_fde() stores a Dwarf_Cie into the Dwarf_Cie that cie_returned points at.

If one has called dwarf_get_fde_list() must avoid dwarf_dealloc-ing the FDEs and the CIEs for those FDEs individually (see its documentation here). Failing to observe this restriction will cause the FDE(s) not dealloc'd to become invalid: an FDE contains (hidden in it) a CIE pointer which will be be invalid (stale, pointing to freed memory) if the CIE is dealloc'd. The invalid CIE pointer internal to the FDE cannot be detected as invalid by libdwarf. If one later passes an FDE with a stale internal CIE pointer to one of the routines taking an FDE as input the result will be failure of the call (returning DW_DLV_ERROR) at best and it is possible a coredump or worse will happen (eventually).

dwarf_get_cie_of_fde() returns DW_DLV_OK if it is successful (it will be unless fde is the NULL pointer). It returns DW_DLV_ERROR if the fde is invalid (NULL).

Each Dwarf_Fde descriptor describes information about the frame for a particular subroutine or function.

int dwarf_get_fde_for_die is SGI/MIPS specific.

6.21.6 dwarf_get_fde_for_die()

```
int dwarf_get_fde_for_die(
    Dwarf_Debug dbg,
    Dwarf_Die die,
    Dwarf_Fde * return_fde,
    Dwarf_Error *error)
```

When it succeeds, dwarf_get_fde_for_die() returns DW_DLV_OK and sets *return_fde to a Dwarf_Fde descriptor representing frame information for the given die. It looks for the DW_AT_MIPS_fde attribute in the given die. If it finds it, is uses the value of the attribute as the offset in the .debug_frame section where the FDE begins. If there is no DW_AT_MIPS_fde it returns DW_DLV_NO_ENTRY. If there is an error it returns DW_DLV_ERROR.

6.21.7 dwarf_get_fde_range()

```
int dwarf_get_fde_range(
    Dwarf_Fde fde,
    Dwarf_Addr *low_pc,
    Dwarf_Unsigned *func_length,
    Dwarf_Ptr *fde_bytes,
    Dwarf_Unsigned *fde_byte_length,
    Dwarf_Off *cie_offset,
    Dwarf_Signed *cie_index,
    Dwarf_Off *fde_offset,
    Dwarf_Error *error);
```

On success, `dwarf_get_fde_range()` returns `DW_DLV_OK`.

The location pointed to by `low_pc` is set to the low pc value for this function.

The location pointed to by `func_length` is set to the length of the function in bytes. This is essentially the length of the text section for the function.

The location pointed to by `fde_bytes` is set to the address where the FDE begins in the `.debug_frame` section.

The location pointed to by `fde_byte_length` is set to the length in bytes of the portion of `.debug_frame` for this FDE. This is the same as the value returned by `dwarf_get_fde_range`.

The location pointed to by `cie_offset` is set to the offset in the `.debug_frame` section of the CIE used by this FDE.

The location pointed to by `cie_index` is set to the index of the CIE used by this FDE. The index is the index of the CIE in the list pointed to by `cie_data` as set by the function `dwarf_get_fde_list()`. However, if the function `dwarf_get_fde_for_die()` was used to obtain the given `fde`, this index may not be correct.

The location pointed to by `fde_offset` is set to the offset of the start of this FDE in the `.debug_frame` section.

`dwarf_get_fde_range()` returns `DW_DLV_ERROR` on error.

6.21.8 `dwarf_get_cie_info()`

```
int dwarf_get_cie_info(
    Dwarf_Cie          cie,
    Dwarf_Unsigned    *bytes_in_cie,
    Dwarf_Small        *version,
    char              **augmenter,
    Dwarf_Unsigned    *code_alignment_factor,
    Dwarf_Signed       *data_alignment_factor,
    Dwarf_Half         *return_address_register_rule,
    Dwarf_Ptr          *initial_instructions,
    Dwarf_Unsigned    *initial_instructions_length,
    Dwarf_Error        *error);
```

`dwarf_get_cie_info()` is primarily for Internal-level Interface consumers. If successful, it returns DW_DLV_OK and sets `*bytes_in_cie` to the number of bytes in the portion of the frames section for the CIE represented by the given `Dwarf_Cie` descriptor, `cie`. The other fields are directly taken from the `cie` and returned, via the pointers to the caller. It returns DW_DLV_ERROR on error.

6.21.9 `dwarf_get_cie_index()`

```
int dwarf_get_cie_index(
    Dwarf_Cie cie,
    Dwarf_Signed *cie_index,
    Dwarf_Error *error);
```

On success, `dwarf_get_cie_index()` returns DW_DLV_OK. On error this function returns DW_DLV_ERROR.

The location pointed to by `cie_index` is set to the index of the CIE of this FDE. The index is the index of the CIE in the list pointed to by `cie_data` as set by the function `dwarf_get_fde_list()`.

So one must have used `dwarf_get_fde_list()` or `dwarf_get_fde_list_eh()` to get a cie list before this is meaningful.

This function is occasionally useful, but is little used.

6.21.10 `dwarf_get_fde_instr_bytes()`

```
int dwarf_get_fde_instr_bytes(
    Dwarf_Fde fde,
    Dwarf_Ptr *outinstrs,
    Dwarf_Unsigned *outlen,
    Dwarf_Error *error);
```

`dwarf_get_fde_instr_bytes()` returns DW_DLV_OK and sets `*outinstrs` to a pointer to a set of bytes which are the actual frame instructions for this fde. It also sets

*outlen to the length, in bytes, of the frame instructions. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. The intent is to allow low-level consumers like a dwarf-dumper to print the bytes in some fashion. The memory pointed to by outinstrs must not be changed and there is nothing to free.

6.21.11 dwarf_get_fde_info_for_reg()

This interface is suitable for DWARF2 but is not sufficient for DWARF3. See int dwarf_get_fde_info_for_reg3.

```
int dwarf_get_fde_info_for_reg(
    Dwarf_Fde fde,
    Dwarf_Half table_column,
    Dwarf_Addr pc_requested,
    Dwarf_Signed *offset_relevant,
    Dwarf_Signed *register_num,
    Dwarf_Signed *offset,
    Dwarf_Addr *row_pc,
    Dwarf_Error *error);
```

dwarf_get_fde_info_for_reg() returns DW_DLV_OK and sets *offset_relevant to non-zero if the offset is relevant for the row specified by pc_requested and column specified by table_column, for the FDE specified by fde. The intent is to return the rule for the given pc value and register. The location pointed to by register_num is set to the register value for the rule. The location pointed to by offset is set to the offset value for the rule. If offset is not relevant for this rule, *offset_relevant is set to zero. Since more than one pc value will have rows with identical entries, the user may want to know the earliest pc value after which the rules for all the columns remained unchanged. Recall that in the virtual table that the frame information represents there may be one or more table rows with identical data (each such table row at a different pc value). Given a pc_requested which refers to a pc in such a group of identical rows, the location pointed to by row_pc is set to the lowest pc value within the group of identical rows. The value put in *register_num any of the DW_FRAME_* table columns values specified in libdwarf.h or dwarf.h.

dwarf_get_fde_info_for_reg returns DW_DLV_ERROR if there is an error.

It is usable with either dwarf_get_fde_n() or dwarf_get_fde_at_pc().

dwarf_get_fde_info_for_reg() is tailored to MIPS, please use dwarf_get_fde_info_for_reg3() instead for all architectures.

6.21.12 dwarf_get_fde_info_for_all_regs()

```
int dwarf_get_fde_info_for_all_regs(
    Dwarf_Fde fde,
    Dwarf_Addr pc_requested,
    Dwarf_Regtable *reg_table,
    Dwarf_Addr *row_pc,
    Dwarf_Error *error);
```

dwarf_get_fde_info_for_all_regs() returns DW_DLV_OK and sets *reg_table for the row specified by pc_requested for the FDE specified by fde.

The intent is to return the rules for decoding all the registers, given a pc value. reg_table is an array of rules, one for each register specified in dwarf.h. The rule for each register contains three items - dw_regnr which denotes the register value for that rule, dw_offset which denotes the offset value for that rule and dw_offset_relevant which is set to zero if offset is not relevant for that rule. See dwarf_get_fde_info_for_reg() for a description of row_pc.

dwarf_get_fde_info_for_all_regs returns DW_DLV_ERROR if there is an error.

int dwarf_get_fde_info_for_all_regs is tailored to SGI/MIPS, please use dwarf_get_fde_info_for_all_regs3() instead for all architectures.

6.21.13 dwarf_fde_section_offset()

```
int dwarf_fde_section_offset(
    Dwarf_Debug      /*dbg*/,
    Dwarf_Fde        /*in_fde*/,
    Dwarf_Off *      /*fde_off*/,
    Dwarf_Off *      /*cie_off*/,
    Dwarf_Error *error);
```

On success dwarf_fde_section_offset() returns the .dwarf_line section offset of the fde passed in and also the offset of its CIE.

It returns DW_DLV_ERROR if there is an error.

It returns DW_DLV_ERROR if there is an error.

It is intended to be used by applications like dwarfdump when such want to print the offsets of CIEs and FDEs.

6.21.14 dwarf_cie_section_offset()

```
int dwarf_cie_section_offset(
    Dwarf_Debug /*dbg*/,
    Dwarf_Cie /*in_cie*/,
    Dwarf_Off * /*cie_off*/,
    Dwarf_Error * /*err*/);
Dwarf_Error *error);
```

On success `dwarf_cie_section_offset()` returns the `.dwarf_line` section offset of the cie passed in.

It returns `DW_DLV_ERROR` if there is an error.

It is intended to be used by applications like `dwarfdump` when such want to print the offsets of CIEs.

6.21.15 `dwarf_set_frame_rule_table_size()`

This allows consumers to set the size of the (internal to libdwarf) rule table when using the 'reg3' interfaces (these interfaces are strongly preferred over the older 'reg' interfaces). It should be at least as large as the number of real registers in the ABI which is to be read in for the `dwarf_get_fde_info_for_reg3()` or `dwarf_get_fde_info_for_all_regs3()` functions to work properly.

The frame rule table size must be less than the marker values `DW_FRAME_UNDEFINED_VAL`, `DW_FRAME_SAME_VAL`, `DW_FRAME_CFA_COL3` (`dwarf_set_frame_rule_undefined_value()` `dwarf_set_frame_same_value()` `dwarf_set_frame_cfa_value()` effectively set these markers so the frame rule table size can actually be any value regardless of the macro values in `libdwarf.h` as long as the table size does not overlap these markers).

```
Dwarf_Half
dwarf_set_frame_rule_table_size(Dwarf_Debug dbg,
                                Dwarf_Half value);
```

`dwarf_set_frame_rule_table_size()` sets the value `value` as the size of libdwarf-internal rules tables of `dbg`.

The function returns the previous value of the rules table size setting (taken from the `dbg` structure).

6.21.16 `dwarf_set_frame_rule_initial_value()`

This allows consumers to set the initial value for rows in the frame tables. By default it is taken from `libdwarf.h` and is `DW_FRAME_REG_INITIAL_VALUE` (which itself is either `DW_FRAME_SAME_VAL` or `DW_FRAME_UNDEFINED_VAL`). The MIPS/IRIX default is `DW_FRAME_SAME_VAL`. Consumer code should set this

appropriately and for many architectures (but probably not MIPS) DW_FRAME_UNDEFINED_VAL is an appropriate setting. Note: an earlier spelling of dwarf_set_frame_rule_inital_value() is still supported as an interface, but please change to use the new correctly spelled name.

```
Dwarf_Half  
dwarf_set_frame_rule_initial_value(Dwarf_Debug dbg,  
                                    Dwarf_Half value);
```

dwarf_set_frame_rule_initial_value() sets the value value as the initial value for this dbg when initializing rules tables.

The function returns the previous value of initial value (taken from the dbg structure).

6.21.17 dwarf_set_frame_cfa_value()

This allows consumers to set the number of the CFA register for rows in the frame tables. By default it is taken from libdwarf.h and is DW_FRAME_CFA_COL. Consumer code should set this appropriately and for nearly all architectures DW_FRAME_CFA_COL3 is an appropriate setting.

```
Dwarf_Half  
dwarf_set_frame_rule_cfa_value(Dwarf_Debug dbg,  
                               Dwarf_Half value);
```

dwarf_set_frame_rule_cfa_value() sets the value value as the number of the cfa 'register rule' for this dbg when initializing rules tables.

The function returns the previous value of the pseudo-register (taken from the dbg structure).

6.21.18 dwarf_set_frame_same_value()

This allows consumers to set the number of the pseudo-register when DW_CFA_same_value is the operation. By default it is taken from libdwarf.h and is DW_FRAME_SAME_VAL. Consumer code should set this appropriately, though for many architectures DW_FRAME_SAME_VAL is an appropriate setting.

```
Dwarf_Half  
dwarf_set_frame_rule_same_value(Dwarf_Debug dbg,  
                                Dwarf_Half value);
```

dwarf_set_frame_rule_same_value() sets the value value as the number of the register that is the pseudo-register set by the DW_CFA_same_value frame operation.

The function returns the previous value of the pseudo-register (taken from the dbg structure).

6.21.19 dwarf_set_frame_undefined_value()

This allows consumers to set the number of the pseudo-register when DW_CFA_undefined_value is the operation. By default it is taken from libdwarf.h and is DW_FRAME_UNDEFINED_VAL. Consumer code should set this appropriately, though for many architectures DW_FRAME_UNDEFINED_VAL is an appropriate setting.

```
Dwarf_Half  
dwarf_set_frame_rule_undefined_value(Dwarf_Debug dbg,  
                                     Dwarf_Half value);
```

`dwarf_set_frame_rule_undefined_value()` sets the value `value` as the number of the register that is the pseudo-register set by the DW_CFA_undefined_value frame operation.

The function returns the previous value of the pseudo-register (taken from the `dbg` structure).

6.21.20 dwarf_set_default_address_size()

This allows consumers to set a default address size. When one has an object where the default address_size does not match the frame address size where there is no debug_info available to get a frame-specific address-size, this function is useful. For example, if an Elf64 object has a .debug_frame whose real address_size is 4 (32 bits). This a very rare situation.

```
Dwarf_Small  
dwarf_set_default_address_size(Dwarf_Debug dbg,  
                               Dwarf_Small value);
```

`dwarf_set_default_address_size()` sets the value `value` as the default address size for this activation of the reader, but only if `value` is greater than zero (otherwise the default address size is not changed).

The function returns the previous value of the default address size (taken from the `dbg` structure).

6.21.21 dwarf_get_fde_info_for_reg3()

This interface is suitable for DWARF2 and later. It returns the values for a particular real register (Not for the CFA virtual register, see `dwarf_get_fde_info_for_cfa_reg3()` below). If the application is going to retrieve the value for more than a few `table_column` values at this `pc_requested` (by calling this function multiple times) it is much more efficient to call `dwarf_get_fde_info_for_all_regs3()` (in spite of the additional setup that requires of the caller).

```
int dwarf_get_fde_info_for_reg3(
    Dwarf_Fde fde,
    Dwarf_Half table_column,
    Dwarf_Addr pc_requested,
    Dwarf_Small *value_type,
    Dwarf_Signed *offset_relevant,
    Dwarf_Signed *register_num,
    Dwarf_Signed *offset_or_block_len,
    Dwarf_Ptr *block_ptr,
    Dwarf_Addr *row_pc,
    Dwarf_Error *error);
```

See also the nearly identical function `dwarf_get_fde_info_for_reg3_b()`.

`dwarf_get_fde_info_for_reg3()` returns `DW_DLV_OK` on success. It sets `*value_type` to one of `DW_EXPR_OFFSET(0)`, `DW_EXPR_VAL_OFFSET(1)`, `DW_EXPR_EXPRESSION(2)` or `DW_EXPR_VAL_EXPRESSION(3)`. On call, `table_column` must be set to the register number of a real register. Not the cfa 'register' or `DW_FRAME_SAME_VALUE` or `DW_FRAME_UNDEFINED_VALUE`.

if `*value_type` has the value `DW_EXPR_OFFSET(0)` then:

It sets `*offset_relevant` to non-zero if the offset is relevant for the row specified by `pc_requested` and column specified by `table_column` or, for the FDE specified by `fde`. In this case the `*register_num` will be set to `DW_FRAME_CFA_COL3`. This is an offset(N) rule as specified in the DWARF3/2 documents.

Adding the value of `*offset_or_block_len` to the value of the CFA register gives the address of a location holding the previous value of register `table_column`.

If offset is not relevant for this rule, `*offset_relevant` is set to zero. `*register_num` will be set to the number of the real register holding the value of the `table_column` register. This is the register(R) rule as specified in DWARF3/2 documents.

The intent is to return the rule for the given pc value and register. The location pointed to by `register_num` is set to the register value for the rule. The location pointed to by `offset` is set to the offset value for the rule. Since more than one pc value will have rows with identical entries, the user may want to know the earliest pc value after which the rules for all the columns remained unchanged. Recall that in the virtual table that the frame information represents there may be one or more table rows with identical data (each such table row at a different pc value). Given a `pc_requested` which refers to a pc in such a group of identical rows, the location pointed to by `row_pc` is set to the lowest pc value within the group of identical rows.

If `*value_type` has the value DW_EXPR_VAL_OFFSET (1) then:

This will be a `val_offset(N)` rule as specified in the DWARF3/2 documents so `*offset_relevant` will be non zero. The calculation is identical to the DW_EXPR_OFFSET (0) calculation with `*offset_relevant` non-zero, but the value resulting is the actual `table_column` value (rather than the address where the value may be found).

If `*value_type` has the value DW_EXPR_EXPRESSION (1) then:

`*offset_or_block_len` is set to the length in bytes of a block of memory with a DWARF expression in the block. `*block_ptr` is set to point at the block of memory. The consumer code should evaluate the block as a DWARF-expression. The result is the address where the previous value of the register may be found. This is a DWARF3/2 expression(E) rule.

If `*value_type` has the value DW_EXPR_VAL_EXPRESSION (1) then:

The calculation is exactly as for DW_EXPR_EXPRESSION (1) but the result of the DWARF-expression evaluation is the value of the `table_column` (not the address of the value). This is a DWARF3/2 val_expression(E) rule.

`dwarf_get_fde_info_for_reg` returns DW_DLV_ERROR if there is an error and if there is an error only the `error` pointer is set, none of the other output arguments are touched.

It is usable with either `dwarf_get_fde_n()` or `dwarf_get_fde_at_pc()`.

6.21.22 dwarf_get_fde_info_for_reg3_b()

This interface is suitable for DWARF2 and later. It returns the values for a particular real register (Not for the CFA virtual register, see `dwarf_get_fde_info_for_cfa_reg3_b()` below). If the application is going to retrieve the value for more than a few `table_column` values at this `pc_requested` (by calling this function multiple times) it is much more efficient to call `dwarf_get_fde_info_for_all_regs3()` (in spite of the additional setup that requires of the caller).

```
int dwarf_get_fde_info_for_reg3_b(
    Dwarf_Fde fde,
    Dwarf_Half table_column,
    Dwarf_Addr pc_requested,
    Dwarf_Small *value_type,
    Dwarf_Signed *offset_relevant,
    Dwarf_Signed *register_num,
    Dwarf_Signed *offset_or_block_len,
    Dwarf_Ptr *block_ptr,
    Dwarf_Addr *row_pc,
    Dwarf_Bool *has_more_rows,
    Dwarf_Addr *subsequent_pc,
    Dwarf_Error *error);
```

This is identical to `dwarf_get_fde_info_for_reg3()` except for the new arguments `has_more_rows` and `subsequent_pc` which allow the caller to know if there are more rows in the frame table and what the next pc value in the frame table for this fde is. The two new arguments may be passed in as NULL if their values are not needed by the caller.

6.21.23 `dwarf_get_fde_info_for_cfa_reg3()`

```
int dwarf_get_fde_info_for_cfa_reg3(Dwarf_Fde fde,
    Dwarf_Addr          pc_requested,
    Dwarf_Small *       value_type,
    Dwarf_Signed*       offset_relevant,
    Dwarf_Signed*       register_num,
    Dwarf_Signed*       offset_or_block_len,
    Dwarf_Ptr           block_ptr ,
    Dwarf_Addr *        row_pc_out,
    Dwarf_Error *       error)
```

This is identical to `dwarf_get_fde_info_for_reg3()` except the returned values are for the CFA rule. So register number `*register_num` will be set to a real register, not one of the pseudo registers (which are usually `DW_FRAME_CFA_COL3`, `DW_FRAME_SAME_VALUE`, or `DW_FRAME_UNDEFINED_VALUE`).

Applications like `dwarfdump` which access the register rules for every pc value in a function may find the following function a slight performance improvement if the new arguments are used appropriately. See `dwarfdump` for an example of use.

6.21.24 `dwarf_get_fde_info_for_cfa_reg3_b()`

```
int dwarf_get_fde_info_for_cfa_reg3_b(Dwarf_Fde fde,
Dwarf_Addr          pc_requested,
Dwarf_Small *       value_type,
Dwarf_Signed*       offset_relevant,
Dwarf_Signed*       register_num,
Dwarf_Signed*       offset_or_block_len,
Dwarf_Ptr           block_ptr ,
Dwarf_Addr *        row_pc_out,
Dwarf_Bool *        has_more_rows,
Dwarf_Addr *        subsequent_pc,
Dwarf_Error *       error)
```

This is identical to `dwarf_get_fde_info_for_cfa_reg3()` except for the new arguments `has_more_rows` and `subsequent_pc` which allow the caller to know if there are more rows in the frame table and what the next pc value is. The two new arguments may be passed in as NULL if their values are not needed by the caller.

For a tool just wanting the frame information for a single `pc_value` this interface is no more useful or efficient than `dwarf_get_fde_info_for_cfa_reg3()`.

The essential difference is that when using `dwarf_get_fde_info_for_cfa_reg3()` for all `pc` values for a function the caller has no idea what is the next `pc` value that might have new frame data and iterating through `pc` values (calling `dwarf_get_fde_info_for_cfa_reg3()` on each) is a waste of cpu cycles. With `dwarf_get_fde_info_for_cfa_reg3_b()` the `has_more_rows` and `subsequent_pc` arguments let the caller know whether there are further rows and if so at what `pc` value.

If `has_more_rows` is non-null then 1 is returned through the pointer if, for the `pc_requested` there is frame data for addresses after `pc_requested` in the frame. And if there are no more rows in the frame data then 0 is set through the `has_more_rows` pointer.

If `subsequent_pc` is non-null then the `pc-value` which has the next frame operator is returned through the pointer. If no more rows are present zero is returned through the pointer, but please use `has_more_rows` to determine if there are more rows.

6.21.25 `dwarf_get_fde_info_for_all_regs3()`

```
int dwarf_get_fde_info_for_all_regs3(
Dwarf_Fde fde,
Dwarf_Addr pc_requested,
Dwarf_Regtable3 *reg_table,
Dwarf_Addr *row_pc,
Dwarf_Error *error)
```

`dwarf_get_fde_info_for_all_regs3()` returns `DW_DLV_OK` and sets

*reg_table for the row specified by pc_requested for the FDE specified by fde. The intent is to return the rules for decoding all the registers, given a pc value. reg_table is an array of rules, the array size specified by the caller, plus a rule for the CFA. The rule for the cfa returned in *reg_table defines the CFA value at pc_requested. The rule for each register contains several values that enable the consumer to determine the previous value of the register (see the earlier documentation of Dwarf_Regtable3). dwarf_get_fde_info_for_reg3() and the Dwarf_Regtable3 documentation above for a description of the values for each row.

dwarf_get_fde_info_for_all_regs3 returns DW_DLV_ERROR if there is an error.

It is up to the caller to allocate space for *reg_table and initialize it properly.

6.21.26 dwarf_get_fde_n()

```
int dwarf_get_fde_n(
    Dwarf_Fde *fde_data,
    Dwarf_Unsigned fde_index,
    Dwarf_Fde     *returned_fde
    Dwarf_Error   *error)
```

dwarf_get_fde_n() returns DW_DLV_OK and sets returned_fde to the Dwarf_Fde descriptor whose index is fde_index in the table of Dwarf_Fde descriptors pointed to by fde_data. The index starts with 0. The table pointed to by fde_data is required to contain at least one entry. If the table has no entries at all the error checks may refer to uninitialized memory. Returns DW_DLV_NO_ENTRY if the index does not exist in the table of Dwarf_Fde descriptors. Returns DW_DLV_ERROR if there is an error. This function cannot be used unless the block of Dwarf_Fde descriptors has been created by a call to dwarf_get_fde_list().

6.21.27 dwarf_get_fde_at_pc()

```
int dwarf_get_fde_at_pc(
    Dwarf_Fde *fde_data,
    Dwarf_Addr pc_of_interest,
    Dwarf_Fde *returned_fde,
    Dwarf_Addr *lopc,
    Dwarf_Addr *hipc,
    Dwarf_Error *error)
```

dwarf_get_fde_at_pc() returns DW_DLV_OK and sets returned_fde to a Dwarf_Fde descriptor for a function which contains the pc value specified by pc_of_interest. In addition, it sets the locations pointed to by lopc and hipc to the low address and the high address covered by this FDE, respectively. The table

pointed to by fde_data is required to contain at least one entry. If the table has no entries at all the error checks may refer to uninitialized memory. It returns DW_DLV_ERROR on error. It returns DW_DLV_NO_ENTRY if pc_of_interest is not in any of the FDEs represented by the block of Dwarf_Fde descriptors pointed to by fde_data. This function cannot be used unless the block of Dwarf_Fde descriptors has been created by a call to dwarf_get_fde_list().

6.21.28 dwarf_expand_frame_instructions()

```
int dwarf_expand_frame_instructions(
    Dwarf_Cie cie,
    Dwarf_Ptr instruction,
    Dwarf_Unsigned i_length,
    Dwarf_Frame_Op **returned_op_list,
    Dwarf_Signed * returned_op_count,
    Dwarf_Error *error);
```

dwarf_expand_frame_instructions() is a High-level interface function which expands a frame instruction byte stream into an array of Dwarf_Frame_Op structures. To indicate success, it returns DW_DLV_OK. The address where the byte stream begins is specified by instruction, and the length of the byte stream is specified by i_length. The location pointed to by returned_op_list is set to point to a table of returned_op_count pointers to Dwarf_Frame_Op which contain the frame instructions in the byte stream. It returns DW_DLV_ERROR on error. It never returns DW_DLV_NO_ENTRY. After a successful return, the array of structures should be freed using dwarf_dealloc() with the allocation type DW_DLA_FRAME_BLOCK (when they are no longer of interest).

Not all CIEs have the same address-size, so it is crucial that a CIE pointer to the frame's CIE be passed in.

Figure 40. Examples dwarf_expand_frame_instructions()

```
void examples(Dwarf_Debug dbg,Dwarf_Cie cie,
              Dwarf_Ptr instruction,Dwarf_Unsigned len)
{
    Dwarf_Signed count = 0;
    Dwarf_Frame_Op *frameops = 0;
    Dwarf_Error error = 0;
    int res = 0;

    res = dwarf_expand_frame_instructions(cie,instruction,len,
                                           &frameops,&count, &error);
    if (res == DW_DLV_OK) {
        Dwarf_Signed i = 0;

        for (i = 0; i < count; ++i) {
            /* use frameops[i] */
        }
        dwarf_dealloc(dbg, frameops, DW_DLA_FRAME_BLOCK);
    }
}
```

6.21.29 dwarf_get_fde_exception_info()

```
int dwarf_get_fde_exception_info(
    Dwarf_Fde fde,
    Dwarf_Signed * offset_into_exception_tables,
    Dwarf_Error * error);
```

`dwarf_get_fde_exception_info()` is an IRIX specific function which returns an exception table signed offset through `offset_into_exception_tables`. The function never returns `DW_DLV_NO_ENTRY`. If `DW_DLV_NO_ENTRY` is NULL the function returns `DW_DLV_ERROR`. For non-IRIX objects the offset returned will always be zero. For non-C++ objects the offset returned will always be zero. The meaning of the offset and the content of the tables is not defined in this document. The applicable CIE augmentation string (see above) determines whether the value returned has meaning.

6.22 Location Expression Evaluation

An "interpreter" which evaluates a location expression is required in any debugger. There is no interface defined here at this time.

One problem with defining an interface is that operations are machine dependent: they depend on the interpretation of register numbers and the methods of getting values from the environment the expression is applied to.

It would be desirable to specify an interface.

6.22.1 Location List Internal-level Interface

6.22.1.1 dwarf_get_loclist_entry()

```
int dwarf_get_loclist_entry(
    Dwarf_Debug dbg,
    Dwarf_Unsigned offset,
    Dwarf_Addr *hipc_offset,
    Dwarf_Addr *lopc_offset,
    Dwarf_Ptr *data,
    Dwarf_Unsigned *entry_len,
    Dwarf_Unsigned *next_entry,
    Dwarf_Error *error)
```

This function is ill suited to use with 21st century DWARF as there is just not enough data provided in the interface. Do not use this interface. Use `dwarf_get_locdesc_entry_c()` instead.

The function reads a location list entry starting at `offset` and returns through pointers (when successful) the high pc `hipc_offset`, low pc `lopc_offset`, a pointer to the location description data `data`, the length of the location description data `entry_len`, and the offset of the next location description entry `next_entry`.

This function will often work correctly (meaning with most objects compiled for DWARF3 or DWARF3) but will not work correctly (and can crash an application calling it) if either some location list applies to a compilation unit with an `address_size` different from the overall `address_size` of the object file being read or if the `.debug_loc` section being read has random padding bytes between loclists. Neither of these characteristics necessarily represents a bug in the compiler/linker toolset that produced the object file being read. The DWARF standard allows both characteristics.

`dwarf_dwarf_get_loclist_entry()` returns `DW_DLV_OK` if successful. `DW_DLV_NO_ENTRY` is returned when the offset passed in is beyond the end of the `.debug_loc` section (expected if you start at offset zero and proceed through all the entries). `DW_DLV_ERROR` is returned on error.

The `hipc_offset`, low pc `lopc_offset` are offsets from the beginning of the current procedure, not genuine pc values.

The example of use has been deleted. Do not use this function.

6.23 Abbreviations access

These are Internal-level Interface functions. Debuggers can ignore this.

6.23.1 dwarf_get_abbrev()

```
int dwarf_get_abbrev(
    Dwarf_Debug dbg,
    Dwarf_Uunsigned offset,
    Dwarf_Abbrev *returned_abbrev,
    Dwarf_Uunsigned *length,
    Dwarf_Uunsigned *attr_count,
    Dwarf_Error *error)
```

The function `dwarf_get_abbrev()` returns `DW_DLV_OK` and sets `*returned_abbrev` to `Dwarf_Abbrev`, a descriptor for the abbreviation that begins at offset `*offset` in the abbreviations section (i.e `.debug_abbrev`) on success. The user is responsible for making sure that a valid abbreviation begins at `offset` in the abbreviations section. The location pointed to by `length` is set to the length in bytes of the abbreviation set in the abbreviations section. The location pointed to by `attr_count` is set to the number of attributes in the abbreviation. An abbreviation entry with a length of 1 is the 0 byte of the last abbreviation entry of a compilation unit.

`dwarf_get_abbrev()` returns `DW_DLV_NO_ENTRY` if the `.debug_abbrev` section is missing or if the offset passed in is past the end of the section.

`dwarf_get_abbrev()` returns `DW_DLV_ERROR` on error. If the call succeeds, the storage pointed to by `*returned_abbrev` should be freed, using `dwarf_dealloc()` with the allocation type `DW_DLA_ABBREV` when no longer needed.

6.23.2 `dwarf_get_abbrev_tag()`

```
int dwarf_get_abbrev_tag(
    Dwarf_Abbrev abbrev,
    Dwarf_Half *return_tag,
    Dwarf_Error *error);
```

If successful, `dwarf_get_abbrev_tag()` returns `DW_DLV_OK` and sets `*return_tag` to the `tag` of the given abbreviation. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.23.3 `dwarf_get_abbrev_code()`

```
int dwarf_get_abbrev_code(
    Dwarf_Abbrev      abbrev,
    Dwarf_Uunsigned   *return_code,
    Dwarf_Error       *error);
```

If successful, `dwarf_get_abbrev_code()` returns `DW_DLV_OK` and sets `*return_code` to the abbreviation code of the given abbreviation. It returns `DW_DLV_ERROR` on error. It never returns `DW_DLV_NO_ENTRY`.

6.23.4 dwarf_get_abbrev_children_flag()

```
int dwarf_get_abbrev_children_flag(
    Dwarf_Abbrev abbrev,
    Dwarf_Signed *returned_flag,
    Dwarf_Error *error)
```

The function `dwarf_get_abbrev_children_flag()` returns `DW_DLV_OK` and sets `returned_flag` to `DW_children_no` (if the given abbreviation indicates that a die with that abbreviation has no children) or `DW_children_yes` (if the given abbreviation indicates that a die with that abbreviation has a child). It returns `DW_DLV_ERROR` on error.

6.23.5 dwarf_get_abbrev_entry_b()

```
int dwarf_get_abbrev_entry_b(Dwarf_Abbrev abbrev,
    Dwarf_Unsigned index,
    Dwarf_Bool filter_outliers,
    Dwarf_Unsigned * returned_attr_num,
    Dwarf_Unsigned * returned_form,
    Dwarf_Signed * returned_implicit_const,
    Dwarf_Off * offset,
    Dwarf_Error * error)
```

`dwarf_get_abbrev_entry_b()` is new in August 2019. It should be used in place of `dwarf_get_abbrev_entry()` as `dwarf_get_abbrev_entry()` cannot return the DWARF5 implicit const value and `dwarf_get_abbrev_entry()` can hide some instances of corrupt uleb abbreviation values.

While the `returned_attr_num` and `returned_form` are only correct if they each fit in a `Dwarf_Half` value, we return larger values in certain cases (see next paragraph).

If `filter_outliers` is passed in zero then erroneous `returned_attr_num` or `returned_form` are returned whether their values are sensible or not and `DW_DLV_OK` is the returned value. This is useful for `dwarfdump` as `dwarfdump` checks abbreviation values quite thoroughly and reports errors in detail (`dwarfdump -kb`).

If `filter_outliers` is passed in non-zero then `DW_DLV_OK` is returned only if `returned_attr_num` and `returned_form` are both legitimate values.

If successful, `dwarf_get_abbrev_entry_b()` returns `DW_DLV_OK` and sets `*attr_num` to the attribute code of the attribute whose index is specified by `index` in the given abbreviation.

The index starts at 0.

The location pointed to by `returned_attr_num` is set to the attribute number (example: `DW_AT_name`). The location pointed to by `returned_form` is set to the form of the attribute (example: `DW_FORM_string`). The location pointed to by `returned_implicit_const` is set to the implicit const value if and only if the

FORM returned is DW_FORM_implicit_const

The location pointed to by offset is set to the byte offset of the attribute in the abbreviations section.

The function returns DW_DLV_NO_ENTRY if the index specified is outside the range of attributes in this abbreviation.

The function returns DW_DLV_ERROR on error and sets *error to an error value instance.

6.23.6 dwarf_get_abbrev_entry()

```
int dwarf_get_abbrev_entry (
    Dwarf_Abbrev abbrev,
    Dwarf_Signed index,
    Dwarf_Half   *attr_num,
    Dwarf_Signed *form,
    Dwarf_Off   *offset,
    Dwarf_Error *error)
```

This function cannot return DW_FORM_implicit_const const values. When convenient all callers should switch to using the dwarf_get_abbrev_entry_b() function.

If successful, dwarf_get_abbrev_entry() returns DW_DLV_OK and sets *attr_num to the attribute code of the attribute whose index is specified by index in the given abbreviation. The index starts at 0. The location pointed to by form is set to the form of the attribute. The location pointed to by offset is set to the byte offset of the attribute in the abbreviations section.

It returns DW_DLV_NO_ENTRY if the index specified is outside the range of attributes in this abbreviation.

It returns DW_DLV_ERROR on error.

6.24 String Section Operations

The .debug_str section contains only strings. Debuggers need never use this interface: it is only for debugging problems with the string section itself.

6.24.1 dwarf_get_string_section_name()

```
int dwarf_get_string_section_name (Dwarf_Debug dbg,
    const char ** sec_name,
    Dwarf_Error *error)
```

dwarf_get_string_section_name() lets consumers access the object string section name. This is useful for applications wanting to print the name, but of course the object section name is not really a part of the DWARF information. Most applications

will probably not call this function. It can be called at any time after the Dwarf_Debug initialization is done. See also `dwarf_get_die_section_name_b()`.

The function `dwarf_get_string_section_name()` operates on the the `.debug_string[dwo]` section.

If the function succeeds, `*sec_name` is set to a pointer to a string with the object section name and the function returns DW_DLV_OK. Do not free the string whose pointer is returned. For non-Elf objects it is possible the string pointer returned will be NULL or will point to an empty string. It is up to the calling application to recognize this possibility and deal with it appropriately.

If the section does not exist the function returns DW_DLV_NO_ENTRY.

If there is an internal error detected the function returns DW_DLV_ERROR and sets the `*error` pointer.

6.24.2 `dwarf_get_str()`

```
int dwarf_get_str(
    Dwarf_Debug     dbg,
    Dwarf_Off      offset,
    char          **string,
    Dwarf_Signed   *returned_str_len,
    Dwarf_Error   *error)
```

The function `dwarf_get_str()` returns DW_DLV_OK and sets `*returned_str_len` to the length of the string, not counting the null terminator, that begins at the offset specified by `offset` in the `.debug_str` section. The location pointed to by `string` is set to a pointer to this string. The next string in the `.debug_str` section begins at the previous `offset + 1 + *returned_str_len`. A zero-length string is NOT the end of the section. If there is no `.debug_str` section, DW_DLV_NO_ENTRY is returned. If there is an error, DW_DLV_ERROR is returned. If we are at the end of the section (that is, `offset` is one past the end of the section) DW_DLV_NO_ENTRY is returned. If the `offset` is some other too-large value then DW_DLV_ERROR is returned.

6.25 String Offsets Section Operations

The `.debug_str_offsets` section contains only table arrays (with headers) and Debuggers should never need to use this interface. The normal string access functions use the section tables transparently. The functions here are only intended to allow dwarfdump (or the like) print the section completely and to help compiler developers look for bugs in the section.

Figure 41. examplestringoffsets `dwarf_open_str_offsets_table_access()` etc

```
void examplestringoffsets(Dwarf_Debug dbg)
{
    int res = 0;
    Dwarf_Str_Offsets_Table sot = 0;
    Dwarf_Unsigned wasted_byte_count = 0;
    Dwarf_Unsigned table_count = 0;
    Dwarf_Error error = 0;

    res = dwarf_open_str_offsets_table_access(dbg, &sot, &error);
    if(res == DW_DLV_NO_ENTRY) {
        /* No such table */
        return;
    }
    if(res == DW_DLV_ERROR) {
        /* Something is very wrong. Print the error? */
        return;
    }
    for(;;) {
        Dwarf_Unsigned unit_length =0;
        Dwarf_Unsigned unit_length_offset =0;
        Dwarf_Unsigned table_start_offset =0;
        Dwarf_Half      entry_size = 0;
        Dwarf_Half      version =0;
        Dwarf_Half      padding =0;
        Dwarf_Unsigned table_value_count =0;
        Dwarf_Unsigned i = 0;
        Dwarf_Unsigned table_entry_value = 0;

        res = dwarf_next_str_offsets_table(sot,
                                           &unit_length, &unit_length_offset,
                                           &table_start_offset,
                                           &entry_size, &version, &padding,
                                           &table_value_count, &error);
        if (res == DW_DLV_NO_ENTRY) {
            /* We have dealt with all tables */
            break;
        }
        if (res == DW_DLV_ERROR) {
            /* Something badly wrong. Do something. */
            return;
        }
        /* One could call dwarf_str_offsets_statistics to
         * get the wasted bytes so far, but we do not do that
         * in this example. */
        /* Possibly print the various table-related values
         * returned just above. */
    }
}
```

```
    for (i=0; i < table_value_count; ++i) {
        res = dwarf_str_offsets_value_by_index(sot, i,
                                                &table_entry_value, &error);
        if (res != DW_DLV_OK) {
            /* Something is badly wrong. Do something. */
            return;
        }
        /* Do something with the table_entry_value
           at this index. Maybe just print it.
           It is an offset in .debug_str. */
    }
}
res = dwarf_str_offsets_statistics(sot, &wasted_byte_count,
                                   &table_count, &error);
if (res == DW_DLV_OK) {
    /* The wasted byte count is set. Print it or something.
       One hopes zero bytes are wasted.
       Print the table count if one is interested. */
}
res = dwarf_close_str_offsets_table_access(sot, &error);
/* There is little point in checking the return value
   as little can be done about any error. */
sot = 0;
}
```

6.25.1 dwarf_open_str_offsets_table_access()

```
int dwarf_open_str_offsets_table_access(
    Dwarf_Debug dbg,
    Dwarf_Strip_Offsets_Table * table_data,
    Dwarf_Error * error);
```

`dwarf_open_str_offsets_table_access()` creates an opaque struct and returns a pointer to it on success. That struct pointer is used in all subsequent operations on the table. Through the function `dwarf_next_str_offsets_table()` the caller can iterate through each of the per-CU offset tables.

If there is no such section, or if the section is empty the function returns `DW_DLV_NO_ENTRY`.

If there is an error (such as out-of-memory) the function returns `DW_DLV_ERROR` and sets an error value through the `error` pointer.

6.25.2 dwarf_close_str_offsets_table_access()

```
int
dwarf_close_str_offsets_table_access(
    Dwarf_Str_Offsets_Table  table_data,
    Dwarf_Error              * error);
```

On success, `dwarf_close_str_offsets_table_access()` frees any allocated data associated with the struct pointed to by `table_data` and returns `DW_DLV_OK`. It is up to the caller to set the `table_data` pointer to `NULL` if desired. The pointer is unusable at that point and any other calls to libdwarf using that pointer will fail.

It returns `DW_DLV_OK` on error. Any error suggests there is memory corruption or an error in the call. Something serious happened.

It never returns `DW_DLV_NO_ENTRY`, but if it did there would be nothing the caller could do anyway..

If one forgets to call this function the memory allocated will be freed automatically by to call to `dwarf_finish()`, as is true of all other data allocated by libdwarf.

6.25.3 `dwarf_next_str_offsets_table()`

```
int dwarf_next_str_offsets_table(
    Dwarf_Str_Offsets_Table table,
    Dwarf_Unsigned          *unit_length_out,
    Dwarf_Unsigned          *unit_length_offset_out,
    Dwarf_Unsigned          *table_start_offset_out,
    Dwarf_Half               *entry_size_out,
    Dwarf_Half               *version_out,
    Dwarf_Half               *padding_out,
    Dwarf_Unsigned          *table_value_count_out,
    Dwarf_Error              * error);
```

Each call to `dwarf_next_str_offsets_table()` returns the next String Offsets table in the `.debug_str_offsets` section. Typically there would be one such table for each CU in `.debug_info[dwo]` contributing to `.debug_str_offsets`. The `table` contains (internally, hidden) the section offset of the next table.

On success it returns `DW_DLV_OK` and sets various fields representing data about the current table (fields described below).

If there are no more tables it returns `DW_DLV_NO_ENTRY`.

On error it returns `DW_DLV_ERROR` and passes back error details through the `error` pointer.

The returned values are intended to let the caller understand the table header and the table in detail. These pointers are only used if the call returned `DW_DLV_OK`.

`unit_length_out` is set to the `unit_length` of a String Offsets Table Header. Which means it gives the length, in bytes, of the data following the `length` value that belongs to this table.

`unit_length_offset_out` is set to the section offset of the table header.

`table_start_offset_out` is set to the section offset of the array of offsets in this table.

`entry_size_out` is set to the size of a table entry. Which is 4 for 32-bit offsets in this table and 8 for 64-bit offsets in this table.

`version_out` is set to the version number in the table header. The only current valid value is 5.

`padding_out` is set to the 16-bit padding value in the table header. In a correct table header the value is zero.

`table_value_count_out` is set to the number of entries in the array of offsets in this table. Each entry is `entry_size_out` bytes long. Use this value in calling `dwarf_str_offsets_value_by_index()`.

6.25.4 dwarf_str_offsets_value_by_index()

```
int dwarf_str_offsets_value_by_index(
    Dwarf_Str_Offsets_Table sot,
    Dwarf_Unsigned index,
    Dwarf_Unsigned *stroffset,
    Dwarf_Error *error);
```

On success, `dwarf_str_offsets_value_by_index()` returns `DW_DLV_OK` and sets the offset from the array of string offsets in the current table at the input `index`.

Valid index values are zero through `table_value_count_out` - 1

A function is used instead of simply letting callers use pointers as libdwarf correctly handles endianness differences (between the system running libdwarf and the object file being inspected) so offsets can be reported properly.

`DW_DLV_ERROR` is returned on error.

`DW_DLV_NO_ENTRY` is never returned.

6.25.5 dwarf_str_offsets_statistics()

```
int dwarf_str_offsets_statistics(
    Dwarf_Str_Offsets_Table table_data,
    Dwarf_Unsigned * wasted_byte_count,
    Dwarf_Unsigned * table_count,
    Dwarf_Error      * error);
```

Normally called after all tables have been inspected to return (through a pointer) the count of apparently-wasted bytes in the section. It can be called at any point that the `Dwarf_Str_Offsets_Table` pointer is valid.

On error it returns `DW_DLV_ERROR` and sets an error value through the pointer.

`DW_DLV_NO_ENTRY` is never returned.

On success it returns DW_DLV_OK and sets values through the two pointers. Calling just after each table is accessed by `dwarf_next_str_offsets_table()` will reveal the sum of all wasted bytes at that point in iterating through the section.

`table_count` is the count of table headers encountered so far.

By wasted bytes we mean bytes in between tables. libdwarf has no idea whether any apparently-valid table data is in fact useless.

6.26 Address Range Operations

These functions provide information about address ranges. The content is in the `.debug_aranges` section. Address ranges map ranges of pc values to the corresponding compilation-unit die that covers the address range. In the DWARF2,3,4 Standards this is described under "Accelerated Access" "Lookup by Address".

6.26.1 dwarf_get_aranges_section_name()

```
int dwarf_get_aranges_section_name(Dwarf_Debug dbg,
                                   const char ** sec_name,
                                   Dwarf_Error *error)
```

`*dwarf_get_aranges_section_name()` retrieves the object file section name of the applicable aranges section. This is useful for applications wanting to print the name, but of course the object section name is not really a part of the DWARF information. Most applications will probably not call this function. It can be called at any time after the `Dwarf_Debug` initialization is done.

If the function succeeds, `*sec_name` is set to a pointer to a string with the object section name and the function returns DW_DLV_OK. Do not free the string whose pointer is returned. For non-Elf objects it is possible the string pointer returned will be NULL or will point to an empty string. It is up to the calling application to recognize this possibility and deal with it appropriately.

If the section does not exist the function returns DW_DLV_NO_ENTRY.

If there is an internal error detected the function returns DW_DLV_ERROR and sets the `*error` pointer.

6.26.2 dwarf_get_aranges()

```
int dwarf_get_aranges(
    Dwarf_Debug dbg,
    Dwarf_Arange **aranges,
    Dwarf_Signed * returned_arange_count,
    Dwarf_Error *error)
```

The function `dwarf_get_aranges()` returns `DW_DLV_OK` and sets `*returned_arange_count` to the count of the number of address ranges in the `.debug_aranges` section (for all compilation units). It sets `*aranges` to point to a block of `Dwarf_Arange` descriptors, one for each address range. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if there is no `.debug_aranges` section.

This not only reads all the ranges, it also reads the per-compilation-unit headers in `.debug_aranges` and verifies they make sense.

Figure 42. Exampleu dwarf_get_aranges()

```
void exampleu(Dwarf_Debug dbg)
{
    Dwarf_Signed count = 0;
    Dwarf_Arange *arang = 0;
    int res = 0;
    Dwarf_Error error = 0;

    res = dwarf_get_aranges(dbg, &arang, &count, &error);
    if (res == DW_DLV_OK) {
        Dwarf_Signed i = 0;

        for (i = 0; i < count; ++i) {
            /* use arang[i] */
            dwarf_dealloc(dbg, arang[i], DW_DLA_ARANGE);
        }
        dwarf_dealloc(dbg, arang, DW_DLA_LIST);
    }
}
```

6.26.3 dwarf_get_arange()

```
int dwarf_get_arange(
    Dwarf_Arange *aranges,
    Dwarf_Unsigned arange_count,
    Dwarf_Addr address,
    Dwarf_Arange *returned_arange,
    Dwarf_Error *error);
```

The function `dwarf_get_arange()` takes as input a pointer to a block of `Dwarf_Arange` pointers, and a count of the number of descriptors in the block. It then searches for the descriptor that covers the given address. If it finds one, it returns `DW_DLV_OK` and sets `*returned_arange` to the descriptor. It returns `DW_DLV_ERROR` on error. It returns `DW_DLV_NO_ENTRY` if there is no `.debug_aranges` entry covering that address.

6.26.4 dwarf_get_cu_die_offset()

```
int dwarf_get_cu_die_offset(
    Dwarf_Arange arange,
    Dwarf_Off *returned_cu_die_offset,
    Dwarf_Error *error);
```

The function `dwarf_get_cu_die_offset()` takes a `Dwarf_Arange` descriptor as input, and if successful returns `DW_DLV_OK` and sets `*returned_cu_die_offset` to the offset in the `.debug_info` section of the compilation-unit DIE for the compilation-unit represented by the given address range. It returns `DW_DLV_ERROR` on error.

6.26.5 dwarf_get_arange_cu_header_offset()

```
int dwarf_get_arange_cu_header_offset(
    Dwarf_Arange arange,
    Dwarf_Off *returned_cu_header_offset,
    Dwarf_Error *error)
```

The function `dwarf_get_arange_cu_header_offset()` takes a `Dwarf_Arange` descriptor as input, and if successful returns `DW_DLV_OK` and sets `*returned_cu_header_offset` to the offset in the `.debug_info` section of the compilation-unit header for the compilation-unit represented by the given address range. It returns `DW_DLV_ERROR` on error.

This function added Rev 1.45, June, 2001.

This function is declared as 'optional' in `libdwarf.h` on IRIX systems so the `_MIPS_SYMBOL_PRESENT` predicate may be used at run time to determine if the version of `libdwarf` linked into an application has this function.

6.26.6 dwarf_get_arange_info_b()

```
int dwarf_get_arange_info_b(
    Dwarf_Arange arange,
    Dwarf_Unsigned *segment,
    Dwarf_Unsigned *segment_entry_size;
    Dwarf_Addr *start,
    Dwarf_Unsigned *length,
    Dwarf_Off *cu_die_offset,
    Dwarf_Error *error)
```

The function `dwarf_get_arange_info_b()` returns `DW_DLV_OK` and returns detailed information on the address range through the pointers.

segment is the segment number for segmented address spaces and it is only meaningful if segment_entry_size is non-zero.

It puts the starting value of the address range in the location pointed to by start, and the length of the address range in the location pointed to by length.

It sets the cu_die_offset. in the .debug_info, section of the compilation-unit DIE for the compilation-unit represented by the address range.

It returns DW_DLV_ERROR on error. and sets error,

6.26.7 dwarf_get_arange_info()

```
int dwarf_get_arange_info(
    Dwarf_Arange arange,
    Dwarf_Addr *start,
    Dwarf_Unsigned *length,
    Dwarf_Off *cu_die_offset,
    Dwarf_Error *error)
```

This is the same as dwarf_get_arange_info_b() except that this earlier function does not have a way to return the segment information.

6.27 General Low Level Operations

This function is low-level and intended for use only by programs such as dwarf-dumpers.

6.27.1 dwarf_get_offset_size()

```
int dwarf_get_offset_size(Dwarf_Debug dbg,
    Dwarf_Half *offset_size,
    Dwarf_Error *error)
```

The function dwarf_get_offset_size() returns DW_DLV_OK on success and sets the *offset_size to the size in bytes of an offset. In case of error, it returns DW_DLV_ERROR and does not set *offset_size.

The offset size returned is the overall address size, which can be misleading if different compilation units have different address sizes. Many ABIs have only a single address size per executable, but differing address sizes are becoming more common.

6.27.2 dwarf_get_address_size()

```
int dwarf_get_address_size(Dwarf_Debug dbg,
    Dwarf_Half *addr_size,
    Dwarf_Error *error)
```

The function dwarf_get_address_size() returns DW_DLV_OK on success and sets the *addr_size to the size in bytes of an address. In case of error, it returns

DW_DLV_ERROR and does not set *addr_size.

The address size returned is the overall address size, which can be misleading if different compilation units have different address sizes. Many ABIs have only a single address size per executable, but differing address sizes are becoming more common.

Use dwarf_get_die_address_size() instead whenever possible.

6.27.3 dwarf_get_die_address_size()

```
int dwarf_get_die_address_size(Dwarf_Die die,
                               Dwarf_Half *addr_size,
                               Dwarf_Error *error)
```

The function dwarf_get_die_address_size() returns DW_DLV_OK on success and sets the *addr_size to the size in bytes of an address. In case of error, it returns DW_DLV_ERROR and does not set *addr_size.

The address size returned is the address size of the compilation unit owning the die

This is the preferred way to get address size when the Dwarf_Die is known.

6.27.4 dwarf_decode_leb128()

See the DWARF5 standard Section 7.6 for a general description of LEB encoded values.

```
int dwarf_decode_leb128(char* leb,
                        Dwarf_Unsigned* leblen,
                        Dwarf_Unsigned* outval,
                        char* endptr)
```

In December 2020 this makes library decoding visible to library users for the first time.

The user should pass in leb with a pointer to the initial byte of the leb number. and pass in endptr with a pointer at least one-past the content of the leb value. Typically endptr points at an end of section (if reading object sections) or some other value representing the end of memory the function should be allowed to read.

On success the function returns DW_DLV_OK and sets leblen (if leblen passed in non-null) to the number of bytes read in decoding. It sets outval to the unsigned value decoded.

If the function detects it has read to the endptr it returns DW_DLV_ERROR.

If the function reads too many bytes without reaching a terminator or endptr it returns DW_DLV_ERROR on the assumption that nobody would intentionally produce wastefully long LEB data, so something is wrong.

Only the argument leblen may be passed in as NULL, the others must be valid non-null values.

There is no way for the library to determine whether the value is signed or unsigned. The caller must know and call the the correct function.

6.27.5 dwarf_decode_signed_leb128()

See the DWARF5 standard Section 7.6 for a general description of LEB encoded values.

```
int dwarf_decode_signed_leb128(char* leb,
    Dwarf_Unsigned* leblen,
    Dwarf_Signed* outval,
    char* endptr)
```

In December 2020 this makes library decoding visible to library users for the first time.

The user should pass in `leb` with a pointer to the initial byte of the leb number. and pass in `endptr` with a pointer at least one-past the content of the leb value. Typically `endptr` points at an end of section (if reading object sections) or some other value representing the end of memory the function should be allowed to read.

On success the function returns `DW_DLV_OK` and sets `leblen` (if `leblen` passed in non-null) to the number of bytes read in decoding. It sets `outval` to the signed value decoded.

If the function detects it has read to the `endptr` it returns `DW_DLV_ERROR`.

If the function reads too many bytes without reaching a terminator or `endptr` it returns `DW_DLV_ERROR` on the assumption that nobody would intentionally produce wastefully long LEB data, so something is wrong.

Only the argument `leblen` may be passed in as NULL, the others must be valid non-null values.

There is no way for the library to determine whether the value is signed or unsigned. The caller must know and call the the correct function.

6.28 Ranges Operations DWARF5 (.debug_rnglists)

These functions provide information about the address ranges indicated by a `DW_AT_ranges` attribute of a DIE. The ranges are recorded in the `.debug_rnglists` section.

The section requires that each group of ranges has a header and the compilation unit may have a `DW_AT_ranges_base` attribute that must be added to the `DW_AT_ranges` attribute value to get the true ranges offset.

(A compiler generating `DW_AT_ranges_base` will add a relocation for that attribute value but will not have to make the `DW_AT_ranges` attributes relocatable and will thus save space in the object (ie, .o) file and save link time.)

See DWARF5 Section 2.17.3 Non-Contiguous Address Ranges and Section 7.28 Range List Table.

Section 7.28 describes the header fields for a Range List Table. There will usually be many such tables, in some sequence, in the .debug_rnglists section. Here we call each header `Dwarf_Rnglists_Head` (a pointer to an opaque struct).

6.28.1 Getting rnglists data for a DIE

This set of interfaces provides access to the DWARF5 .debug_rnglists entries for a particular DIE. Here is an example using the functions described below:

Figure 43. Example .debug_rnglist for attribute

```
int example_rnglist_for_attribute(Dwarf_Attribute attr,
Dwarf_Unsigned attrvalue,Dwarf_Error *error)
{
    /* attrvalue must be the DW_AT_ranges
       DW_FORM_rnglistx or DW_FORM_sec_offset value
       extracted from attr. */
    int res = 0;
    Dwarf_Half theform = 0;
    Dwarf_Unsigned entries_count;
    Dwarf_Unsigned global_offset_of_rle_set;
    Dwarf_Rnglists_Head rnglhead = 0;
    Dwarf_Unsigned i = 0;

    res = dwarf_rnglists_get_rle_head(attr,
        theform,
        attrvalue,
        &rnglhead,
        &entries_count,
        &global_offset_of_rle_set,
        error);
    if (res != DW_DLV_OK) {
        return res;
    }
    for (i = 0; i < entries_count; ++i) {
        unsigned entrylen      = 0;
        unsigned code          = 0;
        Dwarf_Unsigned rawlowpc = 0;
        Dwarf_Unsigned rawhighpc = 0;
        Dwarf_Unsigned lowpc   = 0;
        Dwarf_Unsigned highpc  = 0;
        Dwarf_Bool debug_addr_unavailable = FALSE;

        /* Actual addresses are most likely what one
           wants to know, not the lengths/offsets
           recorded in .debug_rnglists. */
        res = dwarf_get_rnglists_entry_fields_a(rnglhead,
            i,&entrylen,&code,
            &rawlowpc,&rawhighpc,
            &debug_addr_unavailable,
            &lowpc,&highpc,error);
        if (res != DW_DLV_OK) {
            dwarf_dealloc_rnglists_head(rnglhead);
            return res;
        }
        if (code == DW_RLE_end_of_list) {
```

```
        /* we are done */
        break;
    }
    if (code == DW_RLE_base_addressx || code == DW_RLE_base_address) {
        /* We do not need to use these, they have been accounted for already. */
        continue;
    }
    if (debug_addr_unavailable) {
        /* lowpc and highpc are not real addresses */
        continue;
    }
    /* Here do something with lowpc and highpc, these are real addresses */
}
dwarf_dealloc_rnglists_head(rnglhead);
return DW_DLV_OK;
}
```

6.28.1.1 dwarf_rnglists_get_rle_head()

This function is used to enable access to the specific set of rnglist entries applying to a specific DW_AT_rangees attribute.

```
int dwarf_rnglists_get_rle_head( Dwarf_Attribute attr,
                                Dwarf_Half      theform,
                                Dwarf_Unsigned attr_val,
                                Dwarf_Rnglists_Head *head_out,
                                Dwarf_Unsigned   *entries_count_out,
                                Dwarf_Unsigned   *global_offset_of_rle_set,
                                Dwarf_Error     *error);
```

Given a DW_AT_ranges Dwarf_Attribute, the FORM from that attribute, and the value of the the attribute (which might be an index from DW_FORM_rnglistx or a section offset from DW_FORM_sec_offset the function determines which Dwarf_Rnglists_Head applies and returns the pointer on success (meaning it returned . DW_DLV_OK). And on success it also returns the global offset of a set of rnglist entries within that particular Dwarf_Rnglists_Head (not needed except to show it to users) as well as the count of entries in that set (which is crucial to iterate through the rnglist entries applicable).

If not successful none of the pointers head_out, entries_count_out, global_offset will not be touched by the function.

If there is some problem with the section it will return DW_DLV_ERROR and return the

error information through. *error.

There is, currently, no situation in which it will return DW_DLV_NO_ENTRY.

See dwarf_dealloc_rnglists_head() below to release the storage allocated by a successful call here.

6.28.1.2 dwarf_get_rnglist_head_basics()

```
int dwarf_get_rnglist_head_basics(
    Dwarf_Rnglists_Head head,
    Dwarf_Unsigned * rle_count,
    Dwarf_Unsigned * rle_version,
    Dwarf_Unsigned * rnglists_index_returned,
    Dwarf_Unsigned * bytes_total_in_rle,
    unsigned * offset_size,
    unsigned * address_size,
    unsigned * segment_selector_size,
    Dwarf_Unsigned * overall_offset_of_this_context,
    Dwarf_Unsigned * total_length_of_this_context,
    Dwarf_Bool * rnglists_base_present,
    Dwarf_Unsigned * rnglists_base,
    Dwarf_Bool * rnglists_base_address_present,
    Dwarf_Unsigned * rnglists_base_address,
    Dwarf_Bool * rnglists_debug_addr_base_present,
    Dwarf_Unsigned * rnglists_debug_addr_base,
    Dwarf_Error *error)
```

The function dwarf_get_rnglist_head_basics() allows caller to print or display the fields of the Dwarf_Rnglists_Head that might be of interest for understanding the section data for that Dwarf_Rnglists_Head.

It is not needed to access the rangelist data. It currently returns only DW_DLV_OK.

6.28.1.3 dwarf_get_rnglists_entry_fields_a()

```
int dwarf_get_rnglists_entry_fields_a(
    Dwarf_Rnglists_Head head,
    Dwarf_Unsigned entrynum,
    unsigned *entrylen,
    unsigned *code,
    Dwarf_Unsigned *raw1,
    Dwarf_Unsigned *raw2,
    Dwarf_Bool     *debug_addr_unavailable,
    Dwarf_Unsigned *cooked1,
    Dwarf_Unsigned *cooked2,
    Dwarf_Error    *err)
```

This is the function to access the rnglist entries for this `Dwarf_Rnglists_Head`. Call this with `entrynum` in the normal iteration "i = 0; i < `entries_count`; ++i" where `entries_count` was returned by `dwarf_rnglists_get_rle_head()` through a pointer.

On success `DW_DLV_OK` is returned and the following fields are set through the pointers. The `entrylen` value returned is the length, in bytes, of the single entry's length.

The `code` value returned is the type of entry, `DW_RLE_startx_endx` (see `dwarf.h`).

The `raw1` and `raw2` values returned are the actual values in the rangelist entry (address, length, or index depending). For basename entries both values are set to the single value in the entry (an address or index). For end of list entries neither value is set.

If `debug_addr_unavailable` is returns non-zero then the `cooked1` and `cooked2` values are not set usefully and should be ignored. The issue arises because with dwp/dwo object files the `.debug_addr` section will be in the executable and if the `dwarf_set_tied_dbg()` function was not called to enable access to `.debug_addr` the 'cooked' fields cannot be calculated.

The `cooked1` `cooked2` values returned are the actual addresses in the rangelist entry, after any necessary translation of indexes and offsets and lengths. For non-basename entries these two values are the start and end addresses of the rnglist entry. If and only if `debug_addr_unavailable` returns zero. For basename entries these two values are both the basename address. For end-of-list entries neither value means anything.

If the `entrynum` is out of range, `DW_DLV_NO_ENTRY` is returned.

At present `DW_DLV_ERROR` is never returned, but callers should not assume that will always be true.

6.28.1.4 `dwarf_get_rnglists_entry_fields()`

```
int dwarf_get_rnglists_entry_fields(
    Dwarf_Rnglists_Head head,
    Dwarf_Unsigned entrynum,
    unsigned *entrylen,
    unsigned *code,
    Dwarf_Unsigned *raw1,
    Dwarf_Unsigned *raw2,
    Dwarf_Unsigned *cooked1,
    Dwarf_Unsigned *cooked2,
    Dwarf_Error     *err)
```

This is the same as `dwarf_get_rnglists_entry_fields_a()` except this is missing the `debug_addr_unavailable` argument so it's impossible for callers to know that the cooked values are not calculated. Do not use this function.

6.28.1.5 `dwarf_dealloc_rnglists_head()`

```
int dwarf_dealloc_rnglists_head(Dwarf_Rnglists_Head /*head*/);
```

This frees the storage allocated by the `dwarf_rnglists_get_rle_head()` call that created the `Dwarf_Rnglists_Head` pointer.

It only returns DW_DLV_OK.

6.28.2 Getting raw .debug_rnglists entries

This set of interfaces is to read the (entire) `.debug_rnglists` section without reference to any DIE. As such these can only present the raw data from the file. There is no way in these interfaces to get actual addresses. These might be of interest if you want to know exactly what the compiler output in the `.debug_rnglists` section. "dwarfdump ----print-raw-rnglists" (try adding -v or -vv) makes these calls.

Here is an example using all the following calls.

example_rngl

Figure 44. Examplev `dwarf_get_ranges_a()`

```
int example_raw_rnglist(Dwarf_Debug dbg,Dwarf_Error *error)
{
    Dwarf_Uunsigned count = 0;
    int res = 0;
    Dwarf_Uunsigned i = 0;

    res = dwarf_load_rnglists(dbg,&count,error);
    if (res != DW_DLV_OK) {
        return res;
    }
    for(i =0 ; i < count ; ++i) {
        Dwarf_Uunsigned header_offset = 0;
        Dwarf_Small offset_size = 0;
        Dwarf_Small extension_size = 0;
        unsigned version = 0; /* 5 */
        Dwarf_Small address_size = 0;
        Dwarf_Small segment_selector_size = 0;
        Dwarf_Uunsigned offset_entry_count = 0;
        Dwarf_Uunsigned offset_of_offset_array = 0;
        Dwarf_Uunsigned offset_of_first_rangeentry = 0;
        Dwarf_Uunsigned offset_past_last_rangeentry = 0;

        res = dwarf_get_rnglist_context_basics(dbg,i,
                                                &header_offset,&offset_size,&extension_size,
                                                &version,&address_size,&segment_selector_size,
                                                &offset_entry_count,&offset_of_offset_array,
                                                &offset_of_first_rangeentry,
                                                &offset_past_last_rangeentry,error);
        if (res != DW_DLV_OK) {
            return res;
        }
        {
            Dwarf_Uunsigned e = 0;
            unsigned colmax = 4;
            unsigned col = 0;
            Dwarf_Uunsigned global_offset_of_value = 0;

            for ( ; e < offset_entry_count; ++e) {
                Dwarf_Uunsigned value = 0;
                int resc = 0;

                resc = dwarf_get_rnglist_offset_index_value(dbg,
                                                i,e,&value,
                                                &global_offset_of_value,error);
                if (resc != DW_DLV_OK) {
                    return resc;
                }
            }
        }
    }
}
```

```
        }
        /* Do something */
        col++;
        if (col == colmax) {
            col = 0;
        }
    }

}

{
Dwarf_Unsigned curoffset = offset_of_first_rangeentry;
Dwarf_Unsigned endoffset = offset_past_last_rangeentry;
int rese = 0;
Dwarf_Unsigned ct = 0;

for ( ; curoffset < endoffset; ++ct ) {
    unsigned entrylen = 0;
    unsigned code = 0;
    Dwarf_Unsigned v1 = 0;
    Dwarf_Unsigned v2 = 0;
    rese = dwarf_get_rnglist_rle(dbg,i,
        curoffset,endoffset,
        &entrylen,
        &code,&v1,&v2,error);
    if (rese != DW_DLV_OK) {
        return rese;
    }
    curoffset += entrylen;
    if (curoffset > endoffset) {
        return DW_DLV_ERROR;
    }
}
}

return DW_DLV_OK;
}
```

6.28.2.1 dwarf_load_rnglists()

```
int dwarf_load_rnglists(
    Dwarf_Debug dbg,
    Dwarf_Unsigned *rnglists_count,
    Dwarf_Error *error)
```

On a successful call to `dwarf_load_rnglists()` the function returns `DW_DLV_OK`,

sets *rnglists_count (if and only if rnglists_count is non-null) to the number of distinct section contents that exist. A small amount of data for each Range Line Table is recorded in dbg as a side effect. Normally libdwarf will have already called this, but if an application never requests any .debug_info data the section might not be loaded. If the section is loaded this returns very quickly and will set *rnglists_count just as described in this paragraph.

If there is no .debug_rnglists section in the object file this function returns DW_DLV_NO_ENTRY.

If something is malformed it returns DW_DLV_ERROR and sets *error to the applicable error pointer describing the problem.

There is no dealloc call. Calling dwarf_finish() releases the modest amount of memory recorded for this section as a side effect.

6.28.2.2 dwarf_get_rnglist_context_basics()

```
int dwarf_get_rnglist_context_basics(Dwarf_Debug dbg,
    Dwarf_Unsigned context_index,
    Dwarf_Unsigned * header_offset,
    Dwarf_Small * offset_size,
    Dwarf_Small * extension_size,
    unsigned * version, /* 5 */
    Dwarf_Small * address_size,
    Dwarf_Small * segment_selector_size,
    Dwarf_Unsigned * offset_entry_count,
    Dwarf_Unsigned * offset_of_offset_array,
    Dwarf_Unsigned * offset_of_first_rangeentry,
    Dwarf_Unsigned * offset_past_last_rangeentry,
    Dwarf_Error * /*err*/);
```

On success this returns DW_DLV_OK and returns values through the pointer arguments (other than dbg or error)

A call to dwarf_load_rnglists() that succeeds gets you the count of contexts and dwarf_get_rnglist_context_basics() for any "i >= 0 and i < count" gets you the context values relevant to .debug_rnglists.

Any of the pointer-arguments for returning context values can be passed in as 0 (in which case they will be skipped).

You will want *offset_entry_count so you can call dwarf_get_rnglist_offset_index_value() usefully.

If the context_index passed in is out of range the function returns DW_DLV_NO_ENTRY

At the present time DW_DLV_ERROR is never returned.

6.28.2.3 dwarf_get_rnglist_offset_index_value()

```
int dwarf_get_rnglist_offset_index_value(Dwarf_Debug dbg,
    Dwarf_Unsigned context_index,
    Dwarf_Unsigned offsetentry_index,
    Dwarf_Unsigned * offset_value_out,
    Dwarf_Unsigned * global_offset_value_out,
    Dwarf_Error *error)
```

On success `dwarf_get_rnglist_offset_index_value()` returns DW_DLV_OK, sets `* offset_value_out` to the value in the Range List Table offset array, and sets `* global_offset_value_out` to the section offset (in `.debug_addr`) of the offset value.

Pass in `context_index` exactly as the same field passed to `dwarf_get_rnglist_context_basics()`.

Pass in `offset_entry_index` based on the return field `offset_entry_count` from `dwarf_get_rnglist_context_basics()`, meaning for that `context_index` an $offset_entry_index \geq 0$ and $< offset_entry_count$.

Pass in `offset_entry_count` exactly as the same field passed to `dwarf_get_rnglist_context_basics()`.

If one of the indexes passed in is out of range DW_DLV_NO_ENTRY will be returned and no return arguments touched.

If there is some corruption of DWARF5 data then DW_DLV_ERROR might be returned and `*error` set to the error details.

6.28.2.4 dwarf_get_rnglist_rle()

```
int dwarf_get_rnglist_rle(
    Dwarf_Debug dbg,
    Dwarf_Unsigned contextnumber,
    Dwarf_Unsigned entry_offset,
    Dwarf_Unsigned endoffset,
    unsigned *entrylen,
    unsigned *entry_kind,
    Dwarf_Unsigned *entry_operand1,
    Dwarf_Unsigned *entry_operand2,
    Dwarf_Error *error)
```

On success it returns a single DW_RLE* record (see dwarf.h) fields.

`contextnumber` is the number of the current rnglist context.

`entry_offset` is the section offset (section-global offset) of the next record.

`endoffset` is one past the last entry in this rle context.

*entrylen returns the length in the .debug_rnglists section of the particular record returned. It's used to increment to the next record within this rnglist context.

entrykind returns is the DW_RLE number.

Some record kinds have 1 or 0 operands, most have two operands (the records describing ranges).

If the contextnumber is out of range it will return DW_DLV_NO_ENTRY.

If the .debug_rnglists section is malformed or the entry_offset is incorrect it may return DW_DLV_ERROR.

6.29 Ranges Operations DWARF3,4 (.debug_ranges)

These functions provide information about the address ranges indicated by a DW_AT_ranges attribute (the ranges are recorded in the .debug_ranges section) of a DIE. These functions apply to DWARF3 and DWARF4. Each call of dwarf_get_ranges_a() or dwarf_get_ranges() returns a an array of Dwarf_Ranges structs, each of which represents a single ranges entry. The struct is defined in libdwarf.h.

New in DWARF3, for DWARF3, and DWARF4 the section contains just ranges. The ranges are referenced by DW_AT_ranges attributes in various DIES.

For DWARF5 the section requires that each group of ranges has a header and the compilation unit may have a DW_AT_ranges_base attribute that must be added to the DW_AT_ranges attribute value to get the true ranges offset.

(A compiler generating DW_AT_ranges_base will add a relocation for that attribute value but will not have to make the DW_AT_ranges attributes relocatable and will thus save space in the object (ie, .o) file and link time.)

6.29.1 dwarf_get_ranges_section_name()

```
int dwarf_get_ranges_section_name(Dwarf_Debug dbg,
                                  const char ** sec_name,
                                  Dwarf_Error *error)
```

*dwarf_get_ranges_section_name() retrieves the object file section name of the applicable ranges section. This is useful for applications wanting to print the name, but of course the object section name is not really a part of the DWARF information. Most applications will probably not call this function. It can be called at any time after the Dwarf_Debug initialization is done.

If the function succeeds, *sec_name is set to a pointer to a string with the object section name and the function returns DW_DLV_OK. Do not free the string whose pointer is returned. For non-Elf objects it is possible the string pointer returned will be NULL or will point to an empty string. It is up to the calling application to recognize this

possibility and deal with it appropriately.

If the section does not exist the function returns DW_DLV_NO_ENTRY.

If there is an internal error detected the function returns DW_DLV_ERROR and sets the *error pointer.

6.29.2 dwarf_get_ranges()

This is the original call and it will work fine when all compilation units have the same address_size. There is no die argument to this original version of the function. Other arguments (and deallocation) match the use of dwarf_get_ranges_b() and dwarf_get_ranges_a().

6.29.3 dwarf_get_ranges_a()

This is the same as dwarf_get_ranges_b() except it is missing the finaloffset pointer argument, so when reading DWARF4 split-dwarf GNU extension DIEs it's not possible to know the final offset of the ranges, but few applications will care..

```
int dwarf_get_ranges_a(
    Dwarf_Debug dbg,
    Dwarf_Off offset,
    Dwarf_Die die,
    Dwarf_Ranges **ranges,
    Dwarf_Signed * returned_ranges_count,
    Dwarf_Unsigned * returned_byte_count,
    Dwarf_Error *error)
```

Though missing finaloffset this function works properly and is usable on and DWARF2,3,4 objects.

6.29.4 dwarf_get_ranges_b()

```
int dwarf_get_ranges_b(
    Dwarf_Debug dbg,
    Dwarf_Off offset,
    Dwarf_Die die,
    Dwarf_Off *finaloffset,
    Dwarf_Ranges **ranges,
    Dwarf_Signed * returned_ranges_count,
    Dwarf_Unsigned * returned_byte_count,
    Dwarf_Error *error)
```

The function dwarf_get_ranges_b() returns DW_DLV_OK and sets *returned_ranges_count to the count of the number of address ranges in the

group of ranges in the .debug_ranges section where the DW_AT_ranges attribute gives offset offset. This function is new as of 10 September 2020.

DWARF4 GNU split-dwarf extension ONLY: With a .dwp object and the tied (executable,a.out) involved the actual .debug_ranges offset is determined from the DW_AT_GNU_ranges_base from the tied file and the offset from DW_AT_ranges in the .dwp object and returned through the finaloffset pointer. If finaloffset pointer is null the function ignores it.

If there is no use of the GNU split-dwarf extension to DWARF4 the finaloffset value returned is identical to the offset passed in. If the pointer is null it is ignored by the function.

This function is normally used when one has a DIE with the DW_AT_ranges attribute (whose value is the offset needed). The ranges thus apply to the DIE involved.

See also `dwarf_get_aranges()`,

The offset argument should be the value of a DW_AT_ranges attribute of a Debugging Information Entry.

The die argument should be the value of a Dwarf_Die pointer of a Dwarf_Die with the attribute containing this range set offset. Because each compilation unit has its own address_size field this argument is necessary to correctly read ranges. (Most executables have the same address_size in every compilation unit, but some ABIs allow multiple address sized in an executable). If a NULL pointer is passed in libdwarf assumes a single address_size is appropriate for all ranges records.

On success, The call sets *ranges to point to a block of Dwarf_Ranges structs, one for each address range. If the *returned_byte_count pointer is passed as non-NULL the number of bytes that the returned ranges were taken from is returned through the pointer (for example if the returned_ranges_count is 2 and the pointer-size is 4, then returned_byte_count will be 8). If the *returned_byte_count pointer is passed as NULL the parameter is ignored. The *returned_byte_count is only of use to certain dumper applications, most applications will not use it. The finaloffset pointer is only of use to certain dumper applications, and if null is passed the function ignores the argument.

On error the function returns DW_DLV_ERROR.

It returns DW_DLV_NO_ENTRY if there is no .debug_ranges section or if offset is past the end of the .debug_ranges section.

Figure 45. Examplev dwarf_get_ranges_b()

```
void examplev(Dwarf_Debug dbg,Dwarf_Unsigned offset,Dwarf_Die die)
{
    Dwarf_Signed count = 0;
    Dwarf_Ranges *ranges = 0;
    Dwarf_Unsigned bytes = 0;
    Dwarf_Error error = 0;
    Dwarf_Off finaloffset = 0;
    int res = 0;
    res = dwarf_get_ranges_b(dbg,offset,die,
        &finaloffset, &ranges,&count,&bytes,&error);
    if (res == DW_DLV_OK) {
        Dwarf_Signed i;
        for( i = 0; i < count; ++i ) {
            Dwarf_Ranges *cur = ranges+i;
            /* Use cur. */
            functionusingrange(cur);
        }
        dwarf_ranges_dealloc(dbg,ranges,count);
    }
}
```

6.29.5 dwarf_ranges_dealloc()

```
int dwarf_ranges_dealloc(
    Dwarf_Debug dbg,
    Dwarf_Ranges *ranges,
    Dwarf_Signed range_count,
);
```

The function `dwarf_ranges_dealloc()` takes as input a pointer to a block of `Dwarf_Ranges` array and the number of structures in the block. It frees all the data in the array of structures.

6.30 Gdb Index operations

These functions get access to the fast lookup tables defined by gdb and gcc and stored in the `.gdb_index` section. The section is of sufficient complexity that a number of function interfaces are needed. For additional information see "<https://sourceware.org/gdb/onlinedocs/gdb/>" "Index-Section-Format.html#Index-Section-Format". (We split the url to two pieces so it can fit on the printed page join the pieces to make a usable url).

6.30.1 dwarf_gdbindex_header()

```
int dwarf_gdbindex_header(Dwarf_Debug dbg,
    Dwarf_Gdbindex * gdbindexptr,
    Dwarf_Unsigned * version,
    Dwarf_Unsigned * cu_list_offset,
    Dwarf_Unsigned * types_cu_list_offset,
    Dwarf_Unsigned * address_area_offset,
    Dwarf_Unsigned * symbol_table_offset,
    Dwarf_Unsigned * constant_pool_offset,
    Dwarf_Unsigned * section_size,
    Dwarf_Unsigned * unused_reserved,
    const char ** section_name,
    Dwarf_Error * error);
```

The function `dwarf_gdbindex_header()` takes as input a pointer to a `Dwarf_Debug` structure and returns fields through various pointers.

If the function returns `DW_DLV_NO_ENTRY` there is no `.gdb_index` section and none of the return-pointer argument values are set.

If the function returns `DW_DLV_ERROR` `error` is set to indicate the specific error, but no other return-pointer arguments are touched.

If successful, the function returns `DW_DLV_OK` and other values are set. The other values are set as follows:

The field `*gdbindexptr` is set to an opaque pointer to a `libdwarf_internal` structure used as an argument to other `.gdbindex` functions below.

The remaining fields are set to values that are mostly of interest to a pretty-printer application. See the detailed layout specification for specifics. The values returned are recorded in the `Dwarf_Gdbindex` opaque structure for the other `gdbindex` functions documented below.

The field `*version` is set to the version of the `gdb index header` (2)..

The field `*cu_list_offset` is set to the offset (in the `.gdb_index` section) of the cu-list.

The field `*types_cu_list_offset` is set to the offset (in the `.gdb_index` section) of the types-list.

The field `*address_area_offset` is set to the offset (in the `.gdb_index` section) of the address area.

The field `*symbol_table_offset` is set to the offset (in the `.gdb_index` section) of the symbol table.

The field `*constant_pool_offset` is set to the offset (in the `.gdb_index` section) of the constant pool.

The field `*section_size` is set to the length of the `.gdb_index` section.

The field `*unused_reserved` is set to zero.

The field `*section_name` is set to the Elf object file section name (`.gdb_index`). If a non-Elf object file has such a section the value set might be NULL or might point to an empty string (NUL terminated), so code to account for NULL or empty.

The field `*error` is not set.

Here we show a use of the set of cu_list functions (using all the functions in one example makes it rather too long).

Figure 46. Examplew dwarf_get_gdbindex_header()

```
void examplew(Dwarf_Debug dbg
{
    Dwarf_Gdbindex gindexptr = 0;
    Dwarf_Unsigned version = 0;
    Dwarf_Unsigned cu_list_offset = 0;
    Dwarf_Unsigned types_cu_list_offset = 0;
    Dwarf_Unsigned address_area_offset = 0;
    Dwarf_Unsigned symbol_table_offset = 0;
    Dwarf_Unsigned constant_pool_offset = 0;
    Dwarf_Unsigned section_size = 0;
    Dwarf_Unsigned reserved = 0;
    Dwarf_Error error = 0;
    const char * section_name = 0;
    int res = 0;
    res = dwarf_gdbindex_header(dbg, &gindexptr,
        &version, &cu_list_offset, &types_cu_list_offset,
        &address_area_offset, &symbol_table_offset,
        &constant_pool_offset, &section_size,
        &reserved, &section_name, &error);
    if (res == DW_DLV_NO_ENTRY) {
        return;
    } else if (res == DW_DLV_ERROR) {
        return;
    }
    {
        /* do something with the data */
        Dwarf_Unsigned length = 0;
        Dwarf_Unsigned typeslength = 0;
        Dwarf_Unsigned i = 0;
        res = dwarf_gdbindex_culist_array(gindexptr,
            &length, &error);
        /* Example actions. */
        if (res == DW_DLV_OK) {
            for(i = 0; i < length; ++i) {
                Dwarf_Unsigned cuoffset = 0;
                res = dwarf_gdbindex_culist_entry(gindexptr,
                    i, &cuoffset, &culength, &error);
                if (res == DW_DLV_OK) {
                    /* Do something with cuoffset, culength */
                }
            }
        }
        res = dwarf_gdbindex_types_culist_array(gindexptr,
            &typeslength, &error);
        if (res == DW_DLV_OK) {
            for(i = 0; i < typeslength; ++i) {
```

```
        Dwarf_Unsigned cuoffset = 0;
        Dwarf_Unsigned tuoffset = 0;
        Dwarf_Unsigned culength = 0;
        Dwarf_Unsigned type_signature = 0;
        res = dwarf_gdbindex_types_culist_entry(gindexptr,
            i,&cuoffset,&tuoffset,&type_signature,&error);
        if (res == DW_DLV_OK) {
            /* Do something with cuoffset etc. */
        }
    }
    dwarf_gdbindex_free(gindexptr);
}
}
```

6.30.2 dwarf_gdbindex_culist_array()

```
int dwarf_gdbindex_culist_array(Dwarf_Gdbindex gdbindexptr,
    Dwarf_Unsigned *list_length,
    Dwarf_Error *error);
```

The function `dwarf_gdbindex_culist_array()` takes as input valid `Dwarf_Gdbindex` pointer.

While currently only `DW_DLV_OK` is returned one should test for `DW_DLV_NO_ENTRY` and `DW_DLV_ERROR` and do something sensible if either is returned.

If successful, the function returns `DW_DLV_OK` and returns the number of entries in the culist through the `list_length` pointer.

6.30.3 dwarf_gdbindex_culist_entry()

```
int dwarf_gdbindex_culist_entry(Dwarf_Gdbindex gdbindexptr,
    Dwarf_Unsigned entryindex,
    Dwarf_Unsigned *cu_offset,
    Dwarf_Unsigned *cu_length,
    Dwarf_Error *error);
```

The function `dwarf_gdbindex_culist_entry()` takes as input valid `Dwarf_Gdbindex` pointer and an index into the culist array. Valid indexes are 0 through `list_length - 1`.

If it returns `DW_DLV_NO_ENTRY` there is a coding error. If it returns

DW_DLV_ERROR there is an error of some kind and the error is indicated by the value returned through the `error` pointer.

On success it returns DW_DLV_OK and returns the `cu_offset` (the section global offset of the CU in `.debug_info`) and `cu_length` (the length of the CU in `.debug_info`) values through the pointers.

6.30.4 `dwarf_gdbindex_types_culist_array()`

```
int dwarf_gdbindex_types_culist_array(Dwarf_Gdbindex /*gdbindexptr*/,
Dwarf_Unsigned    /*types_list_length*/,
Dwarf_Error      /*error*/);
```

The function `dwarf_gdbindex_types_culist_array()` takes as input valid `Dwarf_Gdbindex` pointer.

While currently only DW_DLV_OK is returned one should test for DW_DLV_NO_ENTRY and DW_DLV_ERROR and do something sensible if either is returned.

If successful, the function returns DW_DLV_OK and returns the number of entries in the types culist through `list_length`

6.30.5 `dwarf_gdbindex_types_culist_entry()`

```
int dwarf_gdbindex_types_culist_entry(
Dwarf_Gdbindex gdbindexptr,
Dwarf_Unsigned entryindex,
Dwarf_Unsigned * cu_offset,
Dwarf_Unsigned * tu_offset,
Dwarf_Unsigned * type_signature,
Dwarf_Error   * error);
```

The function `dwarf_gdbindex_types_culist_entry()` takes as input valid `Dwarf_Gdbindex` pointer and an index into the types culist array. Valid indexes are 0 through `types_list_length - 1`.

If it returns DW_DLV_NO_ENTRY there is a coding error. If it returns DW_DLV_ERROR there is an error of some kind. and the error is indicated by the value returned through the `error` pointer.

On success it returns DW_DLV_OK and returns the `tu_offset` (the section global offset of the CU in `.debug_types`) and `tu_length` (the length of the CU in `.debug_types`) values through the pointers. It also returns the type signature (a 64bit value) through the `type_signature` pointer.

6.30.6 dwarf_gdbindex_addressarea()

```
int dwarf_gdbindex_addressarea(Dwarf_Gdbindex /*gdbindexptr*/,
    Dwarf_Unsigned      /*addressarea_list_length*/,
    Dwarf_Error         /*error*/);
```

The function `dwarf_addressarea()` takes as input valid `Dwarf_Gdbindex` pointer and returns the length of the address area through `addressarea_list_length`.

If it returns `DW_DLV_NO_ENTRY` there is a coding error. If it returns `DW_DLV_ERROR` there is an error of some kind. and the error is indicated by the value returned through the `error` pointer.

If successful, the function returns `DW_DLV_OK` and returns the number of entries in the address area through the `addressarea_list_length` pointer.

6.30.7 dwarf_gdbindex_addressarea_entry()

```
int dwarf_gdbindex_addressarea_entry(
    Dwarf_Gdbindex gdbindexptr,
    Dwarf_Unsigned entryindex,
    Dwarf_Unsigned * low_address,
    Dwarf_Unsigned * high_address,
    Dwarf_Unsigned * cu_index,
    Dwarf_Error   * error);
```

The function `dwarf_addressarea_entry()` takes as input valid `Dwarf_Gdbindex` pointer and an index into the address area (valid indexes are zero through `addressarea_list_length - 1`).

If it returns `DW_DLV_NO_ENTRY` there is a coding error. If it returns `DW_DLV_ERROR` there is an error of some kind. and the error is indicated by the value returned through the `error` pointer.

If successful, the function returns `DW_DLV_OK` and returns The `low_address` `high_address` and `cu_index` through the pointers.

Given an open `Dwarf_Gdbindex` one uses the function as follows:

Figure 47. Examplewgdbindex dwarf_gdbindex_addressarea()

```
void examplewgdbindex (Dwarf_Gdbindex gdbindex)
{
    Dwarf_Unsigned list_len = 0;
    Dwarf_Unsigned i = 0;
    int res = 0;
    Dwarf_Error err = 0;

    res = dwarf_gdbindex_addressarea(gdbindex, &list_len,&err);
    if (res != DW_DLV_OK) {
        /* Something wrong, ignore the addressarea */
    }
    /* Iterate through the address area. */
    for( i = 0; i < list_len; i++) {
        Dwarf_Unsigned lowpc = 0;
        Dwarf_Unsigned highpc = 0;
        Dwarf_Unsigned cu_index = 0;
        res = dwarf_gdbindex_addressarea_entry(gdbindex,i,
                                               &lowpc,&highpc,
                                               &cu_index,
                                               &err);
        if (res != DW_DLV_OK) {
            /* Something wrong, ignore the addressarea */
            return;
        }
        /* We have a valid address area entry, do something
           with it. */
    }
}
```

6.30.8 dwarf_gdbindex_symboltable_array()

```
int dwarf_gdbindex_symboltable_array(Dwarf_Gdbindex gdbindexptr,
                                     Dwarf_Unsigned      *symtab_list_length,
                                     Dwarf_Error         *error);
```

One can look at the symboltable as a two-level table (with The outer level indexes through symbol names and the inner level indexes through all the compilation units that define that symbol (each symbol having a different number of compilation units, this is not a simple rectangular table).

The function `dwarf_gdbindex_symboltable_array()` takes as input valid `Dwarf_Gdbindex` pointer.

If it returns `DW_DLV_NO_ENTRY` there is a coding error. If it returns `DW_DLV_ERROR` there is an error of some kind. and the error is indicated by the value

returned through the `error` pointer.

If successful, the function returns `DW_DLV_OK` and returns The `syntab_list_length` through the pointer.

Given a valid `Dwarf_Gdbindex` pointer, one can access the entire symbol table as follows (using 'return' here to indicate we are giving up due to a problem while keeping the example code fairly short):

Figure 48. Examplex dwarf_gdbindex_symboltable_array()

```
void examplex(Dwarf_Gdbindex gdbindex)
{
    Dwarf_Unsigned syntab_list_length = 0;
    Dwarf_Unsigned i = 0;
    Dwarf_Error err = 0;
    int res = 0;

    res = dwarf_gdbindex_symboltable_array(gdbindex,
        &syntab_list_length,&err);
    if (res != DW_DLV_OK) {
        return;
    }
    for( i = 0; i < syntab_list_length; i++) {
        Dwarf_Unsigned symnameoffset = 0;
        Dwarf_Unsigned cuvecoffset = 0;
        Dwarf_Unsigned cuvec_len = 0;
        Dwarf_Unsigned ii = 0;
        const char *name = 0;
        res = dwarf_gdbindex_symboltable_entry(gdbindex,i,
            &symnameoffset,&cuvecoffset,
            &err);
        if (res != DW_DLV_OK) {
            return;
        }
        res = dwarf_gdbindex_string_by_offset(gdbindex,
            symnameoffset,&name,&err);
        if(res != DW_DLV_OK) {
            return;
        }
        res = dwarf_gdbindex_cuvector_length(gdbindex,
            cuvecoffset,&cuvec_len,&err);
        if( res != DW_DLV_OK) {
            return;
        }
        for(ii = 0; ii < cuvec_len; ++ii ) {
            Dwarf_Unsigned attributes = 0;
            Dwarf_Unsigned cu_index = 0;
            Dwarf_Unsigned reserved1 = 0;
            Dwarf_Unsigned symbol_kind = 0;
            Dwarf_Unsigned is_static = 0;

            res = dwarf_gdbindex_cuvector_inner_attributes(
                gdbindex,cuvecoffset,ii,
                &attributes,&err);
            if( res != DW_DLV_OK) {
```

```
        return;
    }
    /* 'attributes' is a value with various internal
       fields so we expand the fields. */
    res = dwarf_gdbindex_cuvector_instance_expand_value(gdbindex,
              attributes, &cu_index, &reserved1, &symbol_kind, &is_static,
              &err);
    if( res != DW_DLV_OK) {
        return;
    }
    /* Do something with the attributes. */
}
}
```

6.30.9 dwarf_gdbindex_symboltable_entry()

```
int dwarf_gdbindex_symboltable_entry(
    Dwarf_Gdbindex gdbindexptr,
    Dwarf_Unsigned entryindex,
    Dwarf_Unsigned * string_offset,
    Dwarf_Unsigned * cu_vector_offset,
    Dwarf_Error * error);
```

The function `dwarf_gdbindex_symboltable_entry()` takes as input valid `Dwarf_Gdbindex` pointer and an entry index(valid index values being zero through `syntab_list_length -1`).

If it returns `DW_DLV_NO_ENTRY` there is a coding error. If it returns `DW_DLV_ERROR` there is an error of some kind. and the error is indicated by the value returned through the `error` pointer.

If successful, the function returns `DW_DLV_OK` and returns The `string_offset` and `cu_vector_offset` through the pointers. See the example above which uses this function.

6.30.10 dwarf_gdbindex_cuvector_length()

```
int dwarf_gdbindex_cuvector_length(
    Dwarf_Gdbindex gdbindex,
    Dwarf_Unsigned cuvector_offset,
    Dwarf_Unsigned * innercount,
    Dwarf_Error * error);
```

The function `dwarf_gdbindex_cuvector_length()` takes as input valid `Dwarf_Gdbindex` pointer and an a cu vector offset.

If it returns DW_DLV_NO_ENTRY there is a coding error. If it returns DW_DLV_ERROR there is an error of some kind. and the error is indicated by the value returned through the `error` pointer.

If successful, the function returns DW_DLV_OK and returns the `inner_count` through the pointer. The `inner_count` is the number of compilation unit vectors for this array of vectors. See the example above which uses this function.

6.30.11 `dwarf_gdbindex_cuvector_inner_attributes()`

```
int dwarf_gdbindex_cuvector_inner_attributes(
    Dwarf_Gdbindex gdbindex,
    Dwarf_Unsigned cuvector_offset,
    Dwarf_Unsigned innerindex,
    /* The attr_value is a field of bits. For expanded version
       use dwarf_gdbindex_cuvector_expand_value() */
    Dwarf_Unsigned * attr_value,
    Dwarf_Error * error);
```

The function `dwarf_gdbindex_cuvector_inner_attributes()` takes as input valid `Dwarf_Gdbindex` pointer and an a cu vector offset and a `inner_index` (valid `inner_index` values are zero through `inner_count` - 1).

If it returns DW_DLV_NO_ENTRY there is a coding error. If it returns DW_DLV_ERROR there is an error of some kind. and the error is indicated by the value returned through the `error` pointer.

If successful, the function returns DW_DLV_OK and returns The `attr_value` through the pointer. The `attr_value` is actually composed of several fields, see the next function which expands the value. See the example above which uses this function.

6.30.12 `dwarf_gdbindex_cuvector_instance_expand_value()`

```
int dwarf_gdbindex_cuvector_instance_expand_value(
    Dwarf_Gdbindex gdbindex,
    Dwarf_Unsigned attr_value,
    Dwarf_Unsigned * cu_index,
    Dwarf_Unsigned * reserved1,
    Dwarf_Unsigned * symbol_kind,
    Dwarf_Unsigned * is_static,
    Dwarf_Error * error);
```

The function `dwarf_gdbindex_cuvector_instance_expand_value()` takes as input valid `Dwarf_Gdbindex` pointer and an `attr_value`.

If it returns DW_DLV_NO_ENTRY there is a coding error. If it returns DW_DLV_ERROR there is an error of some kind. and the error is indicated by the value returned through the `error` pointer.

If successful, the function returns DW_DLV_OK and returns the following values through the pointers:

The `cu_index` field is the index in the applicable CU list of a compilation unit. For the purpose of indexing the CU list and the types CU list form a single array so the `cu_index` can be indicating either list.

The `symbol_kind` field is a small integer with the symbol kind(zero is reserved, one is a type, 2 is a variable or enum value, etc).

The `reserved1` field should have the value zero and is the value of a bit field defined as reserved for future use.

The `is_static` field is zero if the CU indexed is global and one if the CU indexed is static.

See the example above which uses this function.

6.30.13 dwarf_gdbindex_string_by_offset()

```
int dwarf_gdbindex_string_by_offset(
    Dwarf_Gdbindex    gdbindexptr,
    Dwarf_Unsigned    stringoffset,
    const char        ** string_ptr,
    Dwarf_Error       * error);
```

The function `dwarf_gdbindex_string_by_offset()` takes as input valid `Dwarf_Gdbindex` pointer and a `stringoffset`. If it returns `DW_DLV_NO_ENTRY` there is a coding error. If it returns `DW_DLV_ERROR` there is an error of some kind. and the error is indicated by the value returned through the `error` pointer.

If it succeeds, the call returns a pointer to a string from the 'constant pool' through the `string_ptr`. The string pointed to must never be free()'ed.

See the example above which uses this function.

6.31 GNU linking (.gnu_debuglink, .note.gnu.build-id) operations

This section deals with the way GNU tools allow creation of DWARF separated from the executable file involved. See <https://sourceware.org/gdb/onlinedocs/gdb/Separate-Debug-Files.html> for more information. The function here is new in September 2019, revised in October 2020. An example of use follows the description of arguments.

These functions are concerned with finding DWARF data in a companion file. There is no Split-Dwarf involved, this is a different way of splitting DWARF out of an executable or shared object.. It never applies to simple .o object files, only to executable objects (or shared libraries).

6.31.1 dwarf_gnu_debuglink()

```
int dwarf_gnu_debuglink (Dwarf_Debug dbg,
    char **debuglink_path_returned,
    unsigned char **crc_returned,
    char **debuglink_fullpath_returned,
    unsigned *builid_type returned,
    char **builid_returned,
    unsigned *builid_length_returned,
    char ***paths_returned,
    unsigned *paths_count_returned,
    Dwarf_Error* error);
```

This returns DW_DLV_NO_ENTRY if there is neither a .gnu_debuglink object-file section nor a .note.gnu.build-id section in the object file.

If there is an error it returns DW_DLV_ERROR and sets *error to point to the error value.

On success it returns DW_DLV_OK and sets the fields through the pointers as described below. Two fields must be free()'d to avoid a memory leak. None of the other fields should be freed.

If there is a .gnu_debuglink section the first four fields will be set.

*debuglink_path_returned points to the null-terminated string in the section. Do not free this. The bytes are in the object itself and the pointer is invalid once dwarf_finish() is run on the dbg.

*crc_returned points to a 4-byte CRC value. The bytes pointed to are not a string.

*debuglink_fullpath_returned points to a full pathname derived from the *debuglink_fullpath_returned string. And then
*debuglink_fullpath_strlen is set to the length of
*debuglink_fullpath_returned just as strlen() would count the length.
Callers must free() *debuglink_fullpath_returned.

If there is a .note.gnu.build-id section the builid fields will be set through the pointers.

*builid_type_returned will be set to the value 3.

*builid_owner_name_returned will be set to point to the null-terminated string which will be "GNU". Do not free() this. The bytes are in the object itself and the

pointer is invalid once dwarf_finish() is run on the dbg.

*builddid_returned will be set to point to the group of bytes of length *builddid_length_returned. This is not a string and is not null-terminated. It is normally a 20-byte field to be used in its ascii-hex form. Do not free() this. The bytes are in the object itself and the pointer is invalid once dwarf_finish() is run on the dbg.

If *paths_returned is passed as NULL then no paths calculation will be made and *paths_count_returned is not referenced by libdwarf.

If *paths_returned is passed in non-NULL then *paths_returned and *paths_count_returned provide an array of pointers-to-strings (with the actual strings following the array) and the count of the pointers in the array. When the strings are no longer needed free() *paths_returned. The number of paths returned will depend on which (of the two) sections exist and on how many global paths have been set by dwarf_add_debuglink_global_path(). and defined by the rules described in the web page mentioned above. The default global path is "/usr/lib/debug" and that is set by libdwarf as paths_returned[0].

An example of calling this function follows

Figure 49. Example debuglink()

```
void exampledebuglink (Dwarf_Debug dbg)
{
    int      res = 0;
    char    *debuglink_path = 0;
    unsigned char *crc = 0;
    char    *debuglink_fullpath = 0;
    unsigned debuglink_fullpath_strlen = 0;
    unsigned buildid_type = 0;
    char *   buildidowner_name = 0;
    unsigned char *buildid_itself = 0;
    unsigned buildid_length = 0;
    char **  paths = 0;
    unsigned paths_count = 0;
    Dwarf_Error error = 0;
    unsigned i = 0;

    /* This is just an example if one knows
       of another place full-DWARF objects
       may be. "/usr/lib/debug" is automatically
       set. */
    res = dwarf_add_debuglink_global_path(dbg,
                                           "/some/path/debug",&error);
    if (res != DW_DLV_OK) {
        /* Something is wrong, but we'll ignore
           that. */
    }

    res = dwarf_gnu_debuglink(dbg,
                             &debuglink_path,
                             &crc,
                             &debuglink_fullpath,
                             &debuglink_fullpath_strlen,
                             &buildid_type,
                             &buildidowner_name,
                             &buildid_itself,
                             &buildid_length,
                             &paths,
                             &paths_count,
                             &error);
    if (res == DW_DLV_ERROR) {
        /* Do something with the error */
        return;
    }
    if (res == DW_DLV_NO_ENTRY) {
        /* No such sections as .note.gnu.build-id
```

```
        or .gnu_debuglink */  
    return;  
}  
if (debuglink_fullpath_strlen) {  
    printf("debuglink      path: %s\n", debuglink_path);  
    printf("crc length      : %u  crc: ", 4);  
    for (i = 0; i < 4; ++i) {  
        printf("%02x", crc[i]);  
    }  
    printf("\n");  
    printf("debuglink fullpath: %s\n", debuglink_fullpath);  
}  
if (buildid_length) {  
    printf("buildid type      : %u\n", buildid_type);  
    printf("Buildid owner      : %s\n", buildidowner_name);  
    printf("buildid byte count: %u\n", buildid_length);  
    printf(" ");  
    /* buildid_length should be 20. */  
    for (i = 0; i < buildid_length; ++i) {  
        printf("%02x", buildid_itself[i]);  
    }  
    printf("\n");  
}  
printf("Possible paths count %u\n", paths_count);  
for ( ; i < paths_count; ++i) {  
    printf("%2u: %s\n", i, paths[i]);  
}  
free(debuglink_fullpath);  
free(paths);  
return;  
}
```

6.31.2 dwarf_add_debuglink_global_path()

```
int dwarf_add_debuglink_global_path(Dwarf_Debug dbg,  
                                    const char * path,  
                                    Dwarf_Error* error);
```

This is unlikely to return DW_DLV_ERROR unless one passes in a NULL instead of an open Dwarf_Debug. It cannot return DW_DLV_NO_ENTRY.

On success it returns DW_DLV_OK after adding the path to the global list recorded in the Dwarf_Debug.

6.31.3 dwarf_crc32()

```
int dwarf_crc32(Dwarf_Debug dbg,
                 unsigned char * crc_buf,
                 Dwarf_Error* error);
```

The caller must pass the address of a 4 byte array of unsigned char in `crc_buf`. And the `Dwarf_Debug` must have been opened with `dwarf_init_path()` to be useful. If the executable is named `executable` the file containing most of the DWARF data would often be `executable.debug`. This is normally called from libdwarf code on opening `executable` and libdwarf may call this function on `executable.debug`. Library users could would likely never call it.

On success it returns `DW_DLV_OK` and sets the 4 bytes pointed to by `crc_buf` to the calculated CRC value.

If it returns `DW_DLV_NO_ENTRY` or `DW_DLV_ERROR` something went wrong and `crc_buf` is not touched.

The function was added October 2020.

6.31.4 dwarf_basic_crc32()

```
unsigned int dwarf_crc32(const unsigned char *buf,
                         int len,
                         unsigned int init);
```

This computes the crc on `buf` of length `len` with initial value `init`. See libdwarf source for the details of calling this. It is not likely useful for library uses to call this directly.

The function was added October 2020.

6.32 DWARF5 .debug_sup section access

The `.debug_sup` section is new in DWARF5 and this function returns all the data in that section. The section enables splitting off some DWARF5 information to a separate file, enabling a debugger to find the file, and ensuring the file found actually matches. See the DWARF5 standard.

6.32.1 dwarf_get_debug_sup()

```
int dwarf_get_debug_sup(Dwarf_Debug dbg,
    Dwarf_Half      * version,
    Dwarf_Small     * is_supplementary,
    char           ** filename,
    Dwarf_Unsigned * checksum_len,
    Dwarf_Small    ** checksum,
    Dwarf_Error* error);
```

On success it returns DW_DLV_OK and sets values through the pointer fields (other than `error`). If any of the pointer fields are NULL those pointers are ignored. There is nothing resulting from this call to free or dealloc.

The pointer values are as follows:

`version` is defined to be 2, and any other value is an error (libdwarf does not indicate an error).

`is_supplementary` is a flag and only 0 or 1 should be present. and any other value is an error, though libdwarf does not indicate an error.

`filename` is a null-terminated string.

`checksum_len` is the length, in bytes, of the data `checksum` points to.

If there is no `.debug_sup` section or if that is empty DW_DLV_NO_ENTRY is returned.

On error (for example, if a field runs off the end of the section due to data corruption) DW_DLV_ERROR is returned and `*error` returns the error information as is standard in libdwarf.

6.33 Debug Fission (`.debug_tu_index`, `.debug_cu_index`) operations

We name things "xu" as these sections have the same format so we let "x" stand for either section. The DWARF5 standard refers to Split Dwarf while libdwarf tends to refer to this as "Fission".

These functions get access to the index functions needed to access and print the contents of an object file which is an aggregate of .dwo objects. These sections are implemented in gcc/gdb and are DWARF5. The idea is that much debug information can be separated off into individual .dwo Elf objects and then aggregated simply into a single .dwp object so the executable need not have the complete debug information in it at runtime yet allow good debugging.

For additional information, see "<https://gcc.gnu.org/wiki/DebugFissionDWP>", "<https://gcc.gnu.org/wiki/DebugFission>", and "<http://www.bayarea.net/~cary/dwarf/Accelerated%20Access%20Diagram.png>" and as of 17 February 2017, the DWARF5 standard.

There are FORM access functions related to Debug Fission (Split Dwarf). See `dwarf_formaddr()` and `dwarf_get_debug_addr_index()` and `dwarf_get_debug_str_index()`.

The FORM with the hash value (for a reference to a type unit) is DW_FORM_ref_sig8.

In a compilation unit of Debug Fission object (or a .dwp Package File) DW_AT_dwo_id the hash is expected to be DW_FORM_data8.

The DWARF5 standard defines the hash as an 8 byte value which we could use Dwarf_Unsigned. Instead (and mostly for type safety) we define the value as a structure whose type name is Dwarf_Sig8.

To look up a name in the hash (to find which CU(s) it exists in). use dwarf_get_debugfission_for_key(), defined below.

The second group of interfaces here beginning with dwarf_get_xu_index_header() are useful if one wants to print a .debug_tu_index or .debug_cu_index section.

To access DIE, macro, etc information the support is built into DIE, Macro, etc operations so applications usually won't need to use these operations at all.

6.33.1 Dwarf_Debug_Fission_Per CU

```
#define DW_FISSION_SECT_COUNT 12
struct Dwarf_Debug_Fission_Per_CU_s {
    /* Do not free the string. It contains "cu" or "tu". */
    /* If this is not set (ie, not a CU/TU in DWP Package File)
       then pcu_type will be NULL. */
    const char * pcu_type;
    /* pcu_index is the index (range 1 to N )
       into the tu/cu table of offsets and the table
       of sizes. 1 to N as the zero index is reserved
       for special purposes. Not a value one
       actually needs. */
    Dwarf_Unsigned pcu_index;
    Dwarf_Sig8 pcu_hash; /* 8 byte */
    /* [0] has offset and size 0.
       [1]-[8] are DW_SECT_* indexes and the
       values are the offset and size
       of the respective section contribution
       of a single .dwo object. When pcu_size[n] is
       zero the corresponding section is not present. */
    Dwarf_Unsigned pcu_offset[DW_FISSION_SECT_COUNT];
    Dwarf_Unsigned pcu_size[DW_FISSION_SECT_COUNT];
    Dwarf_Unsigned unused1;
    Dwarf_Unsigned unused2;
};
```

The structure is used to return data to callers with the data from either .debug_tu_index or

.debug_cu_index that is applicable to a single compilation unit or type unit.

Callers to the applicable functions (see below) should allocate the structure and zero all the bytes in it. The structure has a few fields that are presently unused. These are reserved for future use since it is impossible to alter the structure without breaking binary compatibility.

6.33.2 dwarf_die_from_hash_signature()

```
int dwarf_die_from_hash_signature(Dwarf_Debug dbg,
    Dwarf_Sig8 * hash_sig,
    const char * sig_type,
    Dwarf_Die* returned_die,
    Dwarf_Error* error);
```

The function `dwarf_die_from_hash_signature()` is the most direct way to go from the hash data from a `DW_FORM_ref_sig8` or a `DW_AT_dwo_id` (form `DW_FORM_data8`) to a DIE from a .dwp package file or a .dwo object file (.dwo access not supported yet).

The caller passes in `dbg` which should be `Dwarf_Debug` open-initialized on a .dwp package file (or a .dwo object file).

The caller also passes in `hash_sig`, a pointer to the hash signature for which the caller wishes to find a DIE.

The caller also passes in `sig_type` which must contain either "tu" (identifying the hash referring to a type unit) or "cu" (identifying the hash as referring to a compilation unit).

On success the function returns `DW_DLV_OK` and sets `*returned_die` to be a pointer to a valid DIE for the compilation unit or type unit. If the type is "tu" the DIE returned is the specific type DIE that the hash refers to. If the type is "cu" the DIE returned is the compilation unit DIE of the compilation unit referred to.

When appropriate the caller should free the space of the returned DIE by a call something like

```
dwarf_dealloc(dbg,die,DW_DLA_DIE);
```

If there is no DWP Package File section or the hash cannot be found the function returns `DW_DLV_NO_ENTRY` and leaves `returned_die` untouched. Only .dwo objects and .dwp package files have the package file index sections.

If there is an error of some sort the function returns `DW_DLV_ERROR`, leaves `returned_die` untouched, and sets `*error` to indicate the precise error encountered.

6.33.3 dwarf_get_debugfission_for_die()

```
int dwarf_get_debugfission_for_die(Dwarf_Die die,
    Dwarf_Debug_Fission_Per_CU * percu_out,
    Dwarf_Error * error);
```

The function `dwarf_get_debugfission_for_die()` returns the debug fission for the compilation unit the DIE is a part of. Any DIE in the compilation (or type) unit will get the same result.

On a call to this function ensure the pointed-to space is fully initialized.

On success the function returns `DW_DLV_OK` and fills in the fields of `*percu_out` for which it has data.

If there is no DWP Package File section the function returns `DW_DLV_NO_ENTRY` and leaves `*percu_out` untouched. Only .dwp package files have the package file index sections.

If there is an error of some sort the function returns `DW_DLV_ERROR`, leaves `*percu_out` untouched, and sets `*error` to indicate the precise error encountered.

6.33.4 dwarf_get_debugfission_for_key()

```
int dwarf_get_debugfission_for_key(Dwarf_Debug dbg,
    Dwarf_Sig8 * key,
    const char * key_type,
    Dwarf_Debug_Fission_Per_CU * percu_out,
    Dwarf_Error * error);
```

The function `dwarf_get_debugfission_for_key()` returns the debug fission data for the compilation unit in a .dwp package file.

If there is no DWP Package File section the function returns `DW_DLV_NO_ENTRY` and leaves `*percu_out` untouched. Only .dwp package files have the package file index sections.

If there is an error of some sort the function returns `DW_DLV_ERROR`, leaves `*percu_out` untouched, and sets `*error` to indicate the precise error encountered.

6.33.5 dwarf_get_xu_index_header()

```
int dwarf_get_xu_index_header(Dwarf_Debug dbg,
    const char * section_type, /* "tu" or "cu" */
    Dwarf_Xu_Index_Header * xuhdr,
    Dwarf_Unsigned * version_number,
    Dwarf_Unsigned * offsets_count /* L*/,
    Dwarf_Unsigned * units_count /* N*/,
    Dwarf_Unsigned * hash_slots_count /* M*/,
    const char ** sect_name,
    Dwarf_Error * err);
```

The function `dwarf_get_xu_index_header()` takes as input a valid `Dwarf_Debug` pointer and an `section_type` value, which must one of the strings `tu` or `cu`.

It returns `DW_DLV_NO_ENTRY` if the section requested is not in the object file.

It returns `DW_DLV_ERROR` there is an error of some kind. and the error is indicated by the value returned through the `error` pointer.

If successful, the function returns `DW_DLV_OK` and returns the following values through the pointers:

The `xuhdr` field is a pointer usable in other operations (see below).

The `version_number` field is a the index version number. For gcc before DWARF5 the version number is 2. For DWARF5 the version number is 5.

The `offsets_count` field is a the number of columns in the table of section offsets. Sometimes known as `L`.

The `units_count` field is a the number of compilation units or type units in the index. Sometimes known as `N`.

The `hash_slots_count` field is a the number of slots in the hash table. Sometimes known as `M`.

The `sect_name` field is the name of the section in the object file. Because non-Elf objects may not use section names callers must recognize that the `sect_name` may be set to `NULL` (zero) or to point to the empty string and this is not considered an error.

An example of initializing and disposing of a `Dwarf_Xu_Index_Header` follows.

Figure 50. Exampley dwarf_get_xu_index_header()

```
void exampley(Dwarf_Debug dbg, const char *type)
{
    /* type is "tu" or "cu" */
    int res = 0;
    Dwarf_Xu_Index_Header xuhdr = 0;
    Dwarf_Unsigned version_number = 0;
    Dwarf_Unsigned offsets_count = 0; /*L */
    Dwarf_Unsigned units_count = 0; /* M */
    Dwarf_Unsigned hash_slots_count = 0; /* N */
    Dwarf_Error err = 0;
    const char * section_name = 0;

    res = dwarf_get_xu_index_header(dbg,
        type,
        &xuhdr,
        &version_number,
        &offsets_count,
        &units_count,
        &hash_slots_count,
        &section_name,
        &err);
    if (res == DW_DLV_NO_ENTRY) {
        /* No such section. */
        return;
    }
    if (res == DW_DLV_ERROR) {
        /* Something wrong. */
        return;
    }
    /* Do something with the xuhdr here . */
    dwarf_xu_header_free(xuhdr);
}
```

6.33.6 dwarf_get_xu_index_section_type()

```
int dwarf_get_xu_index_section_type(
    Dwarf_Xu_Index_Header xuhdr,
    const char ** typename,
    const char ** sectionname,
    Dwarf_Error * error);
```

The function `dwarf_get_xu_section_type()` takes as input a valid `Dwarf_Xu_Index_Header`. It is only useful when one already has an open `xuhdr` but one does not know if this is a type unit or compilation unit index section.

If it returns `DW_DLV_NO_ENTRY` something is wrong (should never happen). If it returns `DW_DLV_ERROR` something is wrong and the `error` field is set to indicate a

specific error.

If successful, the function returns DW_DLV_OK and sets the following arguments through the pointers:

`typename` is set to the string `tu` or `cu` to indicate the index is of a type unit or a compilation unit, respectively.

`sectionname` is set to name of the object file section. Because non-Elf objects may not use section names callers must recognize that the `sect_name` may be set to NULL (zero) or to point to the empty string and this is not considered an error.

Neither string should be free()'d.

6.33.7 dwarf_get_xu_header_free()

```
void dwarf_xu_header_free(Dwarf_Xu_Index_Header xuhdr);
```

The function `dwarf_get_xu_header_free()` takes as input a valid `Dwarf_Xu_Index_Header` and frees all the special data allocated for this access type. Once called, any pointers returned by use of the `xuhdr` should be considered stale and unusable.

6.33.8 dwarf_get_xu_hash_entry()

```
int dwarf_get_xu_hash_entry(
    Dwarf_Xu_Index_Header xuhdr,
    Dwarf_Unsigned      index,
    Dwarf_Sig8          * hash_value,
    Dwarf_Unsigned      * index_to_sections,
    Dwarf_Error         * error);
```

The function `dwarf_get_xu_hash_entry()` takes as input a valid `Dwarf_Xu_Index_Header` and an `index` of a hash slot entry (valid hash slot index values are zero (0) through `hash_slots_count -1` ($M-1$)).

If it returns DW_DLV_NO_ENTRY something is wrong

If it returns DW_DLV_ERROR something is wrong and the `error` field is set to indicate a specific error.

If successful, the function returns DW_DLV_OK and sets the following arguments through the pointers:

`hash_value` is set to the 64bit hash of of the symbol name.

`index_to_sections` is set to the index into offset-size tables of this hash entry.

If both `hash_value` and `index_to_sections` are zero (0) then the hash slot is unused. `index_to_sections` is used in calls to the function `dwarf_get_xu_section_offset()` as the `row_index`.

An example of use follows.

Figure 51. Examplez dwarf_get_xu_hash_entry()

```
void examplez( Dwarf_Xu_Index_Header xuhdr,
               Dwarf_Unsigned hash_slots_count)
{
    /* hash_slots_count returned by
       dwarf_get_xu_index_header(), see above. */
    static Dwarf_Sig8 zerohashval;

    Dwarf_Error err = 0;
    Dwarf_Unsigned h = 0;

    for( h = 0; h < hash_slots_count; h++) {
        Dwarf_Sig8 hashval;
        Dwarf_Unsigned index = 0;
        int res = 0;

        res = dwarf_get_xu_hash_entry(xuhdr,h,
                                      &hashval,&index,&err);
        if (res == DW_DLV_ERROR) {
            /* Oops. hash_slots_count wrong. */
            return;
        } else if (res == DW_DLV_NO_ENTRY) {
            /* Impossible */
            return;
        } else if (!memcmp(&hashval,&zerohashval,
                           sizeof(Dwarf_Sig8))
                   && index == 0 ) {
            /* An unused hash slot */
            continue;
        }
        /* Here, hashval and index (a row index into
           offsets and lengths) are valid.
           But the row to be passed into
           various functions here is index-1. */
    }
}
```

6.33.9 dwarf_get_xu_section_names()

```
int dwarf_get_xu_section_names(
    Dwarf_Xu_Index_Header xuhdr,
    Dwarf_Unsigned    column_index,
    Dwarf_Unsigned*   number,
    const char **     name,
    Dwarf_Error *     err);
```

The function `dwarf_get_xu_section_names()` takes as input a valid `Dwarf_Xu_Index_Header` and a `column_index` of a hash slot entry (valid `column_index` values are zero (0) through `offsets_count -1 (L-1)`).

If it returns `DW_DLV_NO_ENTRY` something is wrong

If it returns `DW_DLV_ERROR` something is wrong and the `error` field is set to indicate a specific error.

If successful, the function returns `DW_DLV_OK` and sets the following arguments through the pointers:

`number` is set to a number identifying which section this column applies to. For example, if the value is `DW_SECT_INFO` (1) the column came from a `.debug_info.dwo` section. See the table of `DW_SECT_` identifiers and assigned numbers in DWARF5.

`name` is set to the applicable spelling of the section identifier, for example `DW_SECT_INFO`.

6.33.10 `dwarf_get_xu_section_offset()`

```
int dwarf_get_xu_section_offset(
    Dwarf_Xu_Index_Header xuhdr,
    Dwarf_Unsigned    row_index,
    Dwarf_Unsigned    column_index,
    Dwarf_Unsigned*   sec_offset,
    Dwarf_Unsigned*   sec_size,
    Dwarf_Error *     error);
```

The function `dwarf_get_xu_section_offset()` takes as input a valid `Dwarf_Xu_Index_Header` and a `row_index` (see `dwarf_get_xu_hash_entry()` above) and a `column_index`.

Valid `row_index` values are zero (0) through `units_count-1 (N)` but one uses `dwarf_get_xu_hash_entry()` (above) to get row index and it returns a 1-origin index as that is what the DWARF5 standard specifies. Since a zero index from `dwarf_get_xu_hash_entry()` means this is not an actual entry such must be skipped.

Hence it makes (some) sense to subtract one making a zero-origin as that is the sense of all but the first row of the offsets table.

Valid `column_index` values are zero (0) through `offsets_count -1 (L-1)`.

If it returns DW_DLV_NO_ENTRY something is wrong.

If it returns DW_DLV_ERROR something is wrong and the `error` field is set to indicate a specific error.

If successful, the function returns DW_DLV_OK and sets the following arguments through the pointers:

`sec_offset`, (`base_offset`) is set to the base offset of the initial compilation-unit-header section taken from a .dwo object. The base offset is the data from a single section of a .dwo object.

`sec_size` is set to the length of the original section taken from a .dwo object. This is the length in the applicable section in the .dwp over which the base offset applies.

An example of use of `dwarf_get_xu_section_names()` and `dwarf_get_xu_section_offset()` follows.

Figure 52. Exampleza dwarf_get_xu_section_names()

```
void exampleza(Dwarf_Xu_Index_Header xuhdr,
               Dwarf_Unsigned offsets_count, Dwarf_Unsigned index )
{
    Dwarf_Error err = 0;
    Dwarf_Unsigned col = 0;
    /* We use 'offsets_count' returned by
       a dwarf_get_xu_index_header() call.
       We use 'index' returned by a
       dwarf_get_xu_hash_entry() call. */
    for (col = 0; col < offsets_count; col++) {
        Dwarf_Unsigned off = 0;
        Dwarf_Unsigned len = 0;
        const char * name = 0;
        Dwarf_Unsigned num = 0;
        int res = 0;

        res = dwarf_get_xu_section_names(xuhdr,
                                         col,&num,&name,&err);
        if (res != DW_DLV_OK) {
            break;
        }
        res = dwarf_get_xu_section_offset(xuhdr,
                                         index-1,col,&off,&len,&err);
        if (res != DW_DLV_OK) {
            break;
        }
        /* Here we have the DW_SECT_ name and number
           and the base offset and length of the
           section data applicable to the hash
           that got us here.
           Use the values.*/
    }
}
```

6.34 TAG ATTR etc names as strings

These functions turn a value into a string. So applications wanting the string "DW_TAG_compile_unit" given the value 0x11 (the value defined for this TAG) can do so easily.

The general form is

```
int dwarf_get_<something>_name (
    unsigned value,
    char **s_out,
);
```

If the `value` passed in is known, the function returns `DW_DLV_OK` and places a pointer to the appropriate string into `*s_out`. The string is in static storage and applications must never free the string. If the `value` is not known, `DW_DLV_NO_ENTRY` is returned and `*s_out` is not set. `DW_DLV_ERROR` is never returned.

Libdwarf generates these functions at libdwarf build time by reading `dwarf.h`.

All these follow this pattern rigidly, so the details of each are not repeated for each function.

The choice of 'unsigned' for the `value` type argument (the code value) argument is somewhat arbitrary, 'int' could have been used.

The library simply assumes the `value` passed in is applicable. So, for example, passing a TAG value code to `dwarf_get_ACCESS_name()` is a coding error which libdwarf will process as if it was an accessibility code value. Examples of bad and good usage are:

Figure 53. Examplezb `dwarf_get_TAG_name()`

```
void examplezb(void)
{
    const char * out = 0;
    int res = 0;

    /* The following is wrong, do not do it! */
    res = dwarf_get_ACCESS_name(DW_TAG_entry_point,&out);
    /* Nothing one does here with 'res' or 'out'
       is meaningful. */

    /* The following is meaningful.*/
    res = dwarf_get_TAG_name(DW_TAG_entry_point,&out);
    if( res == DW_DLV_OK) {
        /* Here 'out' is a pointer one can use which
           points to the string "DW_TAG_entry_point". */
    } else {
        /* Here 'out' has not been touched, it is
           uninitialized. Do not use it. */
    }
}
```

6.34.1 dwarf_get_ACCESS_name()

Returns an accessibility code name through the s_out pointer.

6.34.2 dwarf_get_AT_name()

Returns an attribute code name through the s_out pointer.

6.34.3 dwarf_get_ATE_name()

Returns a base type encoding name through the s_out pointer.

6.34.4 dwarf_get_ADDR_name()

Returns an address type encoding name through the s_out pointer. As of this writing only DW_ADDR_none is defined in dwarf.h.

6.34.5 dwarf_get_ATCF_name()

Returns a SUN code flag encoding name through the s_out pointer. This code flag is entirely a DWARF extension.

6.34.6 dwarf_get_CHILDREN_name()

Returns a child determination name (which is seen in the abbreviations section data) through the s_out pointer. The only value this recognizes for a 'yes' value is 1. As a flag value this is not quite correct (any non-zero value means yes) but dealing with this is left up to client code (normally compilers really do emit a value of 1 for a flag).

6.34.7 dwarf_get_children_name()

Returns a child determination name through the s_out pointer, though this version is really a libdwarf artifact. The standard function is dwarf_get_CHILDREN_name() which appears just above. As a flag value this is not quite correct (any non-zero value means yes) but dealing with this is left up to client code (normally compilers really do emit a value of 1 for a flag).

6.34.8 dwarf_get_CC_name()

Returns a calling convention case code name through the s_out pointer.

6.34.9 dwarf_get_CFA_name()

Returns a call frame information instruction name through the s_out pointer.

6.34.10 dwarf_get_DS_name()

Returns a decimal sign code name through the s_out pointer.

6.34.11 dwarf_get_DSC_name()

Returns a discriminant descriptor code name through the s_out pointer.

6.34.12 dwarf_get_EH_name()

Returns a GNU exception header code name through the s_out pointer.

6.34.13 dwarf_get_END_name()

Returns an endian code name through the s_out pointer.

6.34.14 dwarf_get_FORM_name()

Returns an form code name through the s_out pointer.

6.34.15 dwarf_get_FRAME_name()

Returns a frame code name through the s_out pointer. These are dependent on the particular ABI, so unless the dwarf.h used to generate libdwarf matches your ABI these names are unlikely to be very useful and certainly won't be entirely appropriate.

6.34.16 dwarf_get_ID_name()

Returns an identifier case code name through the s_out pointer.

6.34.17 dwarf_get_INL_name()

Returns an inline code name through the s_out pointer.

6.34.18 dwarf_get_LANG_name()

Returns a language code name through the s_out pointer.

6.34.19 dwarf_get_LLE_name()

Returns a split-dwarf loclist code name through the s_out pointer.

6.34.20 dwarf_get_LNE_name()

Returns a line table extended opcode code name through the s_out pointer.

6.34.21 dwarf_get_LNS_name()

Returns a line table standard opcode code name through the s_out pointer.

6.34.22 dwarf_get_MACINFO_name()

Returns a macro information macinfo code name through the s_out pointer.

6.34.23 dwarf_get_MACRO_name()

Returns a DWARF5 macro information macro code name through the s_out pointer.

6.34.24 dwarf_get_OP_name()

Returns a DWARF expression operation code name through the s_out pointer.

6.34.25 dwarf_get_ORD_name()

Returns an array ordering code name through the s_out pointer.

6.34.26 dwarf_get_TAG_name()

Returns a TAG name through the s_out pointer.

6.34.27 dwarf_get_VIRTUALITY_name()

Returns a virtuality code name through the s_out pointer.

6.34.28 dwarf_get_VIS_name()

Returns a visibility code name through the s_out pointer.

6.34.29 dwarf_get_FORM_CLASS_name()

Only different from the others in that it applies to an enum value. It returns the name (for example DW_FORM_CLASS_REFERENCE) through the pointer.

```
int dwarf_get_FORM_CLASS_name (
    enum Dwarf_Form_Class fc,
    char **s_out,
);
```

If the enum value is out of the valid range it returns DW_DLV_NO_ENTRY and ignores s_out.

It never returns DW_DLV_ERROR.

6.35 Section Operations

In checking DWARF in linkonce sections for correctness it has been found useful to have certain section-oriented operations when processing object files. Normally these operations are not needed or useful in a fully-linked executable or shared library.

While the code is written with Elf sections in mind, it is quite possible to process non-Elf objects with code that implements certain function pointers (see struct Dwarf_Obj_Access_interface_s).

So far no one with such non-elf code has come forward to open-source it.

6.35.1 dwarf_get_section_count()

```
int dwarf_get_section_count (
    Dwarf_Debug dbg)
```

Returns a count of the number of object sections found.

If there is an incomplete or damaged dbg passed in this can return -1;

6.35.2 dwarf_get_section_info_by_name()

```
int dwarf_get_section_info_by_name(
    const char *section_name,
    Dwarf_Addr *section_addr,
    Dwarf_Unsigned *section_size,
    Dwarf_Error *error)
```

The function `dwarf_get_section_info_by_name()` returns `DW_DLV_OK` if the section given by `section_name` was seen by libdwarf. On success it sets `*section_addr` to the virtual address assigned to the section by the linker or compiler and `*section_size` to the size of the object section.

It returns `DW_DLV_ERROR` on error.

6.35.3 dwarf_get_section_info_by_index()

```
int dwarf_get_section_info_by_index(
    int section_index,
    const char **section_name,
    Dwarf_Addr *section_addr,
    Dwarf_Unsigned *section_size,
    Dwarf_Error *error)
```

The function `dwarf_get_section_info_by_index()` returns `DW_DLV_OK` if the section given by `section_index` was seen by libdwarf. `*section_addr` to the virtual address assigned to the section by the linker or compiler and `*section_size` to the size of the object section.

No free or deallocate of information returned should be done by callers.

6.36 Utility Operations

These functions aid in the management of errors encountered when using functions in the *libdwarf* library and releasing memory allocated as a result of a *libdwarf* operation.

For clients that wish to encode LEB numbers two interfaces are provided to the producer code's internal LEB function.

6.36.1 dwarf_errno()

```
Dwarf_Unsigned dwarf_errno(
    Dwarf_Error error)
```

The function `dwarf_errno()` returns the error number corresponding to the error specified by `error`.

6.36.2 dwarf_errmsg()

```
const char* dwarf_errmsg(
    Dwarf_Error error)
```

The function `dwarf_errmsg()` returns a pointer to a null-terminated error message string corresponding to the error specified by `error`. The string should not be deallocated using `dwarf_dealloc()`.

The string should be considered to be a temporary string. That is, the returned pointer may become stale if you do libdwarf calls on the `Dwarf_Debug` instance other than `dwarf_errmsg()` or `dwarf_errno()`. So copy the `errmsg` string (or print it) but do not depend on the pointer remaining valid past other libdwarf calls to the `Dwarf_Debug` instance that detected an error.

6.36.3 dwarf_errmsg_by_number()

```
const char* dwarf_errmsg_by_number(
    Dwarf_Unsigned errcode)
```

The function `dwarf_errmsg_by_number()` returns a pointer to a null-terminated error message string corresponding to the error number specified by `errcode`. The string should not be deallocated or freed. If the `errcode` is too large for the table of static error strings a string reflecting that fact is returned.

For some places in the code a `Dwarf_Error()` is inconvenient and this function lets dwarfdump report better information in those cases.

Function new December 19, 2018.

6.36.4 dwarf_get_endian_copy_function()

```
void (*dwarf_get_endian_copy_function(Dwarf_Debug /*dbg*/))
    (void *, const void * /*src*/, unsigned long /*srclen*/)
```

When reader client code wants to extract endian-dependent integers from dwarf and the existing interfaces won't do that (for example in printing frame instructions as done by dwarfdump) `dwarf_get_endian_copy_function` helps by returning the proper copy function needed, the one libdwarf itself uses. The client code needs a bit of glue to finish the job, as demonstrated by the ASNAR macro in dwarfdump/print_frames.c

On success this returns a pointer to the correct copy function.

On failure it returns the null pointer. It's up to the client code to decide how to deal with the situation. In no reasonable case will the null pointer be returned.

New December 2018.

6.36.5 dwarf_get_harmless_error_list()

```
int dwarf_get_harmless_error_list (Dwarf_Debug dbg,
                                  unsigned count,
                                  const char ** errmsg_ptrs_array,
                                  unsigned * newerr_count);
```

The harmless errors are not denoted by error returns from the other libdwarf functions. Instead, this function returns strings of any harmless errors that have been seen in the current object. Clients never need call this, but if a client wishes to report any such errors it may call.

Only a fixed number of harmless errors are recorded. It is a circular list, so if more than the current maximum is encountered older harmless error messages are lost.

The caller passes in a pointer to an array of pointer-to-char as the argument `errmsg_ptrs_array`. The caller must provide this array, libdwarf does not provide it. The caller need not initialize the array elements.

The caller passes in the number of elements of the array of pointer-to-char thru `count`. Since the

If there are no unreported harmless errors the function returns `DW_DLV_NO_ENTRY` and the function arguments are ignored. Otherwise the function returns `DW_DLV_OK` and uses the arguments.

libdwarf assigns error strings to the `errmsg_ptrs_array`. The `MINIMUM(count-1, number of messages recorded)` pointers are assigned to the array. The array is terminated with a NULL pointer. (That is, one array entry is reserved for a NULL pointer). So if `count` is 5 up to 4 strings may be returned through the array, and one array entry is set to NULL.

Because the list is circular and messages may have been dropped the function also returns the actual error count of harmless errors encountered through `newerr_count` (unless the argument is NULL, in which case it is ignored).

Each call to this function resets the circular error buffer and the error count. So think of this call as reporting harmless errors since the last call to it.

The pointers returned through `errmsg_ptrs_array` are only valid till the next call to libdwarf. Do not save the pointers, they become invalid. Copy the strings if you wish to save them.

Calling this function neither allocates any space in memory nor frees any space in memory.

6.36.6 dwarf_insert_harmless_error()

```
void dwarf_insert_harmless_error(Dwarf_Debug dbg,  
                                 char * newerror);
```

This function is used to test dwarf_get_harmless_error_list. It simply adds a harmless error string. There is little reason client code should use this function. It exists so that the harmless error functions can be easily tested for correctness and leaks.

6.36.7 dwarf_set_harmless_error_list_size()

```
unsigned dwarf_set_harmless_error_list_size(Dwarf_Debug dbg,  
                                           unsigned maxcount)
```

dwarf_set_harmless_error_list_size returns the number of harmless error strings the library is currently set to hold. If maxcount is non-zero the library changes the maximum it will record to be maxcount.

It is extremely unwise to make maxcount large because libdwarf allocates space for maxcount strings immediately.

The set of errors enumerated in Figure 8 below were defined in Dwarf 1. These errors are not used by the libdwarf implementation for Dwarf 2 or later.

SYMBOLIC NAME	DESCRIPTION
DW_DLE_NE	No error (0)
DW_DLE_VMM	Version of DWARF information newer than libdwarf
DW_DLE_MAP	Memory map failure
DW_DLE_LEE	Propagation of libelf error
DW_DLE_NDS	No debug section
DW_DLE_NLS	No line section
DW_DLE_ID	Requested information not associated with descriptor
DW_DLE_IOF	I/O failure
DW_DLE_MAF	Memory allocation failure
DW_DLE_IA	Invalid argument
DW_DLE_MDE	Mangled debugging entry
DW_DLE_MLE	Mangled line number entry
DW_DLE_FNO	File descriptor does not refer to an open file
DW_DLE_FNR	File is not a regular file
DW_DLE_FWA	File is opened with wrong access
DW_DLE_NOB	File is not an object file
DW_DLE_MOF	Mangled object file header
DW_DLE_EOLL	End of location list entries
DW_DLE_NOLL	No location list section
DW_DLE_BADOFF	Invalid offset
DW_DLE_EOS	End of section
DW_DLE_ATRUNC	Abbreviations section appears truncated
DW_DLE_BADBITC	Address size passed to dwarf bad

Figure 54. Dwarf Error Codes

The set of errors returned by Libdwarf functions is listed below. The list does lengthen: the ones listed here are far from a complete list. Some of the errors are SGI specific. See libdwarf/dwarf_errmsg_list.h for the complete list.

SYMBOLIC NAME (description not shown here)
DW_DLE_DBG_ALLOC
DW_DLE_FSTAT_ERROR
DW_DLE_FSTAT_MODE_ERROR
DW_DLE_INIT_ACCESS_WRONG
DW_DLE_ELF_BEGIN_ERROR
DW_DLE_ELF_GETEHDR_ERROR
DW_DLE_ELF_GETSHDR_ERROR
DW_DLE_ELF_STRPTR_ERROR
DW_DLE_DEBUG_INFO_DUPLICATE
DW_DLE_DEBUG_INFO_NULL
DW_DLE_DEBUG_ABBREV_DUPLICATE
DW_DLE_DEBUG_ABBREV_NULL
DW_DLE_DEBUG_ARANGES_DUPLICATE
DW_DLE_DEBUG_ARANGES_NULL
DW_DLE_DEBUG_LINE_DUPLICATE
DW_DLE_DEBUG_LINE_NULL
DW_DLE_DEBUG_LOC_DUPLICATE
DW_DLE_DEBUG_LOC_NULL
DW_DLE_DEBUG_MACINFO_DUPLICATE
DW_DLE_DEBUG_MACINFO_NULL
DW_DLE_DEBUG_PUBNAMES_DUPLICATE
DW_DLE_DEBUG_PUBNAMES_NULL
DW_DLE_DEBUG_STR_DUPLICATE
DW_DLE_DEBUG_STR_NULL
DW_DLE CU_LENGTH_ERROR
DW_DLE_VERSION_STAMP_ERROR
DW_DLE_ABBREV_OFFSET_ERROR
DW_DLE_ADDRESS_SIZE_ERROR
DW_DLE_DEBUG_INFO_PTR_NULL
DW_DLE_DIE_NULL
DW_DLE_STRING_OFFSET_BAD
DW_DLE_DEBUG_LINE_LENGTH_BAD
DW_DLE_LINE_PROLOG_LENGTH_BAD
DW_DLE_LINE_NUM_OPERANDS_BAD
DW_DLE_LINE_SET_ADDR_ERROR

Figure 55. Dwarf 2 and later Error Codes

This list of errors is not complete; additional errors have been added. Some of the above errors may be unused. Errors may not have the same meaning in different releases. Since most error codes are returned from only one place (or a very small number of places) in the source it is normally very useful to simply search the libdwarf source to find out where a particular error code is generated. See `libdwarf/dwarf_errmsg_list.h` for the complete message set with short descriptions.

6.36.8 dwarf_dealloc()

```
void dwarf_dealloc(
    Dwarf_Debug dbg,
    void* space,
    Dwarf_Untyped type)
```

The function `dwarf_dealloc` frees the dynamic storage pointed to by `space`, and allocated to the given `Dwarf_Debug`. The argument `type` is an integer code that specifies the allocation type of the region pointed to by the `space`. Refer to section 4 for details on *libdwarf* memory management.

6.36.9 dwarf_encode_leb128()

```
int dwarf_encode_leb128(Dwarf_Untyped val,
    int * nbytes,
    char * space,
    int splen);
```

The function `dwarf_encode_leb128` encodes the value `val` in the caller-provided buffer that `space` points to. The caller-provided buffer must be at least `splen` bytes long.

The function returns `DW_DLV_OK` if the encoding succeeds. If `splen` is too small to encode the value, `DW_DLV_ERROR` will be returned.

If the call succeeds, the number of bytes of `space` that are used in the encoding are returned through the pointer `nbytes`

6.36.10 dwarf_encode_signed_leb128()

```
int dwarf_encode_signed_leb128(Dwarf_Signed val,
    int * nbytes,
    char * space,
    int splen);
```

The function `dwarf_encode_signed_leb128` is the same as `dwarf_encode_leb128` except that the argument `val` is signed.

6.37 Finding Memory Leaks

If you are using `dwarf_set_de_alloc_flag(0)` to turn off the garbage collection `dwarfinish()` does and you find memory leaks there are a couple specific tools provided that may ease the process of tracking down the errors you have made.

This chapter is new as of 26 March 2020.

6.37.1 Compiling libdwarf -DDEBUG=1

The first tool is to build libdwarf with options `-g -O0 -DDEBUG=1`. The `-O0` is simply to help a debugger, valgrind or other too identify source lines accurately. The `-DDEBUG=1` Turns on printf statements in `dwarf_alloc.c` and `dwarf_error.c` that emit lines like

```
libdwarfdetector ALLOC ret 0x... size  
libdwarfdetector DEALLOC ret 0x... size  
libdwarfdetector ALLOC creating error string  
libdwarfdetector DEALLOC Now destruct error string
```

at each point of particular interest.

The first two relate to actually malloc/free. The ret 0x... will be a hex address of the pointer your code is presented for allocations inside libdwarf.

The second two relate to allocation/free of a string in Dwarf_Error record when an error record with variable descriptive error information is being built/freed.

6.37.2 Making use of the output of -DDEBUG=1

A small Python 3 program (`alloctrack.py`) in the libdwarf regressiontests on SourceForge.net will read through a file with libdwarfdetector lines and report on mismatches in the alloc/dealloc counts for each memory-blob libdwarf created. All other lines are skipped.

This has been found very useful.

Since the regression tests are large and you won't otherwise need them a copy of `alloctrack.py` follows so you need not clone the test code.

```
#!/usr/bin/env python3
# Copyright 2020 David Anderson
# This Python code is hereby placed into the public domain
# for use by anyone for any purpose.

# Useful for finding the needle of
# a single leaking allocation
# in the haystack of all the libdwarfdetector
# lines libdwarf can emit if compiled -DDEBUG=1
import sys
import os

def trackallocs(fi, valdict):
    line = 0
    while True:
        line = int(line)+1
        try:
            recf = fi.readline()
        except EOFError:
            break
        if len(recf) < 1:
            # eof
            break
        rec = recf.strip()
        if rec.find("ALLOC") != -1:
            if rec.find("libdwarfdetector ALLOC ret 0x") != -1:
                wds = rec.split()
                off = wds[3]
                if off in valdict:
                    (allo, deallo) = valdict[off]
                    if int(allo) == 0:
                        r = (1, deallo)
                        valdict[off] = r
                    else:
                        print("Duplicate use of ", off, "line", line)
                        r = (int(allo)+1, deallo)
                        valdict[off] = r
                else:
                    allo = 1
                    deallo = 0
                    r=(allo, deallo)
                    valdict[off] = r
            continue

        if rec.find("libdwarfdetector DEALLOC ret 0x") != -1:
            wds = rec.split()
```

```
off = wds[3]
if off in valdict:
    (allo, deallo) = valdict[off]
    if int(deallo) == 0:
        r = (allo,1)
        valdict[off] = r
    else:
        print("Duplicate use of ",off,"line",line)
        r = (allo,int(deallo)+1)
        valdict[off] = r
else:
    allo = 0
    deallo = 1
    r=(allo,deallo)
    valdict[off] = r
continue

if __name__ == '__main__':
    if len(sys.argv) > 1:
        fname = sys.argv[1]
    try:
        file = open(fname, "r")
    except IOError as message:
        print("File could not be opened: ", fname, " ", message)
        sys.exit(1)
    else:
        file = sys.stdin

    vals = {}
    trackallocs(file,vals)
    for s in vals:
        (allo, deallo) = vals[s]
        if int(allo) != int(deallo):
            print("Mismatch on ",s," a vs d: ",allo,deallo)
        if int(allo) > 1:
            print("Reuse of ",s," a vs d: ",allo,deallo)
```

