
17 Spring IoC容器如何读取多个属性文件或者配置文件?

更新时间: 2020-06-22 10:10:35



什么是路?就是从没路的地方践踏出来的,从只有荆棘的地方开辟出来的。 —— 鲁迅

背景

在 Spring 项目中,你可能需要从 properties 文件中读入配置注入到 bean 中,例如数据库连接信息,redis server 的地址端口信息等,此时,Properties 配置文件不止一个,需要在系统启动时同时加载多个 Properties 文件,该如何做呢?

Spring 加载多个属性文件

• Spring 老版本 XML 配置方式:

在 applicationContext.xml 使用 context:property-placeholder/,注意,需要增加命名空间: xmlns:context="http://www.springframework.org/schema/context"

示例:

property-placeholder location="classpath:foo.properties, classpath:bar.properties"/>

或者在 applicationContext.xml 使用util:properties,注意,需要用到命名空间:xmlns:util="http://www.springframework.org/schema/util"和 schema: http://www.springframework.org/schema/util http://www.springframework.org/schema/util/spring-util-3.0.xsd

示例:

```
<util:properties id="fileA" location="classpath:META-INF/properties/a.properties"/>
<util:properties id="fileB" location="classpath:META-INF/properties/b.properties"/>
```

然后使用方式如下:

```
@Resource(name="fileA")
private Properties propertyA;

@Resource(name="fileB")
private Properties propertyB;
```

• spring4.x 以上版本,使用注解或者配置。

注解方式, spring boot 同样适用:

```
@PropertySources( {
    @PropertySource("classpath:config001.properties"),
    @PropertySource("classpath:config002.properties")
})
```

也可采用配置方式:

```
@Bean
public static PropertySourcesPlaceholderConfigurer propertySourcesPlaceholderConfigurer() {
PropertySourcesPlaceholderConfigurer propertySourcesPlaceholderConfigurer
= new PropertySourcesPlaceholderConfigurer();
Resource[] resources = new ClassPathResource[]{
    new ClassPathResource("app.properties")
};
propertySourcesPlaceholderConfigurer.setLocations(resources);
propertySourcesPlaceholderConfigurer.setIgnoreUnresolvablePlaceholders(true);
return propertySourcesPlaceholderConfigurer;
}
```

注意:

若属性文件定义在父上下文时:

- @Value 不能在子上下文中获取到值;
- @Value 可以从父上下文获取到值。

若属性文件定义在子上下文:

- @Value 可以在子上下文中获取到值;
- @Value 不能从父上下文获取到值。

2. 使用 @PropertySource 注解定义属性文件时,

若属性文件定义在父上下文时:

- @Value 可以从子上下文获取到值;
- @Value 可以从父上下文获取到值;

可以使用 environment.getProperty 在子上下文中获取到属性值;

可以使用 environment.getProperty 在父上下文中获取到属性值。

若属性文件定义在子上下文:

- @Value 可以从子上下文获取到值;
- @Value 不能从父上下文获取到值;

可以使用 environment.getProperty 从子上下文获取到值;

不能使用 environment.getProperty 从父上下文获取到值。

Spring 读取多个属性文件的原理

• <context:property-placeholder/> 深入原理。

<context:property-placeholder/> 由 PropertyPlaceholderBeanDefinitionParser 类来解读:

```
## Parser for the (@code <context:property-placeholder/>) element.

# @author Juergen Hoeller
# @author Dave Syer
# @author Dave Syer
# @author Chris Beams
# @since 2.5

# Class PropertyPlaceholderBeanDefinitionParser

private static final String SYSTEM_PROPERTIES_MODE_ATTRIBUTE = "system-properties-mode";

private static final String SYSTEM_PROPERTIES_MODE_DEFAULT = "ENVIRONMENT";

## @Override
## @SuppressWarnings("deprecation")
## protected Class(?) ## getBeanClass(Element element elem
```

解析 location 在 doParse 方法:

加载多个属性文件使用 PropertyResourceConfigurer#postProcessBeanFactory:

```
/**
    * {@linkplain #mergeProperties Merge}, (@linkplain #convertProperties convert) and
    * {@linkplain #processProperties process} properties against the given bean factory.
    * @throws BeanInitializationException if any properties cannot be loaded
    */
    @Override
public void postProcessBeanFactory(ConfigurableListableBeanFactory beanFactory) throws BeansException {
        try {
            Properties mergedProps = mergeProperties();

            // Convert the merged properties, if necessary.
            convertProperties(mergedProps);

            // Let the subclass process the properties.
            processProperties(beanFactory, mergedProps);
        }
        catch (IOException ex) {
            throw new BeanInitializationException("Could not load properties", ex);
        }
}
```

最后调用 PropertiesLoaderUtils.fillProperties() 方法, 支持 XML 和属性文件:

```
,

* Actually load properties from the given EncodedResource into the given Properties instance.

* Moaram props the Properties instance to load into
   Oparam props the Properties from the given encodeake:
Oparam props the Properties instance to load into
Oparam resource the resource to load from
Oparam persister the PropertiesPersister to use
Othrows IOException in case of I/O errors
static void fillProperties(Properties props, EncodedResource resource, PropertiesPersister persister)
      InputStream stream = null;
      Reader reader = null;
            string filename = resource.getResource().getFilename();
if (filename != null && filename.endsWith(XML_FILE_EXTENSION)) {
                  stream = resource.getInputStream();
persister.loadFromXml(props, stream);
            else if (resource.requiresReader())
                   reader = resource.getReader()
                  persister.load(props, reader);
            else {
                  stream = resource.getInputStream();
                  persister.load(props, stream);
      finally {
            if (stream != null) {
    stream.close();
            if (reader != null) {
                  reader.close();
            3
     }
3
```

• <util:properties> 深入原理。

UtilNamespaceHandler 解析 <util> 标签,包含多个子标签:

<util: properties> 的解析则调用 UtilNamespaceHandler 解析,使用 PropertiesFactoryBean 来将 classpath 下的属性文件加载到内存中,多个文件都加载时会进行 merge 处理。

最后 PropertiesFactoryBean 调用 PropertiesLoaderUtils.fillProperties() 方法,支持 XML 和属性文件.

• PropertySource 注解深入原理。

从 spring4.3 开始,使用 PropertySourceFactory 的工厂方法来加载属性文件:

```
@Target(ElementType.TYPE)
@Retention(RetentionPolicy.RUNTIME)
@Documented
@Repeatable(PropertySources.class)
public @interface PropertySource {
      * Indicate the name of this property source. If omitted, the {@link #factory()} * will generate a name based on the underlying resource (in the case of
        {@link org.springframework.core.io.support.DefaultPropertySourceFactory}: derived from the resource description through a corresponding name-less
      * {@link org.springframework.core.io.support.ResourcePropertySource} constructor).
* @see org.springframework.core.env.PropertySource#getName()
      * @see org.springframework.core.io.Resource#getDescription()
    String name() default "";
     for examples.
        Each location will be added to the enclosing {@code Environment} as its own
      * property source, and in the order declared.
    String[] value();
    /** * Indicate if failure to find the a {@link #value() property resource} should be
      * (@code true) is appropriate if the properties file is completely optional.
* Default is {@code false}.
      * @since 4.0
    boolean ignoreResourceNotFound() default false;
     * A specific character encoding for the given resources, e.g. "UTF-8".
     * @since 4.3
     String encoding() default "";
      * Specify a custom {@link PropertySourceFactory}, if any.
* By default, a default factory for standard resource files will be used.
        @see org.springframework.core.io.support.DefaultPropertySourceFactory
      * @see org.springframework.core.io.support.ResourcePropertySource
    Class<? extends PropertySourceFactory> factory() default PropertySourceFactory.class;
1
```

PropertySourceFactory 的默认实现 DefaultPropertySourceFactory 使用 ResourcePropertySource 将属性文件资源化。

最后调用 PropertiesLoaderUtils.fillProperties() 方法 来加载资源。

总结

通过阅读代码发现,不管何种形式支持多个属性文件的读取,实现的代码是一致的,都是调用 PropertiesLoaderUtils.fillProperties() 方法来加载资源,底层的实现都是 Properties 的 load() 方法。

扩展: Spring MVC 中如何加载多个 XML 文件

方式一: 使用contextConfigLocation。

```
<servlet-name>springMVC</servlet-name>
                          <servlet-class>
                             org.springframework.web.servlet.DispatcherServlet
                           </servlet-class>
                           <init-param>
                              <param-name>contextConfigLocation</param-name>
                              <param-value>
                                  WEB-INF/spring-core-context.xml,
                                  WEB-INF/spring-DAO.xml,
                                  WEB-INF/spring-Services.xml
                              </param-value>
                           </init-param>
                           <load-on-startup>1</load-on-startup>
                       </servlet>
                       <servlet-mapping>
                           <servlet-name>springMVC</servlet-name>
                          <url-pattern>/</url-pattern>
                       </servlet-mapping>
方式二: 使用 import 注解。
                  <beans>
                       <import resource="spring-core-context.xml"/>
                       <import resource="spring-DAO.xml"/>
                       <import resource="spring-services.xml"/>
                        ... //other configurations
                  </beans>
参考 ResourceUtils, 具体大家可以自己尝试分析。
                                                                               18 Spring loC容器如何读取应用
外部的xml, bt, 图形或者属性文
 ← 16 Resource的前生今世
```