Apache Access Control



Andrew Mallett
LINUX AUTHOR AND TRAINER

@theurbanpenguin www.theurbanpenguin.com



Objectives



Control access using IP Addresses or Hostnames

Display Server-Status page to the localhost only

Provide access to protected content on a website to authorized users and groups



Control Host Access Apache 2.2

Prior to Apache 2.4, host access control would be written similar to the following:

Order allow, deny Allow from localhost

Where the default access is denied except for those hosts listed in the allow list. With Apache 2.4, access control is maintained using the Require directive for both hosts and users



Server Version: Apache/2.4.23 (Unix) Server MPM: event Server Built: Jul 5 2016 07:34:37 Current Time: Thursday, 08-Dec-2016 09:48:59 GMT Restart Time: Thursday, 08-Dec-2016 09:43:58 GMT Parent Server Config. Generation: 1 Parent Server MPM Generation: 0 Server uptime: 5 minutes Server load: 0.00 0.00 0.00 Total accesses: 6 - Total Traffic: 11 kB CPU Usage: u.05 s.08 cu0 cs0 - .0433% CPU load .02 requests/sec - 37 B/second - 1877 B/request 1 requests currently being processed, 74 idle workers Connections Threads Async connections PID total accepting busy idle writing keep-alive closing 3407 0 25 0 yes 3408 0 1 24 0 yes 3409 0 yes 74 Sum 0



Server Status Page

The Server Status page can be viewed via a web browser when this is enabled. Access to this page may be restricted to the Server itself and perhaps your Management Workstation



```
LoadModule status_module modules/mod_status.so

LoadModule authz_host_module modules/mod_authz_host.so

<Location "/status">
    SetHandler server-status
    Require ip 127.0.0.1

</Location>
```

Configuring the Status Page

For this we introduce the Location block and load two additional modules. A Location block is similar to a Directory block, however it is used to secure items outside of the filesystem, unlike the Directory block. In this case we use it to secure access to the module using the URI /status.



Configuring the Status Page



LoadModule auth_basic_module modules/mod_auth_basic.so LoadModule authn_file_module modules/mod_authn_file.so LoadModule authz_user_module modules/mod_authz_user.so

User Access

To be able to authenticate users we need to load an additional 3 modules as a minimum. An Authentication Type, an Authentication Provider and an Authorization module.



LoadModule authn_core_module modules/mod_authn_core.so LoadModule authz_core_module modules/mod_authz_core.so

Core Modules

The core modules need to be loaded as well.



AuthType Basic

AuthName "Only authorized users allowed"

AuthUserFile /etc/httpd/sales.pwd

Require valid-user #Require user fred joe

Authentication Settings

To allow user authentication to a file we can add code similar to this.



htpasswd -c /etc/httpd/sales.pwd fred
htpasswd /etc/httpd/sales.pwd joe
htpasswd -D /etc/httpd/sales.pwd joe
htpasswd -v /etc/httpd/sales.pwd fred
echo Password1 | htpasswd -i /etc/httpd/sales.pwd joe

Configure User Passwords

To manage file based users and passwords we have the htpasswd command.



Authenticating Users



Configuring the Virtual Host




Configuring Passwords



Authenticating Groups





Authenticating Hosts


Authenticating hosts will require the module: authz_host_module

The authorization line in the Location or Directory block would be similar to this: Require ip 127.0.0.1

The server status page can shown when defined in a Location block and requires the module:

status_module





Authenticating Users

authn_file_module

Authenticating users will require the modules: authz_user_module auth_basic_module

The password file can be populated with the command:
htpasswd

Authorization can be either a list of users or all users:

Require user bob joe Require valid-user



Next up: Using Scripts to Deliver Dynamic Content

