Authentication

- BasicAuthentication
- SessionAuthentication
- TokenAuthentication
- RemoteUserAuthentication
- Custom authentication

Authentication

Third party packages:-

- Django OAuth Toolkit
- JSON Web Token Authentication
- Hawk HTTP Authentication
- HTTP Signature Authentication
- Djoser
- django-rest-auth / dj-rest-auth
- django-rest-framework-social-oauth2
- django-rest-knox
- drfpasswordless

JSON Web Token (JWT)

JSON Web Token is a fairly new standard which can be used for token-based authentication. Unlike the built-in TokenAuthentication scheme, JWT Authentication doesn't need to use a database to validate a token.

https://jwt.io/

Simple JWT

Simple JWT provides a JSON Web Token authentication backend for the Django REST Framework. It aims to cover the most common use cases of JWTs by offering a conservative set of default features. It also aims to be easily extensible in case a desired feature is not present.

https://django-rest-framework-simplejwt.readthedocs.io/en/latest/

How to Install Simple JWT

pip install djangorestframework-simplejwt

Configure Simple JWT

```
settings.py
REST FRAMEWORK = {
    'DEFAULT AUTHENTICATION CLASSES': (
      'rest framework simplejwt.authentication.JWTAuthentication',
  ) }
urls.py
from rest framework simplejwt.views import TokenObtainPairView, TokenRefreshView
urlpatterns = [
  path('gettoken/', TokenObtainPairView.as view(), name='token obtain pair'),
  path('refreshtoken/', TokenRefreshView.as view(), name='token refresh'),
```

Configure Simple JWT

You can also include a route for Simple JWT's TokenVerifyView if you wish to allow API users to verify HMAC-signed tokens without having access to your signing key.

urls.py

```
from rest_framework_simplejwt.views import TokenObtainPairView, TokenRefreshView, TokenVerifyView

urlpatterns = [

path('gettoken/', TokenObtainPairView.as_view(), name='token_obtain_pair'),

path('refreshtoken/', TokenRefreshView.as_view(), name='token_refresh'),

path('verifytoken/', TokenVerifyView.as_view(), name='token_verify'),
```

JWT Default Settings

```
from datetime import timedelta
SIMPLE JWT = {
 'ACCESS TOKEN LIFETIME': timedelta(minutes=5),
  'REFRESH TOKEN LIFETIME': timedelta(days=1),
  'ROTATE REFRESH TOKENS': False,
 'BLACKLIST AFTER ROTATION': True,
 'ALGORITHM': 'HS256',
  'SIGNING KEY': settings.SECRET KEY,
  'VERIFYING KEY': None,
 'AUDIENCE': None,
  'ISSUER': None,
```

JWT Default Settings

```
'AUTH HEADER TYPES': ('Bearer',),
'USER ID FIELD': 'id',
'USER ID CLAIM': 'user id',
'AUTH TOKEN CLASSES': ('rest framework simplejwt.tokens.AccessToken',),
'TOKEN TYPE CLAIM': 'token type',
'JTI CLAIM': 'jti',
'SLIDING TOKEN REFRESH EXP CLAIM': 'refresh exp',
'SLIDING TOKEN LIFETIME': timedelta(minutes=5),
'SLIDING TOKEN REFRESH LIFETIME': timedelta(days=1),
```

JWT Default Settings

ACCESS_TOKEN_LIFETIME - A datetime.timedelta object which specifies how long access tokens are valid.

REFRESH_TOKEN_LIFETIME - A datetime.timedelta object which specifies how long refresh tokens are valid.

Use JWT

GET Token

http POST http://127.0.0.1:8000/gettoken/ username="user1" password="geekyshows"

Verify Token

http POST http://127.0.0.1:8000/verifytoken/token="eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJ0b2tlbl90eXBlIjoiYWNjZXNzIiwiZXhwIjoxNjAzNjIxOTAxLCJqdGkiOiI2NmM4ZWJiYjUwMWM0MzA3YWJjMGNjNTY2ZmNmNTJiMyIsInVzZXJfaWQiOjJ9.cwUSWrkFnFdO8fP45aEP6GDa3yaybSVYAG6vGUlkFOo"

Use JWT

Refresh Token

http POST http://127.0.0.1:8000/refreshtoken/refresh="eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiJ9.eyJ0b2tlbl90eXBlIjoicmVmcmVzaCIsImV4cCI6MTYwMzcwODAwMSwianRpIjoiYzYzODBmYjVjMDk3NDVhNjkyYzA5YWRmMGI1ZDQ5OWIiLCJ1c2VyX2lkIjoyfQ.Q-E-8N8VvSZof5IjoNIL-2KECRLqlYzBojbTCj_4dBc"

Permission Classes

Permissions in REST framework are always defined as a list of permission classes.

- AllowAny
- IsAuthenticated
- IsAdminUser
- IsAuthenticatedOrReadOnly
- DjangoModelPermissions
- DjangoModelPermissionsOrAnonReadOnly
- DjangoObjectPermissions
- Custom Permissions