

Client Documentation

class freertr_polka

Methods	Parameters
__init__	queueName
At initialization the class use 'config_mq.py' and 'config.txt' to setup the RabbitMQ server name and Queue names. The CLIENT_QUEUE value can be superseded by a parameter at the construction time.	
close	
Use to dispose the RabbitMQ connection	
router_list	
Send to CLIENT_QUEUE through RabbitMQ all configured routers by this library since the server module was loaded	
router_set	router_id, address, port, user, password
Setup a router (usually an edge router), this method id needed to be called before use of the 'router_id', this will set the connection parameters. When use a telnet client, there's no need to set the user and password, just the IP address and port	
router_del	router_id
Remove a router configuration from server	
tunnel_list	router_id
List all tunnel's configured at FreeRtr, even if they were not configured by this library and send it to CLIENT_QUEUE through RabbitMQ	
tunnel_accesslist	router_id, tunnel_id
Get a list of all access list assigned to a tunnel defined by tunnel_id and send to CLIENT_QUEUE through RabbitMQ	
tunnel_set	router_id, tunnel_id, address, mask, path, description
Set the tunnel parameters, if no description was supplied the tunnel_id will be used as description. The path need to be at the format "<IP1>,<IP2>,...,<IPn>", the last one will be the destination IP.	
tunnel_del	router_id, tunnel_id
Remove a tunnel identified by tunnel_id from FreeRtr configuration	
accesslist_list	router_id
Send a list of all Access List configured in the FreeRtr and send it to CLIENT_QUEUE through RabbitMQ	
accesslist_set	router_id, accesslist_id, protocol, address_in, mask_in, address_out, mask_out, tos
Setup a new Access List in the FreeRtr, the protocol could be 'TCP', 'UDP', 'ICMP' or a protocol number. The ToS can be omitted, in this case the FreeRtr will not filter the ToS flag	
accesslist_del	router_id, accesslist_id
Remove an Access List identified by accesslist_id from FreeRtr configuration	
accesslist_tunnel_assigned	router_id, accesslist_id
Send to CLIENT_QUEUE the tunnel assigned to an Access List identified by accesslist_id	
accesslist_assign	router_id, accesslist_id, ip_destiny
Assign an Access List to a destiny IP	
accesslist_unassign	router_id, accesslist_id
Unassign an Access List	

Sample Python Code

```
1 | from freertr_polka import freertr_polka
2 | freertr = freertr_polka()
3 | freertr.router_set('VIT0071', '10.160.0.20', '22222',
   |   'rare', 'rare')
4 | freertr.tunnel_set('VIT0071', 'tunnel174516',
   |   '40.17.16.1', '255.255.255.252',
   |   '10.45.45.45,10.16.16.16', 'POLKA tunnel from VIT0071[1]
   |   -> SPO0021[2] via MG')
5 | freertr.accesslist_set('VIT0071', 'tunnel_vix_sp', 'tcp',
   |   '10.0.0.0', '255.255.255.0', '10.16.0.0',
   |   '255.255.255.0', '0x20')
6 | freertr.accesslist_assign('VIT0071', 'tunnel_vix_sp',
   |   '40.17.16.1')
7 | freertr.close()
```