



WINDOWS RELEASE 4.0.0

Ether 4.0 User Manual

Build, run, review, and deliver local-first creative work from one portable `.ether` document.

PRODUCT

ETHER by DreamBay

EDITION

4.0.0 release manual

CAPTURE SOURCE

Installed packaged
application

RELEASE EVIDENCE

Every application image in this manual comes from Ether 4.0.0 installed through the reviewed Windows installer under a disposable profile. The capture manifest records SHA-256 hashes for the installer, executable, fixture, and each image.

Installer SHA-256: 02b6cb7135844449b2a2427b680aae9f0a38038ca319c944f996716ebae68dd0

Version 4.0.0 | Windows | DreamBay


Ether is a local-first creative production canvas. An Ether project is one portable `.ether` document containing its graphs, revisions, embedded media, runs, collections, and review decisions. It is designed around a simple visible model: a **node** does work, a **channel** carries a kind of payload, and a **role** tells the receiving node how to use it.

Release-candidate images are inserted only by `docs/manual/capture-release.mjs`, which launches the installed Ether executable under a disposable Windows profile. This source manual deliberately contains no substitute development-renderer captures.

Contents

1. [Start safely](#)
2. [Workspaces](#)
3. [Documents, references, and recovery](#)
4. [Canvas, nodes, connections, and Inspector](#)
5. [Run plans, batches, and Job Center](#)
6. [Review, collections, and export](#)
7. [Providers and intelligent work](#)
8. [Recipes and Codex plugin](#)
9. [Settings, accessibility, and privacy](#)
10. [Examples](#)
11. [Reference index](#)

Start safely



Packaged Ether release capture - Start screen on a clean profile

Choose **New document** to start an untitled usable canvas, or **Open document** to select one supported `.ether` file. Press `Ctrl+S` to name a new document. After a name exists, Save flushes pending work and creates a manual milestone; it does not create a project folder.


Ether opens maximized so the canvas and its supporting panes use the available desktop. The standard Windows title-bar controls remain available to minimize, restore, resize, or close the app.

Ether 4.0 does **not** open, import, or migrate legacy Ether folder projects. A directory containing `project.json`, `graph.json`, or `ether.db` is refused unchanged. Create a new `.ether` document and bring in only the source media you need.


The installed runtime retains its dependency license files and a `THIRD-PARTY-NOTICES.txt` native-library notice. It does not ship benchmark, fixture, specification, source-map, cache, or development-configuration material.

The title bar reports **Saving**, **Saved**, or **Needs attention**. Idle edits autosave after 1.5 seconds and are not deferred longer than ten seconds. `File > Save As` validates a new destination and switches to it only after success. `Save a Copy` validates a copy but leaves the original active. `Compact Document` reclaims abandoned embedded-object pages and reports the actual before/after size.

Workspaces



Packaged Ether release capture - Build workspace with the release atlas




Packaged Ether release capture - Focus workspace

Workspace	Use it for	Primary surfaces
Build	Constructing and wiring workflows	Node Library, canvas, Inspector, compact Job Center
Focus	Editing one selection with less visual noise	canvas, selected node/module, optional Reference Desk
Run	Previewing scope and operating durable work	immutable plan, Job Center, Batch Matrix, live output strip
Review	Choosing and delivering results	Artifact Observatory, Compare, Evaluate, Filter, collections, export

Use the workspace switcher at the top. Left, right, top, and bottom panes have their own collapse and resize controls; their layout is retained per workspace and document. The canvas receives spare window space. The minimap remains adjacent to the Inspector rather than behind it. At narrow widths, labels give way to icon buttons with tooltips instead of vertical text.

Documents, references, and recovery



Packaged Ether release capture - Reference Desk with an embedded reference



Packaged Ether release capture - Production recovery status

References

Drop supported image, video, audio, or text material onto the document and organize it in **Reference Desk**. Drops are linked by default; choose **Embed dropped files** when portability matters. Dropping onto a Reference Set adds assets rather than silently replacing them. In the Reference Set Inspector, enter reference IDs and choose **Add references** or **Replace set** explicitly. Reference Desk supports grid, comparison, role overrides, include/exclude selection, assignment to sets, and a target Batch dimension.

Linked items retain their identity, path, timestamps, size, fingerprint, and an embedded preview. If a link goes missing, it remains visible. Use **Locate**, **Search Folder**, **Relink All**, **Use Embedded Preview**, **Embed Available Copy**, or **Remove**; do not assume a preview is a recovered original. **Make Document Portable** shows the expected size change, missing items, and embeds every available linked source after confirmation.

Read-only, recovery, and repair

Only one process may hold a writable lease. If another writer or an unsuitable cloud/network location has the document, open it read-only where supported. Read-only mode disables changes but preserves inspection and export paths that are safe for the document state.


Interrupted imports and provider staging are recorded in Ether-owned AppData, never beside the document. On the next open, recovery is shown as a reviewable revision rather than silently merged. Damaged metadata may open in read-only recovery. Repair writes a **new** `.ether` file and a report; it never mutates the damaged source. See [Troubleshooting](#) for the recovery decision tree.

Recovery decision flow. Text alternative: Start with the open result. A healthy document continues in writable mode. A writer or location restriction opens read-only. Interrupted work goes to recovery review. Damaged metadata stays unchanged while Repair writes a new document.


```
Open .ether
|
+-- Healthy -----> Writable document
|
+-- Writer/location restriction -----> Read-only -> close writer or save a safe copy
|
+-- Interrupted work -----> Recovery review -> keep or dismiss revision
|
+-- Damaged metadata -----> Read-only recovery -> Repair to a new .ether
```

Open result	-> Review	-> Safe action
Healthy document	Saved state and document header	Continue in writable mode
Writer active or location restricted	Read-only reason	Close the other writer or save a copy to a safe local drive
Interrupted import, save, or provider staging	Recovery revision and reconciliation report	Keep or dismiss the recovered revision after inspection
Damaged metadata	Read-only recovery and repair report	Repair to a new <code>.ether</code> file; preserve the source

Canvas, nodes, connections, and Inspector



Packaged Ether release capture - Canvas containing all 17 canonical nodes



Packaged Ether release capture - Channel lane and role chooser

Select a node or lane to open the contextual Inspector. Empty-canvas click clears selection; left-drag selects, right-drag pans, and selected nodes move as a group. Undo/redo applies graph transactions, including changes from recipes and the plugin. A Group is visual organization only; a Module is a collapsible subgraph with declared inputs, outputs, and exposed parameters.

Each node has an editable **Title**, but its canonical kind is fixed. The card shows connected ports at rest, status when queued/running/blocked/failed/recently done, and one primary action only if the node can actually perform one. **Advanced** disclosures hold diagnostics, provenance, and expert controls. A Prompt deliberately has no Run button.

Channels and roles

Channels use both a shape and color. A valid lane carries one channel and one role. Ether rejects an exact duplicate lane but permits distinct lanes between the same pair when channel, role, or selector differs.

Node, channel, and role flow. Text alternative: Prompt sends Text with the Subject role to Worker. Worker sends approved Text with the Composition role to Image Generator. Reference Set sends Image with the Style role to the same Image Generator. The generator stores an immutable Image output for Review.

```
Prompt ----- Text / Subject -----> LLM Worker
LLM Worker -- Text / Composition -----> Image Generator ---- Image ----> Review
Reference Set --- Image / Style -----/
```

Producer node	-> Channel	-> Role at receiver	-> Receiver node	-> Result
Prompt	Text	Subject	LLM Worker	A versioned refined prompt

Producer node	-> Channel	-> Role at receiver	-> Receiver node	-> Result
LLM Worker	Text, Latest approved	Composition	Image Generator	Positive generation direction
Reference Set	Image, All variants	Style	Image Generator	Ordered visual references
Image Generator	Image	General	Review	Immutable artifact with lineage

Channel	Payload	Typical use
Text	authored or generated text	prompts, constraints, instructions
Image	still media	source, style, subject, generated art
Mask	editable selection geometry/raster	Image Edit guidance
Data	structured values	variables, scores, metadata, routes
Video	moving media	references, captioning, frame extraction
Audio	sound media	references, transcription

Role	Receiving meaning	Role	Receiving meaning	Role	Receiving meaning
General	default context	Negative	excluded constraint	Subject	main subject
Product	item/product	Face	face identity	Clothing	wardrobe
Pose	body/action	Setting	environment	Composition	framing/layout
Style	visual treatment	Lighting	light direction/quality	Colour Palette	color guidance
Typography	type treatment	Motion	movement	Timing	time/rhythm

Click a lane role badge or select the lane. The Inspector offers **Role** and **Output selection: Latest approved, Latest output, or All variants**. Once an output exists you can also pin a specific version to an outgoing lane. Two direct Subject lanes become Subject and Subject 2; a Prompt -> Worker -> Worker chain remains one Subject lineage. Text/Negative enters negative constraints, not the positive prompt.

Allowed cross-channel work is always visible: Image -> Text uses Codex vision; Audio/Video -> Text requires a verified transcription or interpretation capability; Video -> Image extracts a real frame; Media -> Data yields technical metadata (semantic metadata needs Codex); Text/Data and Mask/Data have explicit parsing/serialization adapters. Unsupported connections are blocked with an explanation. Text -> Image belongs on Image Generator, not a hidden edge adapter.

Canonical nodes and controls

All 17 canonical nodes appear in Node Library. The **Setup** section (Title, canonical kind, Save title) is shared. Registry settings save only when valid. The following table lists ordinary controls, then Advanced controls where implemented; provider choices are populated only by verified capabilities.


Node	Ordinary Inspector controls	Advanced / action
Prompt (<code>prompt.text</code>)	Authored text or Manual override text; Assembly: Append incoming context / Manual override; Use assembled text as manual override; Save prompt; assembled read-only text and provenance	no provider action; Diagnostics & provenance
LLM Worker (<code>prompt.worker</code>)	Instruction; Behavior: brainstorm, rewrite, mutate, expand, reinforce, extract, critique, custom; AI profile: fast, balanced, deep, custom; Save worker	Model, Reasoning effort, Variation; Generate Output / Preview plan; immutable output tools
Reference Set (<code>reference.set</code>)	reference IDs; Add references ; Replace set ; member count and the current order readout	Diagnostics. Reference Desk supplies Grid, Filmstrip, Waveform, and List views plus Compare selected ; the Inspector does not expose channel or ordering editors in 4.0
Image Generator (<code>generation.image</code>)	Model profile; capability-derived Aspect ratio, Resolution, Output count; Reset profile defaults; Save provider settings	capability provenance/limitations; Generate Image / Preview plan
Image Edit (<code>edit.image</code>)	Model profile, Output count, source image; recipe selector: Freeform edit, Product clean-up, Object removal, Outpaint scene; frame mode and X/Y/Width/Height; mask Brush, Eraser, Undo, Redo, Clear , Size, Opacity, and Commit mask ; Save edit setup and Save provider settings	capability provenance/limitations; local saved mask precedence; Generate Edit / Preview plan
Mask (<code>edit.mask</code>)	validated Mode text, Feather number, Save mask	Run Mask / Preview plan
Image Transform (<code>edit.transform</code>)	validated Operation text, Preserve aspect ratio; Width and Height appear only when those optional values already exist; Save transform	Run Transform / Preview plan
Compare (<code>review.compare</code>)	validated Selection mode text, Minimum selections; Save compare	human checkpoint; no hidden AI call
Evaluate (<code>review.evaluate</code>)	Instruction, configured-rubric count, AI profile text, Model; Save evaluate	Evaluate Outputs / Preview plan; Diagnostics. No separate reasoning control is exposed in this Inspector
Filter (<code>review.filter</code>)	validated Match text plus configured-rule and route counts; Save filter	Run Filter / Preview plan
Variables (<code>flow.variables</code>)	configured-variable count; Save variables	Run Node / Preview plan
Batch (<code>flow.batch</code>)	configured-dimension and exclusion counts, Parallelism; Save batch	Build Batch / Preview plan
Join (<code>flow.join</code>)	validated Strategy text, Require complete; Save join	Run Join / Preview plan
Collection (<code>output.collection</code>)	Collection ID, validated Membership mode text, Make primary; Save collection	Update Collection / Preview plan
Export (<code>output.export</code>)	Path grant ID, Naming template, validated Format and Collision policy text, Include metadata; Save export	Export Outputs / Preview plan
Note (<code>canvas.note</code>)	Body, validated Style text; Save note	non-runnable; use for annotations

Node	Ordinary Inspector controls	Advanced / action
Drawing (<code>canvas.drawing</code>)	Width, Height, Background, configured-stroke count; canvas Brush , Eraser , Undo , Redo , Brush color, Brush size, and Brush opacity; saved drawing gestures; Publish drawing	produces an immutable Image artifact; Diagnostics


Runnable node Inspectors show **Preview plan** beside their available primary action. Non-runnable Prompt and Note nodes do not. Output versions remain immutable: **Approve**, **Reject**, **Edit** (creates a manual descendant), **Compare**, and **Restore** never overwrite the original. When a manual descendant or outgoing lane is available, its corresponding editor or **Pin** lane control appears conditionally. The shared Advanced **Diagnostics & provenance** section shows node ID, definition ID, and graph ID.

The generic 4.0 Inspector renders booleans as checkboxes, numbers as number fields, strings as validated text fields, and arrays as configured-item counts. A field named "mode," "strategy," "format," or "style" is therefore not necessarily a preset dropdown. Prompt assembly, Worker behavior/profile, provider profile/ratio/resolution/output count, and Image Edit recipes are true selectors. Worker **Variation** is intentionally kept with Model and Reasoning effort in the collapsed Advanced section in the shipped 4.0 UI; this differs from one "ordinary controls" sentence in the design prose but not from the release acceptance contract.


Run plans, batches, and Job Center



Packaged Ether release capture - Run workspace



Packaged Ether release capture - Batch Matrix with a five-item work set and separated concurrency controls



Packaged Ether release capture - Job Center with durable run evidence

Preview plan compiles the exact immutable plan that Run will use. Read provider, requested profile, dimensions, reference count, work-item count, estimated calls, adapters, warnings, and selected output versions before confirmation. Ether refuses execution if the plan content hash changes.

Execution policies are precise:

- **Generate Output** runs one LLM Worker from selected/cached upstream versions.
- **Generate Image / Generate Edit** runs one selected provider node from selected/cached inputs.
- **Run Selected** runs selected runnable nodes in dependency order; outside dependencies stay pinned unless Preview says otherwise.
- **Run Branch** runs the downstream scope from a node or module.
- **Refresh Upstream** deliberately re-runs stale dependencies before a target.
- **Run Recipe** follows its declared scope and checkpoints.


Job Center groups queued, active, completed, blocked, and failed jobs. Open a job for its timeline, work items, attempts, correlation/provenance details, and error action. **Cancel** marks queued work cancelled and asks an active provider to interrupt when supported. **Retry** creates a new attempt for failed work under the same work item and preserves the failed attempt. Ether recovers interrupted queued work when you reopen the document. Terminal jobs do not show a misleading Resume button.

Batch Matrix separates planning into three sections:


- **Full batch** lists dimensions, exclusions, exact work-item count, and estimated provider calls. Select a cell to exclude that item.
- **Provider and model allocation** finds reachable Prompt Workers and Image Generators. For a batch with **M** work items, each lane assigns an exact **N** items to a verified provider, profile, and model. Ether keeps those ordinal assignments stable; unassigned items use the target node's current default.
- **Concurrent run** controls simultaneous work independently from batch size. Sequential (**1**) remains the default. Ether uses one shared limit across the running application: 8 active calls globally, 4 Codex calls across App Server and explicit executable fallback work, 4 Gemini Developer API image calls across all documents/jobs/batches, and a separate 4 only for explicitly selected Antigravity fallback work. A fifth same-family call and ninth global call wait. Unknown providers remain at 1. If a route cannot support four active calls, Ether reports it unavailable instead of silently selecting a serial route.

Ether adds each batch item's dimension names and values to the effective Prompt Worker or Image Generator prompt. Exact allocation lanes retain their selected provider, profile, model, and count; Ether does not substitute another image provider. Preview the plan to inspect requested and effective concurrency before you run it. Independent batches share the same limits, and cancellation, retry, or recovery does not create extra capacity.


Review, collections, and export



Packaged Ether release capture - Review workspace



Packaged Ether release capture - Artifact Observatory



Packaged Ether release capture - Artifact export dialog

In Review, **Artifact Observatory** provides virtualized **Grid**, **Filmstrip**, **Lineage**, and **Collections** views. Empty search means all document artifacts. Filters cover channels, collections, tags, rating, provider, model, run, graph, output version, and dates. Select artifacts for batch actions or open details for provenance, tags, ratings, and recorded evaluation.

Compare is a human checkpoint: choose candidates, add notes, and complete the decision. It does not call Codex. **Evaluate** sends the visible instruction and rubric to Codex, previews the compiled request, and stores structured criteria, scores, explanations, and model provenance. **Filter** deterministically routes items using visible rules; every result explains the matching or nonmatching rule.

Collections are many-to-many and non-destructive. Create one, route selected artifacts, or mark a collection primary; membership never moves the authoritative embedded artifact. **Export Selected** and **Bulk Export** use an explicit folder grant. Set naming, output format, hierarchy, collision handling, metadata sidecars, and lineage reports in the export dialog.

Live Output is an optional disposable mirror and starts **Disabled**. Select a mirror folder, choose naming (artifact title, node title, or stored template), transfer (copy/move), and collision behavior before enabling it. While enabled, use **Reconcile**, **Rebuild mirror**, **Disable**, or **Remove mirror files**. Removing a mirror never removes embedded originals.

Providers and intelligent work

LOCAL RUNTIME EVIDENCE

Provider Health

Ether reports only routes and capabilities observed by this installed application. It never invents a fallback.

RUNTIME

Unavailable

TRANSPORT

unavailable

VERIFIED PROFILES

0

CHECKED

19:37:10

APPLICATION-OWNED RUNTIME

UNAVAILABLE

codex-chatgpt-image-2

Version

0.146.0-alpha.3.1

Process phase

none

Manifest evidence

579e6d66fe30749682

Restart count

0

Codex App Server reported 0.146.0-alpha.3.1; Ether requires 0.144.2.

CONFORMANCE EVIDENCE

Capability profiles

No verified provider profile is available. Generation controls remain unavailable instead of guessing.

DEFAULT NANO BANANA ROUTE

UNAVAILABLE

Gemini Developer API

DOCUMENT PROVIDER REPORT

UNAVAILABLE

codex-chatgpt-image-2

Codex App Server reported 0.146.0-alpha.3.1; Ether requires 0.144.2.

No telemetry leaves this machine. Health checks inspect local process and conformance evidence.

Check again

Packaged Ether release capture - Provider Health with installed runtime evidence

The Provider section of Image Generator and Image Edit is populated only from discovered, verified capabilities. If none is available, the Inspector says that Ether will not guess settings and leaves the operation unavailable. A released Provider Health surface must report the detected runtime/authentication state and its capability evidence; if that surface or a profile is unavailable, do not infer that the provider can run. Enabled controls never guess a ratio, resolution, output count, reference limit, edit mode, or cancellation feature. A version or executable-hash change invalidates stale evidence until a new conformance probe passes.

ETHER by DreamBay - User Manual 4.0.0

Page 17 of 31

Route	What Ether uses	Honest unavailable state
Codex LLM	Codex App Server where available; visible <code>codex exec</code> fallback when App Server cannot initialize	Worker, Evaluate, and semantic adapters remain unavailable if no authenticated supported Codex runtime exists
Codex Image	installed authenticated Codex subscription route with version-pinned image conformance	no inferred image capability and no hidden paid API fallback
Gemini API (primary Nano Banana)	paid Gemini Developer API, Windows-protected key in Electron main, isolated staged import	unavailable until Connect/Test and protected storage are valid; no provider substitution
Antigravity fallback	official <code>agy.exe</code> , isolated per-attempt staging, explicitly selected verified requested profile	disabled until executable/authentication/conformance and the Antigravity safety confirmation are valid

For Nano Banana, select the **Gemini API** profile unless you deliberately need a document's retained Antigravity fallback binding. In **Settings > Gemini API**, paste a key only into the protected password field and choose **Connect**. Ether immediately clears the field, stores the credential with Windows protection in the main process, and never shows it again. **Test** checks account access without generating an image; **Replace** changes the protected credential; **Remove** removes it. The renderer receives only Not configured, Configured, Verified, Needs replacement, or Protected storage unavailable state.

You can connect without opening a workspace. Close any running Ether window, then launch `Ether.exe --connect-gemini`. Ether opens only the bounded **Connect Gemini to Ether** window, using the same protected main-process store and Connect/Test/Replace/Remove controls as Settings. Enter the key in that window only; never place the key after the option, in a command, environment variable, file, prompt, or log.


Gemini API maps **Nano Banana 2** to `gemini-3.1-flash-image` (0.5K, 1K, 2K, 4K), **Nano Banana Pro** to `gemini-3-pro-image` (1K, 2K, 4K), and **Nano Banana 2 Lite** to `gemini-3.1-flash-lite-image` (1K only). The Image Generator shows the exact structural dimensions for the selected documented ratio, model-specific reference limit, and live-conformed JPEG output format. Google's current guide contains some PNG examples, but the Interactions output-format schema and the paid live service accept JPEG only for this route; the generic PNG image-content entries also apply to image inputs. Ether therefore does not disguise a JPEG as PNG or perform an undisclosed conversion. Ether permits a slow high-resolution call to run for up to five minutes before reporting a timeout, never automatically retries an ambiguous timed-out call, and validates the requested and returned pixels/MIME/hash before import. Google documents SynthID on generated images. Google Search and Google Image Search grounding are off: Ether sends no tool request, so it cannot add grounding charges invisibly. Price guidance is an estimate, not Google billing truth.

Antigravity profiles are **Nano Banana 2**, **Nano Banana Pro**, and **Nano Banana 2 Lite** only as an explicit legacy fallback. Existing `google-nano-banana-*` documents keep that exact selection, but a Gemini API authentication, billing, quota, safety, network, server, timeout, cancellation, or malformed-output error never switches to it. Its CLI image tool accepts aspect ratio but has no resolution parameter, so fallback controls remain only the exact conformed 1K pixels. It never labels that output 2K or 4K. A changed CLI version or executable hash disables stale fallback capabilities until a new probe passes.


Open **Settings > Antigravity safety** after you set the official Antigravity **AI Credit Overages** option to **Never**. Check **I confirmed AI Credit Overages is set to Never in Antigravity** to save that confirmation. Ether disables every Antigravity route while the box is unchecked. Checking it permits only CLI profiles that also pass the installed runtime, authentication, version, and conformance checks. Ether cannot change the Google billing setting for you.

For a Worker, ordinary controls are instruction, behavior, and AI profile. Fast, Balanced, Deep, and Custom resolve to inspectable settings. Advanced contains the actual model, reasoning effort, and variation. Worker output is a new output version; it never rewrites a Prompt or another worker's instruction. Image/audio/video context is sent only if the selected Codex model and adapter capability support it.


Recipes and Codex plugin



Packaged Ether release capture - Recipe Gallery



Packaged Ether release capture - Native Edit Permit confirmation



Packaged Ether release capture - Native exact-plan Run Permit confirmation

Recipes are versioned, executable blueprints. Insert one from the recipe gallery, complete its setup sheet, inspect required capabilities, expected calls/work items, substitutions, and checkpoints, then apply the preview. Insertion is one undoable graph transaction. The 12 included recipes are:

1. Prompt to Image
2. Reference-Guided Image
3. Moodboard to Variations
4. Draft with Lite, Finish with Pro
5. Character Consistency Sheet
6. Product Campaign Set
7. Infographic Builder
8. Image Edit with Mask
9. Reference Description to Prompt
10. Batch Variations and Contact Sheet
11. Evaluate and Route
12. Curate, Collect, and Export

If a required provider is unavailable, the setup sheet offers only a declared supported substitution or blocks honestly. The resulting graph/module remains titled, connected, inspectable, and undoable.

The Ether Codex plugin is an external co-producer, not a second in-app chat. It can inspect document health, catalog and capabilities; inspect/validate a graph; preview/apply a transaction; list/instantiate recipes; inspect artifacts, references, and runs; preview immutable plans; start/cancel/retry only with permission; and inspect recovery.

Permit	Allows	Never allows
Inspect	read document/graph/capabilities/health	mutate graph or execute providers
Edit Permit	apply a previewed graph transaction within its temporary document scope	start a provider or grant itself Run permission

Permit	Allows	Never allows
Run Permit	start one exact immutable plan ID and content hash after desktop approval	a changed plan, broad execution, or self-approval

Use the desktop menu to grant an Edit Permit or approve the exact latest Codex plan. A base-revision conflict returns rebaseable information. The plugin can create prompts, workers, references, generation, review, collections, and export preparation in one transaction, then inspect and repair the graph it created.

Settings, accessibility, and privacy

INSTALLED APPLICATION

Settings

These preferences affect this local Ether interface only. Project content remains inside the active ".ether" document.

Telemetry

Off in Ether 4.0

Diagnostics

Local, bounded, rotating JSONL

Redaction

Credentials, user paths, and personal identifiers

Documents

Never stored in renderer preferences

Gemini API

Primary Nano Banana route — paid Google Gemini Developer API.

Google Search and Google Image Search grounding are off. Ether never sends the key to a child process, document, or diagnostic.

Gemini API key

Paste key only here

Connect

Test

Remove

Connection

Not configured

Key visibility

Never displayed after entry

Cost guidance

Estimates only; Google billing is authoritative

I confirmed AI Credit Overages is set to Never in Antigra

Ether cannot change Google billing. Leave this unchecked until you verify the official Antigra

All Antigra

Recovery

The active document's production recovery report.

State

healthy

Report

No report required

Action

No interrupted operation needs attention.


Local-first: renderer settings contain presentation preferences, never unrestricted paths or provider credentials.

Done

Packaged Ether release capture - Settings with protected Gemini API and fail-closed Antigra

ETHER by DreamBay - User Manual 4.0.0

Page 23 of 31



Packaged Ether release capture - Document saving state

Settings and Provider Health expose capability, diagnostics, recent-document, local layout, protected Gemini connection state, and the persisted Antigravity overage confirmation without granting the renderer unrestricted file or shell access. The optional `--connect-gemini` launch opens only the credential connector and does not start a document workspace or provider background discovery. Gemini credentials are main-process-only Windows-protected values, never document or preference data. Folder choices create scoped grants. Media is delivered through authorized `ether-asset://` document/artifact URLs; arbitrary local paths are not rendered.

Keyboard users can reach document commands, workspace switcher, canvas selection, node/channel controls, Inspector, and Job Center in normal focus order. Use the canvas toolbar for Quick prompt, Quick image, Group, Module, Undo, and Redo. Channel shape is never color-only. Tooltips explain icon commands, nodes, provider limits, policies, presets, and advanced controls. The workspace fills the live Windows content area and smoothly follows maximize, restore, resize, and full-screen changes. Respect Windows scaling at 100%, 125%, 150%, and 200%; reduced-motion settings remove nonessential pulsing/interpolation.

Ether is local-first. Documents, generated artifacts, embedded references, and run evidence stay on the machine. AppData holds only Ether-managed recovery, staging, cache, temporary drag-export, and log material. Logs are bounded/redacted; no telemetry leaves the computer in 4.0. Deleting caches or a Live Output mirror cannot delete document contents.

Examples

Create a reference-guided campaign image

1. Create or open a document; add a Reference Set and Image Generator, or insert **Reference-Guided Image**.
2. Drop source images in Reference Desk, set each relevant role (for example Subject, Style, Colour Palette), and Add them to the set.
3. Connect Text/Subject and Image/Style or Image/Subject lanes to Image Generator. Select the output policy on each lane.
4. In Image Generator, select a verified profile, then only its offered ratio, resolution, and output count.
5. Preview plan. Check provider, references, estimated calls, warnings, and scope. Run in Run workspace.
6. Compare results, approve the chosen output, route it to a Collection, then Export Selected.

Turn a brief into a controlled prompt

1. Add Prompt and LLM Worker. Write the source brief in Prompt.
2. Connect Prompt Text to Worker with Subject. Set Worker behavior to Rewrite, Expand, or Custom and select an AI profile.
3. Preview plan and choose Generate Output. Inspect the immutable version, then Approve, Edit (to create a descendant), or Pin it to a downstream lane.
4. Connect that output to Image Generator. A Negative Text lane remains a negative constraint, never merged into the positive body.

Batch, evaluate, and deliver

1. Insert **Batch Variations and Contact Sheet** or add Batch and Image Generator. Define dimensions and check the exact work count in **Full batch**.
2. In **Provider and model allocation**, assign exact item counts to reachable Worker or Image Generator lanes. Leave the remainder on each node's default provider and model.
3. In **Concurrent run**, keep sequential execution or select up to eight total calls. Ether applies the lower Codex, Gemini API, explicit Antigravity fallback, or unknown-provider cap and injects each item's dimension values into its effective prompt.
4. Use Job Center to cancel eligible work or retry failed items without accepting duplicates. Ether recovers interrupted queued work when the document reopens; terminal jobs have no Resume action.
5. In Review, use Evaluate with a visible rubric, Filter with rules that explain every route, then add accepted artifacts to a collection and bulk export.

Reference index

A: Advanced controls; Antigravity; Artifact Observatory; autosave.

B: Batch Matrix; Build; Bulk Export.

C: channels; collections; Compare; Compact Document; connections; Codex; corruption.

D: Data channel; document; Drawing.

E: Edit; Embed; Ether document; Evaluate; execution policies; Export.

F: Filter; Focus.

G: Generate; graph; Group.

I: Image; Inspector; immutable output.

J: Job Center.

L: legacy folder projects; Live Output.

M: Make Document Portable; Mask; modules.

N: Note.

O: output selectors.

P: permits; plugin; Prompt; provider health.

R: read-only; recovery; Reference Desk; roles; Run.

S: Save As; Save a Copy; selectors; settings.

T: troubleshooting.


V: Video; variables.

W: Worker; workspaces.


For errors and recovery steps, read [Ether 4.0 Troubleshooting](#). For release scope and known capability conditions, read [Ether 4.0 Release Notes](#).

Inspector atlas


These installed-release captures show the ordinary controls for every canonical node. Advanced sections stay subordinate to each node's primary setup and action controls.




Packaged Ether release capture - Prompt Inspector




Packaged Ether release capture - LLM Worker Inspector




Packaged Ether release capture - Reference Set Inspector




Packaged Ether release capture - Image Generator Inspector




Packaged Ether release capture - Image Edit Inspector




Packaged Ether release capture - Mask Inspector




Packaged Ether release capture - Transform Inspector




Packaged Ether release capture - Compare Inspector




Packaged Ether release capture - Evaluate Inspector




Packaged Ether release capture - Filter Inspector




Packaged Ether release capture - Variables Inspector




Packaged Ether release capture - Batch Inspector




Packaged Ether release capture - Join Inspector




Packaged Ether release capture - Collection Inspector



Packaged Ether release capture - Export Inspector



Packaged Ether release capture - Note Inspector



Packaged Ether release capture - Drawing Inspector