Harlequin Dylan

Network Library Documentation

Version 1.1



Copyright and Trademarks

Harlequin Dylan: Network Library Documentation

Version 1.1 September 1998

Copyright © 1998 Harlequin Group plc.

Companies, names and data used in examples herein are fictitious unless otherwise noted.

All Rights Reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without the prior written permission of Harlequin Group plc.

The information in this publication is provided for information only and is subject to change without notice. Harlequin Group plc and its affiliates assume no responsibility or liability for any loss or damage that may arise from the use of any information in this publication. The software described in this book is furnished under license and may only be used or copied in accordance with the terms of that license.

Harlequin is a trademark of Harlequin Group plc.

Dylan is a trademark of Apple Computer, Inc.

Other brand or product names are the registered trademarks or trademarks of their respective holders.

US Government Use

The Harlequin Dylan Software is a computer software program developed at private expense and is subject to the following Restricted Rights Legend: "Use, duplication, or disclosure by the United States Government is subject to restrictions as set forth in (i) FAR 52.227-14 Alt III or (ii) FAR 52.227-19, as applicable. Use by agencies of the Department of Defense (DOD) is subject to Harlequin's customary commercial license as contained in the accompanying license agreement, in accordance with DFAR 227.7202-1(a). For purposes of the FAR, the Software shall be deemed to be `unpublished' and licensed with disclosure prohibitions, rights reserved under the copyright laws of the United States. Harlequin Incorporated, One Cambridge Center, Cambridge, Massachusetts 02142."

Europe:

Harlequin Limited Barrington Hall Barrington Cambridge CB2 5RG U.K.

telephone +44 1223 873 800 fax +44 1223 873 873

North America:

Harlequin Incorporated One Cambridge Center Cambridge, MA 02142 U.S.A.

telephone +1 617 374 2400 fax +1 617 252 6505

Electronic Access:

http://www.harlequin.co.uk/ http://www.harlequin.com/

Contents

 Internet addresses 1 Basic Internet address protocol The <ipv6-address> class 4 The <numeric-address> clas </numeric-address></ipv6-address> Sockets 6 The <abstract-socket> class The <server-socket> class The <tcp-server-socket> cl The <socket> class 10 </socket></tcp-server-socket></server-socket></abstract-socket> 	
The <ipv6-address> class 4 The <numeric-address> clas 3 Sockets 6 The <abstract-socket> class The <server-socket> class The <tcp-server-socket> cl The <socket> class 10</socket></tcp-server-socket></server-socket></abstract-socket></numeric-address></ipv6-address>	
The <abstract-socket> class The <server-socket> class The <tcp-server-socket> cl The <socket> class 10</socket></tcp-server-socket></server-socket></abstract-socket>	
The <server-socket> class The <tcp-server-socket> cl The <socket> class 10</socket></tcp-server-socket></server-socket>	
The <buffered-socket> class The <tcp-socket> class 12</tcp-socket></buffered-socket>	8 ass 9
4 Socket conditions 13 <socket-condition> 13 <socket-error> 14 <recoverable-socket-condition> <socket-accessor-error> 18</socket-accessor-error></recoverable-socket-condition></socket-error></socket-condition>	15

Network Library Reference Documentation

1 Overview

This document covers the Network library. The Network library provides Internet address protocols and TCP/IP server and client sockets. It exports a single module, Network.

The Network library is only available in the Professional and Enterprise editions of Harlequin Dylan.

2 Internet addresses

This section covers Internet address protocols.

2.1 Basic Internet address protocol

This section covers the class <internet-address> and related generic functions and constants.

<internet-address>

Open abstract primary instantiable class

Superclasses: <object>

The class of objects representing Internet addresses used as endpoints for peer-to-peer socket connections.

To construct an <internet-address> object you must supply either the name: or address: keyword. For example:

```
make (<internet-address>, name: "www.whatever.com")
Or
```

make (<internet-address>, address: "9.74.122.0")

make on <internet-address> returns an instance of <ipv4-address>.

Keywords:

name: An instance of <string> representing a symbolic inter-

net address.

address: An instance of <string> representing a presentation

(dotted) form Internet address or an instance of

<numeric-address> (see below).

host-name

Open generic function

host-name internet-address => name

Returns an instance of <string> containing a symbolic host name. The internet-address argument must be an instance of <internet-address>.

Usually the name returned is the canonical host name. Note, however, that the implementation is conservative about making DNS calls. Suppose that the <internet-address> instance was created with the name: keyword and no other information. If the application has not made any other requests that would require a DNS call, such as to host-address or aliases (see below), the name that this function returns will be the one specified with the name: keyword, regardless of whether that is the canonical name or not.

host-address

Open generic function

host-address internet-address => address

Returns an instance of <string> containing the presentation form of the host address. In the case of multi-homed hosts this will usually be the same as:

multi-homed-internet-address.all-addresses.first.host-address

In the case of an Internet address created using the address: keyword it will be either the keyword value or all-addresses.first.host-address.

numeric-host-address

Open generic function

numeric-host-address internet-address => numeric-address

Returns the host address as a <numeric-address>.

all-addresses

Open generic function

all-addresses internet-address => sequence

Returns an instance of <sequence> whose elements are <internet-address> objects containing all known addresses for the host.

aliases

Open generic function

aliases internet-address => sequence

Returns an instance of <sequence> whose elements are instances of <string> representing alternative names for the host.

\$loopback-address

Constant

An instance of <internet-address> representing the loopback address: "127.0.0.1".

\$local-host Constant

An instance of <internet-address> representing the host on which the application using sockets is correctly running.

Note that this value is not necessarily the same as would be created by the expression

```
make (<internet-address>, name: "localhost")
```

The address assigned to the symbolic name localhost is dependent on the configuration of DNS. In some cases this may be configured to be the loopback address rather than a real address for the local host.

2.2 The <IPV6-ADDRESS> class

This name is reserved for future development.

2.3 The <NUMERIC-ADDRESS> class

This section describes numeric Internet representation and associated protocols.

<numeric-address>

Sealed abstract primary class

Superclasses: <object>

The class of objects representing the numeric form of an Internet addresses.

Currently only ipv4 (32-bit) addresses are supported. Ipv6 addresses will be added when they are supported by Winsock2. In general <numeric-address> objects are accessed using the functions host-order or network-order, depending on the context in which they are employed.

network-order

Sealed generic function

network-order address => network-order-address

Returns the value of the numeric address in network order. The argument is a general instance of <numeric-address>. The class of the object returned depends upon the particular subclass of the argument; the network-order method for <ipv4-numeric-address> returns an instance of <machine-word>.

Network order is big-endian byte order.

host-order Sealed generic function

host-order address => host-order-address

Like network-order but returns the value in host order.

Host order is either big-endian byte order on a big-endian host machine and little-endian on a little-endian host machine.

2.3.1 IPV4 addresses

<ipv4-numeric-address>

Open abstract primary instantiable class

Superclasses: <numeric-address>

The single slot of this class contains a 32-bit value representing a ipv4 address. This slot is accessed by the generic functions network-order and host-order described above. <ipv4-numeric-address> has two concrete subclasses <ipv4-network-order-address> and <ipv4-host-order-address>. Make <ipv4-numeric-address> returns one or the other of these depending upon the value of the order: keyword.

Keywords:

value: An instance of <machine-word>. Required.

order: One of #"network-order" or #"host-order". Required.

host-order G.f. method

host-order ip4-numeric-address => machine-word

Returns the numeric address in host order as an instance of <machine-word>. The argument is an instance of <ip4-numeric-address>.

network-order G.f. method

network-order <ipv4-numeric-address> => <machine-word>

Returns the numeric address in network order as an instance of <machine-word>. The argument is an instance of <ip4-numeric-address>.

G.f. method

as string ipv4-numeric-address => string

Returns the presentation (dotted string) form of an instance of <ip4-numeric-address>.

<ipv4-network-order-address>

Sealed concrete class

Superclasses: <ipv4-numeric-address>

Concrete subclass for network-order numeric addresses.

make(<ipv4-network-order-address>)

is equivalent to

make(<ipv4-numeric-address>, order: network-order)

<ipv4-host-order-address>

Sealed concrete class

Superclasses: <ipv4-numeric-address>

Concrete subclass for host order numeric addresses.

3 Sockets

This section describes socket classes and protocols.

3.1 The <ABSTRACT-SOCKET> class

<abstract-socket>

Open abstract uninstantiable free class

Superclasses: <object>

The common superclass of all socket objects including <socket> (IP client socket), <server-socket> and <socket-accessor>.

Keywords:

socket-descriptor:

A Windows handle or UNIX fd (file descriptor) for the socket. In general users of the sockets API should not need to use this keyword. Only implementors of new socket classes should be interested.

Each subclass of <abstract-socket> must provide methods for close and for the following generic functions:

local-port

Open generic function

local-port socket => port-number

Returns the local port number for an instance of <socket>, <datagram-socket> or <server-socket>. The return value is an instance of <integer>.

socket-descriptor

Open generic function

socket-descriptor socket => descriptor

Returns the descriptor (handle or fd) for the socket. The argument is an instance of <abstract-socket> and the return value an instance of <accessor-socket-descriptor>.

local-host

Open generic function

local-host socket => host-address

Returns the address of the local host. The argument is an instance of <abstract-socket> and the return value an instance of <internet-address>.

3.2 The <SERVER-SOCKET> class

<server-socket>

Open abstract primary instantiable class

Superclasses: <abstract-socket>

Server-sockets listen on a specified port for connection requests which come in over the network. Either the port: or service: keyword must be supplied.

Keywords:

service: An instance of <string> containing an abstract name

for a service with a "well-known" port, such as "ftp" or "daytime". Valid names depend on the configuration

of the DNS. Required unless port: is supplied.

port: An instance of <integer> identifying the port on which

the <server-socket> should listen for connection requests. Required unless service: is supplied.

protocol: An instance of <string> naming the protocol. Cur-

rently "tcp" is the only supported protocol. You can create instances of protocol-specific subclasses as an alternative to using the protocol: keyword. For example, make(server-socket>, protocol: "tcp", ...) is

equivalent to make(<TCP-server-socket>, ...).

make on (<server-socket>) returns an instance of

<tcp-server-socket> by default.

accept Open generic function

accept server-socket #key => result

Blocks until a connect request is received. Returns a connected instance of <socket>. The particular subclass of <socket> returned depends on the actual class of the argument, which must be a general instance of

<server-socket>. Calling accept on <tcp-server-socket> returns a
connected <tcp-socket>.

with-server-socket Macro

```
with-server-socket (server-var [:: server-class], keywords)
body
end;
```

Creates an instance of <server-socket>, using the (optional) server-class argument and keyword arguments to make the <server-socket>, and binds it to the local variable named by server-var. The body is evaluated in the context of the binding and the <server-socket> is closed after the body is executed.

start-server Macro

Enters an infinite while (#t) accept loop on the server socket. Each time accept succeeds the <socket> returned from accept is bound to socket-var and the body is evaluated in the context of the binding. When body exits, accept is called again producing a new binding for socket-var. The optional keywords are passed to the call to accept.

3.3 The <TCP-SERVER-SOCKET> class

<tcp-server-socket>

Concrete primary sealed class

Superclass: <server-socket>

The class of TCP server sockets. A server socket is an object which listens for requests for connections from the network. When accept is called on the server socket and a request for connection is detected, accept returns a connected <socket>.

Keywords:

element-type: Establishes a new default for the element-type of <TCP-socket> instances returned by calling accept with this server socket as the argument to accept. This default element-type may be overridden for any particular call to accept by using the element-type: keyword to accept. If no element-type: is specified when the server socket is created, <byte-character> is used as the default element-type.

G.f. method accept

accept server-socket :: <tcp-server-socket>, #key element-type => connected-socket

This method on accept returns a connected instance of <tcp-socket>. The element-type: keyword controls the element type of the <tcpsocket> (stream) returned from accept. If the keyword is not supplied, the default value used is #f.

3.4 The <SOCKET> class

socket

Open abstract free instantiable class

Superclasses: <abstract-socket>, <external-stream>

The class of general client sockets. All client sockets are streams.

Keywords:

direction:

Specifies the direction of the stream. It must be one of #"input", #"output", and "#input-output". This keyword is an inherited streams class keyword. See the Streams library documentation in the *System and I/O* library reference for a full description.

element-type: An instance of <class>. Useful values are <bytecharacter> and <byte>. This keyword is an inherited streams class keyword. See the Streams library documentation in the *System and I/O* library reference for a full description.

3.5 The <BUFFERED-SOCKET> class

<buf>
detect

detect

detect

detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect
detect<b

Open abstract free class

Superclasses: <socket>, <double-buffered-stream>

Socket streams whose elements are bytes or characters. These inherit buffering protocols and the implications of read, write, read-element, write-element, force-output and suchlike methods from <doublebuffered-stream>.

Keywords:

force-output-before-read?:

An instance of <boolean>. Defaults value: #t. The methods which implement the stream reading protocols (read, read-line, read-element and so on) for instances of <socket> call force-output by default before blocking. This is to ensure that any pending output has been sent to the peer before the socket blocks waiting to read data sent by the peer. This corresponds to the expected, usual behavior of singlethreaded client sockets and avoids deadlock in usual cases. Multi-threaded applications, particularly applications where one thread is reading and another thread is writing to the same socket, may wish to inhibit the default force-output. If the socket is created with force-output-before-read?: as #f. force-output Will not be called before the read functions block.

3.6 The <TCP-SOCKET> class

The class of TCP client sockets.

<tcp-socket>

Abstract primary sealed class

Superclasses: <buffered-socket>

The class of TCP client sockets.

Keywords:

Of the keywords below, host: and one of either service: or port: are required.

host: An instance of <internet-address> or <string>. The

remote host to connect to. The <string> may be either a host name or a presentation-form Internet address.

Required.

service: An instance of <string>. A <string> containing an

abstract name for a service with a "well-known" port, such as "ftp" or "daytime". Valid names depend on the configuration of the DNS. Required unless port: is

supplied.

protocol: An instance of <string> naming the protocol. Cur-

rently "tcp" is the only supported protocol. You can create instances of protocol-specific subclasses as an alternative to using the protocol: keyword. For example make(<socket>, protocol: "tcp", ...) is equivalent to make(<TCP-socket>, ...). make on <socket> returns an instance of <tcp-server-socket> by default.

port: An instance of <integer> representing the remote port

to connect to. Required unless service: is supplied.

element-type: An instance of <class>. Useful values for <tcpstreams> are <byte-character> and <byte>. This keyword is an inherited streams class keyword. See the
Streams library documentation in the System and I/O

library reference for a full description.

remote-port

Open generic function

remote-port socket => port-number

Returns the remote port number for a <socket>. The value returned is an instance of <integer>.

remote-host

Open generic function

remote-host socket => remote-host-address

Returns the remote host for a <socket>. The value returned is an instance of <internet-address>.

4 Socket conditions

This section lists the socket condition classes in the Network library.

4.1 < socket-condition>

All socket conditions are packaged into general instances of <socket-condition>. Some conditions are considered recoverable and others not.

<socket-condition> Condition

Superclasses: <simple-condition>

The class of socket conditions. It inherits the format-string: and format-arguments: keywords from <simple-condition>.

Slots:

socket-condition-details

Most socket conditions originate in error return codes from Harlequin Dylan's Winsock2 library, an FFI interface to the native socket library Winsock2.

The socket-condition-details slot provides information about the low-level failure which was the source for the condition. In most cases this slot will hold an instance of <socket-accessor-condition>, below.

When creating general instances of <socket-condition>, you can use the details: keyword to set the value for this slot.

4.2 <socket-error>

The class <socket-error> is the superclass of all unrecoverable socket conditions.

<socket-error> Condition

Superclasses: <socket-condition>

The class of socket conditions from which no recovery is possible.

4.2.1 <internal-socket-error>

The class <internal-socket-error> is the class of unexpected socket errors.

<internal-socket-error>

Condition

Superclasses: <socket-error>

The class of unexpected errors from Harlequin Dylan's Winsock2 library, an FFI interface to the native socket library Winsock2.

Inspect the contents of the socket-condition-details slot for more information.

4.3 <recoverable-socket-condition>

The <recoverable-socket-condition> class is the general class of socket conditions for which an application may be able to take some remedial action.

<recoverable-socket-condition>

Condition

Superclasses: <socket-condition>

The general class of socket conditions for which an application may be able to take some remedial action.

For instance, a web browser receiving such conditions as <connection-refused> or <host-not-found> (see below) would normally expect to report those conditions to the user and continue with some other connection request from the user, while a server receiving a <connection-closed> condition from a connected <socket> would probably close the <socket> and continue to handle other requests for connections.

4.3.1 <network-not-responding>

<network-not-responding>

Condition

Superclasses: <recoverable-socket-condition>

The network — probably a local network — is down. Try again later.

4.3.2 <invalid-address>

<invalid-address> Condition

Superclasses: <recoverable-socket-condition>

A badly formed address string has been passed to a function trying to make an <internet-address>.

4.3.3 <host-not-found>

<host-not-found> Condition

Superclasses: <recoverable-socket-condition>

The Domain Name Server (DNS) cannot resolve the named host or internet address. Try again with a different (correct) name or address.

4.3.4 <server-not-responding>

<server-not-responding>

Condition

Superclasses: <recoverable-socket-condition>

The Domain Name Server (DNS) did not respond or returned an ambiguous result. Try again.

4.3.5 < host-unreachable >

<host-unreachable> Condition

Superclasses: <recoverable-socket-condition>

The remote host cannot be reached from this host at this time.

4.3.6 < socket-closed>

<socket-closed> Condition

Superclasses: <recoverable-socket-condition>

The socket or server socket has been closed.

Most operations on closed instances of <TCP-socket> return instances of <stream-closed-error> (from the Streams library) rather than instances of <socket-closed>.

4.3.7 < connection-failed>

<connection-failed> Condition

Superclasses: <recoverable-socket-condition>

The attempt to connect to the remote host was not successful. Connection failed for one of the following reasons: because the connect request timed out or because it was refused, or because the remote host could not be reached.

4.3.8 <connection-closed>

<connection-closed> Condition

Superclasses: <recoverable-socket-condition>

The connection to the remote host has been broken. The socket should be closed. To try again, open a new socket.

4.3.9 <address-in-use>

<address-in-use> Condition

Superclasses: <recoverable-socket-condition>

A process on the machine is already bound to the same fully qualified address. This condition probably occurred because you were trying to use a port with an active server already installed, or a process crashed without closing a socket.

4.3.10 <blooking-call-interrupted>

 discontinuous continuous c

Condition

Superclasses: <recoverable-socket-condition>

A blocking socket call, like read, write or accept, was interrupted.

4.3.11 <out-of-resources>

<out-of-resources> Condition

Superclasses: <recoverable-socket-condition>

The implementation-dependent limit on the number of open sockets has been reached. You must close some sockets before you can open any more. The limits for Windows NT (non-server machines) and Windows 95 are particularly small.

4.4 < socket-accessor-error>

<socket-accessor-error>

Condition

Superclasses: <socket-error>

An implementation-specific error from the C-FFI interface to the native socket library. Usually instances of this class these appear in the socket-condition-details slot of another <socket-condition>.

4.4.1 <win32-socket-error>

<win32-socket-error> Condition

Superclasses: <socket-accessor-error>

A Win32-specific error from the Winsock2 library, a C-FFI interface to the native socket library Winsock2. A function in the FFI library has returned an error return code.

Slots:

WSA-numeric-error-code

Contains the numeric error code that was returned. An instance of <integer>.

WSA-symbolic-error-code

Contains an instance of <string> giving the symbolic (human-readable) form of the error code. For example, the string might be "wsanotsock".

EXPLANATION An explanation if any of the error. An instance of <string>.

calling-function

The name of Winsock2 FFI interface function which returned the error code. An instance of <string>.

Network Library Reference Documentation