mysql 5.7二进制安装 (Percona)

```
rpm --help
rpm -qa | grep mysql
rpm -e --nodeps mysql-libs-5.1.71-1.el6.x86_64
rpm -qa | grep mysql
tar -xvf Percona-Server-5.7.11-4-Linux.x86_64.ssl101.tar.gz
cd Percona-Server-5.7.11-4-Linux.x86 64.ss1101
创建用户:
groupadd mysql
useradd -r -g mysql mysql
创建数据库目录:
mkdir -p /usr/local/mysql : 安装目录
mkdir -p /mysqldata/ : 数据目录
mkdir -p /var/log/mysql/ : 日志目录
下载boost:
安装插件:
yum install readline-devel git gcc gcc-c++ make cmake bison bison-devel ncurses-devel libaio-devel perl
编译安装:
\verb|cmake| - DCMAKE_INSTALL_PREFIX=/usr/local/mysq1 \setminus
-DMYSQL_UNIX_ADDR=/mysqldata/mysql.sock \setminus
-DWITH_BOOST=/usr/local/mysq1/boost \ --??? What for????
-DDEFAULT_CHARSET=utf8 \
-DWITH_MYISAM_STORAGE_ENGINE=1 \
-DWITH INNOBASE STORAGE ENGINE=1 \
-DWITH ARCHIVE STORAGE ENGINE=1 \
-DWITH_BLACKHOLE_STORAGE_ENGINE=1 \
-DWITH_EDITLINE=bundled \
-DENABLED_LOCAL_INFILE=1 \
-DMYSQL DATADIR=/mysqldata \
-DMYSQL TCP PORT=3306 \
-DZLIB_INCLUDE_DIR:PATH=/usr/include \
-DENABLE_DOWNLOADS=1
make -j 8
make install
初始化数据库:
./bin/mysqld --initialize-insecure --user=mysql --basedir=/usr/local/mysql --datadir=/mysqldata --innodb\_undo\_tablespaces=3 --basedir=/usr/local/mysqldata --initialize-insecure --user=mysql --basedir=/usr/local/mysql --datadir=/mysqldata --initialize-insecure --user=mysql --basedir=/usr/local/mysql --datadir=/mysqldata --initialize-insecure --user=mysql --basedir=/usr/local/mysql --datadir=/mysqldata --initialize-insecure --user=mysql --basedir=/usr/local/mysql --datadir=/mysqldata --initialize-insecure --user=mysql --basedir=/user=mysql --ba
./bin/mysql\_ssl\_rsa\_setup \ --user=mysql \ --basedir=/usr/local/mysql \ --datadir=/mysqldata
配置mysq1启动服务:
cp support-files/mysql.server /etc/init.d/mysql
chmod +x /etc/init.d/mysql
chkconfig mysql on:配置myslq开机自动启动
service mysql start : 启动mysql
```

```
vi /etc/profile
添加以下:
export PATH=/usr/local/mysql/bin:$PATH
source /etc/profile
设置mysql root用户密码:
mysql -u root
set password=password('root');
默认root只允许本地访问
use mysql
select user, host from user where user='mysteel';
授予root远程连接权限(生产环境慎用)
grant all privileges on *.* to 'root'@'%' identified by 'mysteel' with grant option;
防火墙配置:
默认3306端口未启用,启用3306端口:
vi /etc/sysconfig/iptables
在-A INPUT -m state --state NEW -m tcp -p tcp --dport 22 -j ACCEPT后面加入以下内容
-A INPUT -m state --state NEW -m tcp -p tcp --dport 3306 -j ACCEPT
重新启动防火墙:
service iptables restart
```