Gemini Web User Guide

1.2.0.BUILD-20120109114932

Copyright © 2009, 2010 VMware Inc. and others

Contributors:

- VMware Inc. initial contribution
- Violeta Georgieva, SAP AG Tomcat context configuration

Table of Contents

| 1. Overview | 1 |
|--|---|
| 1.1. Introduction | 1 |
| 1.2. About This Guide | 1 |
| 2. Installing Gemini Web | |
| 2.1. Prerequisites | |
| 2.2. Installing from the ZIP Download | 3 |
| 3. Configuration | |
| 3.1. Configuring the Embedded Tomcat Servlet Container | |
| 3.2. Configuring the OSGi Framework | |
| \mathcal{C} | |

iv User Guide

Overview 1

1. Overview

1.1 Introduction

1.2 About This Guide

This User Guide contains step-by-step instructions on how to use Gemini Web Container. This User Guide will enable you to:

- Install Gemini Web Container
- Deploy and request a simple web application
- Configure Tomcat
- Configure OSGi Framework

2 Overview

2. Installing Gemini Web

2.1 Prerequisites

The Gemini Web Container, or GW for short, requires Java SE 6 or later to be installed. Java is available from http://www.java.com/ and elsewhere.

2.2 Installing from the ZIP Download

- <u>Download</u> the Equinox JAR, for example <u>org.eclipse.osgi 3.6.0.v20100517.jar</u>, and move it to a suitable directory (e.g. ~/gemini-web-test). On the <u>Download</u> page, first choose the desired Release or Build, then download the JAR from the Framework section.
- Gemini Web Container is distributed as a ZIP file. <u>Download</u> Gemini Web Container and unzip it to ~/gemini-web-test/gemini-web.
- Configure Equinox by creating a directory ~/gemini-web-test/configuration and create files config.ini and Java6-server.profile in the configuration directory. Example files which work with 1.1.0.RELEASE are available in config.ini.zip and Java6-server.profile.zip. Essentially config.ini ensures that Java6-server.profile is used and that the dependencies of Gemini Web Container, which come in the dep directory, are installed and then the Gemini Web Container bundles are installed and started. Java6-server.profile ensures that javax.xml.ws is exported at version 2.1.1 from the system bundle as the Tomcat bundles in Gemini Web Container depend on that version.
- Start Equinox as follows:

```
java -jar org.eclipse.osgi_3.6.0.v20100517.jar -console
```

• You can then deploy WAR files (a trivial example is available in <u>Simple-war.war.zip</u>) and web bundles using the install and start commands from the console.

```
osgi> install file:simple-war.war
Bundle id is 40
osgi> start 40
```

- Drive the WAR or web bundle using a web browser, e.g. http://localhost:8080/simple-war should display "Hello World!".
- Stop Gemini Web Container as follows:

osgi> close



Tip

You need to stop any old instance of Gemini Web before starting it again. Otherwise, the new instance will not start correctly, because the old one still

occupies the http port (and, perhaps, other system resources).

3. Configuration

3.1 Configuring the Embedded Tomcat Servlet Container

Gemini Web Container embeds an OSGi-enhanced version of the <u>Tomcat Servlet Container</u> in order to provide support for deploying Java EE WARs and OSGi Web Application Bundles. You configure the embedded Servlet container using the standard Apache Tomcat configuration. The main difference is that the configuration file is called tomcat-server.xml rather than server.xml. Another difference is that not all standard Apache Tomcat configuration is supported in Gemini Web Container: the restrictions are described in the remainder of this section. If you do not want to use the default settings, you can provide the tomcat-server.xml file located in the \$GW_HOME/config directory.

Here's an extract of the default configuration distributed with the GW.

Description of the Default Apache Tomcat Configuration

The following bullets describe the main elements and attributes in the default tomcat-server.xml file; for details about updating this file to further configure the embedded Apache Tomcat server, see the <u>Apache Tomcat Configuration Reference</u>.



Relative paths

If the configured path to a directory or file does not represent an absolute path, GW typically interprets it as a path relative to the \$GW_HOME directory.

• The root element of the tomcat-server.xml file is <Server>. The attributes of this element represent the characteristics of the entire embedded Tomcat servlet container. The shutdown attribute specifies the command string that the shutdown port number receives via a TCP/IP connection in order to shut down the servlet container. The port attribute specifies

the TCP/IP port number that listens for a shutdown message.

• The <Listener> XML elements specify the list of lifecycle listeners that monitor and manage the embedded Tomcat servlet container. Each listener class is a Java Management Extensions (JMX) MBean that listens to a specific component of the servlet container and has been programmed to do something at certain lifecycle events of the component, such as before starting up, after stopping, and so on.

• The <Service> XML element groups together one or more connectors and a single engine. Connectors define a transport mechanism, such as HTTP, that clients use to send and receive messages to and from the associated service. There are many transports that a client can use, which is why a <Service> element can have many <Connector> elements. The engine then defines how these requests and responses that the connector receives and sends are in turn handled by the servlet container; you can define only a single <Engine> element for any given <Service> element.

The sample tomcat-server.xml file above includes two <Connector> elements: one for the HTTP transport, and one for the AJP transport. The file also includes a single <Engine> element, as required.

- The first connector listens for HTTP requests at the 8080 TCP/IP port. The connector, after accepting a connection from a client, waits for a maximum of 20000 milliseconds for a request URI; if it does not receive one from the client by then, the connector times out. If this connector receives a request from the client that requires the SSL transport, the servlet container automatically redirects the request to port 8443.
- The second AJP Connector element represents a Connector component that communicates with a web connector via the AJP protocol.
- The engine has a logical name of Catalina; this is the name used in all log and error messages so you can easily identify problems. The value of the defaultHost attribute refers to the name of a <Host> child element of <Engine>; this host processes requests directed to host names on this servlet container.
- The <Host> child element represents a virtual host, which is an association of a network name for a server (such as www.mycompany.com) with the particular server on which Catalina is running.
- Note that multiple <Host> elements are not supported in Gemini Web Container.

Connector Configuration

The Gemini Web Container supports the configuration of any connector supported by Apache Tomcat. See the default configuration above for syntax examples, and for further details of the configuration properties supported for various <Connector> implementations, consult the official Tomcat HTTP Connector documentation. For detailed instructions on how to configure Tomcat's SSL support, consult the official Tomcat SSL Configuration HOW-TO.

Cluster Configuration

Gemini Web Container supports standard Apache Tomcat cluster configuration. By default, clustering of the embedded servlet container is disabled, and the default configuration does not include any clustering information. See <u>Tomcat Clustering/Session Replication HOW-TO</u> for detailed information about enabling and configuring clustering.

Default web.xml Configuration

Java Servlet specification enables web applications to provide deployment descriptor (web.xml) in the WEB-INF directory. Apache Tomcat introduces a default web.xml which is similar to web application's web.xml, but provides configurations that are applied to all web applications. When deploying a web application, Apache Tomcat uses the default web.xml file as a base configuration. If the web application provides its own configurations via web.xml (the one located in the web application's WEB-INF) or annotations, they overwrite the default ones. In Gemini Web Container you can also provide default configurations for all web applications. If you want to change/extend the default configurations, you can provide the default web.xml file located in the \$GW_HOME/config directory.



Tip

Be careful when changing/extending the default web.xml as this will affect all web applications.

Here's an extract of the default configuration distributed with the GW.

```
<?xml version="1.0" encoding="ISO-8859-1"?>
<web-app xmlns="http://java.sun.com/xml/ns/javaee"
   xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
    xsi:schemaLocation="http://java.sun.com/xml/ns/javaee http://java.sun.com/xml/ns/javaee/web-app_3_0.xsd
    version="3.0">
         servlet-name>default</servlet-name>
        <servlet-class>org.apache.catalina.servlets.DefaultServlet</servlet-class>
        <init-param>
            <param-name>debug</param-name>
            <param-value>0</param-value>
        </init-param>
        <init-param>
            <param-name>listings</param-name>
            <param-value>false</param-value>
        <load-on-startup>1</load-on-startup>
    </servlet>
    <servlet>
        <servlet-name>jsp</servlet-name>
        <servlet-class>org.apache.jasper.servlet.JspServlet</servlet-class>
        <init-param>
            <param-name>fork</param-name>
            <param-value>false</param-value>
        </init-param>
        <init-param>
            <param-name>xpoweredBv</param-name>
            <param-value>false</param-value>
        </init-param>
        <load-on-startup>3</load-on-startup>
    </servlet>
    <servlet-mapping>
        <servlet-name>default</servlet-name>
        <url-pattern>/</url-pattern>
```

```
</servlet-mapping>
    <servlet-mapping>
    <servlet-name>jsp</servlet-name>
    <url-pattern>*.jsp</url-pattern>
</servlet-mapping>
    <servlet-mapping>
   <session-config>
        <session-timeout>30</session-timeout>
    </session-config>
    <mime-mapping>
        <extension>abs</extension>
        <mime-type>audio/x-mpeg</mime-type>
    </mime-mapping>
    <mime-mapping>
        <extension>ppt</extension>
        <mime-type>application/vnd.ms-powerpoint</mime-type>
    </mime-mapping>
    <welcome-file-list>
        <welcome-file>index.html</welcome-file>
        <welcome-file>index.htm</welcome-file>
<welcome-file>index.jsp</welcome-file>
    </welcome-file-list>
</web-app>
```

The following bullets describe the main elements in the default web.xml file.

- The <Servlet> XML element declares a given servlet and its configurations. The sample web.xml file above includes two <Servlet> elements.
 - The default servlet serves static resources and processes the requests that are not mapped to any servlet. For details about default servlet configuration, see the Apache Tomcat Default Servlet Reference..
 - The jsp servlet serves the requests to JavaServer Pages. It is mapped to the URL pattern "*.jsp" and "*.jspx". For details about jsp servlet configuration, see the <u>Apache Tomcat Jasper 2 JSP Engine.</u>
- The <servlet-mapping> XML element specifies the mapping between the servlet and URL pattern.
- The <session-config> XML element defines the session configuration for one web application. The sample web.xml file above specifies that the session timeout for all web applications will be 30 minutes by default.
- The <mime-mapping> XML element defines a mapping between a filename extension and a mime type. When serving static resources, a "Content-Type" header will be generated based on these mappings.
- The <welcome-file-list> XML element specifies a list of welcome files. When a request URI refers to a directory, the default servlet looks for a "welcome file" within that directory. If the "welcome file" exists it will be served, otherwise 404 status or directory listing will be returned, depending on the default servlet configuration.

Context Configuration

Gemini Web Container supports standard Apache Tomcat web application context configuration. The <u>Apache Tomcat Configuration Reference</u> has a section on <u>The Context Container</u> which describes the mechanism that is used in GW for searching context configuration files and details the context configuration properties.

Context configuration files may be placed in the following locations, where [enginename] is the name of Tomcat's engine ('Catalina' by default) and [hostname] names a virtual host ('localhost' by default), both of which are configured in tomcat-server.xml:

- \$GW_HOME/config/context.xml provides the default context configuration file for all web applications.
- The \$GW_HOME/config/[enginename]/[hostname] directory may contain:
 - The default context configuration for all web applications of a given virtual host in the file context.xml.default.
 - Individual web applications' context configuration files as described in the Apache Tomcat Configuration Reference. For example, the context for a web application with context path foo may be configured in foo.xml.

Note that the following context configuration features are not supported in Gemini Web Container:

- · Custom class loaders.
- Specifying the context path. This is specified using the Web-ContextPath header in the web application's MANIFEST.MF file.
- Specifying the document base directory.

JNDI Resources

By default Gemini Web Container supports standard Apache Tomcat JNDI Resources handling. The <u>Apache Tomcat JDNI Resources How-To</u> describes in details how the JNDI resources can be configured and used.

In addition to that feature Gemini Web Container provides a possibility to switch off the standard Apache Tomcat JNDI Resources handling or to use the OSGi one. One can specify the preferred option using -DuseNaming with one of the following options:

- tomcat the default value: this is the standard Apache Tomcat JNDI Resources handling.
- disabled there is no JDNI Resources handling provided by Gemini Web Container.

osgi - the OSGi JNDI Resource handling will be enabled. (Gemini Naming can be used as implementation for OSGi JNDI Services Specification) The OSGi JNDI Services
 Specification describes in details how JNDI can be utilized from within an OSGi framework.
 One can use either osgi URL scheme in order to look up an OSGi service, or java URL scheme - a feature provided by Gemini Web Container. If java URL scheme is chosen then additional configuration is necessary to be provided via context.xml.

```
<Context>
<Resource name="LogService"
    type="org.osgi.service.log.LogService"
    mappedName="service/org.osgi.service.log.LogService"
    factory="org.eclipse.gemini.web.tomcat.naming.factory.OsgiServiceFactory"/>
</Context>
```

The list below describes in details the different properties:

- name The name of the resource that will be created. The name should be relative to the java:comp/env context.
- type The fully qualified Java class name of the resource (OSGi service) that web application will expect when it performs a lookup or when it uses @Resource annotation.
- mappedName the service/s that should be looked up and the filter details if any. The syntax can be seen in OSGi JNDI Services Specification: 126.6 OSGi URL Scheme.
- factory The class name for the JNDI object factory. Gemini Web Container provides a special JNDI object factory in order to be able to obtain an OSGi service.

3.2 Configuring the OSGi Framework

This section provides information about configuring the OSGi framework by updating the following files in the \$GW_HOME/configuration directory:

Table 3.1. OSGi Framework Configuration Files

| Property File | Description | |
|----------------------|---|--|
| config.ini | Configures the OSGi framework properties. | |
| java6-server.profile | Configures the OSGi framework profile. | |

Configuring OSGi Framework Properties

You specify the framework properties in the \$GW_HOME/configuration/config.ini file. The properties relevant to users are described in the following table.

Table 3.2. Framework Properties

| Property | Description | |
|-------------------|---|----------|
| osgi.bundles | The comma-separated list of bundles which are automatically installed and optionally started once the system is up and running. | |
| osgi.java.profile | Specifies the profile to use using a file: URI with default value file:configuration/java6-server. | profile. |

Configuring OSGi Framework Profile

You specify the framework profile in the \$GW_HOME/configuration/java6-server.profile file. The properties relevant to users are described in the following table.

WARNING: We advise you not to change the framework profile unless you are sure you know exactly what you are doing; updating the profile could cause GW to fail.

Table 3.3. Framework Profile Properties

| Property | Description |
|----------------------------------|---|
| org.osgi.framework.bootdelegatio | This property specifies the packages which are loaded by delegation to the application class loader. Bundles can load classes belonging to these packages without importing the packages. The .* wildcard matches any package suffix. java.* is always boot delegated and must not be specified in this property. Note that the ordering of the packages does not matter. |
| org.osgi.framework.system.packag | This property specifies the packages which are exported by the system bundle. It is very occasionally necessary to extend the set, for example when configuring email logging appenders since the implementation of javax.mail is intimately related to the implementation of javax.activation. |