

Easy POS

User Manual

Point of sale · Customer credit · Profit reports · Automatic backup

Contents

1. Installing and starting
2. Signing in and first-time setup
3. Company settings, logo, advertisement and footer
4. Creating items (cost price and selling price)
5. Making a sale – the POS screen
6. Keyboard shortcuts
7. Customers and credit
8. Printing and receipt printers
9. Sales list, reprint and void
10. Expenses and profit reports
11. Users and permissions
12. Backup and restore
13. Moving to a new computer
14. Troubleshooting

1. Installing and starting

1. Double-click **EasyPOS-Setup-1.0.0.exe**.
2. Choose the install folder (or keep the default) and click **Install**.
3. Open **Easy POS** from the Desktop or Start menu shortcut.

> No internet and no database software are needed. All your data is stored in one file on this computer: `%APPDATA%\Easy POS\data\pos-data.json`. Uninstalling the program does not delete your data.

2. Signing in and first-time setup


On first start sign in with username **admin** and password **admin**. Immediately go to **Settings → My account** and change the password.

Recommended order for a new shop:

1. Settings → enter company details, upload logo, choose paper size and printer, click **Save settings**.
2. Items → add your products.
3. Users → add cashiers.
4. Customers → add credit customers (optional; you can also add them while selling).

Use the left menu to move between pages (or `Alt` + `1` … `8`). **Theme** switches light/dark mode. **Logout** signs the user out. `F11` toggles full screen.

3. Company settings




Open **Settings** (administrator only) and fill in:

Field	What it does
Company name, address, email, contact no., website	Printed at the top of every receipt and invoice.
Upload logo	Choose a PNG/JPG. It is resized automatically and shown on receipts, invoices and in the menu. **Remove** clears it.
Advertisement / promo message	A short advert (e.g. “Buy 2 get 1 free – visit www.myshop.com”) printed near the bottom of every bill.
Invoice footer	Closing text such as “Thank you! Goods once sold are not returnable.”
Paper / printer type	58 mm thermal, 80 mm thermal or A4 invoice.
Printer	Choose a specific printer or use the Windows default.
Currency symbol, tax name and %	Tax is added to the bill total. Leave 0 for no tax.

Print after every sale / Print directly	Automatic printing with or without the Windows print dialog.
POS rules	Allow selling when stock is 0; let cashiers change prices or give discounts.

Click **Print test receipt** to preview the layout. Always click **Save settings** after changes.

4. Creating items




Go to **Items → + New item**.

Field	Meaning
Barcode / code	Scan the product barcode here. Leave blank to auto-create a code.
Item name	Required.
Category	Used for the filter buttons on the POS screen.
Cost price	What you pay the supplier. Used to calculate profit. Cashiers cannot see it.
Selling price	What the customer pays. The profit per unit and margin % are shown live.


Stock on hand / Low-stock alert	Quantity in the shop. Items at or below the alert level are highlighted red.
Track stock	Untick for services or items without stock counting.

- **+ Stock** adds received goods (and optionally updates the cost price).
- **Edit** changes an item. **✕** deletes it; items already sold are only deactivated so old reports stay correct.


5. Making a sale – the POS screen



1. Add items: **scan a barcode**, type a name and press `Enter`, or click an item card. Use the category buttons to filter.
2. Adjust quantity with **– / +** or type in the box. The price can be changed per line (if allowed).
3. Choose the customer with `F3` (leave as Walk-in for cash customers).
4. Add a discount with `F4` – an amount or a percentage.
5. Press `F9` (**PAY**) to open the payment window.



Payment window: pick **Cash / Card / Online / Credit**, type the amount received (or use the quick buttons). The window shows the **change** to give back, or the amount that will go on **credit**. Press `Enter` to complete the sale.



A big **change** display appears after the sale and the receipt prints automatically (if enabled). Press `Enter` for the next customer.


- **Quick cash (F10)** – exact cash payment and print in one key.
- **Hold (F6) / Recall (F7)** – park a bill while serving another customer, then bring it back.
- **Clear (F8)** – empty the bill.

6. Keyboard shortcuts

Key	Action
`F1`	Show shortcut help
`F2`	Focus the search / barcode box
`Enter` in search	Add exact barcode match, or the first search result
`F3`	Choose or create customer
`F4`	Bill discount
`↑` `↓`	Select a bill line
`+` / `−`	Increase / decrease quantity of the selected line (search box must be empty)
`*`	Type the quantity of the selected line
`Delete`	Remove the selected line
`F6` / `F7`	Hold bill / Recall held bill
`F8`	Clear bill
`F9`	Payment
`F10`	Quick cash sale and print
`Ctrl`+`P`	Reprint last receipt
`Esc`	Close a window / clear search
`Alt`+`1`…`8`	Switch pages
`F11`	Full screen

> With a USB barcode scanner, keep the cursor in the search box (press `F2`). Each scan adds the item automatically because scanners send `Enter` after the code.

7. Customers and credit



Create a customer in **Customers → + New customer**, or press `F3` on the POS screen and click **+ New customer**. Optional fields: credit limit (0 = no limit) and opening balance (money the customer already owes).

Selling on credit: select the customer, press `F9`, then either choose **Credit** (whole bill on credit) or type a smaller amount received – the remainder is added to the customer's balance. A customer is required for any credit sale, and the sale is refused if the credit limit would be exceeded.

Receiving money: Customers → 💵 **Receive** → enter the amount and method. The balance goes down and a payment receipt can be printed.

Ledger: shows every credit sale and payment with a running balance. The top of the Customers page shows the total you still have to collect.

8. Printing and receipt printers


- **Small thermal printers (POS printers):** install the printer driver in Windows, then in Settings choose **58 mm** or **80 mm** and select the printer.
- **A4 printers:** choose **A4 invoice** for a full-page invoice with item table.
- Tick **Print directly** to print without the Windows dialog (best for the counter). Untick it to choose a printer every time.

- If the receipt is cut off or too wide, check the paper size matches the printer roll and that the driver paper size is the roll width.

9. Sales list, reprint and void

Sales lists invoices for a date range with search. Click **View / Print** to preview and reprint any invoice. Administrators can **Void** a sale: stock is returned and any credit is removed from the customer. Voided sales show **VOID** and are excluded from reports.

10. Expenses and profit reports



Expenses (rent, electricity, salaries…) are entered under **Expenses → + Add expense**. They are subtracted to give net profit.


Reports (administrator only) – choose a quick range (Today, Yesterday, Last 7 days, This month, …) or custom dates, then a tab:

Tab	Shows
Profit summary	Bills, sales, cost of goods, **gross profit**, expenses, **net profit**, discounts, tax, credit given, payments received, margin %, and a daily chart.
Item profit	Quantity, revenue, cost and profit for every item, best first.
Daily	Sales and profit per day.

By cashier	Sales and profit per user.
Stock value	Stock at cost and at selling price, low-stock items.
Customer credit	Everyone who owes money and how much.

Profit = selling price − cost price of the items sold, after discounts (tax is not counted as profit). **Export CSV** opens in Excel.

11. Users and permissions



Role	Can do
Administrator	Everything: items and cost prices, reports, expenses, users, settings, backups, voiding sales.
Cashier	POS, customers and credit payments, view/reprint own sales. Cannot see cost price or profit.

Users → **+ New user**: enter name, username, password and role. Editing a user with a blank password keeps the old password. A user who has made sales is disabled instead of deleted. At least one active administrator must always exist.

12. Backup and restore

In **Settings → Backup**:

- **Backup folder** – click **Browse…** to choose where backups go (default `Documents\EasyPOS-Backups`). Choosing a USB drive or a synced cloud folder (OneDrive, Google Drive) is recommended.
- **Automatic backup** – runs every N minutes when data has changed, every time the program starts and when it closes. The last N backups are kept; older ones are removed automatically.
- **Backup now** – instant manual backup. **Open folder** shows the backup files in Windows Explorer.
- **Restore** – click Restore next to a backup in the list, or **Restore from file…** to pick one. A safety backup of the current data is made first, then you sign in again.

> Always keep at least one backup on a different drive than the computer's own disk.

13. Moving to a new computer

1. On the old PC, copy the newest `pos-backup-….json` file from the backup folder.
2. Install Easy POS on the new PC and sign in with admin / admin.
3. Settings → Backup → **Restore from file…** → choose the file.

14. Troubleshooting

Problem	Solution
Forgot the admin password	Ask another administrator to reset it in Users. If there is none, restore an old backup made while the password was known.
Nothing prints	Check the printer works in Windows, select it in Settings, and try **Print test receipt**. Untick “Print directly” to see the Windows dialog and any error.
Barcode not found	Make sure the item's code in Items matches the barcode exactly and the item is Active.
“Credit limit exceeded”	Receive a payment from the customer or raise the limit in Customers → Edit.
“Select a customer to sell on credit”	Press `F3` and choose a customer before paying.

Backup warning in Settings	The backup folder may be unavailable (drive removed or full). Choose another folder.