

Easy POS

User Manual

Point of sale · Customer credit · Profit reports · Automatic backup

Contents

1. Installing and starting
2. Signing in and first-time setup
3. Company settings, logo, advertisement and footer
4. Creating items (cost price and selling price)
5. Making a sale – the POS screen
6. Keyboard shortcuts
7. Customers and credit
8. Printing and receipt printers
9. Sales list, reprint and void
10. Expenses and profit reports
11. Inventory: stock levels, adjustments and the inventory log
12. Suppliers and GRN (goods received)
13. Supplier payments
14. Daily cash book
15. Editing a saved bill on the POS screen
16. Users and permissions
17. Backup and restore
18. Moving to a new computer
19. Theme and appearance
20. Troubleshooting

1. Installing and starting

1. Double-click **EasyPOS-Setup-1.0.0.exe**.
2. Choose the install folder (or keep the default) and click **Install**.
3. Open **Easy POS** from the Desktop or Start menu shortcut.

> No internet and no database software are needed. All your data is stored in one file on this computer: `%APPDATA%\Easy POS\data\pos-data.json`. Uninstalling the program does not delete your data.

Installing on a Mac

1. Use **EasyPOS-1.0.0-mac-arm64.dmg** for Apple-silicon Macs (M1, M2, M3, M4) or **EasyPOS-1.0.0-mac-x64.dmg** for Intel Macs (Apple menu → About This Mac shows which you have).
2. Open the DMG and **drag Easy POS onto the Applications folder**, then open it from Applications or Launchpad.

3. The app is not signed with an Apple Developer certificate, so the **first time** macOS may refuse to open it. **Right-click (or Control-click) the app → Open → Open**. If you see "damaged", open **Terminal** and run: `xattr -cr "/Applications/Easy POS.app"`, then open it again. (Or: System Settings → Privacy & Security → **Open Anyway**.)
4. Your data is stored in `~/Library/Application Support/Easy POS/data/pos-data.json`; backups go to `Documents/EasyPOS-Backups` unless you choose another folder.

> On Mac laptops the `F1`–`F12` keys control brightness/volume by default. Hold `Fn` with the key (e.g. `Fn`+`F9` to pay), or turn on "Use F1, F2, etc. keys as standard function keys" in System Settings → Keyboard. `Cmd` works for copy/paste/quit; `Ctrl`+`P` reprints the last receipt.

2. Signing in and first-time setup


On first start sign in with username **admin** and password **admin**. Immediately go to **Settings → My account** and change the password.

Recommended order for a new shop:

1. Settings → enter company details, upload logo, choose paper size and printer, click **Save settings**.
2. Items → add your products.
3. Users → add cashiers.
4. Customers → add credit customers (optional; you can also add them while selling).

Use the left menu to move between pages (or `Alt`+`1`…`9`). **Theme** switches light/dark mode. **Logout** signs the user out. `F11` toggles full screen.

3. Company settings




Open **Settings** (administrator only) and fill in:

Field	What it does
Company name, address, email, contact no., website	Printed at the top of every receipt and invoice.
Upload logo	Choose a PNG/JPG. It is resized automatically and shown on receipts, invoices and in the menu. **Remove** clears it.
Advertisement / promo message	A short advert (e.g. “Buy 2 get 1 free – visit www.myshop.com”) printed near the bottom of every bill.
Invoice footer	Closing text such as “Thank you! Goods once sold are not returnable.”
Paper / printer type	58 mm thermal, 80 mm thermal or A4 invoice.
Printer	Choose a specific printer or use the Windows default.
Currency symbol, tax name and %	Tax is added to the bill total. Leave 0 for no tax.
Print after every sale / Print directly	Automatic printing with or without the Windows print dialog.

POS rules	Allow selling when stock is 0; let cashiers change prices or give discounts.

Click **Print test receipt** to preview the layout. Always click **Save settings** after changes.

4. Creating items




Go to **Items → + New item**.

Field	Meaning
Barcode / code	Scan the product barcode here. Leave blank to auto-create a code.
Item name	Required.
Category	Used for the filter buttons on the POS screen.
Cost price	What you pay the supplier. Used to calculate profit. Cashiers cannot see it.
Selling price	What the customer pays. The profit per unit and margin % are shown live.
Stock on hand / Low-stock alert	Quantity in the shop. Items at or below the alert level are highlighted red.


Track stock	Untick for services or items without stock counting.

- **+ Stock** adds received goods (and optionally updates the cost price).
- **Edit** changes an item. **✕** deletes it; items already sold are only deactivated so old reports stay correct.


Item categories and filters



Create categories: on the **Items** page click 🗀 **Categories**. Type a name and press `Enter` to add. **Rename** changes the name on every item that uses it. **✕** (click twice to confirm) deletes the category – its items are kept and become “Uncategorised”.




Select a category on an item: in the item form, pick it from the **Category** drop-down. Need a new one? Click **+ New** beside the drop-down, type the name and press `Enter` – it is created and selected immediately.




Filters: the Items page has a filter bar – **Search**, **Category** (with item counts), **Stock** (In stock / Low / Out of stock) and **Status** (Active / Inactive / All). **✕ Clear** resets them. The same Category filter is available in **Inventory → Stock levels** and **Reports → Item profit**. On the POS screen the category buttons above the item grid filter the items you sell.


5. Making a sale – the POS screen



1. Add items: **scan a barcode**, type a name and press `Enter`, or click an item card. Use the category buttons to filter.
2. Adjust quantity with **– / +** or type in the box. The price can be changed per line (if allowed).
3. Choose the customer with `F3` (leave as Walk-in for cash customers).
4. Add a discount with `F4` – an amount or a percentage.
5. Press `F9` (**PAY**) to open the payment window.



Payment window: pick **Cash / Card / Online / Credit**, type the amount received (or use the quick buttons). The window shows the **change** to give back, or the amount that will go on **credit**. Press `Enter` to complete the sale.



A big **change** display appears after the sale and the receipt prints automatically (if enabled). Press `Enter` for the next customer.


- **Quick cash (F10)** – exact cash payment and print in one key.
- **Hold (F6) / Recall (F7)** – park a bill while serving another customer, then bring it back.
- **Clear (F8)** – empty the bill.

6. Keyboard shortcuts

Key	Action
`F1`	Show shortcut help
`F2`	Focus the search / barcode box
`Enter` in search	Add exact barcode match, or the first search result
`F3`	Choose or create customer
`F4`	Bill discount
`↑` `↓`	Select a bill line
`+` / `−`	Increase / decrease quantity of the selected line (search box must be empty)
`*`	Type the quantity of the selected line
`Delete`	Remove the selected line
`F5`	Edit a saved bill in the POS screen
`F6` / `F7`	Hold bill / Recall held bill
`F8`	Clear bill
`F9`	Payment
`F10`	Quick cash sale and print
`Ctrl` + `P`	Reprint last receipt
`Esc`	Close a window / clear search
`Alt` + `1` … `9`	Switch pages
`F11`	Full screen

With a USB barcode scanner, keep the cursor in the search box (press `F2`). Each scan adds the item automatically because scanners send `Enter` after the code.

7. Customers and credit



Create a customer in **Customers → + New customer**, or press `F3` on the POS screen and click **+ New customer**. Optional fields: credit limit (0 = no limit) and opening balance (money the customer already owes).

Selling on credit: select the customer, press `F9`, then either choose **Credit** (whole bill on credit) or type a smaller amount received – the remainder is added to the customer's balance. A customer is required for any credit sale, and the sale is refused if the credit limit would be exceeded.

Receiving money: Customers → 💵 **Receive** → enter the amount and method. The balance goes down and a payment receipt can be printed.

Ledger: shows every credit sale and payment with a running balance. The top of the Customers page shows the total you still have to collect.

8. Printing and receipt printers


- **Small thermal printers (POS printers):** install the printer driver in Windows, then in Settings choose **58 mm** or **80 mm** and select the printer.
- **A4 printers:** choose **A4 invoice** for a full-page invoice with item table.
- Tick **Print directly** to print without the Windows dialog (best for the counter). Untick it to choose a printer every time.

- If the receipt is cut off or too wide, check the paper size matches the printer roll and that the driver paper size is the roll width.

9. Sales list, reprint and void

Sales lists invoices for a date range with search. Click **View / Print** to preview and reprint any invoice. Administrators can **Void** a sale: stock is returned and any credit is removed from the customer. Voided sales show **VOID** and are excluded from reports.

10. Expenses and profit reports



Expenses (rent, electricity, salaries…) are entered under **Expenses → + Add expense**. They are subtracted to give net profit.


Reports (administrator only) – choose a quick range (Today, Yesterday, Last 7 days, This month, …) or custom dates, then a tab:

Tab	Shows
Profit summary	Bills, sales, cost of goods, **gross profit**, expenses, **net profit**, discounts, tax, credit given, payments received, margin %, and a daily chart.
Item profit	Quantity, revenue, cost and profit for every item, best first.
Daily	Sales and profit per day.

By cashier	Sales and profit per user.
Stock value	Stock at cost and at selling price, low-stock items.
Customer credit	Everyone who owes money and how much.


Profit = selling price – cost price of the items sold, after discounts (tax is not counted as profit). **Export CSV** opens in Excel.

Expense categories




Expenses can be grouped by category (Rent, Electricity, Water, Salaries, Transport, Maintenance, Marketing, Other are provided). On **Expenses** click 🗔 **Categories** to add, rename or delete categories. In the **Add expense** form choose the **Expense category** from the drop-down (or **+ New** to create one on the spot).

The Expenses page filters by **date, category and text**, and shows the total plus the biggest categories as cards. **Reports → Expense categories** lists each category with its entries, amount and share of total expenses; **Reports → Category profit** shows sales, cost and profit for each *item* category.




11. Inventory: stock levels, adjustments and the log




Inventory → Stock levels shows every item with quantity, alert level and stock value at cost and selling price. Low-stock items are red.

⚖ **Adjust / Count** corrects stock: **Set counted qty** (stock-take – type what you counted), **Add**, or **Remove**. Choose a reason (damaged, expired, lost, customer return…) and an optional note. The window shows the new stock before you save.



Inventory → Inventory log records every stock movement: sales, voided sales, GRN received, voided GRN, adjustments, bill edits and opening stock. Each line shows the change, stock *before → after*, reference number, user and note. Filter by dates, type or item, and export to CSV. The **Log** button on a stock row opens the history of just that item.


12. Suppliers and GRN (goods received)



1. **Purchases → Suppliers → + New supplier** (name, phone, address, and an opening balance if you already owe them).
2. **Purchases → GRN → + New GRN**. Pick the supplier, date and the supplier's invoice number.
3. Type an item name or scan its barcode and press `Enter` to add it. For each line enter **quantity**, **cost price** and optionally a **new selling price**.
4. Enter a discount, the amount **Paid now** (**Full** pays everything) and the payment method. Whatever is not paid is added to the supplier's balance.
5. Click **Save GRN**. Stock increases, the item cost price is updated (untick the box to keep old costs), and an entry is written to the inventory log.


Open a GRN with **View** to see its lines. Administrators can **Void** a GRN – the stock is removed again.

13. Supplier payments



The **Suppliers** tab shows how much you owe each supplier and the total payable. Use 💸 **Pay** to record a payment (cash, bank, cheque or online), with a date and a note such as the cheque number. **Ledger** shows all purchases and payments with a running balance. The **Supplier payments** tab lists every payment for a period (and lets you delete a wrong entry). Cash payments automatically appear in the cash book.


14. Daily cash book



Cash Book shows the cash drawer for one day: **opening cash → cash in → cash out → closing cash**. Use ◀ ▶ or the date box to change day.


Cash IN	Cash OUT
Cash sales, customer payments received in cash, GRN refunds, manual “Cash in”	Cash paid on GRN, supplier payments in cash, cash expenses, sale refunds (voids), manual “Cash out” (bank deposit, drawings…)

- **+ Cash in / − Cash out** – record money that is not a sale or expense (owner capital, bank deposit, petty cash).
- **⚙ Opening balance** – set the cash that was in the drawer when you started using the program (do this once).
- **🔒 Close day / count cash** – type the cash you counted. The program shows *over* or *short* against the expected closing cash and saves it.
- Card, bank and online payments are listed separately below the table because they are not in the drawer. Credit sales are not cash until the customer pays.



The **Day-wise summary** tab lists opening, in, out, closing, counted cash and difference for every day. Click a date to open that day's book.

15. Editing a saved bill on the POS screen




If a bill was entered wrongly you can correct it without leaving the POS screen:

1. Press `F5` (or the ✏️ button on the bill panel, or **Sales → ✏ Edit**). Choose the bill from the list – or type the invoice number and press `Enter`.
2. The bill opens in the normal bill panel with a yellow **"Editing INV-..."** banner. Change quantities, prices, items, customer or discount exactly as when selling.
3. Press `F9` and **Save changes**. Stock, customer credit, cash book and profit are all corrected automatically, and the stock changes are written to the inventory log.
4. Use **Cancel edit** to leave the bill unchanged.

The invoice number and original date stay the same; edited bills show an **EDITED** tag in the Sales list. Administrators can always edit bills; cashiers only if you tick **Settings → Cashier can edit own saved bills**. Voided bills cannot be edited.

16. Users and permissions



Role	Can do
Administrator	Everything: items and cost prices, inventory, GRN and suppliers, cash book, reports, expenses, users, settings, backups, voiding sales.
Cashier	POS, customers and credit payments, view/reprint own sales (edit them only if allowed). Cannot see cost price, profit, purchases, inventory log or cash book.

Users → **+ New user**: enter name, username, password and role. Editing a user with a blank password keeps the old password. A user who has made sales is disabled instead of deleted. At least one active administrator must always exist.

17. Backup and restore

In **Settings → Backup**:


- **Backup folder** – click **Browse…** to choose where backups go (default `Documents\EasyPOS-Backups`). Choosing a USB drive or a synced cloud folder (OneDrive, Google Drive) is recommended.
- **Automatic backup** – runs every N minutes when data has changed, every time the program starts and when it closes. The last N backups are kept; older ones are removed automatically.
- **Backup now** – instant manual backup. **Open folder** shows the backup files in Windows Explorer.
- **Restore** – click Restore next to a backup in the list, or **Restore from file…** to pick one. A safety backup of the current data is made first, then you sign in again.

> Always keep at least one backup on a different drive than the computer's own disk.


18. Moving to a new computer

1. On the old PC, copy the newest `pos-backup-….json` file from the backup folder.
2. Install Easy POS on the new PC and sign in with admin / admin.
3. Settings → Backup → **Restore from file…** → choose the file.

19. Theme and appearance



Click 🎨 **Theme** (left menu or top bar) to choose **Light / Dark** mode, the **Style** – **Desktop** (flat panels, grid tables, window-style dialogs, like a classic desktop program) or **Rounded** (soft modern cards) – the **Density** (**Comfortable** or **Compact** for small screens and long lists) and one of six accent colours. The top bar shows where you are and the date/time; the bottom status bar shows the signed-in user, shop name, last backup and the time. Your choices are remembered on this computer.



> Easy POS is **powered by ECODES IT SOLUTIONS — https://ecodes.lk**. The credit is shown on the login screen, the menu, the POS screen and Settings, and can be printed on receipts (Settings → POS rules → "Print Powered by...").

20. Troubleshooting

Problem	Solution
Forgot the admin password	Ask another administrator to reset it in Users. If there is none, restore an old backup made while the password was known.
Nothing prints	Check the printer works in Windows, select it in Settings, and try **Print test receipt**. Untick "Print directly" to see the Windows dialog and any error.
Barcode not found	Make sure the item's code in Items matches the barcode exactly and the item is Active.
"Credit limit exceeded"	Receive a payment from the customer or raise the limit in Customers → Edit.
"Select a customer to sell on credit"	Press `F3` and choose a customer before paying.
Backup warning in Settings	The backup folder may be unavailable (drive removed or full). Choose another folder.