

PUSH POSSIBLE®

30 SEPTEMBER 2026

CONFIGURATION GUIDE

SCALE



 **Manhattan**
Associates®

Table of Contents

DOCUMENT REVISION HISTORY	1
INITIAL NOTES.....	2
OVERVIEW	3
1. CONFIGURATION PROCESS	4
1.1 TECHNICAL VALUES	4
1.2 WAREHOUSE.....	5
1.2.1 Country	5
1.2.2 Warehouse.....	5
1.2.3 Company	6
1.2.4 Users	7
1.3 INVENTORY CONTROL	9
1.3.1 Zone Type	9
1.3.2 Zone	9
1.3.3 Units of Measure	11
1.3.4 Location Type.....	12
1.3.5 Location Status	13
1.3.6 Location Class	13
1.3.7 Location Template	14
1.3.8 Location	14
1.3.9 Storage Template.....	17
1.3.10 Item Class	18
1.3.11 Item	19
1.3.12 Item Unit of Measure	20
1.3.13 Item Categories	22
1.3.14 Item Cross Reference	25
1.3.15 Item Location Capacity	26
1.3.16 Item Location Assignment	27
1.3.17 Inventory Control Values.....	27
1.3.18 Inventory status.....	28
1.3.19 Adjustment type	29
1.3.20 Inventory transfer work criteria and Inventory adjustment work criteria	29
1.4 RECEIVING.....	30
1.4.1 Putaway location group	30
1.4.2 Location selection	31
1.4.3 Locating rule	32
1.4.4 Locating rule assignment criteria.....	33
1.4.5 Location rule assignment	34
1.4.6 Disposition Code	35
1.4.7 Receipt ID type.....	36
1.4.8 RF receiving check in initiation	36
1.4.9 Receiving preferences.....	37
1.4.10 Work group.....	38
1.4.11 Work type	39
1.4.12 Work profile	40
1.4.13 Receipt work criteria	41
1.4.14 Work Creation master	42


1.5	WORK	42
1.5.1	Work system values	43
1.5.2	Work type	44
1.5.3	Work criteria	44
1.5.4	Work creation master	47
1.5.5	Work profile	48
1.5.6	Work special handling	50
1.6	OUTBOUND	51
1.6.1	Outbound Status Action	52
1.6.2	Functional area	53
1.6.3	Custom status flow	54
1.6.4	Carrier	57
1.6.5	Dock area management carrier assignment	59
1.6.6	Dock management flow	59
1.6.7	Dock area anchor criteria	61
1.6.8	Packing preferences	63
1.6.9	Shipping preferences	64
1.6.10	Planned Shipment Filters – Not used	65
1.6.11	Comment Type - Not used	65
1.7	ALLOCATION	66
1.7.1	Allocation rule assignment criteria	66
1.7.2	Allocation location selection	67
1.7.3	Allocation rule	68
1.7.4	Allocation rule assignment	69
1.8	WAVE	70
1.8.1	Container type	71
1.8.2	Override data	71
1.8.3	Wave steps	72
1.8.4	Wave flow	73
1.8.5	Wave maximums	74
1.8.6	Wave criteria	75
1.8.7	Wave master	75
1.9	VALUE ADDED SERVICES	76
1.10.1	VAS activity criteria	76
1.10.2	VAS Activity	76
1.10	CYCLE COUNTING	77
1.10.1	Cycle count system values	77
1.10.2	Cycle count Preferences	78
1.10.3	Cycle count item criteria	78
1.10.4	Cycle count location criteria	79
1.10.5	Cycle count master	81
1.10.6	Cycle count threshold	82
1.10.7	Cycle count work criteria	83
1.11	WORK ORDERS	84
1.11.1	Bill of materials	84
1.11.2	Work order preferences	84
1.11.3	Work order system values	85
1.11.4	Work order finished item work criteria	85
1.11.5	Work order component work criteria	85

1.12 REPLENISHMENT	85
1.12.1 Replenishment location criteria	86
1.12.2 Replenishment item criteria	87
1.12.3 Replenishment empty location criteria	88
1.12.4 Replenishment master	89
1.12.5 Replenishment work criteria	90
1.13 CONTAINER CREATION	91
1.13.1 Container creation system values	92
1.13.2 Container creation criteria	92
1.13.3 Container Class	93
1.13.4 Container type	94
1.13.5 Container Group	94
1.13.6 Packing class	94
1.14 QUALITY CONTROL (QC)	95
1.14.1 QC assignment criteria	96
1.14.2 QC evaluation method	96
1.14.3 QC assignment	97
1.15 INTERFACES	97
1.15.1 Interface system values	98
1.15.2 Interface data maps (not required if XML)	98
1.15.3 Interface process	99
1.15.4 Interface upload criteria	102
1.15.5 Carrier Interface	102
1.16 DOCUMENT PRINTING	104
1.16.1 Shipment data selection	104
1.16.2 Document master	104
1.16.3 Document Type	104
1.16.4 Document	105
1.16.5 Label master	106
1.16.6 Document routing	107
CONCLUSION	108
LINKS AND DOCUMENTATION	108



DOCUMENT REVISION HISTORY



Date	Changed By	Version	Notes
29 JULY 2022	RAPHAEL COLOMBEL	1.0	INITIAL DOCUMENT CREATION
29 JULY 2023	BRANDON REITZ / TABOUBI KHALLOULI WIEM	1.1	INITIAL DOCUMENT CREATION



INITIAL NOTES

The version of SCALE used in this project is SCALE 2020, meaning some parts of this report might differ according to the version of SCALE used.

The document "Manhattan SCALE - Configuration Flow Diagrams", which can be found [here](#) (URL still valid on 29 July 2022) was used as a reference to build this report. All the figures, except if mentioned otherwise, are taken from the report, and follow the color code defined in the following table.


KEY	
	Requires Configuration
	Optional Configuration
	Related Configuration

OVERVIEW

The process of building the SCALE configuration can be divided into different functional areas. The following are the main functional areas: Items, Locations, Inventory Management, Receiving, Work, Outbound Flow, Allocation, Wave, Cycle Counting, Work Orders, Replenishment, Container Creation (sometimes called Cubing) and Quality Check (also known as QC). Not all functional areas are required, for example, some warehouses do not have replenishment flows and would not require configuration in this functional area.

These functional areas are sometimes interconnected. Therefore, it is advised to follow a certain order when creating the configuration, as some steps require the definition of certain parameters beforehand. It is not compulsory to follow the order defined in this document although it is recommended. This document serves as a reference for how to use the configuration tool and how the functional areas communicate with one another.

If, at any time, additional information is required (regarding a folder or a field in the configuration), you can go to the Help Window or AIM, as shown in the following figures.



1. CONFIGURATION PROCESS

1.1 Technical Values

Prior to starting with the basic process of warehouse configuration, technical values need to be verified. These do not apply to functional processing, instead, they manage path names, audit log activity, filter record maximums, and other technical details. These values should only be changed by a technical expert. There is support documentation available on AIM for each of these fields. The highlighted values below are typically updated for each new environment.

Configurations

File Actions View Help

Technical values

Configuration	Description	System value	System created	Key
DO NOT CHANGE! Max Rows for Database Lim...	10000	Yes	320	
Default System Language	en-US	Yes	80	
Folder storing documents for FedEx Rating Soft...		Yes	480	
Folder storing labels for FedEx Rating Software		Yes	450	
Folder storing templates for docs, labels, emails	https://uhadstgmei46.file.core.windows.net/its/Printing	Yes	170	
Is audit of try/catch blocks active?	Y	Yes	40	
Is audit processing active?	N	Yes	30	
Leaf container commit size	500	Yes	490	
Max Size of a Printed File for Wave Labels (KB)	1024	Yes	270	
Metadata export scripts directory	https://uhadstgmei46.file.core.windows.net/its/Export	Yes	430	
Missing Manifest Exception logged	N	Yes	330	
MSMQ cluster		Yes	420	
Name or IP Address of the Reporting Server.	westeuropessrsstg.manhscale.com	Yes	140	
Notification Message Template Directory	https://uhadstgmei46.file.core.windows.net/its/NotificationTemplate	Yes	400	
Number of concurrent Allocation threads	4	Yes	10	
Number of concurrent Complete Wave threads	4	Yes	50	
Number of concurrent container creation queues	4	Yes	60	
Number of concurrent Replenishment threads	4	Yes	290	
Number of concurrent Routing threads	4	Yes	150	
Number of concurrent Ship Confirm threads	4	Yes	260	
Number of concurrent wave label generation qu...	2	Yes	250	
Number of concurrent work creation threads	4	Yes	240	
Number of records displayed in configs	1000	Yes	190	
Number of records displayed in insight and look...	5000	Yes	160	
Number of records to trigger filter in configs	1000	Yes	180	
Number of threads per item download batch	1	Yes	470	
Order Entry limit for Ship To/Item retrieval	1000	Yes	110	
Personal Alerts Path	https://uhadstgmei46.file.core.windows.net/its/Printing	Yes	310	
Record Limit for Data Retrieval web service	1000	Yes	230	
RF Style Sheet	RFStylesMedium.css	Yes	340	
SQL Server Reporting Services Report Server U...	http://westeuropessrsstg.manhscale.com/ReportServer	Yes	360	
SRC file path	https://uhadstgmei46.file.core.windows.net/its/Screen Flows	Yes	440	
SSRS Application Template Directory	https://uhadstgmei46.file.core.windows.net/its/Reporting/SSRS	Yes	380	
SSRS Report Manager Upload Folder	https://uhadstgmei46.file.core.windows.net/its/Reporting/SSRS	Yes	390	
System Currency Symbol	\$	Yes	70	
Time between user activity checks (in minutes)	30	Yes	200	
Time the printing engine sleeps (in seconds)	1	Yes	130	
URL load balancer server name	uhadstg.manhscale.com	Yes	410	
Workflow Directory	https://uhadstgmei46.file.core.windows.net/its/Workflow	Yes	350	

1.2 Warehouse


A common starting point for SCALE configuration is with the warehouse, then the company and the users. In this section we detail the steps to configure these functional areas.

1.2.1 Country

First, we start by reviewing the list of countries. Select the country in which the warehouse is located and ensure that it is active.

Refer to the following image and note the configuration file path [Functional areas -> Rating/routing -> General rating/routing -> Country].


2



Identifier	Description	System value 1	System created	Active
FR	France	FRANCE	Yes	Yes
GB	United Kingdom	UNITED_KINGDOM	Yes	Yes
US	United States	UNITED_STATES	Yes	Yes
AF	Afghanistan	AFGHANISTAN	Yes	No
AL	Albania	ALBANIA	Yes	No
DZ	Algeria	ALGERIA	Yes	No
AS	American Samoa	AMERICAN_SAMOA	Yes	No
AD	Andorra	ANDORRA	Yes	No
AO	Angola	ANGOLA	Yes	No
AI	Anguilla	ANGUILLA_ISLANDS	Yes	No
AG	Antigua & Barbuda	ANTIGUA	Yes	No
AR	Argentina	ARGENTINA	Yes	No
AM	Armenia	ARMENIA	Yes	No


Commented [BR1]: Is the list going be larger? we only have 3 active countries

Select **France** (by right clicking and choosing **Open**) and verify that the **Inactive** checkbox is unchecked.




1.2.2 Warehouse

Warehouses [User/warehouse -> Warehouse] represent the physical building where items are stored prior to their distribution for sale. To create a warehouse, navigate to the correct menu option, right click the **Warehouse** menu option, or right click anywhere in the right-hand pane, select **New**, and enter the relevant information. Switch to the **Interface** tab, check the first two checkboxes.




Warehouse: 001
 Description: Cambrai
 Time zone: (UTC+01:00) Brussels, Copenhagen, Ma.
 Returns address: ☐ Returns address | ☐ Freight bill to address | ☒ Interface | ☐ Authorized users | ☐ Miscellaneous | ☐ User defined data
 Address 1: Bat 2 avenue de France, zone e-valley
 Address 2 (optional):
 Address 3 (optional):
 City, state postal code: 62860 Epinoy
 Country: France Fax number:
 Attention to: Phone number:
 Email address: test@manh.com
 UCC/EAN number:
☐ Inactive
 Last updated: 2/7/2022 2:09:33 PM User: rcolombel




Warehouse: 001
 Description: Cambrai
 Time zone: (UTC+01:00) Brussels, Copenhagen, Ma.
☒ Upload receipt lines with 0 quantity received
☒ Upload closed receipts with 0 quantity received
☐ Split consolidated shipments on upload
☐ Inactive
 Last updated: 2/7/2022 2:09:33 PM User: rcolombel

In the **Authorized Users** tab, it is important to make sure that the only users with access are the users that will be working in this warehouse. This is especially critical when a single environment will have multiple warehouses configured. Lastly, in the **Miscellaneous** tab, update the path of the **Rendered pdf file directory**, where SQL Server Reporting Services will save rendered (created) pdf files. Make sure the **Inactive** checkbox is **unchecked**. Click **OK**.



Warehouse: 001
 Description: Cambrai
 Time zone: (UTC+01:00) Brussels, Copenhagen, Ma.
☒ apoulain ☒ Haddad02 ☒ mpachins ☒
☒ ehompson ☒ Haddad03 ☒ ndeive ☒
☒ leval ☒ LUSSEV ☒ ndjemourne ☒
☒ bsausage ☒ jbellytzhalla ☒ ngrassindalphone ☒
☒ celbrek ☒ jelliot ☒ plachesse ☒
☒ chupport ☒ Inedig ☒ parnieves ☒
☒ dcarvelli ☒ lsmth ☒ qclmentine ☒
☒ Haddad01 ☒ messupport ☒ rcolombel ☒
☐ Inactive
 Last updated: 2/7/2022 2:09:33 PM User: rcolombel




Warehouse: 001
 Description: Cambrai
 Time zone: (UTC+01:00) Brussels, Copenhagen, Ma.
☒ Interface | ☒ Authorized users | ☒ Miscellaneous | ☐ User defined data
 Starting move file download dir.:
 Default location for unslotted:
 SQL Server Reporting Services:
 Rendered document pdf file directory: https://uhadstgmei46 file core windows.n
☐ Inactive
 Last updated: 2/7/2022 2:09:33 PM User: rcolombel

1.2.3 Company



Companies [User/warehouse -> Company] are unique entities that ship product from the warehouse, usually under their own brand name. The system can support multiple companies in one warehouse. Each company can have its own customer base and item(s) in the system. This is particularly useful for 3PL application, as it enables the definition of unique item/company and customer/company relationships in the same warehouse. For example, the same item in the warehouse can be associated with two different companies and SCALE would be able to track this item independently for each company.

Navigate to the **Company** menu option, **Right click** and select **New**. Fill in the relevant information in all the tabs (some of this might be repetitive and contain the same input as for the warehouse section above).



Commented [BR2]: Needed ?


Switch to the **Interface** tab, check the first two checkboxes. In the **Assigned Users** tab, it is important to make sure that the only users with access are the users that will be working in the warehouse where this company is created. This is especially critical when a single environment will have multiple warehouses configured. Make sure the **Inactive** checkbox is **unchecked**. Click **OK**.

1.2.4 Users

All employees using the application must have a User defined in the system. To define a new user, navigate to the **User profile** [User/warehouse -> User profile] menu option, **right click** and select **New**. Once a user profile is defined, SCALE will recognize the employee in the system. SCALE references the username to identify an employee for such things as assigning work and tracking productivity, among other things.

Choose a short and easily recognizable **Username**, for example, a common naming convention is first initial and last name. Fill in the corresponding **Email address** belonging to this user. Choosing a **default warehouse** will configure the system to associate the selected warehouse with the user each time they access SCALE. **Preferences** can be defined to speed up warehouse processes. For example, set the receiving preference for a user that will always be following the same receiving flow, so that they can skip one step in the RF menu.



User profile - Edit existing

Username: rcolombel
Description: rcolombel

General | Preferences | Company access | Warehouse access | Work profile

Default warehouse: 001 Email address: rcolombel@manh.com


Department:

Security information
Security group: Vocollect passw... |

Payroll information
Payroll id: Wage rate: 0.0000
Hire date: 5/10/2006

☐ Inactive

Last updated: 6/22/2022 1:06:17 PM User: rcolombel



User profile - Edit existing

Username: rcolombel
Description: rcolombel

General | Preferences | Company access | Warehouse access | Work profile

Processing
Cycle counting: Shipping
Packing: Work order:
Receiving:


Default printers
Default document: Default label printer:

System
Desktop template: Default template
RF style sheet:
Excel export direct:

☐ Inactive

Last updated: 6/22/2022 1:06:17 PM User: rcolombel

Most importantly, grant the user access to the correct companies and warehouses through the **Company access** and **Warehouse access** tabs.



User profile - Edit existing

Username: rcolombel
Description: rcolombel


General | Preferences | Company access | Warehouse access | Work profile

Company authorization
All List

Tracked

☐ Inactive

Last updated: 6/22/2022 1:06:17 PM User: rcolombel



User profile - Edit existing

Username: rcolombel
Description: rcolombel

General | Preferences | Company access | Warehouse access | Work profile


Warehouse authorization
All List

001

☐ Inactive

Last updated: 6/22/2022 1:06:17 PM User: rcolombel

Then, in the **Work profile** and **Authorized adjustment types** tabs, check all the required checkboxes (it is possible to check all the boxes if applicable). Make sure the **Inactive** checkbox is **unchecked** and then click **OK**.



User profile - Edit existing

Username: rcolombel
Description: rcolombel

General | Preferences | Company access | Warehouse access | Work profile


Work profile authorization
All List

Default work profile:

☒ CONSO MOND BP	☒ PRELACTIF UVC MSGPAL	☒ PREPACT
☒ CONSO MSG COLUS	☒ PREPACTIF PCB MON BP VAS	☒ PREP BUP
☒ CONSO MULTIBP	☒ PREPACTIF PCB MOND BP	☒ Puberty
☒ CYCLE COUNTING	☒ PREPACTIF PCB MSGCOL	☒ Puberty CI
☒ Pickings with cycle count	☒ PREPACTIF PCB MSGCOL VAS	☒ REAPPRO
☒ PRELACTIF UVC MSGCOL	☒ PREPACTIF PCB MUL BP VAS	☒ REAPPRO

☐ Inactive

Last updated: 6/22/2022 1:06:17 PM User: rcolombel



User profile - Edit existing

Username: rcolombel
Description: rcolombel

Work profile | Authorized adjustment types | User attributes | User defined data

Adjustment type authorization
All None List


☒ Adjustment	☒ Reapprovisionnement inventaire
☒ EXOTEC STORED TDF	☒ Status Change
☒ INJECTION EXO REAP PCB	☒ Transport
☒ INJECTION EXO REC UVC	
☒ INJECTION EXO TRANSPORT UVC	
☒ INJECTION_EXOTEC_MHE	
☒ Inverse	

☐ Inactive

Last updated: 6/22/2022 1:06:17 PM User: rcolombel

1.3 Inventory Control

In this section, we set up the warehouse by defining the different zones, locations within these zones, and how they are all characterized. Additionally, we will create Items (including any associated configurations) and define general inventory parameters. The following figure illustrates the required configurations to thoroughly define all locations.



1.3.1 Zone Type

The functionality of the warehouse largely depends on the zone configurations and the setup of locations within these zones. First, we review the zone types within the warehouse. A **Zone type** [Functional areas -> Inventory control -> Zone type] identifies the purpose of a zone and these are predefined in the system, but you can create additional zone types if necessary. A zone type can be associated with multiple zones. Usually, a warehouse has all three zone types: Allocation, Locating and Work. Make sure the **Inactive** checkbox is **unchecked** for each of these zone types.

Identifier	Description	System value 1	System created	Active
Allocation	Allocation		Yes	Yes
Locating	Locating		Yes	Yes
Work	Work		Yes	Yes

1.3.2 Zone

Zones are not physical positions; they manage what activity can occur in a group of locations. A **Zone** [Functional areas -> Inventory control -> Zone] can also be used to group locations together for processing. This minimizes processing time and increases control over which locations are considered during system processes such as locating and allocation. When defining zones, it is important to use a certain naming convention for consistency and to make it easier to define the subsequent configurations.

An example naming convention for Zones can be seen below:

- Allocation zones are preceded by **A-**
- Locating zones are preceded by **L-**



- Work zones are preceded by **W-**

This can be seen in the following figure. This naming convention is not official, however it is useful to make the configuration clearer and easily understandable, since each physical location in the warehouse can have a unique value for Allocation, Locating and Work zones.


Warehouse	Location	Location template	Location class	Location subclass	Location type	Location status	Locating zone	Allocation zone	Work zone	Active
001	001	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Picking			W-Consolidation	Yes
001	002	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Storage			W-Consolidation	Yes
001	003	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Picking			W-Consolidation	Yes
001	004	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Picking			W-Consolidation	Yes
001	005	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Storage			W-Consolidation	Yes
001	006	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Picking			W-Consolidation	Yes
001	007	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Picking			W-Consolidation	Yes
001	008	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Storage			W-Consolidation	Yes
001	009	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	010	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	011	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	012	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	013	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	014	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	015	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	016	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	017	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	018	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	019	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	020	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Storage			W-Consolidation	Yes
001	021	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	022	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	023	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	024	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	025	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	026	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	027	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	028	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	029	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	030	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Storage			W-Consolidation	Yes
001	031	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	032	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Storage			W-Consolidation	Yes
001	033	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes
001	034	CONSOLIDATION	Shipping Dock	Staging	CONSOLIDATION	Empty			W-Consolidation	Yes

To create a new Zone, **right click**, select **New**. Name your zone (remember the recommended naming convention) and select the Zone type.

For the 001 warehouse, Locating zones are created per grade (A, B, C) and “classe” (Classe A/B/C) and Allocation zones are created per type (Picking , Reserve, Masse) and unit of measure (UVC, PCB, SPCB).

For “Work” **Zone types**, the corresponding **Work profiles** should be included. Refer to section **1.5 Work** for details on this configuration. Make sure the **Inactive** checkbox is **unchecked**.




1.3.3 Units of Measure

Units of Measure (UOM) [*General -> Units of measure*] in SCALE belong to the following categories:

- Dimensions
- Quantity
- Volume
- Weight

SCALE supports all units of measure used by businesses, but the most common default values are usually system created and already available. For the Haddad warehouse, dimensions will be measured in Centimeters (cm); quantity in Pallet, **PCB**, **SPCS** and **UVC**; volume in Cubic Centimeters (cm³) and weight in (kg).

Right click, select **New**, and define the dimension unit of measure to be used for length, width and height measurements. Make sure **Inactive** is unchecked. Repeat the process for all quantity units of measure that will be used in the warehouse. Note that this step does not define the unit count that corresponds to each quantity UOM. That is configured in a different section. Also, in the example below the Quantity UM pallets will be set to PAL.



Dimension units of measure - Edit existing

File Actions Help

Identifier: cm

Record type: UMDIMENS

Description: Centimeters


System defined values

External Rating Symbol: cm

☐ Inactive
System modified

OK Cancel

Last updated: 11/17/2021 2:52:08 PM User: ngrassindalphonse



Quantity units of measure - Edit existing

File Actions Help

Identifier: PAL

Record type: UMQUANTITY

Description: Pallet

System defined values


Quantity UM Symbol: PAL

☐ Inactive
System modified

OK Cancel

Last updated: 2/14/2022 8:36:22 AM User: rcolombel

The same process described above can be followed for the volume and weight units of measure. See the figures below for reference.



Volume units of measure - Edit existing

File Actions Help

Identifier: cm3


Record type: UMVOLUME

Description: Cubic Centimeters

☐ Inactive
System modified

OK Cancel

Last updated: 11/17/2021 2:53:04 PM User: ngrassindalphonse



Weight units of measure - Edit existing

File Actions Help

Identifier: Kg

Record type: UMWEIGHT

Description: Kilograms

System defined values

External Rating Symbol: Kg

☐ Inactive
System modified

OK Cancel



Last updated: 11/17/2021 2:52:40 PM User: ngrassindalphonse

1.3.4 Location Type

A **Location type** [Functional areas -> Inventory control -> Location type] is used to define the maximum weight and dimensions (length, width, and height) for each type of location in the warehouse. This allows SCALE to determine if an item or container can fit at a location. The dimensions are used whenever item location capacity is not configured for an Item. The units of measure used here were defined in the previous section.

Location type	Length	Width	Height	Dimension um	Maximum weight	Weight um	Active
Bacs pkg carton alveole	60.00000	40.00000	40.00000	cm	25.00000	Kg	Yes
Bacs picking carton	60.00000	40.00000	40.00000	cm	25.00000	Kg	Yes
CONSOLIDATION	9999.00...	9999.00...	9999.00...	cm	9999.00000	Kg	Yes
EMBALLAGE	9999.00...	9999.00...	999.000...	cm	9999.00000	Kg	Yes
Masse	999.000...	999.000...	999.000...	cm	9999.00000	Kg	Yes
Palletier	120.000...	80.00000	180.000...	cm	600.00000	Kg	Yes
QUAIS EXPE	9999.00...	9999.00...	9999.00...	cm	9999.00000	Kg	Yes
Receiving Anomalie	999.000...	999.000...	999.000...	cm	9999.00000	Kg	Yes

Right click, select **New**, and fill in the maximum values. Define these as needed, but SCALE does not require the configuration of dimensions or weight. For example, if the location is a receiving dock without a weight limit, then there is no need to set a maximum weight value. Make sure the **Inactive** checkbox is **unchecked**.

1.3.5 Location Status

A **Location status** [Functional areas -> Inventory control -> Location status] indicates the status of a location, which can be updated by SCALE during processing. These statuses are system created and usually there is no need for additional statuses. Refer to the AIM documentation as described in the **Overview** section for detailed descriptions of each system status seen below. Make sure the **Inactive** checkbox is **unchecked**.

Identifier	Description	System value 1	System created	Active
Empty	Empty		Yes	Yes
Frozen	Frozen		Yes	Yes
Picking	Picking		Yes	Yes
Storage	Storage		Yes	Yes

1.3.6 Location Class

A **Location class** [Functional areas -> Inventory control -> Location class] identifies the purpose of a location. Each location will be associated with a location class ("category"). Location classes are usually system created, but additional classes can be configured. Refer to the AIM documentation as described in the **Overview** section for detailed descriptions of each system created class seen below.

Identifier	Description	System value 1	System created	Active
Equipment	Material Handling Equipment	Y	Yes	Yes
Inventory	Inventory Storage	Y	Yes	Yes
P&D	Pickup and Dropoff Area	Y	Yes	Yes
Put to Store	Put to Store	Y	Yes	Yes
Receiving Dock	Receiving Dock	Y	Yes	Yes
Receiving Pre-C...	Receiving Pre-Check In	N	Yes	Yes
Receiving Pre-Lo...	Receiving Pre-Locate	N	Yes	Yes
Shipping Dock	Shipping Dock	Y	Yes	Yes
Work Order Build	Work Order Build Location	Y	Yes	Yes


For the basic receiving and shipping flow, SCALE requires at least one location of each of the following location classes: "Receiving Dock", "Inventory Storage" and "Shipping Dock".

System value 1 corresponds to the **Include in Item Balance Upload** checkbox, which defines the location classes that should be included as part of the Item Balance Upload sent to the ERP system. When this field is inactive, the inventory in all locations belonging to this location class will not be included in the uploaded data.

1.3.7 Location Template

A **Location template** [Functional areas -> Inventory control -> Location template] defines the naming structure for a group of locations in the warehouse. This information is usually provided by clients according to their preference or to match the existing setup of the warehouse.


Right click, select **New**, and fill in the details to achieve the desired naming convention. Note that the length determines the number of characters allowed for each field and the field type can be set to Alpha or Numeric. Make sure the **Inactive** checkbox is **unchecked**.



1.3.8 Location

A **Location** [Functional areas -> Inventory control -> Location] is the unique place in the warehouse where an item or license plate can be picked, putaway, or replenished. To properly configure locations, the configurations in the previous sections (1.3.1 – 1.3.7) must be completed correctly.

Right click, select **New**, and choose the **Location template** and **Warehouse** configured in the previous sections. This window is used to define the naming convention to be used for this set of locations.



SCALE provides the option to define the Starting and Ending locations using **Increments**. For example, assume the starting location is 0000 and the ending location is 1000:


- An increment of 0001 will create 1001 locations (increasing the location Id by 1 every time)
- An increment of 0010 will create 101 locations (increasing the location Id by 10 every time)
- An increment of 1000 will create 2 locations (0000 and 1000)

Increments work the same way for the Alpha fields: A to B is an increment of 1 whereas A to C is an increment of 2.


The **General** tab is also where the **Location class**, **Location type** and **Location status** are defined. Although, when creating new locations, the status is usually prepopulated as "Empty". Shipping locations require a subclass that further specifies the purpose of these locations. For example, packing stations in the warehouse are configured with a shipping location class and a packing location subclass.

Note the Inventory subsection on the right-hand side contains checkboxes that control inventory tracking and allocation. **Allocate in transit** indicates whether the system should include "In Transit" quantity when computing "Available" quantity at this location. **Multi item** determines if a location can contain different items or must be mono SKU. **Track license plates** is used to track item quantity at the license plate level.

In the **Zones** tab, select the Locating, Allocation and Work zones. This is where having the recommended naming convention is beneficial as it will be easier to know which zones should be assigned to each location.




In the **Work** tab, fill in the Pick-up and drop-off information.




In the **Quantity um list** tab, select the different units of measurement that will be handled at this location.


Commented [BR3]: Need to better understand ours



In the **Dock** tab, the configuration will be grayed out if there is only one shipping dock door/area configured for the warehouse. However, if there are multiple shipping dock door/areas, then this tab is used to assign the correct one to the respective location. This will be the dock door that is automatically populated during the dock management flow process.




Lastly, fill in the **User defined data** if necessary.



1.3.9 Storage Template


The following sections (1.3.9 – 1.3.16) are related to item configurations. Like the location master, the item master is provided by the customer and downloaded into SCALE at once. Minor updates might follow, but the full download is usually only completed one time. The figure below highlights all the configuration that ties into item configuration.



A storage template identifies all the units of measure linked with an item category; a unit of measure can be shared across multiple storage templates. Default storage template is applied to all items if no other storage template is created or associated to the correct items and UM values.

In our example, we will have **UVC, SPCB, PCB and Pallets (PAL)** in a unique default template applied to all items of the warehouse.


To define the storage templates, go to the **Inventory Control** folder. Then head to **Storage Template**, right click, **New** and create your storage template as shown in the following figure. Make sure **Inactive** is unchecked.



Sequence	UM	Treat as full percent	Group during check in
1	UVC	100	Yes
2	SPCS	100	Yes
3	PCB	100	Yes
4	PAL	100	No

1.3.10 Item Class

This part is optional, but very useful to minimize configuration time for replenishment and item location capacity because item class can be used to group items that have the same unit of measure (linked through the storage template associated), space requirement and container dimensions. To create an item class, go to the **Inventory Control** folder. Then head to **Item Class**, right click, **New** and create your class as shown in the following figure, by assigning the correct storage template. Make sure **Inactive** is unchecked



1.3.11 Item

First, we look at the parts related to the item. In this part is defined not only the information directly linked to the item (such as the Item name, size or price).

Now that we have defined the information linked to the users and warehouse, we can start looking at the items and their storage templates.

Here, we will give the example of the creation of an item. Theoretically, all items which go through the warehouse must be created, which implies they must have a reference number. Therefore, for a real warehouse, we need the client's item information.

First, go to the **Item** tab, **right click**, **New**.

Item - Edit existing

File Actions Help

Item template: Company: Haddad

Item: 1CC956-A9Y-E3

Description: HOODIE & PRINTED LEGGING SET

General Item char(1) Item char(2) Handling(1) Handling(2)

Allocation rule: NMFC code:

Locating rule: Item class: OUTERWEA

☒ Inventory tracking Packing class:

Storage templ... *Default

☐ Inactive

Last updated: 6/27/2022 1:55:40 PM User: bsauvage

OK Cancel

Configurations

File Actions View Help

Location Launch

Item	Company	Description	tem class	Active
1CC956-A9Y-E3	Haddad	HOODIE & PRINTED LEGGING ...	OUTE...	Yes
1CC956-A9Y-E4	Haddad	HOODIE & PRINTED LEGGING ...	OUTE...	Yes
1CC956-A9Y-E46	Haddad	HOODIE & PRINTED LEGGING ...	OUTE...	Yes
1CC956-A9Y-E47	Haddad	HOODIE & PRINTED LEGGING ...	OUTE...	Yes
1EB189-001-LY	Haddad	TANK TOP DRESS	TOPS	Yes
1EC193-F65-LW	Haddad	LVG PULLON RAINBOW SKINN...	PANT ...	Yes
1EC469-G2H-LR	Haddad	LVG LS FULL ZIP HOODIE	HEAV...	Yes
1ED593-A11-LW	Haddad	LVG LONG SLEEVE TEE SHIRT	KNIT T...	Yes
1ED595-MON-LR	Haddad	LVG DENIM WOVEN DRESS	WOVE...	Yes
1ED599-001-LY	Haddad	LVG RUFFLE TOP DENIM SET	SETS	Yes
ART001-01	Haddad	001-01 Levi's Kids - Jeans Bébé 1...	PANTA...	Yes
ART001-02	Haddad	001-02 Levi's Kids - Jeans Bébé 1...	PANTA...	Yes
ART001-03	Haddad	001-03 Levi's Kids - Jeans Bébé 1...	PANTA...	Yes
ART001-05	Haddad	001-01 Levi's Kids - Jeans Bébé 1...	PANTA...	Yes
ART001-06	Haddad	001-01 Levi's Kids - Jeans Bébé 1...	PANTA...	Yes
ART001-TESTT...	Haddad	001-01 Levi's Kids - Jeans Bébé 1...	PANTA...	Yes
ART002-01	Haddad	002-01	PANTA...	Yes
BSA-ART001-05	Haddad	001-01 Levi's Kids - Jeans Bébé 1...	OUTE...	Yes
ITEM_NGA_01	Haddad	ITEM_NGA_01		Yes


Each item will be configured as a **Haddad** company.

In the **General** tab, write the item reference number in **Item**, give a **Description** to this item (typically, its name). For example, for a book, the description could be its title. Then, in the **Categories** tab, you can fill the information according to what has been defined with the client.


Make sure the **Inactive** box is unchecked.

1.3.12 Item Unit of Measure

Item unit of measure allows you to define, for each item, its main dimensions, weight and quantity by which it is handled (UVC, SPCB, PCB or PAL). All these values are applied to item which can be either identified by its individual reference number (defined in the paragraph **Item**), or by using an Item Class.



In our case, we defined each Item unit of measure individually. To do so, **right click** in the blank window, **New**. In the new window, select either **Item class** or **Item**. In our case, we select **Item**, as we decided to define each item individually. Click on the **Research** button (the little magnifying glass), write the information related to the item you are looking for (remember to use the % wild card if necessary), and click on the item and then **OK**. **Right click** in the blank part of the window, **New** and write the information you have for that item. An example is provided in the following figure.



Sequence	Quantity unit	Conversion qty	Length	Width	Height	Weight	Movement class
1	UVC	1.000	10.000	2.000	2.000	0.500	A
2	PCB	10.000	10.000	10.000	10.000	2.500	

Then click **OK**. Repeat as many times as needed.

Note: each item can be given several Sequences in a single unit of measure, but you cannot create several units of measure for a single item.

1.3.13 Item Categories

It is possible to identify specific characteristics of the items in the Item categories such as value-added inserts (catalogs, promotional gifts, etc.), special handling instructions, pay terms, or any other user-defined message/label. These information at Item level can be used then in configuration of item filter for warehouse processes (replenishment, allocation, location etc.)

Ten different Item categories are available and can be configured in SCALE to store specific item values.

To configure an item category, go to the **Inventory Control** folder, then in the **Item Categories** folder select the preferred **Item Category**, **right click**, **New** and create your category fields as shown in the following figure. Make sure **Inactive** is unchecked.

Configurations

File Actions View Help

Wave steps

Launch

Configurations

- Functional areas
 - Allocation
 - Cycle count
 - Inventory control
 - Adjustment type
 - Harmonized code
 - Immediate needs
 - Inventory attribute v
 - Inventory control va
 - Inventory status
 - Item
 - Item categories
 - Item category 01

Identifier	Description	system value	system create	Active
Label	Label		No	Yes
SMS	SMS		No	Yes
Stock	Stock		No	Yes

We also need a new category (item category 02) for the Product status:

Configurations

File Actions View Help

Wave steps

Launch

Configurations

- Functional areas
 - Allocation
 - Cycle count
 - Inventory control
 - Adjustment type
 - Harmonized code
 - Immediate needs
 - Inventory attribute v
 - Inventory control va
 - Inventory status
 - Item
 - Item categories
 - Item category 01
 - Item category 02

Identifier	Description	system value	system create	Active
Carry Over	Article Carry Over		No	Yes
Close Out	Article Close out		No	Yes
Consumable	Article Consumable		No	Yes
New	Article New		No	Yes
Nos	Article Nos		No	Yes
Sample	Article Sample		No	Yes

We use item category 03 for the "Famille de produit"

Configurations

File Actions View Help

Wave steps

Launch

Identifier	Description	system value	system create	Active
1 PC SUIT	1 PC SUIT		No	Yes
ACCESSO...	ACCESSORIES		No	Yes
BABY ON...	BABY ONE PIECE		No	Yes
BAGS	BAGS		No	Yes
BODYSUIT	BODYSUIT		No	Yes
BOTTOMS	BOTTOMS		No	Yes
BOXED SET	BOXED SET		No	Yes
COLD WE...	COLD WEATHER		No	Yes
PANTALON	Famille Pantalon		No	Yes
HEADWE...	HEADWEAR		No	Yes
HEAVY W...	HEAVY WEIGHT OUTERWEAR		No	Yes
KNIT BOT...	KNIT BOTTOMS		No	Yes
KNIT TOP	KNIT TOP		No	Yes
LAYERIN...	LAYERING TOP		No	Yes
OUTERW...	OUTERWEAR		No	Yes
PANT SET	PANT SET		No	Yes
SETS	SETS		No	Yes
SLEEPWE...	SLEEPWEAR		No	Yes
SOCKS	SOCKS		No	Yes
TOPS	TOPS		No	Yes
UNDERW...	UNDERWEAR		No	Yes
WOVEN B...	WOVEN BOTTOMS		No	Yes

We use item category 04 for the “Sous-Famille de Produit”:

Configurations

File Actions View Help

Wave steps

Launch

Identifier	Description	system value	system create	Active
Short	Sous famille Short		No	Yes

We use item category 05 for the Rotation class:

Configurations

File Actions View Help

Wave steps

Launch

Configurations

- Functional areas
 - Allocation
 - Cycle count
 - Inventory control
 - Adjustment type
 - Harmonized code
 - Immediate needs
 - Inventory attribute v
 - Inventory control va
 - Inventory status
 - Item
 - Item categories
 - Item category 01
 - Item category 02
 - Item category 03
 - Item category 04
 - Item category 05
 - Item category 06
 - Item category 07
 - Item category 08
 - Item category 09
 - Item category 10

Identifier	Description	system value	system create	Active
A	Classe de rotation A		No	Yes
B	Classe de rotation B		No	Yes
C	Classe de rotation C		No	Yes
Z	Classe de rotation Z		No	Yes

We use item category 06 for the “classe de vente”:

Configurations

File Actions View Help

Wave steps

Launch

Configurations

- Functional areas
 - Allocation
 - Cycle count
 - Inventory control
 - Adjustment type
 - Harmonized code
 - Immediate needs
 - Inventory attribute v
 - Inventory control va
 - Inventory status
 - Item
 - Item categories
 - Item category 01
 - Item category 02
 - Item category 03
 - Item category 04
 - Item category 05
 - Item category 06
 - Item category 07
 - Item category 08
 - Item category 09
 - Item category 10

Identifier	Description	system value	system create	Active
A	Classe de vente A		No	Yes
B	Classe de vente B		No	Yes
C	Classe de vente C		No	Yes
Z	Classe de vente Z		No	Yes

1.3.14 Item Cross Reference

“You can create a cross-reference record for any item defined in the system. Generally, a cross-reference number is established to identify an item's UPC or GS1 number. A user processing an item can use either the item number or the cross-reference number to identify it on an RF device.” (Source: Item cross reference Help window)

<https://emlb-scale2018.manh.com/Scale/Help/WebHelp/Content/Itemcross.htm>)

Go to **Item cross reference**, right click, **New** and fill in the fields. The first field should contain the reference number you defined in the paragraph **Item**, the **Company** field is relevant only if you have several companies. If it is not the case, it can stay blank. Write the cross-reference item number and quantity unit of measure. Click **OK**.

Configurations

File Actions View Help


Wave steps Launch

Item	Company	Cross reference item number	Quantity um
1CC956-A9Y-E3	Haddad	EAN1234	UVC
1CC956-A9Y-E4	Haddad	EAN1234DD	UVC
1CC956-A9Y-E46	Haddad	EAN1234DD	UVC
1CC956-A9Y-E47	Haddad	EAN1234DD	UVC
1EB189-001-LY	Haddad	EAN001-05	UVC
1EC193-F65-LW	Haddad	EAN001-05	UVC
1EC469-G2H-LR	Haddad	EAN001-05	UVC
1ED593-A1I-LW	Haddad	EAN001-05	UVC
1ED595-M0N-LR	Haddad	EAN001-05	UVC
1ED599-001-LY	Haddad	EAN001-05	UVC
ART001-01	Haddad	EAN001-01	UVC
ART001-02	Haddad	EAN001-02	UVC
ART001-03	Haddad	EAN001-02	UVC
ART001-05	Haddad	EAN001-05	UVC
ART001-06	Haddad	EAN001-05	UVC
ART001-TESTTO...	Haddad	EAN001-05	UVC
ART002-01	Haddad	EAN001-05	UVC
BSA-ART001-05	Haddad	EAN1234	UVC
JU-ART001	Haddad	JU-ART001	UVC
JU-ART002	Haddad	JU-ART002	UVC
JU-ART003	Haddad	JU-ART003	UVC
JU-ART004	Haddad	JU-ART004	UVC
JU-ART005	Haddad	JU-ART005	UVC
JU-ART006	Haddad	JU-ART006	UVC
JU-ART007	Haddad	JU-ART007	UVC
JU-ART008	Haddad	JU-ART008	UVC
JU-ART009	Haddad	JU-ART009	UVC
JU-ART010	Haddad	JU-ART010	UVC
JU-ART011	Haddad	JU-ART011	UVC
JU-ART012	Haddad	JU-ART012	UVC

1.3.15 Item Location Capacity

This feature allows us to define, for either a specific Item or for an Item class, the maximum amount of a quantity we can store in a certain location or location type. Maximum capacity is taken into consideration during putaway and replenishment process, in case of manual location override or RF transfer this criterion is disregarded.

In our case we use item location capacity for the item class "Pantalon".



1.3.16 Item Location Assignment

This feature enables you to assign a permanent location to an item. A permanent location identifies the one location where a specific item/unit of measure is stored.

We are not going to use the item location assignment for this warehouse


1.3.17 Inventory Control Values

In this part, we will see how to define inventory adjustments (positive, negative or transfers) with or without work, for every movement across the warehouse that requires work to be completed by a user the following configuration are required:

- Work Group
- Work Type
- Work Profile
- Work Criteria
- Work Creation Master.

Work Special Handling configuration is also usually configured, despite is optional to change default validation fields to confirm work in RF.

Inventory Management



These technical values regulates the management of inventory in SCALE, are usually set up by default and should only be reviewed from technical experts.

The description and use for each inventory control value, reported in the figure below, is detailed in AIM.


Configurations

File Actions View Help

Launch				
Configurations	Description	System value	System create	Key
Functional areas				
Allocation				
Cycle count				
Inventory control				
Adjustment type	Adj Type For Status Change during Transfer	Status Cha...	Yes	160
Harmonized code	Adjustment type for Lot Status Change		Yes	140
Immediate needs	Allow duplicate license plates across warehous...	N	Yes	190
Inventory attribute v	Allow Duplicate Serial Numbers?	N	Yes	50
Inventory control va	Default inventory status for adjustments	Available	Yes	40
Inventory status	Delimiter used to ensure unique license plate I...	@	Yes	200
Item	Dock Location Separator Value		Yes	180
Item categories	Edit UserDef Fields in RF Inventory Managem...	N	Yes	60
Item class	Generate Cycle Count on Location Override Pick	Y	Yes	230
Item cross referenc	Generate Cycle Count on Location Override Pu...	N	Yes	220
Item location assig	Inventory status for frozen lots		Yes	130
Item location capac	Location check digit format	ZZZ	Yes	80
Item template	Reuse Closed License Plates?	N	Yes	170
Item UOM	Short Pick Inventory Action	40	Yes	150
Location	Should item be validated throughout system?	Y	Yes	110
Location class	Should location be validated throughout system?	Y	Yes	120
Location status	Show All Allocation Failures for Allocate Compl...	N	Yes	240
Location template	Use Location UM Overrides	N	Yes	100
Location type	Whether inventory is being tracked by default	Y	Yes	70
Lot template	Write Location UM overrides on Item UM Chan...	N	Yes	10


1.3.18 Inventory status

This indicates the status of items in a location. Theoretically, you will only need two statuses: Available and Held (both normally system created), but you might need to modify or add statuses.



1.3.19 Adjustment type

An adjustment type record defines the parameters for a specific inventory management transaction. When defining an Adjustment type, you will have to choose if you want to check **Include In Interface Uploads**. Check this checkbox if you want to interface records for this adjustment type back to the ERP.



1.3.20 Inventory transfer work criteria and Inventory adjustment work criteria


A work criteria determines the required characteristics of a work request to be eligible for work creation within a defined work master (filter data tab) and what is the required order of work instructions generation and release to the warehouse (order by tab).

Then create work unit checkbox in the Order by tab when the system will break a work instruction group and create a new one.

In our case, we are not going to use this part

1.4 Receiving

This section will present an overview on how to define the receiving process. This can be divided into three different subsections, which can be seen on the following figure. The first subsection deals with the location and locating rules. Secondly, the right side of the process flow focuses on the work that will be created for the users to perform the receiving operations. Note that disposition codes are not specifically tied to either side of the process.



1.4.1 Putaway location group

A putaway location group allows a series of received items to be putaway as one group. Once you create one putaway group (using either a location range or a locating zone), then all groups will have to be created using either ranges or zones, whichever one you chose for the first group.

Configurations

File Actions View Help

Putaway location group

Warehouse / Putaway location group name From location To location Locating zone

001	BOX FULL PRICE			L-Stock HBE Nos
001	GRADE A			L-Gr A - Classe A...
001	GRADE B			L-Gr B - Classe A...
001	GRADE C			L-Grade C

Commented [BR4]: Need to work on it, I don't know how does it works

Putaway groups can be used as alternatives to nesting for creating pallets during the check in process. The putaway groups will be stored in the parent LPN field in the inventory records even after putaway completion.

Commented [BR5]: Need more infos

1.4.2 Location selection

There are numerous locations in the warehouse, but not all are positioned in the right zone or have the right characteristics.

Therefore, we use location selection records, along with locating strategy records, to identify the characteristics that a location must have to be considered during locating. It also determines the order that the system will organize the eligible location.


Only the locations in that table which respect criteria are eligible to be considered as locations during locating. This gives us a list of potential locations, but we now have to choose among that list to find the ideal location for our putaway group, this can be achieved by configuring the locating rules as shown in the next section.

The location selection for the 001 warehouse is divided per cellule which will putaway goods according to their 'GRADE' and 'Converted qty um'.

Commented [BR6]: To validate

Template_field 2 is composed of the cellule + the alley.

Template_field 4 indicates the level of the shelf.



Location selection - Edit existing

File Actions Help

Record type:

LOC SEL

Filter name:

Cell 2 Pckg UVC GRA

Description:

Cell 2 Pckg UVC GRA

Table name:

Location

Filter data

Order by

Filter criteria

And

Attribute:

Operand:

Value:

Or

LOCATION.warehouse = N'001'

AND LOCATION.LOCATION_STS != N'Frozen'

AND LOCATION.ACTIVE = N'Y'

AND LOCATION.ALLOCATION_ZONE = N'A-Picking UVC'

AND LOCATION.TEMPLATE_FIELD1 = N'200'

AND LOCATION.LOCATING_ZONE = N'L-Gr A - Classe A/B/C'

Add rule

Delete selected rule

Delete last rule

Insert left parenthesis

Insert right parenthesis

Delete parenthesis

Up

Down

Inactive

System created

OK

Cancel

Last updated: 6/22/2022 10:53:59 AM User: rcolombel

1.4.3 Locating rule

A locating rule identifies the sequence and rule details the system will use to locate a product. A rule detail determines which location the system will assign that product to. Generally, a locating rule includes multiple details, which the system processes in numerical order (10, 20, 30, etc.).

LAST MODIFIED: 30/9/2026 9:56 PM
SCALE CONFIGURATION WALKTHROUGH

32

Locating rule - Edit existing

File Actions View Help

Locating name: GRA CV/CR A/B PCB

Description: GRA CV/CR A/B PCB

☐ Delayed locating

Detail records

User defined data

quen	Locating strategy	Location selection	quar	
▶ ...	Fill one and only one location within th...	Cell 3/4 Pckg Classe A/B	No	^
!...	Empty location	Cell 4 Rsv A/B Niv 2/3	No	
i...	Empty location	Cell 3 Rsv A/B Niv 2/3	No	
...	Empty location	Cell 4 Rsv A/B Niv 4/5	No	
i...	Empty location	Cell 3 Rsv A/B Niv 4/5	No	▼

☐ Inactive


OK Cancel Apply

Last updated: 6/28/2022 1:13:14 PM User: bsauvage

Commented [BR7]: Not clear at all

1.4.4 Locating rule assignment criteria


This function indicates how the system will determine when to use a certain Location rule assignment. For example, you could define a criterion to indicate a value such as "less than 20 eaches of Item A." Then, when the system attempts to allocate/locate this quantity, it will use the Location rule assignment that is associated with this criterion to assign a rule to the item. Haddad criteria mainly depends on the converted_qty_um (if it is UVC or PCB), the rotation class (item_category5), the sale class (item_category6) and the grade (lot).



1.4.5 Location rule assignment

Now that you have defined the Locating rule and its related assignment criteria, you must define the order in which it will be assigned, relatively to other Locating rules. To do so, we define priorities: the rule with the smallest priority number will have the most importance.

Priority	Criteria	Locating rule	Active
20	GRA - CV/CR A/B - PCB	GRA CV/CR A/B PCB	Yes
30	GRA - CV/CR C - PCB	GRA CV/CR C PCB	Yes
40	GRA - UVC	GRA UVC	Yes
50	GRB - PCB	GRB CV/CR A/B/C PCB	Yes
60	CPO	GRA/B/C CPO	Yes
70	GRB - UVC	GRB UVC	Yes
100	Samples-UVC-SMS	Samples-UVC-SMS	Yes
130	Consommables	Consumable	Yes
140	Anomalie	Anomalie	Yes
200	QC-Quality Control	QC-Quality Control	Yes



The priority of Locating Rule Assignment can determine a different rule for a receipt in case the rule assignment criteria are not mutually exclusive.

1.4.6 Disposition Code

After defining the information tied to the locating rules and the way they are assigned, we look at the second subsection of Receiving which is the definition of Disposition Codes.


These codes indicate the status of the inventory within a receipt container. For example, the item(s) could be in good condition, damaged, broken, etc. These codes are helpful when processing returns. Also, since these codes are linked to a specific locating rule, the system can locate product differently based on its disposition code. For Haddad we will use disposition code only for the Receiving Preferences 'RECEP QUALIF'.

Identifier	Description	System value 1	System create	Active
D01	D01- Reconditionnement nécess...		No	Yes
D02	D02 - Recolissage nécessaire		No	Yes
D03	D03 - Restauration nécessaire		No	Yes
D04	D04 - Erreur data		No	Yes
D05	D05 - Déterioré		No	Yes
D06	D06 - Autres		No	Yes
QC	QC - Receipt Quality Control	QC-Quality Control	No	Yes

1.4.7 Receipt ID type

A receipt ID type indicates what type of number is used as a receipt's ID. Common receipt ID types include PO number and manufacturer number. Some are already system created.

You will want to define valid receipt ID types based on the interface design and mapping between the host system and SCALE. Some are already system created, to satisfy the most common requirements.



Receipt id type - Edit existing (Left)

Identifier: STANDARD
Record type: RCPTIDTYPE
Description: STANDARD
System defined values: Returns: No
Buttons: Inactive, System created, OK, Cancel
Last updated: 2/16/2022 1:16:40 PM User: plachasse

Receipt id type - Edit existing (Right)

Identifier: RETOUR SAUVAGE
Record type: RCPTIDTYPE
Description: RETOUR SAUVAGE
System defined values: Returns: Yes
Buttons: Inactive, System created, OK, Cancel
Last updated: 6/27/2022 8:19:57 AM User: rcolombel

1.4.8 RF receiving check in initiation

This step will not always be necessary for simple configurations, as it is a personalization feature.


In order to associate a RF receiving initiation workflow to a user's receiving preference, the workflow first needs to be defined in the system. This is done by creating an initiation workflow record.

Configurations

File Actions View Help

RF receiving check in initiation Launch


Description	System value 1	System created	Active	Identifier
Header-Item	Header Item-Bas...	Yes	Yes	10
Trailer ID-Item GS1	GS1 Trailer ID It...	Yes	Yes	100
Trailer ID-License Plate ...	GS1 Trailer ID L...	Yes	Yes	110
Item GS1	GS1 Item-Based ...	Yes	Yes	120
License Plate GS1	GS1 LP-Based R...	Yes	Yes	130
Blind GS1	GS1 Blind-Based...	Yes	Yes	140
Header Item-Based RF ...	Header Item-Bas...	No	Yes	150
Header-License Plate	Header LP-Bas...	Yes	Yes	20
Header-Item Inv Attrib	Header Item-Bas...	No	Yes	200
Trailer ID-Item	Trailer ID Item-Ba...	Yes	Yes	30
Trailer ID-License Plate	Trailer ID LP-Bas...	Yes	Yes	40
Item	Item-Based RF W...	Yes	Yes	50
License Plate	LP-Based RF Wo...	Yes	Yes	60
Blind	Blind-Based RF ...	Yes	Yes	70
Header-Item GS1	GS1 Header Item...	Yes	Yes	80
Header-License Plate GS1	GS1 Header LP-...	Yes	Yes	90



1.4.9 Receiving preferences


This step requires previously defining the Receiving docks, Inventory statuses, Work types (and in some cases Work teams) and eventually an “RF receiving check in initiation” for non-standard RF workflows. The Assigned users will not need to be checked.

In the General tab you can define the default **Receiving Dock**, inventory status and work type.



In the **RF** tab is where the **Check-In Initiation Workflow** is defined as well as the receiving operation executed during check in using the execution method configuration (only check in, check in and locate, quick receiving).

To allow putaway group creation the execution method needs to be set as **Check In and Locate (Immediate)**. Alternatively, in this tab you can also set the automatic pallet nesting during check in if desired.



Receiving preferences - Edit existing

File Actions Help

Preference name: RECEP STD PCB

Description: RECEP STD PCB

General Description Workbench Authorized users User defined data

Initiation method

Workflow: Header Item-E

Execution method

Check in

Check in and locate

Check in and locate (immediate)

Quick receive - user

Quick receive - system

Advanced options

Application identifier tem...

Nest during check in

Process immediate needs

Quick receiving options

Bypass location capacity validation


Override system selected location

Inactive

OK Cancel

Last updated: 6/1/2022 7:12:35 AM User: cftsupport

In the **Workbench** tab we define the container level used during the locating operation and any advanced options we'd like during check in.



Receiving preferences - Edit existing

File Actions Help

Preference name: RECEP STD PCB

Description: RECEP STD PCB

General RF Workbench Authorized users User defined data

Container locating method

Parent

Child

Advanced options

Disposition code required

Reason code required

QC inspection active

Verify item dimensions

Verify item unit of measure

Inactive

OK Cancel

Last updated: 6/1/2022 7:12:35 AM User: cftsupport

Note that the “*Default” Reception preference is made Inactive.

1.4.10 Work group

Finally, the last subsection of the receiving process configuration is based on work configuration. We start by looking at the Work groups.

Identifier	Description	System value	System create	Active
Cycle Counting	Cycle Counting Work Group		No	Yes
Packing	Packing Work Group		No	Yes
Picking	Picking Work Group		No	Yes
Receiving	Receiving Work Group		No	Yes
Shipping	Shipping Work Group		No	Yes

Here, we simply create a Work group associated to Receiving.

1.4.11 Work type

Work type	Description	Work group	Default priority	Labor type	Active
Batch Pick	Batch Pick	Picking	0 Automatic Direct L...		Yes
CONSO MO...	CONSO MONO BP	Packing	0 Automatic Direct L...		Yes
CONSO MSG...	CONSO MSG COLIS	Packing	0 Automatic Direct L...		Yes
CONSO MUL...	CONSO MULTI BP	Packing	0 Automatic Direct L...		Yes
Cycle Counting	Cycle Counting	Cycle Counting	0 Automatic Direct L...		Yes
Dock Transfe...	Dock Transfer BR	Packing	0 Automatic Direct L...		Yes
Order Pick	Order Pick	Picking	0 Automatic Direct L...		Yes
Packing	Packing	Packing	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF MONO BP PCB ...	Picking	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF MONO BP PCB	Picking	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF PCB MSGCOL	Picking	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF PCB MSGCOL ...	Picking	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF PCB MULTI BP ...	Picking	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF PCB MULTI BP	Picking	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF UVC MSGCOL	Picking	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF UVC MSGCOL ...	Picking	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF UVC MSGPAL	Picking	0 Automatic Direct L...		Yes
PREP ACTIF ...	PREP ACTIF UVC MSGPAL V...	Picking	0 Automatic Direct L...		Yes
PREP RSV P...	PREP RSV PAL CPO	Picking	0 Automatic Direct L...		Yes
Putaway	Putaway	Receiving	0 Automatic Direct L...		Yes
Putaway CPO	Putaway CPO	Receiving	0 Automatic Direct L...		Yes
REAPPRO P...	REAPPRO PAL ROT A	Picking	50 Automatic Direct L...		Yes
REAPPRO P...	REAPPRO PAL ROT A Grad...	Picking	80 Automatic Direct L...		Yes
REAPPRO P...	REAPPRO PAL ROT B	Picking	60 Automatic Direct L...		Yes
REAPPRO P...	REAPPRO PAL ROT B Grad...	Picking	81 Automatic Direct L...		Yes
REAPPRO P...	REAPPRO PCB ROT C Z	Picking	70 Automatic Direct L...		Yes
REAPPRO P...	REAPPRO PCB ROT C Z Gr...	Picking	82 Automatic Direct L...		Yes
REAPPRO U...	REAPPRO UVC ROT A	Picking	50 Automatic Direct L...		Yes
REAPPRO U...	REAPPRO UVC ROT A Grad...	Picking	80 Automatic Direct L...		Yes
REAPPRO U...	REAPPRO UVC ROT B	Picking	60 Automatic Direct L...		No
REAPPRO U...	REAPPRO UVC ROT C Z	Picking	70 Automatic Direct L...		Yes
REAPPRO U...	REAPPRO UVC ROT C Z Gr...	Picking	82 Automatic Direct L...		Yes
Receiving	Receiving	Receiving	0 Automatic Direct L...		Yes
Shipping	Shipping	Shipping	0 Automatic Direct L...		Yes
Work order P...	Work order Picking	Picking	0 Automatic Direct L...		Yes
Work order P...	Work order Putaway	Packing	0 Automatic Direct L...		Yes

Each work type is tied to a specific work group as you can see above.

1.4.12 Work profile

Work profile	Description	Active
CONSO MONO BP	CONSO MONO BP	Yes
CONSO MSG COLIS	CONSO MSG COLIS	Yes
CONSO MULTI BP	CONSO MULTI BP	Yes
CYCLE COUNTING	CYCLE COUNTING	Yes
Picking with cycle count	Picking with cycle count	Yes
PREL ACTIF UVC MSGC...	PREL ACTIF UVC MSGCOL	Yes
PREL ACTIF UVC MSGPAL	PREL ACTIF UVC MSGPAL	Yes
PREP ACTIF PCB MON B...	PREP ACTIF PCB MONO BP VAS	Yes
PREP ACTIF PCB MONO...	PREP ACTIF PCB MONO BP	Yes
PREP ACTIF PCB MSGC...	PREP ACTIF PCB MSGCOL	Yes
PREP ACTIF PCB MSGC...	PREP ACTIF PCB MSGCOL VAS	Yes
PREP ACTIF PCB MUL B...	PREP ACTIF PCB MULTI BP VAS	Yes
PREP ACTIF PCB MULTI ...	PREP ACTIF PCB MULTI BP	Yes
PREP SUP	PREP SUP	Yes
Putaway	Putaway	Yes
Putaway CPO	Putaway CPO	Yes
REAPPRO PCKG PCB P...	REAPPRO PCKG PCB PCKG UVC	Yes
REAPPRO RSV PAL/PCB	REAPPRO RSV PAL/PCB	Yes

Each work profile is tied to its specific work type and work zones. In the details record, the **Work Processing** tab defines how the work will be assigned and completed. See below for an example.

Work profile - Edit existing

File Actions View Help

Work profile: PREP ACTIF PCB MSGCOL

Description: PREP ACTIF PCB MSGCOL VAS

Detail records Authorized users Warehouse access Work team/equip

Sequence: 10 Work types: PREP ACTIF PCB MSGCOL VAS

☐ Inactive

OK Cancel Apply

Last updated: 2/23/2022 3:48:08 PM User: rcolombel

Work profile detail - Edit existing

File Actions Help

Work profile: PREP ACTIF PCB MSGCOL VAS

Sequence: 10

Work type Work processing User defined data

☐ Check all

☐ Batch Pick

☐ CONSO MONO BP

☐ CONSO MSG COLIS

☐ CONSO MULTI BP

☐ Cycle Counting

☐ Dock Transfer BP

☐ Order Pick

☐ Picking

☐ PREP ACTIF MONO BP PCB

☐ PREP ACTIF MONO BP PCB VAS

☐ PREP ACTIF PCB MSGCOL

☒ PREP ACTIF PCB MSGCOL VAS

☐ PREP ACTIF PCB MULTI BP

☐ PREP ACTIF PCB MULTI BP VAS

☐ PREP ACTIF UVC MSGCOL

☐ PREP ACTIF UVC MSGCOL VAS

☐ PREP ACTIF UVC MSGPAL

☐ PREP ACTIF UVC MSGPAL VAS

☐ PREP RSV PAL CPO

☐ Putaway

☐ Putaway CPO

☐ REAPPRO PAL ROT A

☐ REAPPRO PAL ROT A Grade B

☐ REAPPRO PAL ROT B

☐ REAPPRO PAL ROT B Grade B

☐ REAPPRO PCB ROT C Z

☐ REAPPRO PCB ROT C Z Grade B

☐ REAPPRO UVC ROT A

☐ REAPPRO UVC ROT A Grade B

☐ REAPPRO UVC ROT C Z

☐ REAPPRO UVC ROT C Z Grade B

☐ Receiving

☐ Shipping

☐ Work order Picking

OK Cancel

Last updated: 4/13/2022 10:45:23 PM User: rcolombel

It is important to make sure the warehouse access and authorized users are configured correctly.

Work profile - Edit existing

File Actions View Help

Work profile: PREP ACTIF PCB MSGCOL

Description: PREP ACTIF PCB MSGCOL VAS

Detail records Authorized users Warehouse access Work team/equip

Warehouse authorization

☒ All ☐ List

001

☐ Inactive

OK Cancel Apply

Last updated: 2/23/2022 3:48:08 PM User: rcolombel

Work profile - Edit existing

File Actions View Help

Work profile: PREP ACTIF PCB MSGCOL

Description: PREP ACTIF PCB MSGCOL VAS

Warehouse access Work team/equipment type Work zone Vocollect

☐ Check all

☐ W-AGVINJ	☒ W-Picking Samples
☐ W-AKANE	☒ W-Picking SPCB
☒ W-Consolidation	☒ W-Picking UVC (cell 05)
☒ W-Consolidation perso	☒ W-Picking UVC (cell 08)
☒ W-CTRL	☒ W-Picking UVC Grade A
☒ W-Emballage	☒ W-Picking UVC Grade B
☒ W-Expedition	☒ W-Recep
☒ W-Perso	☒ W-Reserve PCB
☒ W-Picking PCB	



☐ Inactive

OK Cancel Apply

Last updated: 2/23/2022 3:48:08 PM User: rcolombel

1.4.13 Receipt work criteria


Filter name	Description	System created	Active
Putaway Work CPO	Putaway Work CPO	No	Yes
Putaway Work PAL	Putaway Work PAL	No	Yes
Putaway Work PCB SP...	Putaway Work PCB SPCS	No	Yes
Putaway Work UVC	Putaway Work UVC	No	Yes

1.4.14 Work Creation master

Work creation masters define how the system generates work, based on the other work creation configurations. This step ties all the previously created information together.

One **Work Creation Master** needs to be created for each **Receipt Work Criteria** of the receiving work type.




1.5 Work

This section will deal with the creation and assignment of work according to the operator, the area in the warehouse and the type of item, for example. We will follow the next steps for configuration.

- Work System Values


- Then the same steps will be repeated for the Receipt, Shipment Allocation, Shipment Container, Inventory Transfer and Cycle Count:

- Work Type
- Work Criteria
- Work Creation Master
- Work Profile
- Work Special Handling



1.5.1 Work system values

These values are usually all system created. They accommodate specific events that may occur during the work process. When the system encounters an unexpected experience during work creation or work execution, it will display the appropriate system defined values. **You should not need to create unique values on this window.**



1.5.2 Work type

Please refer to section 1.4.11 for details on defining the work type.

1.5.3 Work criteria

Work criteria are independently created. The following work criteria must be configured and are ordered by priority:

- **Receipt Work Criteria** – Please refer to section 1.4.13 for details on this configuration.
- Dock Management Work Criteria:

	MONO BP	MONO BP	No	Yes
	MSGCOL	MSGCOL	No	Yes
○	MSGPAL	MSGPAL	No	Yes

Dock management work criteria - Edit existing

File Actions Help

Record type:

Filter name:

Description:

Table name:

Filter data | Order by

Filter criteria

☒ And ☐ Or

Attribute: Operand: Value:

Up Down

Add rule
Delete selected rule
Delete last rule
Insert left parenthesis
Insert right parenthesis
Delete parenthesis

☐ Inactive ☐ System created

OK Cancel

Last updated: 6/20/2022 11:50:58 AM User: breitz

Dock management work criteria - Edit existing

File Actions Help

Record type:

Filter name:

Description:

Table name:

Filter data | Order by

Filter criteria

☒ And ☐ Or

Attribute: Operand: Value:

Up Down

Add rule
Delete selected rule
Delete last rule
Insert left parenthesis
Insert right parenthesis
Delete parenthesis

☐ Inactive ☐ System created

OK Cancel

Last updated: 4/29/2022 12:52:52 PM User: rcolombel

Dock management work criteria - Edit existing

File Actions Help

Record type:

Filter name:

Description:

Table name:

Filter data | Order by |

Filter criteria

☒ And ☐ Or

Attribute: Operand: Value:

Up Down

Add rule
Delete selected rule
Delete last rule
Insert left parenthesis
Insert right parenthesis
Delete parenthesis

☐ Inactive ☐ System created

OK Cancel

Last updated: 6/20/2022 11:51:02 AM User: breitz

- Shipment Allocation Work Criteria:
- Shipment Container Work Criteria
- Replenishment Work Criteria

Replenishment work criteria - Edit existing

File Actions Help

Record type:

Filter name:

Description:

Table name:

Filter data | Order by |

Filter criteria

☒ And ☐ Or

Attribute: Operand: Value:

Up Down


Add rule
Delete selected rule
Delete last rule
Insert left parenthesis
Insert right parenthesis
Delete parenthesis

☐ Inactive ☐ System created

OK Cancel

Last updated: 6/30/2022 9:07:31 AM User: rcolombel


- Inventory Transfer Work Criteria
- Cycle Count Work Criteria



- Work criteria windows manage the following activities:
 - they determine which work requests are selected for work processing
 - they create a work unit
 - and they determine the order in which work instructions are generated and released to the warehouse floor

1.5.4 Work creation master

- Please refer to section 1.4.14 for details on the work creation master for receiving.
- For the Picking:



- For Dock Transfer:

LAST MODIFIED: 30/9/2026 9:56 PM

SCALE CONFIGURATION WALKTHROUGH

Work creation master - Edit existing

File Actions Help

Work creation name: CONSO MSG COLIS

Description: CONSO MSG COLIS

General

Maximums

User defined data

Work type: CONSO MSG COLIS

Process: Dock Management V

Work unit field: Tree unit id

Work criteria: MSGCOL

Creation method: Pre-build

SRC identifier: Dock management w

Priority: 1

☐ Auto print documents

OK Cancel

Last updated: 2/23/2022 9:10:08 AM User: rcolombel

Work creation master - Edit existing

File Actions Help

Work creation name: CONSO MSGPAL MONO

Description: CONSO MSGPAL MONO

General

Maximums

User defined data

Work type: CONSO MONO BP

Process: Dock Management V

Work unit field: Tree unit id

Work criteria: MONO BP

Creation method: Pre-build

SRC identifier: Dock management w

Priority: 1

☐ Auto print documents

OK Cancel

Last updated: 4/29/2022 2:31:44 PM User: rcolombel

Work creation master - Edit existing

File Actions Help

Work creation name: CONSO MULTI BP MSGPAL

Description: CONSO MULTI BP MSGPAL

General

Maximums

User defined data

Work type: CONSO MULTI BP

Process: Dock Management V

Work unit field: Tree unit id

Work criteria: MSGPAL

Creation method: Pre-build

SRC identifier: Dock management w

Priority: 1

☐ Auto print documents

OK Cancel

Last updated: 4/29/2022 2:31:17 PM User: rcolombel

1.5.5 Work profile

Please review section 1.4.12 for details on creation of work profiles.

Work profile - Edit existing

File Actions View Help

Work profile: CONSO MSG COLIS

Description: CONSO MSG COLIS

Detail records

Authorized users

Warehouse access

Work team/equip

Sequence	Work types
10	CONSO MSG COLIS

☐ Inactive

OK Cancel Apply

Last updated: 2/23/2022 9:03:56 AM User: rcolombel

Work profile detail - Edit existing

File Actions Help

Work profile: CONSO MSG COLIS

Sequence: 10

Work type | Work processing | User defined data

☐ Check all

☐ Batch Pick	☐ PREP ACTIF UVC MSGPAL VAS
☐ CONSO MONO BP	☐ PREP RSV PAL CPO
☒ CONSO MSG COLIS	☐ Putaway
☐ CONSO MULTI BP	☐ Putaway CPO
☐ Cycle Counting	☐ REAPPRO PAL ROT A
☐ Dock Transfer BR	☐ REAPPRO PAL ROT A Grade B
☐ Order Pick	☐ REAPPRO PAL ROT B
☐ Packing	☐ REAPPRO PAL ROT B Grade B
☐ PREP ACTIF MONO BP PCB	☐ REAPPRO PCB ROT C Z
☐ PREP ACTIF MONO BP PCB VAS	☐ REAPPRO PCB ROT C Z Grade B
☐ PREP ACTIF PCB MSGCOL	☐ REAPPRO UVC ROT A
☐ PREP ACTIF PCB MSGCOL VAS	☐ REAPPRO UVC ROT A Grade B
☐ PREP ACTIF PCB MULTI BP	☐ REAPPRO UVC ROT C Z
☐ PREP ACTIF PCB MULTI BP VAS	☐ REAPPRO UVC ROT C Z Grade B
☐ PREP ACTIF UVC MSGCOL	☐ Receiving
☐ PREP ACTIF UVC MSGCOL VAS	☐ Shipping
☐ PREP ACTIF UVC MSGPAL	☐ Work order Picking

OK Cancel

Last updated: 2/23/2022 9:40:55 AM User: rcolombel

Work profile - Edit existing

File Actions View Help

Work profile: CONSO MSG COLIS

Description: CONSO MSG COLIS

Detail records | Authorized users | Warehouse access | Work team/equip

Warehouse authorization

☒ All ☐ List

☒ 001

☐ Inactive

OK Cancel Apply

Last updated: 2/23/2022 9:03:56 AM User: rcolombel

Work profile - Edit existing

File Actions View Help

Work profile: CONSO MSG COLIS

Description: CONSO MSG COLIS

Work team/equipment type Work zone Vocollect region User defined

☐ Check all

☐ W-AGV INJ	☒ W-Picking Samples
☒ W-AKANE	☒ W-Picking SPCB
☒ W-Consolidation	☒ W-Picking UVC (cell 05)
☒ W-Consolidation perso	☒ W-Picking UVC (cell 08)
☒ W-CTRL	☒ W-Picking UVC Grade A
☒ W-Emballage	☒ W-Picking UVC Grade B
☒ W-Expedition	☒ W-Recep
☒ W-Perso	☒ W-Reserve PCB
☒ W-Picking PCB	

☐ Inactive

OK Cancel Apply

Last updated: 2/23/2022 9:03:56 AM User: rcolombel

1.5.6 Work special handling

A special handling constraint record defines processing validations or restrictions required for a specific group of work instructions. You can use them to increase security for expensive product, support a customer account's requests, provide guidelines for new employees, and minimize errors occurring in specific warehouse zones.

Item	Account	Company	Username	Work type	Work zone
				REAPPRO...	W-Picking S...
				REAPPRO...	W-Picking S...
				Putaway C...	W-Picking S...
				Putaway C...	W-Picking U...
				Putaway C...	W-Recep
				Cycle Coun...	
				PREP ACT...	W-Picking P...
				PREP ACT...	W-Picking P...
				PREP ACT...	W-Picking P...
				PREP ACT...	W-Picking P...
				PREP ACT...	W-Picking P...
				PREP ACT...	W-Picking P...
				PREP RS...	W-Reserve ...
				PREP ACT...	W-Emballage

- If we continue with our previously started example, we want to associate our Work special handling to a specific type of Work.

You have now set up the Work configuration for one part of Receiving, you must now repeat this entire process for the rest of Receiving, Shipment Allocation, Shipment Container, Replenishment, Inventory Transfer and Cycle Count.


For Picking:

The image displays two side-by-side screenshots of the 'Work special handling - Edit existing' dialog box in the Manhattan Associates software. Both windows have a menu bar with 'File', 'Actions', and 'Help'. The left window is on the 'General' tab, showing fields for 'Item', 'Account', 'Work', 'Username', 'Work type' (set to 'PREP ACTIF P'), and 'Work zone' (set to 'W-Picking PCB'). The right window is on the 'Key values' tab, showing various verification and picking options. It includes sections for 'Shipping container verification' (with 'Container verify' selected), 'Location verify method' (with 'None' selected), 'Picking' (with 'Use converted qty' checked), 'Receipt putaway verify method' (with 'Existing LP - no override' selected), and 'Override pick' (with 'Location' selected). Both windows have 'OK' and 'Cancel' buttons at the bottom right and a status bar at the bottom left indicating 'Last updated: 6/9/2022 8:55:50 AM User: rcolombel'.

1.6 Outbound

We will now see how to configure the Outbound process. It can be split into different subsections:

- Dock management and carrier
- Customer and preferences
- Consolidation



1.6.1 Outbound Status Action

Configurations

File Actions View Help

Outbound status action

Launch

Description	System value 1	System created	Active	Identifier
Default status for a container with no detail	100	Yes	Yes	10
Default status of short picked/short putaway port.	100	Yes	Yes	70
Default status when added from shipping	100	Yes	Yes	30
Default status when added from wave	100	Yes	Yes	40
Default status when added in order entry	100	Yes	Yes	20
Default status when shipment is cancelled	100	Yes	Yes	50
Default status when shipment is rejected	100	Yes	Yes	60

Outbound status action - Edit existing

File Actions Help

Identifier: 60

Record type: STSACTOUT

Description: Default status when shipment is rejected

System defined values

System Status: In Pool

☐ Inactive

☒ System created

☒ System rejected


OK Cancel

Last updated: 6/12/2001 5:08:47 PM User: SYSTEM

1.6.2 Functional area

This window usually has two system created functional areas: Inbound and Outbound. Within each of these areas is enclosed a status flow, made of numerous statuses.

The system defined statuses accommodate all processes generally completed for a functional area. They are provided to minimize setup time and to support the default status flow, so theoretically you should not need to add any new ones.



You should review this step and add a status in case of special requirements either in inbound or outbound flow common for all processes. The status to be added need to be defined in the **Outbound Internal Status Name Configuration**.

In case a special process needs a particular flow, a custom status flow needs to be defined as explained in the following chapter.

1.6.3 Custom status flow

A custom status flow accommodates the processing needs of special or unique items. Custom flows are defined per functional area. They cannot be shared across functional areas: in other words, a custom flow associated with the outbound functional area cannot also be used by the inbound functional area.

In our case, 2 custom flows have been defined to manage the outbound flow: MSGCOL (Messagerie colis) and MSGPAL (Messagerie palette) as shown in the image below:

- **MSGCOL (Messagerie colis)** for Shipment that have less or equal than 3 CASES:

Configurations

File Actions View Help

Outbound status action

Launch

Flow name	Functional area	Description	Active
MONOBP	Outbound Status Flow	FLUX MONO BP	No
MSGCOL	Outbound Status Flow	FLUX MESSAGERIE COLIS	Yes
MSGPAL	Outbound Status Flow	FLUX MESSAGERIE PALETTE	Yes

Custom status flow - Edit existing

File Actions Help

Flow name: MSGCOL Functional area: Outbound

Description: FLUX MESSAGERIE COLIS

Detail records User defined data

Status name	Status ...	Mandat...	Related status
☒ In Pool Pending	90	Yes	In Pool
☒ In Pool	100	Yes	
☒ Wave Pending	200	Yes	In Wave
☒ In Wave	201	Yes	
☒ Picking Pending	300	No	In Picking

☐ Inactive

OK Cancel

Last updated: 2/15/2022 1:13:19 PM User: rcolombel

Configurations

File Actions View Help

Outbound status action

Launch

Flow name	Functional area	Description	Active
MONOBP	Outbound Status Flow	FLUX MONO BP	No
MSGCOL	Outbound Status Flow	FLUX MESSAGERIE COLIS	Yes
MSGPAL	Outbound Status Flow	FLUX MESSAGERIE PALETTE	Yes

Custom status flow - Edit existing

File Actions Help

Flow name: MSGCOL Functional area: Outbound

Description: FLUX MESSAGERIE COLIS

Detail records User defined data

Status name	Status ...	Mandat...	Related status
☒ In Picking	301	No	
☒ Packing Pending	400	No	In Packing
☒ In Packing	401	No	
☒ Staging Pending	600	No	
☐ En Attente AK...	630	No	

☐ Inactive

OK Cancel

Last updated: 2/15/2022 1:13:19 PM User: rcolombel

Configurations

File Actions View Help

Outbound status action

Launch

Flow name	Functional area	Description	Active
MONOBP	Outbound Status Flow	FLUX MONO BP	No
MSGCOL	Outbound Status Flow	FLUX MESSAGERIE COLIS	Yes
MSGPAL	Outbound Status Flow	FLUX MESSAGERIE PALETTE	Yes

Custom status flow - Edit existing

File Actions Help

Flow name: MSGCOL Functional area: Outbound

Description: FLUX MESSAGERIE COLIS

Detail records User defined data

Status name	Status ...	Mandat...	Related status
☐ Appel Akanea	640	No	
☒ Loading Pending	650	No	
☒ Ship Confirm P...	700	No	
☒ Load Confirm ...	800	Yes	
☒ Closed	900	Yes	

☐ Inactive

OK Cancel

Last updated: 2/15/2022 1:13:19 PM User: rcolombel

Configurations

File Actions View Help

Outbound status action

Launch

Flow name	Functional area	Description	Active
MONOBP	Outbound Status Flow	FLUX MONO BP	No
MSGCOL	Outbound Status Flow	FLUX MESSAGERIE COLIS	Yes
MSGPAL	Outbound Status Flow	FLUX MESSAGERIE PALETTE	Yes

Custom status flow - Edit existing

File Actions Help

Flow name: MSGCOL Functional area: Outbound

Description: FLUX MESSAGERIE COLIS


Detail records User defined data

Status name	Status ...	Mandat...	Related status
☐ Delivered	990	No	
☐ Complete Reje...	994	No	
☐ Finished Item L...	995	No	
☐ Component It...	996	No	
☐ Immediate Nee...	997	No	


☐ Inactive

OK Cancel

Last updated: 2/15/2022 1:13:19 PM User: rcolombel



- MSGPAL (Messagerie palette) for Shipment that have more than 3 CASES:



The custom status flow needs to be linked to a specific wave flow in the dedicated Override step, please refer to paragraph Override Data in the wave process description.

Commented [BR8]: Not always mandatory, if the customer indicates the wished status flow in the download document. Maybe we should add somewhere this hypothesis

1.6.4 Carrier

This window contains all the information regarding Carriers. However, you will usually only fill in the **General**, **Address** and eventually the **Dock** tabs.

Carrier - Edit existing

File Actions Help

Carrier: DHL

Service: DHL

Description: DHL

General

Address

Rating

Internet information

Dock

User d

Type: Less Than Truckload

Load size definition:

SCAC:

Shipping calendar:

Pro number set name:

☒ Can be used to ship

☒ Can be used in carrier assignment

☐ Inactive

☐ System created

OK


Cancel

Last updated: 2/14/2022 1:44:43 PM User: rcolombel

Carrier	Service	Description	Type	Can be used to ship	Active
Custom	Custom	Custom Carrier	Custom	No	No
DHL	DHL	DHL	LTL	Yes	Yes
FED1	FED1	FED1	Custom	Yes	Yes
FED2	FED2	FED2	Custom	Yes	Yes
IFS	IFS	IFS	TL	Yes	Yes
RELAIS COLIS	RELAIS COLIS	RELAIS COLIS	TL	Yes	Yes


Commented [BR9]: List to modify

SCALE has many more features for carrier management and evaluation in the folder **Rating/routing**, but we will not detail their use here.



1.6.5 Dock area management carrier assignment

The system uses these records to help ensure that all a shipment's containers/details are assigned to the carrier's appropriate dock location area (staging or dock door). The system references this record when using the dock location selection strategy.



Warehouse	Dock area	Carrier	Carrier service	Carrier group	Active
001	049	DHL	DHL		Yes
001	051	FED1	FED1		Yes
001	052	FED2	FED2		Yes

Commented [BR10]: List to modify

Note that these records are **optional**, and if they do not exist, the dock assignment process will assign the default dock locations as defined on the dock management flow header or detail.

1.6.6 Dock management flow

A dock management flow record includes information which determines how the system will assign a dock location destination to a shipment line/container, and if the line/container is eligible for assignment. Each flow record is made up of a series of detail records that identify what selection and assignment strategies that the system should use when a quantity hits a certain status in your status flow.

At minimum it is required to add a detail line for each of the subclass of the shipping dock location in use for the warehouse (Packing, Staging, Dock Door), in case a custom status flow is used it can be linked to the required dock management in this configuration.

Warehouse	Default location	Custom status flow
001	PACK-01	MSGCOL
001	PACK-01	MSGPAL

 dockMgmtFlow.htm - Edit existing

File

Actions

View

Help

Warehouse:

001

Custom status flow:

MSGPAL

Default location:

PACK-01

☐ Manual dock door assignment

 Detail records

 User defined data

Status	Location subclass	Default location	Low nest after putaway	Create
In Packing	Packing	PACK-01	☒	
Staging Pending	Packing	PACK-01	☒	
En Attente AKA...	Staging	010	☒	
Appel Akanea	Staging subcl...	105	☐	

<

>

Add

Remove

OK

Cancel

Apply

Last updated: 6/27/2022 9:42:53 AM User: breitz

 dockMgmtFlow.htm - Edit existing

File

Actions

View

Help

Warehouse:

001

Custom status flow:

MSGPAL

Default location:

PACK-01

☐ Manual dock door assignment

 Detail records

 User defined data

Status	Location subclass	Default location	Low nest after putaway	Create
En Attente AKA...	Staging	010	☒	
Appel Akanea	Staging subcl...	105	☐	
Loading Pending	Staging	110	☐	
Ship Confirm Pe...	Dock Door	PORTE02	☐	

<

>

Add

Remove

OK

Cancel

Apply

Last updated: 6/27/2022 9:42:53 AM User: breitz

For the status “Appel Akanea” a specific location subclass has been created in “Generic config header”. We have created a second staging location subclass to let the system differentiate two staging locations with two different statuses.

Generic config header - Edit existing

FileActionsViewHelp

Record type:

SHPDCKLOCSUBCLS

Description:

Shipping Dock Location Subclass

Detail records

User defined data

Identifier	Description	System create
10	Dock Door	Yes
30	Packing	Yes
40	Staging	Yes
50	Staging subclass 2	No

☒ System created

OKCancelApply

Last updated: 12/20/2007 9:59:46 AM User: System

1.6.7 Dock area anchor criteria

This window defines which dock areas are assignable to shipping containers when they are being anchored. The system will add all dock areas to the eligible list that match the user defined filter criteria. Later, the dock location assignment strategy will choose the container's exact destination dock location.

Filter name	Description	System created	Active
CONSO MONO BP	CONSO MONO BP	No	Yes
CONSO MSGCOL DHL	CONSO MSGCO...	No	Yes
EMP AKANEA	EMP AKANEA	No	No



Dock area anchor criteria - Edit existing

×

FileActionsHelp

Record type:

DOCKAREAANCHORCRITERI

Filter name:

CONSO MONO BP

Description:

CONSO MONO BP

Table name:

Shipment header view

Filter data

Filter criteria

☒ And

☐ Or

Attribute:

Operand:

Value:

SHIPMENT_HEADER_VIEW.SHIPMENT_ID MATCHES

Up

Down

Add rule

Delete selected rule

Delete last rule

Insert left parenthesis

Insert right parenthesis

Delete parenthesis

☐ Inactive

☐ System created

OK

Cancel

Last updated: 2/16/2022 4:57:21 PM User: rcolombel



Dock area anchor criteria - Edit existing

×

FileActionsHelp

Record type:

DOCKAREAANCHORCRITERI

Filter name:

CONSO MSGCOL DHL

Description:

CONSO MSGCOL DHL

Table name:

Shipment header view

Filter data

Filter criteria

☒ And

☐ Or

Attribute:

Operand:

Value:

SHIPMENT_HEADER_VIEW.SHIPMENT_ID MATCHES
AND SHIPMENT_HEADER_VIEW.CARRIER = 'DHL'

Up

Down

Add rule

Delete selected rule

Delete last rule

Insert left parenthesis

Insert right parenthesis

Delete parenthesis

☐ Inactive

☐ System created

OK

Cancel


Last updated: 6/13/2022 11:00:04 PM User: cftsupport

Commented [BR11]: Why did we add dhl only


1.6.8 Packing preferences

A packing preference record allows you to manage how a user or group of users will pack shipments. You can create specific preference records for employees with unique packing processing needs.

Packing tab is dedicated to set up behavior of SCALE for the Packing stations, no changes required in case of Pick&Pack process.



Quality control tab is dedicated to set up behavior of SCALE for the quality workbench QC is performed on outbound.




The screenshot shows the 'Packing preferences - Edit existing' dialog box with the 'Quality control' tab selected. The 'Preference name' is '*Default' and the 'Description' is 'Default Packing Preferences'. The 'Quality control' tab contains the following settings:

- ☒ Blind QC inspection
- ☐ Lot verification required
- ☒ Prompt when unknown item counted

A yellow box highlights the text 'Lot verification required' next to the 'Prompt when unknown item counted' checkbox. At the bottom, there is an 'Inactive' checkbox, 'OK' and 'Cancel' buttons, and a status bar indicating 'Last updated: 6/30/2022 8:37:03 AM User: rcolombel'.

Close Container tab is dedicated to control behavior of SCALE for the close container operation both in UI and RF.



The screenshot shows the 'Packing preferences - Edit existing' dialog box with the 'Close container' tab selected. The 'Preference name' is '*Default' and the 'Description' is 'Default Packing Preferences'. The 'Close container' tab contains the following settings:

- General settings**
 - ☐ Auto manifest at close
 - ☐ Allow container creation during close
 - ☒ Allow VAS override at close container and load confirm
 - ☒ Assign shipment to load
 - ☐ Use drop down
- Initiation method**
 - ☐ Always shipment id
 - ☒ Always container id
 - ☐ Container id unless no open containers
- Auto print at close**
 - ☐ No
 - ☐ Yes
 - ☒ Prompt

At the bottom, there is an 'Inactive' checkbox, 'OK' and 'Cancel' buttons, and a status bar indicating 'Last updated: 6/30/2022 8:37:03 AM User: rcolombel'.

1.6.9 Shipping preferences

A shipping preference record allows you to manage how a user or group of users will ship confirm orders. The default shipping preference record should accommodate most employees. Create specific preference records for employees with unique processing needs.

 Shipping preferences - Edit existing

File Actions Help

Preference name:

Description:

☒ General ☐ Work type ☐ Assigned users ☐ User defined data

Shipping/container

☐ Auto print at load confirm

☒ Compute delivery date

☐ Create dock work on assigning load to dock door

☐ Create orders from shipments

☐ Manifest un-manifested containers during ship confirm

☒ Transfer failed shipments during load confirm

Split shipment mode

☐ Prompt

☐ Split shipment

☐ Split shipment if not in range

☒ Do not split shipment

Status range

Loading Pending Ship Confirm Pending

RFID writer endpoint:

☐ Inactive

OK Cancel

Last updated: 2/15/2022 5:09:26 PM User: rcolombel

 Shipping preferences - Edit existing

File Actions Help

Preference name:

Description:

☒ General ☐ Work type ☐ Assigned users ☐ User defined data

Work type

Auto work execution:

Consolidation:

Immediate dock transf...:

☐ Inactive

OK Cancel

Last updated: 2/15/2022 5:09:26 PM User: rcolombel

1.6.10 Planned Shipment Filters – Not used


1.6.11 Comment Type - Not used

1.7 Allocation

Allocation rules are used both for waving and replenishment process to determine from where the stock can be taken.

For the configuration of the Allocation process, we first look at the criteria to assign allocation rules, before selecting the allocation locations, then creating the rule and finally assigning the latter rule.


So, we first define how the rule is selected, then where it will affect the warehouse, then what it will do, and finally tie all this information together in an Allocation rule assignment.



1.7.1 Allocation rule assignment criteria

This window enables the definition of criteria to select a specific rule. We first create the **assignment criteria** and will later tie it to a **rule** thanks to a **rule assignment**.

Launch				
	Filter name	Description	System created	Active
▶	Haddad assignment CPO	Haddad assignment CPO	No	Yes
	Haddad assignment	Haddad assignment	No	Yes



Allocation rule assignment criteria - Edit existing

File Actions Help

Record type:

Filter name:

Description:

Table name:

Filter data

Filter criteria

☒ And ☐ Or

Attribute: Operand: Value:

COMPANY = N'Haddad'
AND INTERNAL_SHIPMENT_NUM IS NOT NULL
AND USER_DEF3 IS NULL

Up
Down

Add rule
Delete selected rule
Delete last rule
Insert left parenthesis
Insert right parenthesis
Delete parenthesis

☐ Inactive
☐ System created

OK Cancel

Last updated: 4/28/2022 10:30:04 AM User: rcolombel

In this specific example, we have a criterion named “user_def3” that will define if we use the “Haddad assignment” or the “Haddad assignment CPO”

1.7.2 Allocation location selection

Those allocation location selection will be linked to the allocation rule. The allocation rule will indicate a location to allocate according to those following details.

Allocation location selection - Edit existing

File Actions Help

Record type:

ALLOC SEL

Filter name:

Reserve PAL

Description:

Reserve PAL

Table name:

Location

Filter data

Order by

Filter criteria

And

Or

Attribute:

Operand:

Value:

LOCATION.ALLOCATION_ZONE = N'A-Reserve PCB'

AND LOCATION.ACTIVE = N'Y'

AND LOCATION.INVENTORY_ATTRIBUTES.LOC_INV_ATTRIBUTE1 IS NULL

AND LOCATION.LOCATION_STS != N'Frozen'

AND LOCATION.INVENTORY.INVENTORY_STS = N'Available'

AND LOCATION.INVENTORY.warehouse = N'001'

AND LOCATION.LOCATING_ZONE != N'L-Articles CPO'

Add rule

Delete selected rule

Delete last rule

Insert left parenthesis

Insert right parenthesis

Delete parenthesis

Up

Down

Inactive

System created

OK

Cancel

Last updated: 6/7/2022 3:22:01 PM User: cftsupport

1.7.3 Allocation rule

Now that we defined how the rule will be assigned and where the operator will go and pick from, we define what the rule consists in.

Allocation name	Description	Active
*Default	Default Allocation Rule	No
Affectation CPO	Affectation CPO	Yes
▶ Affectation Standard	Affectation Standard	Yes
Affectation WO	Affectation WO	Yes
Allocate KO	OD Allocate KO	Yes
Réappro RSV PAL	Réappro RSV PAL	Yes
Réappro RSV PCB	Réappro RSV PCB	Yes

 Allocation rule - Edit existing

File Actions View Help

Allocation name:

Description:

 Detail records  User defined data

Sequence	Strategy	Location selection	Eligible ums	Lot
▶ 10	Closest Match ...	Reserve PAL	PAL	Specified lot (s...
20	Closest Match ...	Picking PCB	PCB,SPCS	Specified lot (s...
30	Closest Match ...	Picking UVC	UVC	Specified lot (s...

☐ Inactive

OK Cancel Apply

Last updated: 2/14/2022 4:07:46 PM User: rcolombel

In our example, the 'Reserve Pal' location selection will be filter according to the "allocation location selection" criteria. It will look into this area to do the picking. If nothing is found in "Reserve Pal" location the system will redirect the research toward the "Picking PCB" location and then "Picking UVC".

1.7.4 Allocation rule assignment

Finally, once we have defined how the rule is selected, where it will affect the warehouse and what it will do, we need to tie all this information together in an Allocation rule assignment.

Priority /	Criteria	Allocation rule	Active
▶ 10	Haddad assignment	Affectation Standard	Yes
20	Haddad assignment CPO	Affectation CPO	Yes

Allocation rule assignment - Edit existing

×

File Actions Help

Priority: 10

✓ General

User defined data

Criteria:

Haddad assignment

Allocation rule:

Affectation Standard

☐ Always override

☐ Inactive


OK

Cancel

Last updated: 3/25/2022 2:24:08 PM User: rcolombel


1.8 Wave

For this section, the focus will be on wave flows and how they are selected. The following figure illustrates the steps to complete in order to be able to use the Wave master properly.



1.8.1 Container type

Defining a container type consists in informing the system of the sizes of the different available containers used by the warehouse and their empty weight. This step may seem unimportant, but SCALE requires this information to know the container type that can be assigned to an item and where these containers can be stored. The following figure shows a typical example of how to define a Container type.



The screenshot shows the 'Configurations' application window with the 'Container type' configuration table. The table has columns for Container type, Description, Container class, Length, Width, Height, Dimension um, Use as default, and Active. The 'Container type' column is highlighted in blue.


Container type	Description	Container class	Length	Width	Height	Dimension um	Use as default	Active
CS	Carton CS	CS	60.000	40.000	40.000	cm	No	Yes
FAC	Carton OUV FACIALE	CS	60.000	50.000	50.000	cm	No	Yes
PAL	Palette	PAL	120.00	80.000	180.00	cm	No	Yes
PCB	PCB Complet	PCB	999.00	999.00	999.00	cm	No	Yes

1.8.2 Override data

This step allows you to override or update data (that you normally would not have access to) during the wave process. You can configure this "override data" wave step to replace a specific data field with a value that you define. To configure this action, you will need to create an override data record (and a corresponding criteria record) and include this "override data" wave step in your default flow. Additionally, the system allows you to include multiple "override data" wave steps in your wave flow. This allows you to override different types of data at different times during the wave. To create additional steps, you will first need to copy the default override wave step, and then create the wave step(s) based on this base override data functionality.

Note that only override data wave steps (with the specific base Namespace/Class/Method) will appear in the Wave Step Field on the Override Data Window.

Override data are usually personalized SQL scripts as shown below:



Override wave step - Edit existing

File Actions Help

Identifier: Consol Shipments Stats

Description: Consolidate Shipments Statistics

Wave step: Consolidate Shipments Stats

Priority: 1

☒ Custom SQL

Statement  User defined data

```
exec dbo.WVST_ShipmentsConsolidated <<LAUNCH_NUM>>;
```

☐ Inactive

OK Cancel

Last updated: 12/9/2009 8:05:09 AM User: System

1.8.3 Wave steps

A wave step identifies a specific process that will occur during the wave, such as carrier routing or replenishment. Default wave steps are shipped with the system and cannot be changed.

It takes custom programming to add a new wave step different than an override one. As best practice different override steps in copy from the default one is usually created in advance to be set before and after relevant wave steps in case of need.

Basically, in this step you will create all the existing steps within all the waves. These steps will then be put into order and tied to a specific wave later.

We are going to create a new wave step:

Wave steps - Edit existing

File Actions Help

Record type: LAUNCHSTE Identifier: 20

Description: Allocation

☒ General ☐ User defined data

☒ API ☐ Web service ☐ Stored proc

Assembly name: WMW.Jsharp.Inventory.BL

Namespace: com.pronto.bl.inv

Class: Allocation

Method: allocateShipmentsFromLaunch

☐ Inactive ☒ System created

OK Cancel

Last updated: 12/20/2002 1:32:45 PM User: SYSTEM

1.8.4 Wave flow

In this step, we put in order the wave steps we created previously, according to the wave they belong to. We will later associate each wave flow with the appropriate wave in the Wave Master Window.

Wave flow - Edit existing

File View Actions Help

Wave flow: Prélèvement Standard

Description: Prélèvement Standard

☒ Detail records ☐ User defined data

Sequence	Description
10	Start Wave
20	Start Wave Statis...
25	OD WaveStart_A...
40	Consolidate Ship...
60	Replenishment
70	Work Order...

☐ Inactive

OK Cancel Apply

Last updated: 2/14/2022 2:19:55 PM User: rcolombel

Wave flow - Edit existing

File View Actions Help

Wave flow:

Description:

☒ Detail records ☐ User defined data

Sequence	Description
80	Rule Assignment
90	Allocation
120	Container Creation
150	Pick Group Creati...
190	VAS Assignment
205	OD Wave Def...

☐ Inactive

Last updated: 2/14/2022 2:19:55 PM User: rcolombel

Wave flow - Edit existing

File View Actions Help

Wave flow:

Description:

☒ Detail records ☐ User defined data

Sequence	Description
190	VAS Assignment
205	OD Wave_Befor...
210	Work Creation S...
280	Complete Wave

☐ Inactive

Last updated: 2/14/2022 2:19:55 PM User: rcolombel

When creating a new Wave flow, remember to click **Apply** once you have written down the **Wave flow name** and **Description** to have access to the **Detail records**. You can then **right click, New** and select the Wave steps you wish to add. Remember to set up the wave steps in the right order, using the **Sequence** field. More information on the suggested order for wave steps are detailed in AIM.

1.8.5 Wave maximums

During the wave building process, the wave maximum record determines when a wave will stop accepting shipments. When the system stops accepting shipments, it generates a new wave and therefore continues accepting shipments. You will establish wave maximums on the Wave Maximums Window. This maximum may be number of lines, of shipments, a quantity, a weight or even a volume.


These maximums are later associated with the appropriate waves via the Wave Master Window.

In our case, no maximums needed to be defined.

1.8.6 Wave criteria

This step allows the definition of the criteria which will determine which shipments will be included in which type of wave. If a shipment line matches a criteria rule, then the system will select the entire shipment for the wave.

Note that all the shipment lines do not have to match for a shipment to be selected.



1.8.7 Wave master

This step ties all the previously created information together under a Wave master also including the document and label masters (detailed in the Document Printing Paragraph).

In the wave master is also selected the wave execution mode that regulate if and how a wave will be built starting from shipment in the pool.

Wave master - Edit existing

File Actions Help

Wave name: Vague de PREL Standard
Description: Vague de PREL Standard

Mode
☐ Automatic ☒ Manual ☐ Build inactive

General Selection criteria Replenishment Masters Warehouses User def

Priority: 1
Wave criteria: Commandes sar
Wave flow: Prélèvement Sta
Wave maximums:
☐ Auto release
☐ Maintain allocated replenishments upon wave cancellation

☐ Inactive
Last updated: 2/28/2022 9:08:08 AM User: rcolombel

OK Cancel

Wave master - Edit existing

File Actions Help

Wave name: Vague de REAPPRO Standard
Description: Vague de REAPPRO Standard

Mode
☐ Automatic ☒ Manual ☐ Build inactive

General Selection criteria Replenishment Masters Warehouses User def

Priority: 1
Wave criteria: Commandes sar
Wave flow: Vague de Reapp
Wave maximums:
☐ Auto release
☐ Maintain allocated replenishments upon wave cancellation

☐ Inactive
Last updated: 3/9/2022 1:00:10 PM User: rcolombel

OK Cancel

1.9Value Added Services

1.10.1 VAS activity criteria

Configurations

File Actions View Help

Launch

VAS activity

Container type
Customer
Customer categories
Delivery type
Dock management
Freight consolidator
Packing class
Packing criteria
Packing preferences
Shipment process typ
Shipping preferences
Store location assign
Store location assign
Quality control
Rating/routing
Receiving

Filter name	Description	System created	Active
COLIS1015	COLIS1015	No	Yes
ITEM1015	ITEM1015	No	Yes
SEEDING1015	SEEDING1015	No	Yes
1015	1015	No	No
Seeding	Seeding	No	No
VAS TEST	VAS TEST	No	No
VAS TEST COM...	VAS TEST COMMANDE	No	No

1.10.2 VAS Activity

Configurations

File Actions View Help

Launch

VAS activity

Container type
Customer
Customer categories
Delivery type
Dock management
Freight consolidator
Packing class
Packing criteria
Packing preferences
Shipment process typ
Shipping preferences
Store location assign
Store location assign
Quality control
Rating/routing

Name	Application level	Activity criteria	Instructions
1015	All containers		Type de scotch Haddad
COLIS1015	All containers	COLIS1015	COLIS1015
ITEM1015	All containers	ITEM1015	ITEM1015
SEEDING...	All containers	ITEM1015	SEEDING1015
VAS TEST	All containers		TEST VAS


LAST MODIFIED: 30/9/2026 9:56 PM

SCALE CONFIGURATION WALKTHROUGH

76

1.10 Cycle counting

Cycle counting is a crucial concept, as it enables a comparison between what should be in a location and what is physically there. Doing so will allow SCALE to give accurate numbers regarding the inventory. However, cycle counting can either be planned or not. In both cases, SCALE needs to support adjustments and inventory transfer, regardless of if it was planned.



1.10.1 Cycle count system values

All these system-created values are used by the system to process cycle counts. Refer to the Help menu to know if you need to modify any of those values (depending on if the cycle counting is planned or not).

Keep in mind that to be able to confirm count an adjustment type need to be assigned as the System value for the positive and negative adjustments of both Activity and Planned count.

This adjustment type is used, in case of quantity discrepancy during cycle count, to update the quantity in a location.

Configurations
File Actions View Help


Launch

Configurations	Description	System value	ystem create	Key
Functional areas				
Allocation				
Cycle count				
Cycle count item cri	Activity Count - Negative Adjustment	Ajustement	Yes	30
Cycle count locatio	Activity Count - Positive Adjustment	Ajustement	Yes	40
Cycle count master	Auto Print Cycle Count List	N	Yes	10
Cycle count prefere	Auto Release Cycle Count Plan	Y	Yes	20
Cycle count system	Create work for activity driven cycle co...	Y	Yes	90
Cycle count thresh	Default cycle count group size	50	Yes	100
Inventory control	Planned Count - Negative Adjustment	Ajustement	Yes	50
Order entry	Planned Count - Positive Adjustment	Ajustement	Yes	60
Packing/shipping	SRC identifier for activity driven work	80	Yes	110
Quality control	Work unit field for activity driven work	FromLoc	Yes	70
Rating/routing				
Receiving				

1.10.2 Cycle count Preferences


This step defines when cycle counts should be executed: should they be executed immediately or created as “pending” requests. You will probably not need to change anything here but check in the “*Default” preferences to see if they correspond to what you are expecting.

In our case, we create “Cambrai - Inventaires” preference where “Perform threshold counts immediately” and “Verify bad count on RF” icons are checked.



1.10.3 Cycle count item criteria

This step defines which items are eligible for cycle counting by using a filter. This criterion will then be tied to its associated cycle count via the Cycle count master.




1.10.4 Cycle count location criteria

These records are used by the system to filter the number of locations eligible for a cycle count, according to settings defined on the cycle count master record. The system will only create cycle count requests for locations that match this criterion.

For our case, we create two Filters: **All** and **CC LOCATION Annual**.

- **All**: To select all the active locations to perform the Cycle count on the whole warehouse.
- **CC LOCATION Annual**: To select locations that have not been counted in the last 360 days. This criterion is used for the annual cycle count plan.



- Cycle count location criteria: **All**

Configurations

File Actions View Help

Launch

Configurations

- Functional areas
 - Allocation
 - Cycle count
 - Cycle count item criteri
 - Cycle count location cn
 - Cycle count master
 - Cycle count preference
 - Cycle count system val
 - Cycle count threshold
 - Inventory control
 - Order entry
 - Packing/shipping
 - Quality control
 - Rating/routing
 - Receiving
 - Replenishment
 - Value added services
 - Wave
 - Work
 - Work order
 - Yard management
 - General
 - Personalization/extensibility
 - Security
 - Technical
 - UHAD
 - User/warehouse

Filter name	Description	system create	Active
All	All	No	Yes
CC LOCATION Annual	Cycle count location annual	No	Yes

Cycle count location criteria - Edit existing

File Actions Help

Record type: CC LO CRIT

Filter name: All

Description: All

Table name: Location

Filter data

Filter criteria

☒ A Attribute: Operand: Value:

LOCATION.LOCATION_TEMPLATE = N'Stock / Pref

Up

Do

Add rule

Delete selected r

Delete last rule

Insert left parenth

Insert right paren

Delete parentheses


☐ Inactive

☐ System created

OK Cancel

Last updated: 4/19/2022 3:10:45 PM User: rcolombel


- Cycle count location criteria: CC LOCATION Annual



1.10.5 Cycle count master

In this step, we tie the previous steps together under an associated Cycle count.

In our case, we are going to use this cycle count master.



We create this " Inventaire Annuel " cycle count master for annual cycle count plan to create schedule-based cycle count work.


1.10.6 Cycle count threshold

This step determines when the system should trigger the creation of a non-plan based ("activity-driven") cycle count request for a location. When the system checks to see if a location meets a threshold, it will first look to see if a location matches three variables: Location Type, Work Zone, and Movement Class.

If it the location does not meet all these variables, the system searches for only Location Type and Movement Class. If no location meets those criteria, the system searches for Location Type only. If no locations meet this, the system looks for an all-blank threshold.


In this configuration is also specified the minimum time interval between 2 consecutive counts on the same location in number of days.

In our case, we create threshold to verify empty locations for picking work zones.



1.10.7 Cycle count work criteria


All work criteria records are created on a work criteria window. There is one work criteria window for each type of work creation process. A work criteria record manages the following activities: it determines which work requests are selected for work processing; it creates a work unit; and it determines the order that work instructions are generated and released to the warehouse floor.



1.11 Work orders

Work Order processing manages the creation of finished items from component parts. All work order related information, such as components and instructions, can be stored on a bill of material record or manually entered when the work order is created. Component part allocation can be performed automatically when the work order is created or released. Employees can also manually allocate components. You can use work creation to support the movement of component parts to the build location and finished items to their storage locations. You can also choose not to use work creation and instead use paperwork to move items. Also, the system supports bill of material revision numbers. When you copy an existing bill of material record, the system assigns the new record a revision number. This allows you to support multiple versions of one finished item.

In the environment used as guideline for examples of this document there was no configuration of work order at all, so the information provided were based on AIM online help.



1.11.1 Bill of materials

A bill of material record defines a finished item and its requirements. These requirements include what component parts are required to create the finished item and instructions on how to assemble the finished item from its components. When a work order is generated for a finished item, the system defaults relevant bill of material records on both the work order request and any paperwork generated for the finished item.

Bill of materials - Edit existing

File Actions View Help

Item: XYZ Company: Haddad

Item description: XYZ

Revision num.: 1 Quantity u.: UVC

Planned unit build time (h): 0 : 0 Build loc.: [dropdown]

Item characteristics Components Instructions User defined data

Item length: 0.10000 U.: [dropdown] Item size: 12 ANS

Item width: 0.10000 Item color: ROUGE

Item height: 0.10000 Item style: [dropdown]

Item volume: 0.001 Item value: 0.00000

Weight per pie: 0.10000 Item cost: 40.00000

Item class: LAYERING TO ☒ Inventory tracked

Note: Finished item's characteristics are managed by existing item information.

☐ Inactive Apply OK Cancel

Last updated: 7/10/2022 10:42:37 PM User: rcolombel

Bill of materials - Edit existing

File Actions View Help

Item: XYZ Company: Haddad

Item description: XYZ

Revision num.: 1 Quantity u.: UVC

Planned unit build time (h): 0 : 0 Build loc.: [dropdown]

Item characteristics Components Instructions User defined data


Level	Seq	Item	Item description	Qty per item	Qty um	From location
1	1	X	X	1.00000	UVC	
1	2	Y	Y	1.00000	UVC	
1	3	Z	Z	1.00000	UVC	

☐ Inactive Apply OK Cancel

Last updated: 7/10/2022 10:42:37 PM User: rcolombel

1.11.2 Work order preferences

A work order preference record allows you to manage how a user or group of users will process work orders. The default record should accommodate most employees. However, you can create specific preference records for employees with unique processing needs.



1.11.3 Work order system values

These values manage how work orders are processed in your warehouse. They are system created and you should not need to modify them.

1.11.4 Work order finished item work criteria


1.11.5 Work order component work criteria

1.12 Replenishment

The replenishment process determines when product should be moved from bulk storage locations and transported to forward picking locations. This allows employees to efficiently complete picks for individual orders without compromising the integrity of larger UM increments. Replenishments are triggered by the system when the location's quantity falls below a minimum threshold percent. You can set this percent value at the location/location type level, or for an item/item class. A replenishment generates an allocation request from the bulk location. The product is marked as In Transit to the forward location.


The allocation of product for the replenishment is managed by the allocation rule defined on the replenishment master.

Commented [WTK12]: To Modify.



Below is included a basic scheme of the configuration required to set up correctly all replenishment processes:


REPLENISHMENT CONFIGS



1.12.1 Replenishment location criteria


This step determines when a location may be considered for replenishment.

- If this record is associated with a replenishment master that generates replenishment based on item location capacity, it determines which locations are evaluated for replenishment needs.
- If this record is associated with a replenishment master which generates replenishment based on pool or wave demand, this record determines which locations the system will attempt to replenish. Any location, inventory, or inventory attributes value(s) can be used to define a replenishment location criteria record.



1.12.2 Replenishment item criteria

A replenishment item criteria record identifies which item(s) you want the system to evaluate for replenishment eligibility when you are running demand-based replenishment for a wave or a pool. When replenishment is attempted for either shipments in the order pool or in a wave, the system uses this record to define what types of items should be considered for replenishment. This criterion narrows the amount of processing time required to run the replenishment wave step, while ensuring that important items are ready for allocation.




1.12.3 Replenishment empty location criteria

You will use this window to identify which location(s) the system should replenish product to if either of the following situations occurs:

- The amount of product that you must replenish exceeds the locations available for replenishment. After the system replenishes to all the locations that currently contain the product, this field identifies the next location(s) that it can replenish to.

OR


- No locations currently contain the item that you need to replenish. In this case, you will use this field to determine where to start replenishment.




1.12.4 Replenishment master

In the replenishment master all the previous replenishment configuration and the assigned allocation rule for a specific replenishment process are linked together.

In the **General** tab is specified the replenishment type that define the criteria to calculate the requested quantity, the work creation method, allocation rule and increment.



In **Replenishment Criteria** tab are linked the location and item criteria



Replenishment master - Edit existing

File Actions View Help

Replenishment name: Reapro Rot A GRA PCB

Description: Réa Rot A Grade A PCB

General Demand ums Replenishment criteria Replenishment m

Pallet
PCB
SPCS
UVC

Inactive

Last updated: 6/30/2022 10:50:46 AM User: rcolombel

OK Cancel

Replenishment master - Edit existing

File Actions View Help

Replenishment name: Reapro Rot A GRA PCB

Description: Réa Rot A Grade A PCB

General Demand ums Replenishment criteria Replenishment m

Location criteria: Picking UVC

Empty location criteria: Picking UVC Slow


Item criteria: Articles rotation A

Inactive

Last updated: 6/30/2022 10:50:46 AM User: rcolombel

OK Cancel

In the **Replenishment Strategy** tab is specified the rounding criteria for the **Increment** specified in the **General** tab, more than one strategy can be applied in the sequence.



Replenishment master - Edit existing

File Actions View Help

Replenishment name: Reapro Rot A GRA PCB

Description: Réa Rot A Grade A PCB

Demand ums Replenishment criteria Replenishment modes Replenishment m

Manual
Wave
Real time

Inactive

Last updated: 6/30/2022 10:50:46 AM User: rcolombel

OK Cancel

Replenishment master - Edit existing

File Actions View Help

Replenishment name: Reapro Rot A GRA PCB

Description: Réa Rot A Grade A PCB

Replenishment modes Replenishment strategy User defined data

Sequence	Strategy	Description
10 30	Round up to the next whole number increment	




Inactive

Last updated: 6/30/2022 10:50:46 AM User: rcolombel

OK Cancel

1.12.5 Replenishment work criteria


All work criteria records are created on a work criteria window. There is one work criteria window for each type of work creation process. A work criteria record manages the following activities: it determines which work requests are selected for work processing; it creates a work unit; and it determines the order that work instructions are generated and released to the warehouse floor.



1.13 Container creation


The container creation process involves the system creating containers for shipment line-item quantities via the execution of a wave step. This wave step determines how many container(s) it will create to pack these allocated item quantities. There are four strategies that can be used by this wave step to determine how to distribute quantities into newly created containers: Consolidate and Do Not Split, Split And Do Not Consolidate, Consolidate And Split Only Once, and 3D Cubing.

Container Creation



1.13.1 Container creation system values

This step allows you to manage certain settings that will affect the execution of the container creation wave step.




The System value field allows you to select different types of values according to the Key. For example, for the Key 10 (Container Creation Strategy) shown in the figure above, you must choose one of the four strategies mentioned earlier (Consolidate and Do Not Split, Split and Do Not Consolidate, Consolidate and Split Only Once, and 3D Cubing).

1.13.2 Container creation criteria


This step allows you to create a filter to define for which items or shipments you want the system to create containers during the wave, and in which order you want the system to do this. Container

creation criteria records help the container creation process selectively create containers only for the items/shipments that you choose.



In our case, we only create the “Default Container Creation Criteria” filter, which will select all the items/shipments included in a wave (therefore having a Launch number different from “NULL”).


1.13.3 Container Class



For Haddad warehouse we have different type of container class: Carton (CS), Palette (PAL), PCB Complet (PCB).

1.13.4 Container type


Dealt with in the “Wave” section.



Container type	Description	Container class	Length	Width	Height	Dimension um	Use as default	Active
CS	Carton C5	CS	60.00000	40.00000	40.00000	cm	No	Yes
FAC	Carton OUV FACIALE	CS	60.00000	50.00000	50.00000	cm	No	Yes
PAL	Palette	PAL	120.00000	80.00000	180.00000	cm	No	Yes
PCB	PCB Complet	PCB	999.00000	999.00000	999.00000	cm	No	Yes

1.13.5 Container Group

A container group identifies all the containers that can be used to pack an item, or group of items. During the container creation wave step, the system processes through a container group's details in sequence order. After you define a container group, you will link it to the correct packing class on the Packing Class Window.




Container group	Description	Active
*Default	Default Container Group	Yes
Emballage HADDAD	Emballage HADDAD	Yes
Emballage OUV FACADE	Emballage OUV FACADE	Yes

Sequence	Container type	Fill percent	Container shape
10	C5	100	Standard

1.13.6 Packing class

A packing class determines which container type(s) the system can evaluate when determining how to pack items during container creation in the wave. You can also indicate on a packing class which

items can pack together in the same container. Packing classes can be associated with an item on the Item Window, and on a shipment line record.




1.14 Quality control (QC)

Commented [BR13]: Will evolve

SCALE features modules for both inbound and outbound quality control. The inbound quality control process involves the system taking a certain portion of a receipt's item quantity and routing it to a special location so it can be inspected. The outbound quality control process involves taking a subset of the shipping containers that are being shipped out of the warehouse and inspecting the contents to verify that they match what the system believes to be in the container.

Here, we will focus on the case of performing QC manually on a shipping container. We will first define the assignment criteria, before selecting an evaluation method and finally tie this information together using the QC assignment feature.



1.14.1 QC assignment criteria

Here, we create a filter to select specific containers.

QC assignment criteria - Edit existing

File Actions Help

Record type: QCASSIGNCRIT

Filter name: Quality control

Description: Colls en zone Quality control

Table name: Shipping container

Filter data

Filter criteria

And Attribute: Operand: Value:

Or

(WORK_INSTRUCTION.INCOMING_PD_LOC LIKE N'QCTR1' OR WORK_INSTRUCTION.WORK_TYPE = N'PREP ACTIF UVC MSGCOL)

Up Down

Add rule

Delete selected rule

Delete last rule

Insert left parenthesis

Insert right parenthesis

Delete parenthesis

☐ Inactive

☒ System created

OK Cancel

Last updated: 3/1/2022 9:08:08 AM User: rcolombel

In this case, we want to select shipping containers, so we set the filter to make eligible only shipping containers from the warehouse we are working in (we only have one warehouse, which explains why the rule is set to "IS NOT NULL").

1.14.2 QC evaluation method

Then, moving to the evaluation method, we notice all the evaluation methods are system created and correspond to a specific identifier. We will choose the one named "Manual".

Configurations

File Actions View Help

QC evaluation method

Launch

Description	System value 1	System created	Active	Identifier
Manual	Yes	Yes	Yes	30
Start Work	Yes	Yes	Yes	20
Wave	Yes	Yes	Yes	10

QC evaluation method - Edit existing

File Actions Help

Identifier: 30

Record type: QCEVALMETHOD

Description: Manual

☐ Inactive


☒ System created

OK Cancel

Last updated: 4/22/2016 1:32:34 PM User: System

1.14.3 QC assignment


Finally, we assign the criteria and evaluation method to a QC. In the **General** tab, we indicate the assignment criteria defined in the first step of QC. In the tab **QC evaluation method**, we check the evaluation method selected in the previous step ("Manual").



1.14.4 Interfaces

In this section, you can set up how SCALE communicates with the ERP host system. You can invoke an interface upload/download by either starting it manually from SCALE, or have the system kick it off automatically via a scheduled job. The interface will process through all the appropriate files/records in order of last modified time (earliest to latest).


This task is usually performed at the very beginning of the project by experienced consultants.



1.14.5 Interface system values

To share records between the ERP and the system, you will need to identify several system settings, some of which are defined for a specific functional area (such as shipping or receiving).

We updated the following parameters



Description	System value	system create	Key
Allow duplicate Receipt IDs on add?	Y	Yes	60
Allow duplicate Shipment IDs on add?	Y	Yes	100
Allow zero in UD7, UD8, UD9, and U...	N	Yes	210
Delimiter token		Yes	10
Include 0 inventory items in item bala...	N	Yes	50
Input Directory for Interface File Dow...	https://uhadstgme46 file core windows net/ils/Interface/Input	Yes	30
Interface Date Format	wwMMdd	Yes	190
Interface Error File Output Directory	https://uhadstgme46 file core windows net/ils/Interface/Out...	Yes	40
Interface Error Original Data Output...	https://uhadstgme46 file core windows net/ils/Interface/Out...	Yes	220
Interface XSL Files Location	https://uhadstgme46 file core windows net/ils/Interface/XSL	Yes	180
Output Directory for Interface File U...	https://uhadstgme46 file core windows net/ils/Interface/Upl...	Yes	150
Receiving Upload Level	Header	Yes	80
Shipping interface download record t...	Shipments	Yes	110
Status that new Receipt records are ...	20	Yes	70
Status that new shipping records are ...	100	Yes	120
Upload deleted shipments?	Y	Yes	140
Upload receipt containers at this stat...	10	Yes	90

1.14.6 Interface data maps (not required if XML)

An interface data map record is required to map the interface file in case of delimited or fixed length mode. It identifies what fields should be included in an interfaced file, and the position of each field, SCALE uses these records to read files it obtains from the ERP.

On the left side you have all the available fields for a specific record type and on the left side you can specify the actual fields to be mapped, fields are moved to the selected fields windows using the dedicated Add and Remove buttons. As mode you can select delimited data or as fixed length data. Note that if you choose fixed length mode, the system will require that each field defined for this data map be given a specific length.

Interface data map - Display

FileActionsViewHelp

Data map na...REDTL

Record type:Receipt Detail Download

Action:New

Mode

☒ Delimited file

☐ Fixed length

Available fields

Catch weight required

Conversion height

Conversion length

Conversion qty

Conversion um

Conversion weight

Conversion width

Customer order number

Date time stamp

Erp order number

Erp order type

Erp order type

Add >

Add >>

< Remo

<<Rem

#

Selected fields

1REDTL

2Interface record id

3Interface link id

4Erp order line num...

5Item

6Company

7Total qty

8Quantity um

9Item list price

10Item net price

11Lot

12Purchase order id

Up

Down

☒ System created

Last updated: 6/14/2002 2:47:11 PM User: System

OK

Cancel

1.14.7 Interface process

Each interface functional area has already a set of process parameters as Default in SCALE, which determines how its data can be downloaded and/or uploaded between SCALE and the ERP. For each Interface Process Window, a series of detail records are present in a sequence that determine in what order the system will execute them.

Detail records indicate the different processes that have been defined for this particular functional area and should be adapted to business needs from upload and download interface by expert technical consultants.

LAST MODIFIED: 30/9/2026 9:56 PM
SCALE CONFIGURATION WALKTHROUGH

99

Interface process - Edit existing

File Actions View Help

Key: 10003

Description: Receiving

☒ Detail records ☐ User defined data

Sequence	Description	Interface mode	Process	XML encoding
10	Receiving Delimited file	Delimited file	Download	UTF-8
20	Receiving Delimited file	Delimited file	Upload	UTF-8
30	Receiving Direct Data Interface tables	Interface tables	Download	UTF-8
40	Receiving Direct Data Interface tables	Interface tables	Upload	UTF-8
70	Receiving XML Data XML	XML	Download	UTF-8
80	Receiving XML Data XML	XML	Upload	UTF-8
90	Receiving Fixed Length	Fixed length	Download	UTF-8

☒ System created

OK Apply Cancel

Last updated: 3/29/2004 9:17:25 AM User: System

Configurations

File Actions View Help

Interface process

Launch	Description	Header key	System created
☒ Interface process	Interface system value	10008: Yes	
☒ Inventory transaction i	Inventory Transaction	10006: Yes	
☒ Item balance interface	Item Balance	10005: Yes	
☒ Receiving interface upl	Item Master	10004: Yes	
☒ Shipping interface upl	Order Entry	10000: Yes	
☒ Next number	Receipt Entry	10001: Yes	
☒ Personal alerts data quer	Receiving	10003: Yes	
☒ SCALE transform	Shipping	10002: Yes	
☒ Scheduled job	Work Order	10007: Yes	
☒ Service system values			
☒ Single sign-on system val			
☒ Staging interface types			
☒ Tables with dropdown list			
☒ Technical values			
☒ Yes or no validation			
☒ UHAD			
☒ User/warehouse			

Interface process detail - Edit existing

File Actions View Help

Sequence: 40

Description: Receiving Direct Upload

☒ General ☒ Upload ☐ Flow control ☐ User defined data

Interface mode: Interface table

Max trans per XML: 50

Data source batch: 0

Process: ☒ Download ☒ Upload

XML encoding: ☒ ASCII ☐ UTF-7 ☒ UTF-8 ☐ Unicode

File extensions: File extens... Processed file ext:



Error file ex...


☒ Inactive

☒ System created

Last updated: 2/14/2022 9:54:35 AM User: plachasse

OK Cancel Apply





1.14.8 Interface upload criteria

For each communication from SCALE to the host system it is required to configure the upload criteria:

- Receiving interface
- Shipping interface
- Item balance interface
- Inventory Transaction interface

Criteria are used as filter for the records to be uploaded for the specified upload process detail, so SCALE will place the records in the upload directory defined on the interface process detail.

1.14.9 Carrier Interface

Generic Config Header

Launch

Record type	Description	System created
METADATAFILTERCONDITION	Available metadata filter conditions	Yes
METADATAFILTEROPERAND	Available metadata filter operands	Yes
METADATASQLCLAUSETYPE	Screen metadata SQL clause type enumeration	Yes
MOVEMENTCLS	Movement Class	Yes
NETCOST	NETCOST	Yes
NMFC	National Motor Freight Classifications	Yes
OUTPUT	Output Format for Stationing XML	Yes

Generic config header - Edit existing

FileActionsViewHelp

Record type:

TRANSFORM

Description:

SCALE Transform

Detail records

System

User defined data

Identifier	Description	System created
10	Flat Item to WWM Item	Yes
120	Legacy Download to ILS Download	Yes
130	ILS Upload to Legacy Upload	Yes
140	Bill of Materials Interface	Yes
150	Work Order Interface	Yes
20	Flat Receipt to WMW Receipt	Yes
30	Flat Shipment to WMW Shipment	Yes
70	Order Entry Interface	Yes
80	WMW to Fixed Length	Yes

☒ System created

OKCancelApply

Last updated: 12/9/2009 8:05:10 AM User: System

STATUS	Outgoing Internal Status Names	Yes
TABLES	Tables with Dropdown Lists	Yes
TRANSFORM	SCALE Transform	Yes

XSL Transformation

No xsl

Shipping interface upload criteria

No shipping interface upload criteria

Interface process

1.15 Document Printing

Scale allows the printing of documents and labels for all the warehouse processes, most common documents templates and related configurations are already present in SCALE, in the following paragraphs are reported the configuration required to print documents.

Usually documents and labels are printed during the wave process or during work creation process.

1.15.1 Shipment data selection

You will use the data selection windows to identify which document types should be generated for a specific group of records in a wave, based on the characteristics of the record.

For example, if the document type is a bill of lading, you can generate it for all shipment records assigned to an LTL or truckload carrier. You will also use this window to determine the order that the documents will be printed. You can create paperwork for the following wave records: container IDs, work instructions and shipments.

Later, you will associate the document type with a document master record. The document master record determines which document type will be printed for the records defined on the data selection window.

You will use one of the data selection windows to determine which document types are printed for specific records in a wave. There is one data selection record for each type of wave record that might require paperwork. In our case, no Shipment data selection was needed.

1.15.2 Document master

The document master controls all aspects of paperwork document (non-label) generation during a wave; including determining which documents can be generated, the order in which those documents are produced, and how they'll be printed. Note that this record must be defined on the wave master record being run to be used


In our case, since there was no Shipment data selection, there was also no Document master.

1.15.3 Document Type

A document type determines the format of the document (paper or label), and, for which functional areas it is used.

It is a general document category (both paperwork and label), such as a pick list or a shipping label, representing the physical structure (label or document) of all paperwork associated with the type.

The majority of document types are already present in the system, but you can also create new types to use special document layouts requested by your customer.




1.15.4 Document

In this configuration are included already all the available document templates in SCALE that can be used to print any document or label.

In case new document are needed to satisfy customer requirement a new document need to be created


Then associate it with a template, which provides its structure and identifying what application will generate the document (SSRS, Prologistics, etc), and associate it with a document type and document criteria.

If you are creating a custom report in SSRS, save it on the server under <https://DataBaseServerAddress/Reports/browse/ILS/Reporting>, where **DataBaseServerAddress** should be replaced by your own database server address. Here, our database has the address is psql23.btb.fr, so your custom Report file should be saved in <https://psql23.btb.fr/Reports/browse/ILS/Reporting>. Then, in your Configuration, in the Document window, in the Printed As option, select Reporting Services Document and then in Document Template you should be able to select your custom report.



1.15.5 Label master

In order to use the Label master for a specific label, you first need to create the according **Document type** (second figure - first red rectangle), **Label selection criteria** (second figure - second red rectangle) and the **Label master criteria** (first figure - first red rectangle).



Label master - Edit existing

File Actions View Help

Label master: Prefomato

Description: Prefomato

Data selection: Prefomato by Conta

Detail records | User defined data

Print Mode: ☒ Print during wave ☐ Print at release ☐ Manual

d field 5	Document type	User defined field 6	Label selection criteria	User defined field 7
	Prefomato Label		Prefomato	0.00000

☐ Inactive

☐ System created

Last updated: 10/11/2019 4:28:47 PM User: tyler.cote

OK Cancel Apply

In the Document type window, be careful to check the **Label** box as shown below.

Document type - Edit existing

File Actions Help

Document type: Prefomato Label

Description: Prefomato Label

Print procedures: ☐ Shipping Container ☐ Wave - Labels

Classification: ☒ Document ☒ **Label**

SQL Server Reporting Services: SSRS file name record id: Rendered document pdf file folder:

Last updated: 10/11/2019 2:26:22 PM User: tyler.cote

OK Cancel

Label selection criteria - Edit existing

File Actions Help

Record type: LABELSELCRITERIA

Filter name: Prefomato

Description: Prefomato

Table name: Shipping container

Filter data: ☒ And ☐ Or

Attribute: SHIPMENT_HEADER_VIEW_ORDER_TYPE

Operand: =

Value: NOP

Last updated: 10/11/2019 2:28:13 PM User: tyler.cote

OK Cancel

Label master criteria - Edit existing

File Actions Help

Record type: LABELMASTER

Filter name: Prefomato by Container

Description: Prefomato by Container

Table name: Shipping container

Filter data: ☒ And ☐ Or

Attribute: Shipping_Container.INTERNAL_CONTAINER_NUM

Operand: >=

Value: 0

AND SHIPMENT_HEADER_VIEW_ORDER_TYPE = NOP

OR SHIPMENT_HEADER_VIEW_ORDER_TYPE = NOP

Last updated: 1/31/2020 10:35:39 AM User: gloria.sala

OK Cancel

1.15.6 Document routing


LAST MODIFIED: 30/9/2026 9:56 PM

SCALE CONFIGURATION WALKTHROUGH

Since we defined documents and labels to be printed, for each of them we need to provide the printing parameters in the document routing.

In the **Routing Criteria** tab is determined if a document should be printed, based on printing criteria commonly included in the printed document itself like Warehouse, Company Ship To, Carrier and Container Class and what machine the document will be printed from; for example, a particular packing station's client machine.

In the **Routing Selection** tab is set up a number of copies on which the printed document will be routed to, and which document will be used. The printer needs to be inserted in the **Print Device Configuration** to be selected for the routing.



CONCLUSION

This document was not made to give a comprehensive list of steps to do, but to give a general idea of the steps which need to be done to complete a very simplistic configuration. For more detailed information regarding each feature, you can always go to the dedicated Help menu regarding that feature.

Other sources of help such as Yammer or the [Manhattan SCALE - ManhWiki](#) can be useful.

LINKS AND DOCUMENTATION

[Manhattan SCALE - ManhWiki](#) :

http://wiki.manh.com/index.php/Manhattan_SCALE

Yammer (SCALE Support) :

https://www.yammer.com/manh.com/#/threads/inGroup?type=in_group&feedId=815112

AIM (Advanced Information Manager):

<http://mamatters/manhproducts/aim/default.aspx>

SCALE Training Documentation:

<https://manh1.sharepoint.com/sites/psa/PSOAmericas/scale/Reference%20Material/Forms/AllItems.aspx?viewid=c872f4c0%2Dd7d8%2D42db%2Dab45%2D318a606f33cb&id=%2Fsites%2Fpsa%2FPSOAmericas%2Fscale%2FReference%20Material%2FManhattan%20SCALE%20Training%20Documentation>