

JULIO

SCALE SOLUTION DESIGN DOCUMENT

Date Created: 7/22/2024

Date Modified: 9/3/2024

Date Printed:

Functional Design Sign off Date:

Document Version: 1.5

TABLE OF CONTENTS

I. INTRODUCTION	6
II. STATISTICS AND LAYOUT	7
First Floor	8
Second Floor	9
III. TECHNOLOGY	10
IV. KEY DECISIONS / ASSUMPTIONS	11
V. TERMINOLOGY	13
VI. INTERFACES	16
1.0 Download from ERP to SCALE	16
1.1 Item Master	17
1.2 Receipt Download	17
1.2.1 Returns	18
1.3 Shipment Download	18
1.4 Bill of Materials	19
1.5 Work Orders	19
2.0 Upload from SCALE to ERP	19
2.1 Receipt Confirmation	20
2.1.1 Receiving Interface Upload Criteria	20
2.2 Shipment Confirmation	21
2.2.1 Shipping Interface Upload Criteria	21
2.3 Inventory Transactions	21
2.4 Item Balance	21
2.5 Active SCALE users note	22
2.5.1 Upload Folder Structure	22
VII. INBOUND	24
3.0 PRE-RECEIVING	24
3.1 Receipt Creation	24
3.1.1 Interface	24
3.1.2 Receipt ID Types	24
3.1.3 Create Receipt from Purchase Order Insight	24
3.1.4 Create Receipt using Receipt Insight	25
3.1.5 Create Receipt from Shipment	25
3.1.6 Blind Receipts	25
3.2 Viewing Receipts	25
3.3 Generate Receiving Documents	27
4.0 APPOINTMENT SCHEDULING / PROGRAMACIÓN DE CITAS	28
4.1 Operations / Operaciones	28
5.0 UNLOADING	31
6.0 QUALITY AUDIT	32
7.0 RECEIVING	32
7.1 Receiving Preferences	32

7.1.1	<i>Recibo Importacion</i>	32
7.1.2	<i>Recibo Insumos</i>	34
7.1.3	<i>Recibo Standard</i>	34
7.1.4	<i>Recibo a VAS</i>	35
7.1.5	<i>Recibo Dev</i>	35
7.1.6	<i>Recibo Dev Ciega</i>	36
7.2	Disposition and Reason Codes	36
7.3	Putaway Location Group	37
7.4	Verify Receipts	38
8.0	EXCEPTIONS	39
8.1	Items missing weight or dimensions	39
8.2	Overages	39
8.3	Shortages	39
8.4	Receipt not in SCALE	40
8.5	Unknown Product	40
8.6	Damages	40
9.0	PUTAWAY	40
9.1	Locating Rules	41
9.1.1	<i>Devolucion</i>	41
9.1.2	<i>Almacenaje Colgado TA</i>	42
9.1.3	<i>Almacenaje VAS Etiquetado</i>	42
9.2	Putaway Work Creation	42
9.3	Putaway Work Execution	42
9.4	Location Override	43
VIII.	OUTBOUND	45
10.0	WAVE PROCESSING / PROCESAMIENTO DE LA OLA	50
10.1	Waving Strategy / Estrategia de Ola	51
10.1	Wave Selection / Selección de Olas	53
10.1.1	Add Shipments to Wave / Agregar envíos a ola	58
10.2	Run Wave / Ejecución de Ola	59
10.1	Build Wave	60
10.2	Wave Steps / Pasos de Ola	60
10.2.1	Start Wave / Inicio de Ola	61
10.2.2	Rule Assignment / Asignación de reglas	61
10.2.3	Allocation / Asignación	61
10.2.4	Container Creation / Creación de contenedores	65
10.2.5	Load Building / Construcción de cargas	66
10.2.6	Work Creation - Shipping Containers / Creación de trabajo - Contenedores de envío	67
10.2.7	Work Creation - Allocation Request / Creación de trabajo - Solicitaciones de asignación	67
11.0	WAVE MANAGEMENT / GESTIÓN DE OLAS	68
11.1	Cancel Wave / Cancelar una ola	68
11.2	Release Wave / Liberación de Ola	69
11.3	Hold Codes / Códigos de Bloqueo	69
11.4	Print Wave Documents or Labels / Imprimir documentos o etiquetas de Ola	70
11.5	Post Wave Shipment Changes / Cambios en el envío posterior a la ola	70
12.0	WORK MANAGEMENT / GESTION DE TRABAJOS	71

12.1	Work Viewing / Visualización de Trabajos	71
12.2	Work Priority / Prioridad de trabajo	72
13.0	PICKING / RECOLECCIÓN.....	73
13.1	Calzado (Footwear).....	73
13.2	Colgado (Hanging)	74
13.3	Doblado (Folded).....	75
13.4	Task Interleaving / Tareas Cicladas.....	76
14.0	PACKING / EMPAQUE	76
14.1	Value Added Service (VAS) / Servicio de Valor Agregado (VAS)	76
14.2	QC Confirmation / Confirmación de control de calidad.....	76
14.3	Close Container / Cierre de Contenedor.....	76
14.4	Shipping Container Insight / Visor de Contenedores de Envío.....	78
14.5	Hospital Packing Area / Área de Recuperación de Empaque	80
14.6	Carrier changes / Cambio de transportista	80
14.7	Packing Exceptions / Excepciones de Empaque.....	83
15.0	DOCK MANAGEMENT / GESTION DE MUELLES (ANDÉNES)	83
15.1	Dock Door Assignment / asignación de puerta de muelle (Andén)	84
16.0	LOAD CONFIRMATION / CONFIRMACION DE CARGA	85
16.1	Processing / Procesamiento	85
IX.	INVENTORY CONTROL.....	88
17.0	INVENTORY MANAGEMENT	88
17.1	Adjustments.....	88
17.2	Transfers	89
17.3	Status Change.....	90
18.0	CYCLE COUNT.....	91
18.1	Generating Cycle Counts	91
18.1.1	Plan Based Cycle Counting	91
18.1.2	Activity Based Cycle Counting	92
18.2	Executing Cycle Counts	93
18.2.1	Work Execution	93
18.2.2	Cycle Count Reconciliations	95
19.0	REPLENISHMENT	97
20.0	WORK ORDERS.....	97
X.	LABOR MANAGEMENT.....	98
21.0	KEY FEATURES	98
21.1	Using Labor Management Data	98
21.2	Generating Labor Management Data Records	98
21.3	Labor Groups	98
21.4	Labor Plans	99
21.5	Direct/Indirect Labor	100
21.6	View Labor Activity	100
21.7	Reporting.....	101
XI.	PERFORMANCE MANAGEMENT SUMMARY.....	102

22.0	REPORTING REQUIREMENTS.....	102
23.0	EVENT MANAGEMENT REQUIREMENTS	102
24.0	HISTORICAL REPORTING – ANALYSIS	102
<i>XII.</i>	<i>SYSTEM EXTENSIONS.....</i>	<i>103</i>
<i>XIII.</i>	<i>OPEN ISSUES.....</i>	<i>106</i>
<i>XIV.</i>	<i>RESOLVED ISSUES</i>	<i>106</i>
<i>XV.</i>	<i>FUTURE FUNCTIONALITY</i>	<i>107</i>
<i>XVI.</i>	<i>REVISION HISTORY</i>	<i>109</i>

I. INTRODUCTION

This document is designed to outline the proposed process for the SCALE implementation at Grupo Julio distribution center in Mexico. This implementation design includes one Distribution Center that will follow the functionality described in this document. Future implementations at other Grupo Julio's facilities may result in either change being made to this document or entirely new functional flows per facility.

The objective of this document is to define the proposed process and scope from a Manhattan Associates' perspective and to identify key extensions to the Manhattan Associates suite of products. This document serves as a reference throughout the process for confirmation of the approach and definition of tasks. It will also serve as a reference for Manhattan Associates' customer support organization after implementation, and potentially a reference point for any future Grupo Julio's implementations.


IMPORTANT: The Spanish Language segments of this document are provided to aid in communication only. If there is a difference between the two languages, the English version is used.

IMPORTANTE: Los segmentos en español de este documento se proporcionan únicamente para ayudar en la comunicación. Si hay una diferencia entre los dos idiomas, se utiliza la versión en inglés.


II. STATISTICS AND LAYOUT

Criteria	Statistic
Peak season	September ~ December
Low season	January ~ March
Working shifts	1 (7am ~ 5:30pm)
Average units received during peak season	15,630
Average units shipped during peak season	382,285
Total SKUs	193,524
Company	Julio
Warehouse	CEDIS JULIO
City	Ciudad de México
Number of licenses	35

First Floor



Second Floor



III. TECHNOLOGY

- Host ERP: Intelisis
- WM Platform: Windows
- Version: Manhattan Active® SCALE
- Warehouse Mobile Vendor: Honeywell CT47 and CK65
- MHE Vendor: Invenova (Put to Light)
- Voice solution: None
- Label Printer: Zebra 203 DPI
- Cubiscan: It will not be used

IV. KEY DECISIONS / ASSUMPTIONS

- 1) The scope of this document is limited to the standardized flows identified for the distribution center (DCs) of Grupo Julio in Mexico. In case additional flows are required for the future, a new design will need to be developed, to include potential new flows not covered by this design.
- 2) Item master in SCALE is maintained with company information. All inventory in SCALE will have the company Grupo Julio.
- 3) Host system assigns the company Grupo Julio for the interfaced Item Master, Receipt or Shipment. There is no manually maintained items.
- 4) Item Master in SCALE includes units of measure, dimensions, and weights for all products for all units of measure. This information will be interfaced into SCALE from the Host system.
- 5) All dimensions are stored using CM (Centimeters).
- 6) All weights are stored using KG (Kilos).
- 7) Grupo Julio will manage items with company information. An item that belongs to company A cannot be used to fulfill an order for company B, which means items cannot be shared across companies.
- 8) Item master in SCALE does not maintain Item Cross Reference.
- 9) Grupo Julio has only one storage template (pza), that is configured to have a single UOM (pza).
- 10) The storage template has the 'Group during check-in' set to 'Yes'.
- 11) Grupo Julio maintains item location capacity by Item.
- 12) Grupo Julio has all items configured with the same Item Class: *Doblado*.
- 13) Grupo Julio does not have decimals for inventory quantities.
- 14) Grupo Julio does not track serial numbers for items.
- 15) Grupo Julio does not track lots.
- 16) Handling Hazardous materials is outside the scope of this implementation.
- 17) Grupo Julio uses base SCALE cross-docking. In 2015 version Grupo Julio had an extension (**EX02**) that was developed but never used. Grupo Julio has decided to not migrate this extension at this moment. If, in the future, Grupo Julio decides to revisit this extension, additional efforts will be required to analyze the requirements and the necessary adjustments to port the extension.
- 18) Item categories is not used by Grupo Julio.
- 19) An item in an order (shipment in SCALE) may have multiple details lines. This can happen because the order may be consolidated.
- 20) Grupo Julio will not use Cubiscan for gathering dimensions and weight of the items during receiving.
- 21) Location Unit of Measure Override will not be used.
- 22) Grupo Julio does not have license plate tracked inventory locations. The only license plate tracked locations are the receiving dock locations.
- 23) Reserve locations are not license plate tracked.
- 24) P&D locations are not used in regular picking work. P&D will be used by PTL (Put to Light) integration.
- 25) Base inbound QC is out of the scope of this implementation.
- 26) Grupo Julio does not use "Quick Receive".

- 27) Returns and Rejections are interfaced to SCALE as a Receipt ID Type of DEV INS or DEV TDA.
- 28) Grupo Julio uses blind receiving when receiving returns from some clients (*Faturado*). In this case, the Receipt ID Type will be DEV CIE.
- 29) Grupo Julio uses Receipt from Shipment to generate receipts for small orders from some clients. When this is done, the Receipt ID Type used is the DEV CTE. This receipt will also be interfaced to the ERP.
- 30) Picking sequence and Putaway sequence will be provided by Grupo Julio to be configured in SCALE. Picking and Putaway sequence are numerical values that can be associated with a location and used in the Order by criteria configuration to determine how Putaway and Picking should occur in the warehouse.
- 31) Grupo Julio will also have the check digit in the location's label, alongside the location code.
- 32) Purchase orders will be downloaded into SCALE by ERP. Grupo Julio will generate the receipts based on the expected deliveries for that particular PO, in a 1:M (one to many) mapping.
- 33) Grupo Julio does not have any 'allocate in transit' enabled.
- 34) Grupo Julio does not have any permanent locations.
- 35) An item master change from the host sends the mode as 'Save' for the item being updated. A full item master download into SCALE is not sent. Only the item that is updated is sent.
- 36) Grupo Julio leverages certified SCALE platform support for various technologies and hardware.
- 37) Grupo Julio does not transfer inventory between warehouses in SCALE.
- 38) Grupo Julio does not transfer inventory between companies in SCALE.
- 39) Grupo Julio leverages a manual SOP to close the receipt in SCALE if no more receiving is expected against it.
- 40) A customized document (**DOC1**) is printed before starting to receive. Grupo Julio would like to cancel the printing of this document. This will be decided during tests with users. The custom document already exists and will be migrated by Grupo Julio with the support from LDM.
- 41) For products received from their manufacturers (*maquileros*), Grupo Julio will use ASN to check-in the products.
- 42) GS1 receiving is out of the scope of this implementation. GS1, QR, or 2D barcodes are out of the scope of this implementation to be scanned in SCALE during the check-in process.
- 43) Item price labels (Client/Supplier SKU labels) are not printed in SCALE. Grupo Julio prints price labels to be stamped on their imported products. This process is taken outside of SCALE.
- 44) Grupo Julio receives everything as EA (*pza*), not receiving CS or PL.
- 45) Outbound Value-Added Service (VAS) is out of the scope of this implementation.
- 46) For the purposes of this document, a download is referred to as a file or information that is sent from a system and is processed by SCALE.
- 47) For the purposes of this document, upload is referred to as a file generated by SCALE and made available to a different system.
- 48) Screenshots are for illustrative purposes only and actual options can be configured.

- 49) Grupo Julio does not setup item images in SCALE for the initial go live.
- 50) This document uses suggested naming conventions for configurations like locating rule names, zones, work type names, etc. Actual names may change during the configuration phase.
- 51) Grupo Julio receives imported products in their DC. For imported products, even if the product is damaged, it will be received.
- 52) For imported products, in case more quantity is received than expected, a new Purchase Order will be created to check-in the additional product.
- 53) Grupo Julio does not use 3D cubing during container creation.
- 54) Grupo Julio does not use Pallet Building.

V. TERMINOLOGY

Client Terminology	MA Terminology	Definition
	SCALE	Supply Chain Architected for Logistics Execution warehouse management.
INTELISIS	HOST / ERP	Client's ERP system integrating with Scale
	ITEM	Item Identifier for regular inventory. For client, this is item code, style, color, and size.
	ITEM CROSS REFERENCE	Global Trade Item Number. Definition of an SKU in a specific Unit of Measurement (UoM).
	RECEIPTS	Goods purchased by Client. Purchase orders and receipts have a 1:M mapping. SCALE maintains these as receipts with PO interfaced on receipt header.
	TRAILER ID	A container or truck being received into the DC. One inbound trailer has one receipt.
	SHIPMENT	Goods to be shipped to stores, wholesale customers, or retail supermarkets. The order in ERP and shipment in scale will be a 1:1 mapping.
	WAVE	A wave represents the different steps that the system uses to retrieve orders from the pool, and process them into the outbound portion of SCALE
	RUN WAVE	a group of orders when processed resulting in inventory allocation

Client Terminology	MA Terminology	Definition
	POOL	Any orders pending processing to be shipped immediately after interface to SCALE
	WORK INSTRUCTION	Transaction tracked by SCALE to coordinate the movement of inventory for a variety of warehouse processes. A group of work instruction is a work unit
	SHIPPING CONTAINER	An object that can be used to hold or transport inventory for a shipment.
	RECEIVING CONTAINER	An object that can be used to hold or transport inventory for a receipt.
	LPN (LOGISTICS UNIT)	An object that can be used to hold or transport inventory. When nested, the tree unit is referred to as the parent logistics unit.
	P&D	Pick up and Drop location
	ODWS	Override Data Wave Step. SCALE provides a wave step that allows performing crud operation to data during the wave process.
	EXIT POINT	An external process that performs logic in line with the base process. Used to update data or perform additional logic.
	ASN	Advanced Shipping Notice. Receipt that contains all information that will be received into the warehouse, including the container IDs.
DEV	RMA	Returns Merchandise Authorizations. Receipt interfaced into SCALE with the information of the returning items.
	SOP	Standard Operational Procedure. Documentation containing steps that must be followed to execute a procedure. May include steps executed in different systems and outside of systems.
	MHE	Material Handling Equipment.
	PTL	Put to Light system. Used by Grupo Julio during sorting process.

Client Terminology	MA Terminology	Definition
TA / TP		TA = Temporada Atual (Current Season) TP = Temporada Pasada (Previous Season)

UOM DEFINITION:

This is an example of a unit of measure definition displaying four UOMs and their respective representation to the other UOMs. This is not the baseline unit of measures.




Figure 1 - Unit of Measure

VI. INTERFACES

SCALE provides multiple formats for the movement of data, including XML, fixed or delimited files, web service calls and API calls. The host system can download and upload information into/from SCALE using any of these modes.

For example, if using the XML mode, it allows the host system to create XML files with key information for downloads, and SCALE reads this key information to download the information into the SCALE tables. This method also allows the host to read key information from SCALE's interface upload files.

Config Note: Grupo Julio will use Web Services calls to interface data into SCALE. To read data from SCALE, the ERP will read XML files stored in an Azure file storage.

Config Note: In the current version (2015), Grupo Julio is using Direct to Table as the upload option. This configuration needs to be disabled for the interface areas (Item, Receipts, Shipments) as in Active SCALE the database is not available for external access.

Each interface touchpoint between Host and SCALE below can be run manually as well as through scheduled jobs as defined by client. The timing and frequency of all downloads into SCALE are to be finalized during integration testing, along with the process and mechanism to do so (i.e., scheduled jobs or on-demand options). The upload schedule (i.e., scheduled jobs, on-demand options) of information out of SCALE also needs to be determined during integration testing.

Note: Warehouse notifications can be configured to notify Grupo Julio's team when a download or upload interface has failed for any reason.

1.0 Download from ERP to SCALE




Figure 2 - Interface Download

1.1 Item Master

The item master file is maintained within the Host. Conversion quantities, weights, and dimensions are also maintained through this Item Master Download as those pieces of information are available in the host. The host system downloads a record into the SCALE Item Master when an item is modified or created. If an item already exists in the Item Master, then the record is flagged as a change, and SCALE updates the existing item with the latest information bridged from the host. Key pieces of information include (but are not limited to) the following:

- o Item Master Level:
 - Item (SKU)
 - Description
 - Company
 - Cross Reference
 - Item Categories
 - Packing Class
 - Storage Template
 - Item Unit of Measure Level:
 - Item Dimensions
 - Item Weight
 - Movement Class (A, B, C)

Client maintains a movement class for an item to classify fast movers or slow-moving items. Manhattan Associates recommends this to be at the unit of measure level and leverage the movement class analysis to slot the product accordingly.

Config Note: To be able to use the Web Services download interface option, the 'Item XML Download' must be enabled under the 'Interface Process' configuration.

1.2 Receipt Download

Purchase Orders and Receipts are interfaced to SCALE. Grupo Julio interfaces Purchase Orders especially for *Recibos Nacionales* (National Receipts). For these receipts, a user will manually create the receipts based on what will be received on a particular delivery from the vendor, so one Purchase Order may generate one or multiple Receipts in SCALE. In some other scenarios, like returns from their stores, Grupo Julio will interface the Receipts to SCALE. These files are sent in advance of the actual receipt. The information downloaded to SCALE from the Host contains header and detail-level information. Key pieces of receipt information include (but are not limited to) the following:

- o Header level information:
 - Receipt ID
 - Purchase Order ID
 - Receipt ID Type (Example: REC NAC, REC IMP, DEV TDA)
 - Source/Vendor Information

- o Detail level information
 - Item #
 - UOM (lowest)
 - Quantity Ordered/Requested
 - Order Line #

Note: Grupo Julio will interface container-level information (ASN) for some receipts only.

Operational and Interface Note: Manhattan Associates recommends exploring the use of the ASN receiving and having container level information at the receipt interface as much as possible to streamline the receiving processing time.

Config Note: To be able to use the Web Services download interface option, the 'Receiving XML Download' must be enabled under the 'Interface Process' configuration.

1.2.1 Returns

Grupo Julio processes and receives returns.

Returns Merchandise Authorizations (RMA) are used to receive merchandise into the warehouse that has been returned or refused by the customer. RMA is processed as a receipt in SCALE. Host downloads the RMA into SCALE with a Returns Receipt Type, and the warehouse receives it following a similar process as receiving.

Grupo Julio will also have scenarios where they don't receive the information of the merchandise being returned (returns from clients). For this scenario Grupo Julio will use a blind receipt to check-in the returned products. These receipts will also be interfaced back to the ERP. An extension (**EX05**) will be used to capture the Source ID (Vendor), the *Factura* (User Defined 2) and the *Concepto* (User Defined 3). All these 3 fields will be required whenever the Receiving Preference is configured to use the EX05. More details of this extension will be in a separate document.

1.3 Shipment Download

Sales orders are created in the Host and information is interfaced to SCALE for Sales Orders on a random basis as shipments. These records are sent in advance of the actual required ship date, though can be interfaced the same day. The information downloaded to SCALE from Host contains header & detail level information. Key pieces of that information include (but are not limited to) the following:

- o Header level information:
 - Shipment ID #
 - Ship To Information (Name and Address of the customer)
 - Date Information (i.e., Ship Date, Delivery Date)
 - Customer Info

- Customer PO
- Order Type
- Carrier Information
- Route
- o Detail level information:
 - Item #
 - Description
 - Quantity Ordered
 - Order Line #

Note: Client interfaces orders at any moment during the day into SCALE.

Until a shipment has been waved, SCALE can process updates and deletes from the Host against the shipment. After a shipment is waved, SCALE will not allow updates to the shipment.

The shipments will migrate from Host to SCALE using the SCALE base Shipment interface. Grupo Julio will interface all the necessary information required to wave a shipment. Any additional required information may be populated using Override Data Wave Steps.

Config Note: To be able to use the Web Services download interface option, the 'Shipping XML Download' must be enabled under the 'Interface Process' configuration.

1.4 Bill of Materials

Grupo Julio will not leverage Bill of Materials interface in this implementation.

1.5 Work Orders

Grupo Julio will not leverage Work Orders interface in this implementation.

2.0 Upload from SCALE to ERP




Figure 3 - Interface Download

2.1 Receipt Confirmation

The Interface Data option creates the receipt upload records from SCALE for all receipt containers that have reached the status 'Putaway Pending' or have been closed manually. Grupo Julio requires the receipt containers to be interfaced as soon as possible to their ERP. This is due to the use of the Immediate Needs and the necessity to invoice the client.

By interfacing the receipt containers at this status Grupo Julio understands that some discrepancies could happen in case they need to cancel an already interfaced receipt container. In this case they may have duplicate inventory in their ERP. According to Grupo Julio this is a very exceptional scenario, that should never occur. Grupo Julio needs to have an SOP in place to handle this exceptional scenario. Manhattan Associates recommends to have the interface of the containers at the Closed status to avoid this scenario.

The receipt upload records are the output of the receiving and putaway processes within SCALE. The upload includes the receipt header, receipt detail, and receipt container. The interface sends information to the Host identifying a subset of inventory to be allocable.

Config Note: Upload Receipt Containers at This Status or Higher will be set to 'Putaway Pending'. Receiving Upload Level will be set to 'Container'. This is a global setting for all receipt types.

Config Note: To be able to use the XML upload interface option, the 'Receiving XML Upload' must be enabled under the 'Interface Process' configuration. The 'Upload Directory' should be set to `https://{storage}/ils/Interface/Upload/Receiving/`.

Config Note: In the current version (2015), Grupo Julio is using Direct to Table as the upload option. This configuration needs to be disabled as in Active SCALE the database is not available for external access.

2.1.1 Receiving Interface Upload Criteria

This configuration can be used to filter the receiving records to be uploaded for the specified upload process detail. Different filter criteria can be set on each receiving process detail. The system will place the records in the upload directory defined on the interface process detail.

The filter search value will list the statuses for the Leading status and Trailing status Attribute fields which will include both inbound and outbound statuses for selection.

If the process detail's directory is blank, then the upload directory of the interface system value will be used. The receiving data should satisfy the conditions set by the receiving interface system values.

2.2 Shipment Confirmation

The shipment upload files are the output of the outbound process within SCALE and are generated right after the shipment reaches the configured statuses. The upload includes shipment header, shipment detail, shipment comment, and shipping container. It will also include the inventory attributes and serial numbers, for the inventory that has this information.

Config Note: To be able to use the XML upload interface option, the 'Shipping XML Upload' must be enabled under the 'Interface Process' configuration. The 'Upload Directory' should be set to `https://{storage}/ils/Interface/Upload/Shipping/`.

2.2.1 Shipping Interface Upload Criteria

You will use shipping interface upload criteria records to determine the following:

- Which shipment/shipment line upload records that the system will place in the upload directory defined on the interface process detail.
- Which shipments the system will write header/detail upload records when a certain trailing status is met, and that status is defined to include in the interface upload.

Notes: These criteria records apply to the shipping upload interface only. The system will upload the shipment data using these records only as the shipment's status changes from one value to the next. The upload will not happen on the initial download of the shipment (regardless of whether that status has been configured for upload).

2.3 Inventory Transactions

SCALE maintains four-wall inventory at a detailed level and can communicate any changes in inventory levels to Host through the Inventory Transactions Interface. All inventory adjustments and status changes are eligible to be uploaded to the Host system. Due to business requirements, Grupo Julio will not interface all the inventory adjustments at the moment they happen.

Config Note: To be able to use the XML upload interface option, the 'Inventory Transaction XML Upload' must be enabled under the 'Interface Process' configuration. The 'Upload Directory' should be set to `https://{storage}/ils/Interface/Upload/Inventory/`.

2.4 Item Balance

Grupo Julio only uses the Item Balance for their annual inventory. Grupo Julio will evaluate the use of the Item Balance at a higher frequency (once a week) for faster inventory discrepancies identification, but this would not automatically affect their fiscal inventory.

Config Note: Grupo Julio will have the Item Balance configured to be generated once a week. The exact date/time will be defined during the testing phase.

Config Note: To be able to use the XML upload interface option, the 'Item Balance XML Upload' must be enabled under the 'Interface Process' configuration. The 'Upload Directory' should be set to `https://{storage}/ils/Interface/Upload/Balance/`.

2.5 Active SCALE users note

- The upload configuration is available for Lower and Production level users.
- Lower-level users
 - o All editable fields will be enabled
 - o Can Create, Delete, Copy criteria records
- Production level users
 - o Can view all editable fields. No permission for editing
 - o Can select and copy text values
 - o Cannot Create, Delete, Copy criteria records.

2.5.1 Upload Folder Structure

The upload folders used by Grupo Julio will follow the below structure. This is required so the ERP integration is able to pick the correct files and process them accordingly.

Interface Process	Folder	File Extension
Inventory Transaction	<code>https://{storage}/ils/Interface/Upload/Inventory</code>	it.xml
Item Balance	<code>https://{storage}/ils/Interface/Upload/Balance</code>	ib.xml
Receiving	<code>https://{storage}/ils/Interface/Upload/Receiving</code>	rc.xml
Shipping	<code>https://{storage}/ils/Interface/Upload/Shipping</code>	sh.xml

Config Note: The Upload directory can be configured using the Interface process detail configuration, as shown in the below picture. The {storage} should be replaced with the information from Grupo Julio's Azure Storage.

Interface process detail - Edit existing

File Actions View Help

Sequence: 80

Description: Receiving XML Upload

General Upload Flow control User defined data

Upload directory: <https://{storage}.core.windows.net/ils/Interface/Upload/Receiving>

Upload criteria

Shipping: Shipping delete criteria:

Receiving: Item balance:

Inventory transaction:

Figure 4 - Interface process detail example

VII. INBOUND

3.0 PRE-RECEIVING

3.1 Receipt Creation

3.1.1 Interface

Intelisis sends receipt download records using the Web Services. These records are then processed and validated through the SCALE interface to ensure the data format is correct.

3.1.2 Receipt ID Types

To group receipts from SCALE screens and to drive processing rules, it is helpful for SCALE to store different *Receipt ID Types* and *Receipt Types*.

The following list of Receipt ID Types is configured in the system:

Receipt ID Type	Description	Interfaced
DEV CIE	Returns from Clients	N
DEV TDA	Returns from Stores	Y
REC NAC	Receipts from national vendors	Y
REC IMP	Receipts from external vendors	Y
REC INS	Receipts from <i>insumos</i>	Y

Receipt type is a free format field on a receipt record. It is commonly used to identify what type of supplier sent the receipt, such as manufacturer, vendor, etc. The system does not validate this value. Following Receipt types are used:

Receipt ID Type	Receipt Type	Description
DEV CIE	DEV CIE	Returns from Clients
DEV TDA	DEV TDA	Returns from Stores
REC NAC	OC	Receipts from national vendors
REC IMP	REC IMP	Receipts from external vendors
REC INS	REC INS	Receipts from <i>insumos</i>

3.1.3 Create Receipt from Purchase Order Insight

Grupo Julio creates Receipts based on Purchase Orders. This is used especially for receipts from national vendors, where Receipts are created based on the deliveries that will be done on a given day.

3.1.4 Create Receipt using Receipt Insight

Grupo Julio will not manually create Receipts from the Receipt Insight screen. This is not a limitation of SCALE.

Config Note: Security groups should have removed the permission to manually create Receipts.

3.1.5 Create Receipt from Shipment

Grupo Julio uses the Receipt from Shipment in some scenarios, where they need to process a return of small shipments sent to specific clients. They may create a full return receipt or partial. Once received back, the receipt containers generated from this receipt will be interfaced to the ERP as all the other receipt containers.

The Receipt ID Type for the receipt generated will be of the type DEV CTE.

Config Note: Security groups can be used to limit access to this functionality only to supervisors, in case Grupo Julio decides to restrict the permission on this feature.

3.1.6 Blind Receipts

Grupo Julio created Blind Receipts for the returns from their clients (*Faturados*). This is required because Grupo Julio doesn't know exactly which products their clients are returning.

3.2 Viewing Receipts

All receipts that are downloaded or created in SCALE can be viewed from the **Receipt Insight** screens. The lines can be viewed using **Receipt Line Insight**. If ASNs are downloaded or created, they can be viewed using **Receipt Container Insight**.

Receipt insight

Summary: Receipts: 54, Lines: 3.2k, Units: 1.5m, Volume: 9.1b

Filters: Warehouse: CDI-2, Include closed receipts: No

Receipt id	Receipt id type	Company	Receipt date	Trailing status	Leading status	Trailer id
IMP-002667	Orden de Compra	NAL	7/27/2023	Check In Pending	Check In Pending	
IMP-002675	Orden de Compra	NAL	7/25/2023	Check In Pending	Check In Pending	
IMP-002684	Orden de Compra	NAL	8/1/2023	Check In Pending	Closed	
IMP-002700	Orden de Compra	NAL	4/28/2023	Check In Pending	Check In Pending	
IMP-002709	Orden de Compra	NAL	8/2/2023	Check In Pending	Check In Pending	
IMP-002711	Orden de Compra	NAL	7/27/2023	Check In Pending	Check In Pending	
IMP-002714	Orden de Compra	NAL	7/28/2023	Check In Pending	Check In Pending	
IMP-002720	Orden de Compra	NAL	7/28/2023	Check In Pending	Check In Pending	
IMP-002725	Orden de Compra	NAL	8/1/2023	Check In Pending	Check In Pending	
IMP-002731	Orden de Compra	NAL	8/2/2023	Check In Pending	Check In Pending	
IMP-002738	Orden de Compra	NAL	7/31/2023	Check In Pending	Check In Pending	
IMP-002739	Orden de Compra	NAL	8/1/2023	Check In Pending	Check In Pending	
IMP-002748	Orden de Compra	NAL	8/2/2023	Check In Pending	Check In Pending	
IMP-002758	Orden de Compra	NAL	7/27/2023	Check In Pending	Check In Pending	
IMP-002759	Orden de Compra	NAL	7/26/2023	Check In Pending	Check In Pending	
IMP-002761	Orden de Compra	NAL	7/31/2023	Check In Pending	Check In Pending	

1 - 54 of 54 records

Figure 5 - Receipt Insight

Receipt line insight

Summary: Receipts: 56, Lines: 3.2k, Total Qty: 1.6m, Open Qty: 1.5m

Filters: Warehouse: CDI-2

Receipt id	Receipt type	ERP order line number	Item	Description	Company	Total Qty	Open
EDW000010C	PO	3	RL48040-1220-V13-H	PANTALON H NAESTRI	NAL	200	200
EDW000010C	PO	4	AC38EC0001-11002-HRQ	KIDALA ECOLIN	NAL	100	100
EDW000010C	PO	2	RL480120-1220-H2M-Q14	CAMISA H ML RIMON	NAL	400	400
IMP-002667	ReceiptType	2	RL22109-2320-HQ2H-7Y	CHAQUETA M DISNEY 100 FASHION	NAL	9	9
IMP-002667	ReceiptType	9	RL22101-2320-H2L-7Y	CHAQUETA M COLORRND	NAL	23	23
IMP-002667	ReceiptType	10	RL22101-2320-H2L-9Y	CHAQUETA M COLORRND	NAL	14	14
IMP-002667	ReceiptType	1	RL22109-2320-HQ2H-5Y	CHAQUETA M DISNEY 100 FASHION	NAL	14	14
IMP-002667	ReceiptType	3	RL22107-2320-H2T-5Y	CHAQUETA M ELITA FASHION	NAL	27	27
IMP-002667	ReceiptType	13	RL22101-2320-H2L-5Y	CHAQUETA M COLORRND	NAL	18	18
IMP-002667	ReceiptType	12	RL22101-2320-H2L-13Y	CHAQUETA M COLORRND	NAL	38	38
IMP-002667	ReceiptType	5	RL22107-2320-H2T-9Y	CHAQUETA M ELITA FASHION	NAL	57	57
IMP-002667	ReceiptType	4	RL22107-2320-H2T-7Y	CHAQUETA M ELITA FASHION	NAL	40	40
IMP-002667	ReceiptType	17	RL22101-2320-H2L-13Y	CHAQUETA M COLORRND	NAL	25	25
IMP-002667	ReceiptType	23	RA41307-2320-V3A-HVL	CHAQUETA H COLORRND	NAL	35	35
IMP-002667	ReceiptType	6	RL22107-2320-H2T-13Y	CHAQUETA M ELITA FASHION	NAL	66	66

1 - 100 of 1208 records

Figure 6 - Receipt Line Insight

Receipt container insight

</

Figure 7 - Receipt Container Insight

3.3 Generate Receiving Documents

Once a receipt has been created, documents can be printed against it. Grupo Julio currently prints a document with the items being received (**DOC01**) and provides that to the user, that starts the check in process.

Grupo Julio will not leverage the base Receiving Worksheet at this moment. They may use it in the future, in case needed. This document contains various data from the receipt that can be printed from SCALE by selecting a receipt from the **Receipt Insight** and choosing the Print Selected Documents option from **Actions**. The Receiving Worksheet is used to aid in the systematic receiving process and serves as a receiving journal after the receiving process.




Figure 8 - Printing Receiving worksheet

Receipt Num: NODIMS-01		RECEIVING WORKSHEET		ERP Order #:	
Receipt ID Type: ASN				Receiving Date: 4/27/2020	
Warehouse TN 3819 Logistics Way TN 37013 US				Source Info Total Quantity Rcvd: 20	
Line #	Item	Item Description	Total Qty	Open Qty.	
1	3000	Bleach	1	1	
T/U/H/L:			0 L	0 W	0 H 0 LBS
Line #	Item	Item Description	Total Qty	Open Qty.	
2	34000032129	HsyNgt DkCh/AI 10.56oz	20	0	
T/U/H/L:			10 L	9 W	7 H 8 LBS

Figure 9 - Receiving work sheet sample

Config Note: The receiving worksheet (**DOC02**) may be changed to display additional information. Any changes to the Receiving Worksheet, if necessary, will be performed by Grupo Julio with support from Logística de Mexico.

Config Note: The disposition codes are recommended to be barcoded on the receiving worksheet.

4.0 APPOINTMENT SCHEDULING / PROGRAMACIÓN DE CITAS

4.1 Operations / Operaciones

Grupo Julio handles inbound appointment scheduling for the current go live. Outbound appointment scheduling is not leveraged (not available in SCALE; no SOP defined) and is out of scope of this document.

Grupo Julio utilizará la programación de citas de recibo para esta implementación. La programación de citas de salida no se utilizará (no está disponible en SCALE; no se define un SOP) y está fuera del alcance de este documento.

To better facilitate the receiving, Grupo Julio personnel assign an appointment for the given receipt using the **Schedule Appointment** function in the **Receipt Insight** screen option. This is documented for reference purposes in case appointment visibility is needed inside SCALE. This needs a receipt ID visibility in SCALE in advance. Users can then go back and view what receipts are scheduled for a given day by viewing the **Appointments Calendar**.

Para facilitar mejor la recepción, el personal de Grupo Julio asigna una cita para el recibo dado utilizando la función **Programar cita** en la opción **del visor de recibos**. Esto se documenta con fines de referencia en caso de que se necesite visibilidad de citas dentro de SCALE. Es necesaria tener un ID de recibo en SCALE previamente. A continuación, los usuarios pueden volver atrás y ver qué recibos están programados para un día determinado consultando el **Calendario de citas**.

The screenshot shows the 'Receipt Insight' application interface. On the left, there are search filters for 'Basic criteria' (Receipt id, Receipt id type, Item, Company, License plate, Receiving dock, Source name, Ship from, From receipt date, To receipt date, Internal receipt number) and 'Advanced criteria' (Warehouse, 'Wilt's' 3PL, Include closed receipts). The main table displays receipt data with columns: Receipt id, Receipt id type, Company, Trailer id, Trailer location, Receipt date, and Closed d. A right-click context menu is open over a row, showing options like 'New container', 'Assign trailer id', 'Check in', 'Create pre-check in containers', 'Close', 'Delete appointment', 'Immediate needs', 'Print preview', 'Print default docs', 'Print selected docs', 'Schedule appointment', and 'Yard check in & out'.

Receipt id	Receipt id type	Company	Trailer id	Trailer location	Receipt date	Closed d
163867-01	Purchase Order				7/21/2015	
AH0204.B	Purchase Order	04-"Electronic" Avenue			2/4/2005	
AH0207.B	Purchase Order	04-"Electronic" Avenue			2/4/2005	
AH0513.A	Purchase Order				5/13/2005	
AH0824.A	Purchase Order	02-Fred's Food Company			8/24/2005	
AH0923.A	Purchase Order	02-Fred's Food Company			8/23/2005	
AKH0329.A	Purchase Order				3/29/2005	
BLIND156	Blind				5/17/2005	
BLIND158	Blind				5/18/2005	
BLIND161	Blind				5/21/2005	
BLIND209	Blind	04-"Electronic" Avenue			7/14/2005	
BLIND213	Blind				8/10/2005	
CATCHWEIGHTTEST	Customer Return				3/29/2005	
NABISCO.01	Purchase Order				1/4/2007	
RCVMMONEEDS1	Blind	02-Fred's Food Company			6/24/2005	

Figure 10 - Appointment Scheduling / Programación de citas

This allows for enhanced management of dock door locations, as well as the personnel required to unload the trailers at the dock. Users may enter the following information when scheduling an inbound appointment for a receipt:

- Trailer ID
- Dock Door
- Start Date/Time
- End Date/Time

Esto permite una mejor gestión de las ubicaciones de las puertas del muelle, así como del personal necesario para descargar los remolques en el muelle. Los usuarios pueden ingresar la siguiente información al programar una cita entrante para un recibo:

- ID del remolque
- Puerta de muelle
- Fecha y hora de inicio
- Fecha y hora de finalización

Dock schedules can be viewed from the **Receipt Insight** under the **Appointments** node. This screen offers a view of daily appointments for each receiving dock. Appointments can only be scheduled for open receipts in SCALE.

Las programaciones de las citas se pueden ver desde **Visor de Recibo** en el nodo **Citas**. Esta pantalla ofrece una vista de las citas diarias para cada puerta de recibo. Las citas solo se pueden programar para recibos abiertos en SCALE.

Scheduled appointments can also be deleted from the **Receipt Insight** by searching for the receipt, right-clicking on it, and choosing the **Delete Appointment** option.

Las citas programadas también se pueden eliminar de **Visor de Recibo** buscando el recibo, haciendo clic con el botón derecho en él y eligiendo la opción **Eliminar cita**.

Figure 11 - Receiving Appointment Schedule Window / Ventana de programación de citas de recepción

A graphical calendar screen for managing inbound receipt appointments is also available. The screen shows activity for the day per dock door and allows the user to easily see and schedule open spots on the calendar. From this screen, the user can preview appointment details, schedule new appointments, change existing appointments, or delete appointments. The information and coloring of the screen can be customized to maximize the benefit for the user.

También está disponible una pantalla gráfica de calendario para administrar las citas de recibo. La pantalla muestra la actividad del día por puerta de recibo y permite al usuario ver y programar fácilmente los espacios abiertos en el calendario. Desde esta pantalla, el usuario puede obtener una vista previa de los detalles de la cita, programar nuevas citas, cambiar las citas existentes o eliminar citas. La información y el color de la pantalla se pueden personalizar para maximizar el beneficio para el usuario.

Design note: Grupo Julio will manually assign the receiving docks based on the availability of them.

Nota de diseño: Grupo Julio asignará manualmente los muelles de recepción en función de la disponibilidad de los mismos.




Figure 12 - Receiving Appointment Schedule Window / Ventana de programación de citas de recepción

5.0 UNLOADING

Upon the arrival of the truck and verification of the appointment schedule as applicable (outside of SCALE), delivery documentation is obtained from the driver and matched to the corresponding documents on Grupo Julio's system (outside SCALE).

Once it is verified that the document is expected, items are unloaded from the truck onto a pre-receiving dock area. From there they perform an Inbound QC. Only after the QC is that the Purchase Order will be created in their ERP and a Receipt will be interfaced into SCALE.

Nowadays, a document is printed from Grupo Julio's system and another document is printed in SCALE (custom receiving worksheet). Users compare both documents if the quantities are good.

Design Note: Manhattan Associates recommends this process to be changed. Users can check the quantities in their RF guns during check-in.

In case quality issues are detected by the Quality Team, they may elect to perform a QC to more than 15% of the products. In case the products should not be received in SCALE, the Purchase Order will not get generated in Grupo Julio's system.

Client may detect quantity differences during the unloading. Depending on the origin of the products (importation, national vendor, etc) they may create an additional receipt to receive the total amount that was unloaded. In case they receive less inventory than the quantity

on the receipt, Grupo Julio is going to receive that missing quantity and later make an adjustment, coordinated with their ERP.

Users organize the items based on the model/size.

6.0 QUALITY AUDIT

Client does not use the base Inbound QC process from SCALE. Instead, they have a custom QC process, based on some parameters their Quality Department elects.

For example, they perform this QC process for external providers (importation). They may also elect some national providers, because they are new providers or because they have had issues in the past with this provider.

From 10% to 15% of the received items are sent for QC. Once the QC is completed with success, the Purchase Order is created in Grupo Julio's ERP and interfaced into SCALE as a Receipt.

In case the QC fails, Grupo Julio may transfer the units that are not conforming or the whole batch of units, depending on their parameters of acceptance, to reprocess. In rare cases, for importation, they may need to send the products for destruction.

7.0 RECEIVING

After unloading the truck and physically organizing the products, and executing manual quality audit SOP, systematic receiving is then initiated via a check-in process. Checking In product is the process that creates the inventory inside of SCALE based on Receiving Preference of the user performing the action. Some items received must pass by an inbound inspection check.

7.1 Receiving Preferences

Grupo Julio will have a few different Receiving Preferences. They may use the workflow Header-Item or Blind. This document will list the main preferences used by Grupo Julio, although other variations may be used.

7.1.1 *Recibo Importacion*

This receiving preference is used to check-in products coming from importation, using putaway groups.

The receiving preference is configured in SCALE as below:

- Default Inventory Status: *Disponible* (Available)
- Create Putaway Work: Yes

- Execute group putaway: Yes
- License Plate Assignment: System
- Workflow: Header-Item
- Execution Method: Check in and Locate (immediate)
- Nest During Check In: No
- Process immediate needs: No
- Container Locating Method: Parent
- Disposition Code Required: No
- Reason Code Required: No

The user selects *Receiving* option from Warehouse Mobile Main Menu, then selects *Recibo Importacion*.

Once selected, the user scans:

- Receipt ID
- Item (the product)
- Quantity in lowest UOM (UND)
- Reason Code
- Disposition Code
- Putaway Group ID

After entering the required information, SCALE locates the LPN to the corresponding location and putaway work is created. SCALE determines a putaway location based on the locating rule assigned during the Check-In process.

The user continues to receive the next item for the same receipt or exits the current receipt and start over with a new receipt ID. Exiting a receipt on the Warehouse Mobile does NOT close that receipt. Users can go back to that receipt at any point in time.

Once the user is done checking-in the items into a putaway group, they need to close it by accessing the option Close Putaway Group from the main Warehouse Mobile menu.




Figure 13 – Recibo Importacion receiving flow example

The configuration of the other receiving preferences will be listed below, although the operation from the user standpoint is pretty similar.

7.1.2 *Recibo Insumos*

This receiving preference is used to check-in *insumos*, using putaway groups. The configuration follows as below:

- Default Inventory Status: *Disponible* (Available)
- Create Putaway Work: Yes
- Execute group putaway: Yes
- License Plate Assignment: System
- Workflow: Header-Item
- Execution Method: Check in and Locate (immediate)
- Nest During Check In: No
- Process immediate needs: No
- Container Locating Method: Child
- Disposition Code Required: No
- Reason Code Required: No

7.1.3 *Recibo Standard*

This receiving preference is used to check-in standard products (not importation, not *insumos*, not returns), using putaway groups. The configuration follows as below:

- Default Inventory Status: *Disponible* (Available)
- Create Putaway Work: Yes
- Execute group putaway: Yes
- License Plate Assignment: System
- Workflow: Header-Item
- Execution Method: Check in and Locate (immediate)
- Nest During Check In: No
- Process immediate needs: Yes
- Container Locating Method: Child
- Disposition Code Required: No
- Reason Code Required: No

7.1.4 *Recibo a VAS*

This receiving preference is used to check-in imported products that must be sent to an area to stamp a pricing label, using putaway groups. The configuration follows as below:

- Default Inventory Status: VAS
- Create Putaway Work: Yes
- Execute group putaway: Yes
- License Plate Assignment: System
- Workflow: Header-Item
- Execution Method: Check in and Locate (immediate)
- Nest During Check In: No
- Process immediate needs: No
- Container Locating Method: Child
- Disposition Code Required: Yes
- Reason Code Required: Yes

Based on the Reason Code a different Locating Rule will be applied, taking the inventory to a different area.

7.1.5 *Recibo Dev*

These receiving preferences are used to check-in returns that were interfaced into SCALE. They have different inventory status and may use **[EX05]** to only allow users to enter one quantity at a time. The receiving preferences are “*Recibo Dev Defecto*”, “*Recibo Dev Disponible*” and “*Recibo Dev Disponible Mul*”. The configuration follows as below:

- Default Inventory Status: *Disponible* (Available) / *Defectuoso* (Damaged)
- Create Putaway Work: Yes
- Execute group putaway: Yes
- License Plate Assignment: System
- Workflow: Header-Item
- Execution Method: Check in and Locate (immediate)
- Nest During Check In: No
- Process immediate needs: No

- Container Locating Method: Parent
- Disposition Code Required: No
- Reason Code Required: No

7.1.6 Recibo Dev Ciega

These receiving preferences are used to check-in returns that were **not** previously interfaced into SCALE. They have different inventory status and may use **[EX05]** to only allow users to enter one quantity at a time. The receiving preferences are “*Recibo Dev Ciega Defec*”, “*Recibo Dev Ciega Disponib*” and “*Recibo Dev Cie Multiple*”. The configuration follows as below:

- Default Inventory Status: *Disponible* (Available) / *Defectuoso* (Damaged)
- Create Putaway Work: Yes
- Execute group putaway: Yes
- License Plate Assignment: System
- Workflow: Blind
- Execution Method: Check in and Locate (immediate)
- Nest During Check In: No
- Process immediate needs: No
- Container Locating Method: Child
- Disposition Code Required: No
- Reason Code Required: No

7.2 Disposition and Reason Codes

Client will have disposition codes and reason codes to indicate different locating rules to be used for the products being returned. Below is a list of the current disposition codes in use by Client. This list may be changed during the build phase.

Disp Code	Inventory Status
Cuarentena	
Defectuoso	Defectuoso
Disponible	Disponible
VAS	VAS

Reason Code	Disposition Code
Compostura Alta	Cuarentena
Compostura Baja	Cuarentena
Compostura Media	Cuarentena
Disponible	Disponible
Etiquetado	VAS
Monarch	VAS
Revision	VAS
Seleccion	VAS

7.3 Putaway Location Group

A putaway location group allows a series of received items to be putaway as one group. Once you create one putaway group (using either a location range or a locating zone), then all groups will have to be created using either ranges or zones, whichever one you chose for the first group, for that same warehouse. Different warehouses may have different configuration options, so warehouse A may use Locating Zones while warehouse B may use Location Ranges.

When the system is performing locating, it locates to a location associated with a Putaway Group that includes the destination location selected during locating. It associates the receipt container to the existing Putaway Group. If there is not an existing Putaway Group for the destination location, the system will either create a new Putaway Group with the System ID or the user will assign a Putaway Group ID. The system will then update the Parent License Plate on the receiving dock inventory for this license plate with the Putaway Group ID.

When work is executed, the pick is for the entire putaway group. One use of these groups is if you want all returned items to be placed on a certain area of the receiving dock, destined to be putaway either back into their original inventory locations, or to a special returns "repair" area.

Grupo Julio has the Putaway Location Group configured using locating zones. The Putaway Location Groups will be configured as follows:

- Locating zone: The locating zones in the warehouse
- Group assignment method: Manual
- One per user: No
- Verify Group ID: No
- Maximum units: 0
- Quantity UM list: None selected

After entering the required information, SCALE locates the LPN to the corresponding location and putaway work is created. SCALE determines a putaway location based on the locating rule assigned by the Disposition Code. For this type of receiving preference, there is no need to print another label as the products received under this preference should be located to the picking locations.

Design note: EX05 implements a change to the Warehouse Mobile putaway group confirmation, showing the total units on the selected putaway group id.

Design note: Grupo Julio performs a few validations before checking-in inventory, making sure that the putaway groups will have the correct items on it. As the receiving upload interface happens at the "Putaway Pending" status, once the inventory is checked-in and located it is already eligible for interfacing. In the rare scenario of a user mistake during

the check-in, Grupo Julio cannot just cancel the Putaway Group and check-in again, as this would create duplicate inventory at the ERP. In case this happens, Grupo Julio needs to execute an SOP, involving the operational team and other areas of the company, to make the necessary changes in ERP to avoid duplicity. This is not a SCALE limitation, but a side effect of Grupo Julio's decision to interface the receiving upload at this early stage.

Config Note: To help preventing the generation of duplicate inventory, Manhattan Associates recommends Grupo Julio to limit the access of opening closed Putaway Groups to just supervisors. This can be achieved by using the base Security Permissions -> Putaway group insight -> Form specific -> Uncheck Open.




Figure 14 - Remove 'Open' from permissions

7.4 Verify Receipts

For receipts where all receipt details are received complete, SCALE automatically closes the receipt upon the putaway of the last LPN. If all detail lines were not received completely (such as with a short ship), the receipt must be manually closed. To manually close a receipt, a user selects the receipt that is completed and uses the Close action from the **Receipt Insight**. Upon confirmation of the close, SCALE updates the receipt status to Closed and does not allow additional products to be received.

Note: A closed receipt can be re-opened in SCALE to allow additional receiving

The screenshot shows the 'Receipt Insight' application. At the top, there are summary cards for 'Receipts: 54', 'Lines: 3.2k', and 'Units: 1.5m'. Below these is a table with columns: Receipt id, Receipt id type, Company, Receipt date, Trailing status, Leading status, Trailer id, Trailer location, and Closed. A list of receipts is displayed, with the first one (IMP-002667) selected. An 'Actions' menu is open on the right, showing options like 'New container', 'New line', 'Assign trailer id', 'New appointment', 'Edit appointment', 'Delete appointment', 'Cancel close', 'Check in', 'Create pre-check in containers', 'Close' (highlighted with a red box), 'Print preview', 'Immediate needs', 'Print default docs', 'Print selected docs', and 'Yard check in & out'.

Receipt id	Receipt id type	Company	Receipt date	Trailing status	Leading status	Trailer id	Trailer location	Closed
IMP-002667	Orden de Compra	NAL	7/27/2023	Check In Pending	Check In Pending			
IMP-002675	Orden de Compra	NAL	7/25/2023	Check In Pending	Check In Pending			
IMP-002684	Orden de Compra	NAL	8/1/2023	Check In Pending	Closed			
IMP-002700	Orden de Compra	NAL	4/28/2023	Check In Pending	Check In Pending			
IMP-002709	Orden de Compra	NAL	8/2/2023	Check In Pending	Check In Pending			
IMP-002711	Orden de Compra	NAL	7/27/2023	Check In Pending	Check In Pending			
IMP-002714	Orden de Compra	NAL	7/28/2023	Check In Pending	Check In Pending			
IMP-002720	Orden de Compra	NAL	7/28/2023	Check In Pending	Check In Pending			
IMP-002725	Orden de Compra	NAL	8/1/2023	Check In Pending	Check In Pending			
IMP-002731	Orden de Compra	NAL	8/2/2023	Check In Pending	Check In Pending			
IMP-002738	Orden de Compra	NAL	7/31/2023	Check In Pending	Check In Pending			
IMP-002739	Orden de Compra	NAL	8/1/2023	Check In Pending	Check In Pending			
IMP-002748	Orden de Compra	NAL	8/2/2023	Check In Pending	Check In Pending			
IMP-002758	Orden de Compra	NAL	7/27/2023	Check In Pending	Check In Pending			

Figure 15 - Receipt Insight

8.0 EXCEPTIONS

8.1 Items missing weight or dimensions

Client will leverage an SOP to add the missing information into Host system and download the Item Master interface before receiving the item in SCALE.

8.2 Overages

Grupo Julio will not over receive. In case the provider sends more products than anticipated they will generate an additional receipt on their ERP and it will be interfaced into SCALE. After this process is completed, then users will use regular receiving preferences to receive the product.

8.3 Shortages

When a receipt is not received in full, the user must manually close it, if the rest of the balance is no longer expected.

Grupo Julio usually receives the missing products with a different inventory status, then coordinate with the Inventory Team and ERP to make the necessary adjustments.

This screenshot is identical to Figure 15, showing the 'Receipt Insight' application with the same summary cards, table of receipts, and the 'Actions' menu open with 'Close' highlighted.

Figure 16 - Closing receipt Shortages

8.4 Receipt not in SCALE

Whenever a receipt is not in SCALE, Grupo Julio will make the necessary adjustments on their ERP, to then interface the Receipt into SCALE.

The only exception for that is for returns from some clients (*Faturado*), that will be received as a Blind Receipt into SCALE.

8.5 Unknown Product

When an item is available for receiving but doesn't exist neither on the receipt nor the item master, it is called an Unknown Product. The check in clerk informs the supervisor, who coordinates with the supplier team. Client manually moves this product away from the receiving dock to avoid any obstruction. The supervisor coordinates with the merchandising team and an item master is interfaced with this item if it must be received. A new receipt is then created in the host for this known (unknown before item master download) product and interfaced into SCALE.

8.6 Damages

Damages are received in a Damaged status into a specific location (multi-item). A Quality Control process should take place to review the inventory at this location and transfer the inventory that may be good to a picking location and make the necessary adjustments with the inventory that is really damaged. The location used to store the damaged products is not included in the regular allocation location selections. Only a special selection, used to ship out the damaged products, will have access to this location.

9.0 PUTAWAY

Putaway involves executing the task to move the inventory to the system-directed location from the receiving dock.

Locating takes each receipt container from the Check-In process and tries to find a place in the warehouse to store the product. Locating Rules are based on a series of sequences that use a combination of strategy and Location selection to try and find the right place in inventory for the item. If the system locates the receipt container to a location, work is created to move the product from the Receiving Dock to the destination location in the warehouse for all receipts.

Client uses a manual SOP to troubleshoot if a container is located to the 'SUPERVISOR-001' location. Transaction history and process history can be leveraged to review the locating rule sequences to determine the root cause. Client cancels the check-in (if not uploaded) for this container and check in after making the needed corrections.

Design note: Grupo Julio usually has issues with incorrect locating during season changes. To minimize this impact, Grupo Julio should develop a proper SOP, with all the steps required to perform a season change, including actions performed in SCALE, in ERP and any other system involved on this process.

Config Note: Grupo Julio will have the location “SUPERVISOR-001” as a virtual multi-item location to handle locating exceptions. This approach is used to troubleshoot locating issues.

9.1 Locating Rules

Once the inventory has been checked in to SCALE, a putaway location is found using locating rules. Locating rules could be specified on the item or during the receipt download interface or the receiving process by certain functions such as Locating Rule Assignment, Disposition Codes, etc.

The locating rules are used to perform putaway work from the receiving dock location to inventory locations.

To allow for easy addition of new items and locating rules, the locating rule is assigned on the Receipt Check-In using the Locating Rule Assignment configuration.

Config Note: The Receiving System Value Locating Rule Assignment During is set to Receipt Check-In.

Below there is a list of a few locating zones currently in use by Client. This is not the final list, though.

Locating Zone	Description
L-Reserva Calzado	Reserve locations for shoes
L-Reserva Calzado TP	Reserve locations for shoes from past seasons
L-Drop Calzado	Locations to drop items during outbound
L-Devolucion	Locations for returns

Config Note: Grupo Julio will review the complete list of zones and eliminate the zones that are not in use anymore during the build phase.

Below there is a list of a few Locating Rules with the corresponding strategy and location selection. This is not the final list, though.

9.1.1 Devolucion

Seq	Strategy	Location Selection	Split Quantity
10	<i>Consolidate to location that already contains</i>	Devolucion	N
15	<i>Use specific (mult-item) location regardless of status</i>	Devolucion	N
30	<i>Use specific (mult-item) location regardless of status</i>	Almacenaje Supervisor	N

9.1.2 Almacenaje Colgado TA

Seq	Strategy	Location Selection	Split Quantity
10	<i>Consolidate to location that already contains</i>	Almacenaje Colgado TA	N
15	<i>Use specific (mult-item) location regardless of status</i>	Almacenaje Colgado TA	N
20	<i>Empty location</i>	Almacenaje Colgado TA	N
30	<i>Use specific (mult-item) location regardless of status</i>	Almacenaje Supervisor	N

9.1.3 Almacenaje VAS Etiquetado

Seq	Strategy	Location Selection	Split Quantity
30	<i>Use specific (mult-item) location regardless of status</i>	Almacenaje VAS Etiquetado	N
40	<i>Use specific (mult-item) location regardless of status</i>	Almacenaje Supervisor	N

Config Note: Grupo Julio will review the complete list of locating rules and eliminate the ones that are not in use anymore during the build phase.

9.2 Putaway Work Creation

Upon receiving and palletization of the items, if necessary, SCALE generates system work records for each located Putaway Group ID/LPN. The work unit for the putaway work equals the Putaway Group ID/LPN. This allows the user to scan the Putaway Group ID/LPN in the Warehouse Mobile Work option to initiate the putaway in a user-directed mode. Client creates work for Receipt Putaway and uses User directed putaway.

Client configures the needed access for all Receiving users. For example, if the same user can move containers from Receiving Dock to the QC location, the user may have access to also pick and move containers from the QC location to the inventory locations.

9.3 Putaway Work Execution

To initiate putaway work, Client utilizes the option Work Execution on warehouse mobile. A user selects the Work Profile related to the putaway work execution from the menu option. Upon selection, SCALE prompts the user to enter a work unit, which in this scenario is the Putaway Group ID/LPN. The work profile is set to be User Directed.

Upon scanning the Putaway Group ID/LPN barcode, SCALE assigns the work unit to the user. SCALE then displays the current receiving dock location and item information and

displays the number of units associated with the work unit. Upon confirmation, SCALE updates the LPN(s) to status In Putaway and displays the putaway location for the first item. To complete the step of putaway, the user is prompted to confirm the putaway location. The user scans the location for validation upon putaway.

The user may skip the putaway instruction and proceed to the next item on the work unit if multiple work instruction lines exist. This is done by using the Skip button. If the user skips the putaway, the system continues directing the user through the putaway locations in the location sequence before looping back to put away the skipped items.

Upon putaway to the final inventory location, SCALE updates the LPN to status Closed and updates the on-hand quantity at the final putaway location.




Figure 17 - Putaway work execution

9.4 Location Override

Manhattan Associates does not recommend the use of location override for all users. Client should have configured this option just to a few specific security groups, to be used just in exceptional scenarios.

Certain users can be granted security to override the system's suggested location for the inventory. If this needs to happen, the user picks the LPN from the receiving dock, just as with the other work; however, when they are prompted for the Putaway Screen the user selects the Override option on the screen.

This redirects the user to a screen where they can scan the location name from the barcode in which they want to put the product away. The system validates that location is valid before accepting the user's override. After validation passes, the system updates work, the LPN to note the new location, and writes Transaction History noting the change in the putaway location. Finally, the user is presented with the Putaway Confirmation screen where they complete the Putaway the same as with other work units.

Another variation for overriding location is to use the Locate option. By using it, the user is requested to select a locating rule. The system will then decide on a suitable putaway location based on the locating rule.




Figure 18 - Putaway Override - Locate option

Note: The user will be manually selecting the locating rule that SCALE will use to find a location for putaway in this scenario.

If a user selects the option to override, SCALE has the option to create an activity-based cycle count at the original putaway location.

VIII. OUTBOUND

Outbound is the process in SCALE whereby inventory is shipped out of the warehouse via Shipments. From a high-level perspective, the following processes are required. Rectangles represent processes normally done by the system and trapezoids represent processes normally requiring user interaction.

Salidas es el proceso en SCALE mediante el cual el inventario se envía fuera del almacén a través de Envíos. Desde una perspectiva de alto nivel, se requieren los siguientes procesos. Los rectángulos representan procesos normalmente realizados por el sistema y los trapecios representan procesos que normalmente requieren interacción del usuario.




Figure 19 - High-Level typical SCALE Outbound Process / Proceso de salida SCALE típico de alto nivel

Shipment Creation

This is the process by which a shipment is entered into the system. This is normally a system process that is initiated on a schedule to interface records from an existing host system.

Creación de envíos

Este es el proceso mediante el cual se ingresa un envío en el sistema. Normalmente se trata de un proceso del sistema que se inicia según una programación para interconectar registros de un sistema ERP existente.

Wave Processing

Assigning shipments to a wave and running the wave is normally a system process, whereby shipments are grouped logically based on user-defined criteria to be processed together during the outbound process. Example groupings include: 'Priority Orders', 'High Volume Shipments with only one Item'. Once assigned to a Wave, the wave can be run either automatically or manually. Running the wave initiates the processing of Wave Steps, which may include the following: Allocation, Work Creation, Carrier Assignment, Load Building, etc.

Procesamiento de la Ola

La asignación de envíos a una ola y la ejecución de la ola es normalmente un proceso del sistema, mediante el cual los envíos se agrupan lógicamente en función de criterios definidos por el usuario para ser procesados juntos durante el proceso de salida. Los grupos de ejemplo incluyen: 'Pedidos prioritarios', 'Envíos de alto volumen con un solo artículo'. Una vez asignada a una ola, la ola se puede ejecutar automática o manualmente. La ejecución de la ola inicia el procesamiento de pasos de la ola, que pueden incluir lo

siguiente: asignación, creación de trabajo, asignación de transportista, construcción de carga, etc.

Picking

This is typically a user process whereby the system directs users to picking locations in a logical sequence to retrieve inventory allocated for shipments and bring it to packing stations, consolidation areas, or staging areas.

Surtido

Este suele ser un proceso de usuario mediante el cual el sistema dirige a los usuarios a ubicaciones de selección en una secuencia lógica para recolectar el inventario alocado para los envíos y llevarlo a estaciones de empaque, áreas de consolidación o áreas de preparación.

Packing

This is typically a user process where inventory is placed into boxes and the boxes are identified in the system. There are three main options for performing packing (1) During the Wave where the system uses dimensions and configured Container Types to calculate the most efficient way to pack the items, (2) During the picking process where users identify what boxes the items are being picked into while they are being picked, (3) After picking where items are dropped off at discreet packing stations and a separate team packs items into boxes.

Empaque

Este es típicamente un proceso de usuario donde el inventario se coloca en cajas y las cajas se identifican en el sistema. Hay tres opciones principales para realizar el empaque (1) Durante la ola, donde el sistema utiliza dimensiones y tipos de contenedores configurados para calcular la forma más eficiente de empaquetar los artículos, (2) Durante el proceso de recolección donde los usuarios identifican en qué cajas se recogen los artículos mientras se recogen, (3) Después de recoger dónde se dejan los artículos en estaciones de empaque discretas y un equipo de separación empaqueta los artículos en cajas.

Staging

This is a user process where containers are taken from a packing location to a staging area. Here they await the arrival of the method of transport. At this point, multiple shipping containers can be consolidated onto parent pallets for easier transport. This can also be a holding area where shipments are waiting for future shipping.

Preparación o Espera

Este es un proceso de usuario en el que los contenedores se llevan desde una ubicación de empaque a un área de preparación. Aquí esperan la llegada del método de transporte. En este punto, se pueden consolidar múltiples contenedores de envío en pallets principales para facilitar el transporte. Esto también puede ser un área de espera donde los envíos están esperando futuros embarques.

Shipping

This is a user process where shipments can be assigned to specific Shipping Loads and subsequently Load Confirmed. A Shipping Load can represent a truck, a sea container, a van, etc.

Embarque

Este es un proceso de usuario donde los envíos pueden asignarse a cargas de envío específicas y posteriormente confirmar la carga. Una carga de embarque puede representar un camión, un contenedor marítimo, una furgoneta, etc.

The assignment of a Carrier to a shipment can be done systematically during the wave or manually after the wave process.

La asignación de un transportista a un envío se puede hacer sistemáticamente durante la ola o manualmente después del proceso de ola.

Loading is the action in which a user takes the shipping containers \ parent pallets and confirms them onto the truck via a dock door.

La carga es la acción en la que un usuario toma los contenedores de envío \ pallets padres y los confirma en el camión a través de una puerta de muelle.

Load Confirmation is the process that represents the truck, container, etc. has already been loaded and has left the warehouse. The shipping process encompasses the dock management functionality of SCALE. Load Confirmation is the final status in the order flow in SCALE and represents the removal of stock from within the four walls of the warehouse

La confirmación de carga es el proceso que representa que el camión, contenedor, etc. ya ha sido cargado y ha salido del almacén. El proceso de envío abarca la funcionalidad de gestión de andenes de SCALE. La confirmación de carga es el estado final en el flujo de pedidos en SCALE y representa la eliminación de stock dentro de las cuatro paredes del almacén.

Shipment Trailing & Leading Statuses

These values are defined on the shipment header record. The trailing status is the least advanced status associated with the record; the leading status is the most advanced status associated with the record. The system obtains this information from the containers created for the header. You can use this information to research container activity and perform troubleshooting tasks.

Estados de seguimiento y de seguimiento de envíos

Estos valores se definen en el registro de encabezado del envío. El estado final es el estado menos avanzado asociado con el registro; El estado principal es el estado más avanzado asociado con el registro. El sistema obtiene esta información de los

contenedores creados para la cabecera. Puede usar esta información para investigar la actividad del contenedor y realizar tareas de solución de problemas.

Below are all the Outbound Execution default statuses available in SCALE:

- (90) In Pool Pending: The shipment's status before it is processed via the interface. The purpose of this status is to be a temporary status used by the interface download process to ensure that shipments do not get picked up for processing while the interface process is running. Also, shipments in this status cannot be added to a wave.
- (100) In Pool: The shipment has not been processed in a wave but has been created in the pool or downloaded via the interface. No work can be performed against this shipment.
- (200) Wave Pending: The wave is being built. It has not been run.
- (201) In Wave: A wave run was initiated, and the wave has not been released.
- (300) Picking Pending: A wave was released, but none of the work has been initiated.
- (301) In Picking: At least one work instruction associated with this shipment has been assigned to an employee.
- (400) Packing Pending: At least one work instruction associated with this shipment has been pick confirmed. It can now be packed.
- (401) In Packing: At least one work instruction associated with this shipment has been packed.
- (600) Staging Pending: All items of a shipment have been picked, packed, and/or consolidated.
- (650) Loading Pending: All items of a shipment have been picked, packed, or consolidated, and/or staged.
- (700) Ship Confirm Pending: At least one container associated with this shipment has been closed.
- (800) Load Confirm Pending: All shipments on the load have been ship confirmed and the load is ready to be confirmed.
- (900) Closed: The shipping load has been confirmed.
- (998) Delete Rejected: A quantity on a shipment detail line was rejected. The quantity will be deleted from the system.

- (999) Rejected: During allocation, if any quantity on the line is rejected, this status will indicate that rejected quantity

A continuación, se muestran todos los estados predeterminados de ejecución saliente disponibles en SCALE:

- (90) En grupo pendiente: el estado del envío antes de que se procese a través de la interfaz. El propósito de este estado es ser un estado temporal utilizado por el proceso de descarga de la interfaz para garantizar que los envíos no se recojan para su procesamiento mientras se ejecuta el proceso de interfaz. Además, los envíos en este estado no se pueden agregar a una ola.
- (100) En el grupo: El envío no se ha procesado en una ola, sino que se ha creado en el grupo o se ha descargado a través de la interfaz. No se puede realizar ningún trabajo contra este envío.
- (200) Ola pendiente: La ola se está construyendo. No se ha ejecutado.
- (201) En Ola: Se inició una ejecución de olas, y la ola no ha sido liberada.
- (300) Surtido Pendiente: Se lanzó una ola, pero ninguno de los trabajos se ha iniciado.
- (301) En surtido: Al menos una instrucción de trabajo asociada con este envío ha sido asignada a un empleado.
- (400) Embalaje pendiente: Se ha confirmado al menos una instrucción de trabajo asociada con este envío. Ahora se puede empacar.
- (401) En embalaje: Se ha empacado al menos una instrucción de trabajo asociada con este envío.
- (600) Pendiente de Stage: Todos los artículos de un envío han sido recogidos, embalados y/o consolidados.
- (650) Carga pendiente: Todos los artículos de un envío han sido recogidos, embalados o consolidados, y/o escalonados.
- (700) Confirmación del envío pendiente: Se ha cerrado al menos un contenedor asociado a este envío.
- (800) Confirmación de carga pendiente: Todos los envíos en la carga han sido confirmados por el envío y la carga está lista para ser confirmada.
- (900) Cerrado: La carga de envío ha sido confirmada.

- (998) Suprimir rechazado: Se rechazó una cantidad en una línea de detalles de envío. La cantidad se eliminará del sistema.
- (999) Rechazada: Durante la asignación, si se rechaza cualquier cantidad de la línea, esta situación indicará que la cantidad rechazada

10.0 WAVE PROCESSING / PROCESAMIENTO DE LA OLA

A wave is a method for retrieving shipments from the pool and processing them through a wave flow. All shipments are processed through the system in a wave (a wave is simply a collection of shipments that generate an amount of work that can be handled by the operation in a single session). All wave activity is defined on the wave master record.

Una ola es un método para agrupar envíos del sistema y procesarlos a través de un flujo de olas. Todos los envíos se procesan a través del sistema en una ola (una ola es simplemente una colección de envíos que generan una cantidad de trabajo que puede ser manejada por la operación en una sola sesión). Toda la actividad de las olas se define en el registro maestro de olas.

Outbound shipments are created in Host and sent to SCALE. At random basis, these shipments are interfaced into SCALE. Any orders that fail validation are logged for further review and will be reviewed manually by looking at the **Interface Error Insight** screen for corrective actions. Once corrected, the shipment(s) can be reprocessed during the next scheduled interface download (or the interface can be manually invoked).

Los envíos salientes se crean en el ERP y se envían a SCALE. De forma aleatoria, estos envíos se interconectan a SCALE. Cualquier pedido que no supere la validación se registra para una revisión adicional y se revisará manualmente mirando la pantalla **Visor Interface Error** para ver las acciones correctivas. Una vez corregidos, los envíos se pueden volver a procesar durante la próxima descarga programada de la interfaz (o la interfaz se puede llamar manualmente).

Once successfully downloaded, the shipments are viewable as SCALE shipments in the Pool in the **Planned Shipment Insight**. The shipments can be viewed by Order Type and Scheduled Ship Date (Grupo Julio can create Planned shipment filter criteria records to view shipments in pool by other criteria of their choice).

Una vez descargados correctamente, los envíos se pueden ver como envíos SCALE en el grupo en **Visor Planeación de Envíos**. Los envíos se pueden ver por Tipo de pedido y Fecha de envío programada (Grupo Julio puede crear registros de criterios de filtro de envío planificado para ver los envíos agrupados por otros criterios de su elección).




Figure 20 - Planned Shipment Insight / Información sobre envíos planificados

Following order types are used by Grupo Julio's Host. This list may change during the build phase. The Order Types (codes) used may also change during the build phase.

Order Types	Description	Interfaced	Frequency
Pedido CTE	Orders from clients	Y	Random
Pedido INS	Orders for <i>insumos</i>	Y	Random
Pedido TDA	Orders from stores	Y	Random

El ERP de Grupo Julio utiliza los siguientes tipos de pedido. Esta lista puede cambiar durante la fase de construcción. Los tipos de pedido (códigos) utilizados también pueden cambiar durante la fase de construcción.

Tipos de Pedidos	Descripción	Interfaz	Frecuencia
Pedido CTE	Pedidos de clientes	Y	Random
Pedido INS	Pedidos de insumos	Y	Random
Pedido TDA	Pedidos de tiendas	Y	Random

10.1 Waving Strategy / Estrategia de Ola

Shipments interfaced into SCALE are processed differently depending on the shipment order type. Every shipment that is interfaced has a unique item per line with the requested quantity in the lowest unit of measure.

Los envíos interfazados en SCALE se procesan de manera diferente según el tipo de pedido de envío. Cada envío que está interfazado tiene un artículo único por línea con la cantidad solicitada en la unidad de medida más baja.

Grupo Julio runs several waves throughout the day. The planning department sends an email to the wave supervisor with the list of shipments that should be waved and the total number of pieces it should have. The wave supervisor then filters the shipments on the **Planned Shipment Insight** and add them to a new wave. After creating the wave, the supervisor will review if the created wave has the correct quantity of pieces as sent by the planning department. In case of a discrepancy, the wave supervisor will reply to the email, informing the difference. The planning department and the wave supervisor will work together to find out the discrepancy. After fixing it, the wave is ready to be executed.

Grupo Julio puede correr olas durante todo el día. El equipo de planeación envía un correo al supervisor de olas con un listado de pedidos que se deben olear y la cantidad total de piezas que debería tener. El supervisor de olas va a filtrar los pedidos utilizando el **Visor Planeación de Envíos** y adicionarlos a una nueva ola. Después de crear la ola, el supervisor va a revisar se la ola creada tiene la correcta cantidad de piezas conforme enviado por el equipo de planeación. En caso de que tenga discrepancias, el supervisor de olas va a contestar el correo, indicando la diferencia. El equipo de planeación y el supervisor de olas van a trabajar juntos para identificar la diferencia. Después de arreglar esto, la ola está lista para ejecución.

Planned Shipment Filters display planned shipments based on the criteria that you select. You could, for example, define a rule in SCALE configuration for a particular customer, carrier, and order type. You could then display shipment records that meet those criteria in the Planned Shipment Insight. You can define pool views using any combination of shipment or shipment line values. If you specify a shipment line in your filter criteria, the system will use it to determine if shipments should be included in a pool view. If a shipment line matches a rule, then the system will select the entire shipment for the pool view.

Los filtros de envío planificado muestran los envíos planificados en función de los criterios seleccionados. Podría, por ejemplo, definir una regla en la configuración de SCALE para un cliente, transportista y tipo de pedido determinados. A continuación, puede mostrar los registros de envío que cumplan esos criterios en Visor Planeación de Envíos. Puede definir vistas de grupo utilizando cualquier combinación de valores de envío o de línea de envío. Si especifica una línea de envío en los criterios de filtro, el sistema la utilizará para determinar si los envíos deben incluirse en una vista de grupo. Si una línea de envío coincide con una regla, el sistema seleccionará todo el envío para la vista de grupo.

All shipments are processed through the system in a wave. A wave consists of a series of wave steps. Each wave step controls a function of the wave.

Todos los envíos se procesan a través del sistema en una oleada. Una ola consiste en una serie de pasos de ola. Cada paso de ola controla una función de la ola.

Wave Flow

The sequence below shows an example of the order in which wave steps could be executed as part of the wave process.

Sequence	Description
10	Start Wave
20	Override Data: Set Default Status Flow
30	Replenishment
40	Rule Assignment
50	Allocation
60	Container Creation
70	Pallet Building
80	Load Building
90	Work Creation Replenishment
100	Work Creation Shipping Containers
110	Paperwork – Labels
120	Complete Wave

Flujo de olas

La siguiente secuencia indica un ejemplo del orden en que se podría ejecutar pasos de ola como parte del proceso de ola.

Secuencia	Descripción
10	Inicio de ola
20	Anular datos: establecer el flujo de estado predeterminado
30	Reabastecimiento
40	Asignación de reglas
50	Asignación
60	Creación de contenedores
70	Construcción de pallets
80	Construcción de cargas
90	Creación de trabajos de reabastecimiento
100	Creación de trabajo de Contenedores de envío
110	Hojas de trabajo – Etiquetas
120	Ola completa

10.1 Wave Selection / Selección de Olas

The wave selection process describes the use of wave flows and the wave masters. It also describes the process of running these waves. Grupo Julio leverages the criteria mentioned above to select orders and batch them to be run as a wave.

El proceso de selección de olas describe el uso de flujos de ola y los maestros de ola. También describe el proceso de ejecutar estas olas. Grupo Julio utilizará los criterios mencionados anteriormente para seleccionar pedidos y agruparlos para que se ejecuten como una ola.

The Wave Master defines the Wave Flow, Replenishment Master(s), and Paperwork Master for the wave. The wave flow defines the sequence and specific steps SCALE performs when running the wave. Examples of Wave Flow steps include allocation, work creation, printing documents, etc. The Wave Flows are defined via the Wave Flow windows in the fixed station Configuration option. The Replenishment Master defines what replenishment masters are eligible to evaluate demand within the wave. The paperwork master defines the documentation that is printed with the wave.

El Maestro de Ola define el Flujo de Ola, el Maestro (s) de Reabastecimiento y el Maestro de hojas de trabajo para la ola. El flujo de ola define la secuencia y los pasos específicos que SCALE realiza al ejecutar la ola. Ejemplos de pasos de flujo de ola incluyen asignación, creación de trabajo, impresión de documentos, etc. Los flujos de ola se definen a través de las ventanas de flujo de olas en la opción Configuración de estación fija. El maestro de reabastecimiento define qué maestros de reabastecimiento son elegibles para evaluar la demanda dentro de la ola. El maestro de hojas de trabajo define la documentación que se imprime con la ola.

For Grupo Julio, the following wave flows are configured in the system:

Para Grupo Julio, los siguientes maestros de ola están configurados en el sistema:

- Ola Tiendas y Clientes

Sequence	Description
10	Start Wave
20	Start Wave Statistics
30	Set Custom Status Flow
33	Set Online in PTS
39	Shipment Distribution Before
40	Shipment Distribution
46	Set Consolidation To SH
47	Set Route
70	Rule Assignment
80	Allocation
85	Set Delete COMPANY NULL
90	Allocation Statistics
95	Container Creation
96	Container Creation Statistics
98	Work Creation Shipping Containers
110	Work Creation Allocation Requests
120	Labor Plan Execution

125	Paperwork – Labels
140	Complete Wave

- Ola Flujo Don y Des

Sequence	Description
10	Start Wave
20	Start Wave Statistics
22	Override: Remove Store Distribution
25	Set Eligible to NULL
30	Set Custom Status Flow
70	Rule Assignment
80	Allocation
85	Set Delete COMPANY NULL
90	Allocation Statistics
100	Work Creation Allocation Requests
120	Labor Plan Execution
140	Complete Wave

- Ola Flujo Express

Sequence	Description
10	Start Wave
20	Start Wave Statistics
30	Set Custom Status Flow
40	Set Eligible to NULL
50	Set Online in PTS
60	Shipment Distribution Before
70	Shipment Distribution
80	Set Consolidation To SH
90	Set Route
100	Rule Assignment
110	Allocation
120	Allocation Statistics
130	Container Creation
140	Container Creation Statistics
150	Work Creation Shipping Containers
160	Work Creation Allocation Requests
170	Labor Plan Execution
180	Paperwork - Labels
190	Complete Wave

- Ola Flujo Insumos

Sequence	Description
10	Start Wave

20	Start Wave Statistics
22	Override: Remove Store Distribution
25	Set Eligible to NULL
26	Rem Consolidation Allowed
30	Set Custom Status Flow
70	Rule Assignment
80	Allocation
85	Set Delete COMPANY NULL
90	Allocation Statistics
100	Work Creation Allocation Requests
120	Labor Plan Execution
140	Complete Wave

- Ola Flujo Muestras

Sequence	Description
10	Start Wave
20	Start Wave Statistics
22	Override: Remove Store Distribution
25	Set Eligible to NULL
26	Rem Consolidation Allowed
30	Set Custom Status Flow
70	Rule Assignment
80	Allocation
85	Set Delete COMPANY NULL
90	Allocation Statistics
92	Dock Assignment
100	Work Creation Allocation Requests
120	Labor Plan Execution
140	Complete Wave

- Ola PH y Colombia

Sequence	Description
10	Start Wave
20	Start Wave Statistics
30	Set Custom Status Flow
35	Set Consolidation To SH
70	Rule Assignment
80	Allocation
85	Set Delete COMPANY NULL
90	Allocation Statistics
95	Container Creation
96	Container Creation Statistics
98	Work Creation Shipping Containers

110	Work Creation Allocation Requests
120	Labor Plan Execution
125	Paperwork - Labels
140	Complete Wave

- Ola Flujo Uniformes

Sequence	Description
10	Start Wave
20	Start Wave Statistics
25	Override: Remove Store Distribution
30	Set Custom Status Flow
35	Set Eligible to NULL
70	Rule Assignment
80	Allocation
81	Set Alloc Zone on Work Colgado
85	Set Delete COMPANY NULL
90	Allocation Statistics
100	Work Creation Allocation Requests
120	Labor Plan Execution
140	Complete Wave

- Ola Flujo Clientes Esp

Sequence	Description
10	Start Wave
20	Start Wave Statistics
25	Set Eligible to NULL
30	Set Custom Status Flow
70	Rule Assignment
80	Allocation
85	Set Delete COMPANY NULL
90	Allocation Statistics
100	Work Creation Allocation Requests
120	Labor Plan Execution
140	Complete Wave

- Ola Flujo Online

Sequence	Description
10	Start Wave
20	Start Wave Statistics
25	Set Eligible to NULL
30	Set Custom Status Flow
70	Rule Assignment
80	Allocation

85	Set Delete COMPANY NULL
90	Allocation Statistics
116	Work Creation Allocation Requests
117	Set Alloc Zone on Work Online
118	VAS Assignment
120	Labor Plan Execution
140	Complete Wave

- Ola Flujo TDA Movil

Sequence	Description
10	Start Wave
20	Start Wave Statistics
25	Set Eligible to NULL
30	Set Custom Status Flow
70	Rule Assignment
80	Allocation
90	Allocation Statistics
140	Complete Wave

10.1.1 Add Shipments to Wave / Agregar envíos a ola

To initiate the wave process, wave personnel select a shipment (or multi-selects more than one shipment) from the **Planned Shipment Insight Screen** and selects *Add to Wave*. Next, the user is prompted to add the shipment(s) selected to an existing open wave, or they may select *Create New Wave* to manually assign the shipment(s) to a new wave. When executing the *New Wave* action, the system prompts the user to select a *Wave Master* to act as a template that manages the movement of shipments through the wave cycle. User selects the appropriate wave master.

Para iniciar el proceso de olas, el personal de ola selecciona un envío (o selecciona varias veces más de un envío) en la **pantalla Visor de envíos planificados** y selecciona *Agregar a ola*. A continuación, se solicita al usuario que agregue los envíos seleccionados a una ola abierta existente, o puede seleccionar *Crear nueva ola* para asignar manualmente los envíos a una nueva ola. Al ejecutar la acción *Nueva ola*, el sistema solicita al usuario que seleccione un *Maestro de Ola* para que actúe como plantilla que gestione el movimiento de los envíos a través del ciclo de ola. El usuario selecciona el *Maestro de Ola* apropiado.

After confirming the *Wave Master* for the wave, the system assigns a wave number (via a next-up counter) to group the selected shipments. The shipments are removed from their previous pool view. The wave is created in the Active Wave folder of the **Wave Insight Screen**. The wave has a unique wave number and the wave name as specified when creating the wave.

Después de confirmar el *Maestro de Ola* para la ola, el sistema asigna un número de ola (a través de un contador creciente) para agrupar los envíos seleccionados. Los envíos se eliminan de su vista de grupo anterior. La ola se crea en la carpeta Ola Activa de la **Pantalla Visor de Ola**. La ola tiene un número de ola único y el nombre de ola especificado al crear la ola.




Figure 21 - Planned Shipment Insight screen




Figure 22 - Add shipments to wave using Planned Shipment Insight

10.2 Run Wave / Ejecución de Ola

After reviewing the appropriate wave and making any necessary changes, personnel use the Run Wave action on the desired wave in the **Wave Insight Screen**. Upon confirmation of the run wave request, the system executes the steps

detailed in the Wave Flow associated with the wave. Upon completion of running the wave, the system moves the wave into the *Completed Wave* bucket. This can be seen by selecting the 'Show Completed Wave' status on the filter.

Después de revisar la ola y realizar los cambios necesarios, el personal selecciona la acción Ejecutar ola en la ola deseada en la **Pantalla Visor de Ola**. Tras la confirmación de la solicitud de ejecución de ola, el sistema ejecuta los pasos detallados en el flujo de ola asociado con la ola. Al finalizar la ejecución de la ola, el sistema mueve la ola al estatus de *ola completada*. Esto se puede ver seleccionando el estado 'Mostrar ola completada' en el filtro.




Figure 23 - Run wave using Wave Insight screen

10.1 Build Wave

Design note: Grupo Julio does not leverage the Build Wave scheduled job.

Nota de diseño: Grupo Julio no utiliza creación de ola automática.

10.2 Wave Steps / Pasos de Ola

The following sections explain the logic the system uses when executing the various key wave steps that are included in standard wave flow. Please note that there may be additional wave steps that may be added during the build phase.

En las secciones siguientes se explica la lógica que utiliza el sistema al ejecutar los distintos pasos clave de ola que se incluyen en el flujo de ola estándar. Tenga en cuenta que puede haber pasos de ola adicionales que se pueden agregar durante la fase de construcción.

10.2.1 Start Wave / Inicio de Ola

Start Wave is required for all wave flows and marks each shipment with a status of In Wave.

El Inicio de Ola es necesario para todos los flujos de olas y marca cada envío con un estado de "En Ola."

10.2.2 Rule Assignment / Asignación de reglas

During the allocation rule set assignment process, the system does the following:

- Selects all shipment lines that do not have an allocation rule assigned
- Reviews each active allocation rule assignment record in priority order
- Using the filter tied to the allocation rule assignment record to determine eligibility, the system updates the allocation rule on the matching details. If the shipment line already had a rule assigned by a previous sequence, then it is only updated if the "Always Override" setting is selected

This assignment is configurable based on Shipment Detail fields.

Durante el proceso de asignación del conjunto de reglas de asignación, el sistema hace lo siguiente:

- Selecciona todas las líneas de envío que no tienen asignada una regla de asignación
- Revisa cada registro de asignación de regla de asignación activo en orden de prioridad
- Utilizando el filtro vinculado al registro de asignación de reglas de asignación para determinar la elegibilidad, el sistema actualiza la regla de asignación en los detalles coincidentes. Si la línea de envío ya tenía una regla asignada por una secuencia anterior, solo se actualiza si se selecciona la configuración "Anular siempre"

Esta asignación se puede configurar en base a los campos de Detalles del envío.

10.2.3 Allocation / Asignación

SCALE allocates inventory towards a shipment by using the allocation rule defined on the shipment detail. Allocation rules define what locations and units of measure are eligible for allocation and how SCALE should allocate that inventory. For example, an allocation rule can be configured to allocate inventory only from Active bins and to allocate the inventory with the corresponding strategy (FEFO, LEFO, FIFO, LIFO, etc). Allocation rules can have multiple sequences. SCALE attempts to allocate inventory using the first sequence and if inventory could not be 100% allocated, SCALE continues to the next allocation rule sequence to attempt to allocate the remaining inventory.

SCALE asigna inventario a un envío utilizando la regla de asignación definida en el detalle del envío. Las reglas de asignación definen qué ubicaciones y unidades de medida son elegibles para la asignación y cómo SCALE debe asignar ese inventario. Por ejemplo, se puede configurar una regla de asignación para asignar inventario solo desde contenedores activos y para asignar el inventario con la estrategia correspondiente (FEFO, LEFO, FIFO, LIFO, etc). Las reglas de asignación pueden tener varias secuencias. SCALE intenta asignar el inventario utilizando la primera secuencia y, si el inventario no se pudo asignar al 100%, SCALE continúa con la siguiente secuencia de reglas de asignación para intentar asignar el inventario restante.

Allocation rules are set on the shipment detail in one of three ways.

- The allocation rule can be set at the item level (in the Item Master configuration) which in turn automatically defaults on the shipment detail.
- The interface can also set the allocation rule on the shipment detail.
- In addition, the allocation rule can be determined in the wave just prior to allocation occurring. This is done using the Rule Assignment functionality as defined in the above wave step. Allocation Rule Assignment sets the allocation rule on the shipment detail based on allocation rule assignment criteria. For example, based on the customer and order type, the allocation rule can be set to one, that is allocated in only full cases. If no allocation rule is set on the shipment detail, the *Default allocation rule is used.

Las reglas de asignación se establecen en el detalle del envío de una de tres maneras.

- La regla de asignación se puede establecer en el nivel de artículo (en la configuración maestra de artículos) que, a su vez, se establece automáticamente en el detalle del envío.
- La interfaz también puede establecer la regla de asignación en el detalle del envío.
- Además, la regla de asignación se puede determinar en la ola justo antes de que ocurra la asignación. Esto se hace utilizando la funcionalidad de asignación de reglas de asignación como se define en el paso de ola anterior. Asignación de regla de asignación establece la regla de asignación en el detalle del envío en función de los criterios de asignación de reglas de asignación. Por ejemplo, según el cliente y el tipo de pedido, la regla de asignación se puede establecer en uno, que se asigna solo en casos completos. Si no se establece ninguna regla de asignación en el detalle del envío, se utiliza la regla de asignación *Predeterminada.

To allow for maximum flexibility and easy addition of new items and allocation rules, the allocation rule is assigned on the Shipment Detail using the *Allocation*

Rule Assignment functionality in the wave. Grupo Julio can still manually set the allocation rule in the interface or via the Shipment Detail screen as needed.

Para permitir la máxima flexibilidad y la fácil adición de nuevos artículos y reglas de asignación, la regla de asignación se asigna en el Detalle de envío utilizando la funcionalidad *Asignación de regla de asignación* en la ola. Grupo Julio aún puede establecer manualmente la regla de asignación en la interfaz o a través de la pantalla Detalles del envío según sea necesario.

Allocation strategy and *allocation location selection* are two of the key configurations used in determining the allocation location.

La estrategia de asignación y la selección de ubicación de *asignación* son dos de las configuraciones clave utilizadas para determinar la ubicación de asignación.

An *allocation strategy* is a method for selecting picking locations based on a storage management goal, such as emptying locations. These strategies are predefined and represent a specific system algorithm that the system uses to allocate product.

Una *estrategia de asignación* es un método para seleccionar ubicaciones de picking en función de un objetivo de administración de almacenamiento, como vaciar ubicaciones. Estas estrategias están predefinidas y representan un algoritmo de sistema específico que el sistema utiliza para asignar el producto.

Allocation Location Selection configuration allows users to filter by any field within the Location or Location Inventory tables in SCALE. Through the combination of pre-defined strategies and customer-driven location selections, SCALE can meet most allocation requirements. Each Allocation Rule Detail is made up of an Allocation Strategy and Location Selection.

La configuración de selección de ubicación de asignación permite a los usuarios filtrar por cualquier campo dentro de las tablas Ubicación o Inventario de ubicación en SCALE. A través de la combinación de estrategias predefinidas y selecciones de ubicación indicadas por el cliente, SCALE puede cumplir con la mayoría de los requisitos de asignación. Cada detalle de regla de asignación se compone de una estrategia de asignación y una selección de ubicación.

Allocation Zones / Zonas de Asignación

Grupo Julio's warehouses will have different allocation zones. Below we have a partial list of the current zones. The current zones may be removed during the build phase, depending on the configuration optimization and test results.

El almacén de Grupo Julio va a tener diferentes zonas de asignación. Abajo tenemos una lista parcial de las zonas actuales. Las zonas actualmente en uso

pueden ser eliminadas, a depender de las optimizaciones de configuración durante las pruebas.

Allocating Zone
A-Donacion
A-Drop Colgado
A-Put to Store Calzado
A-Reserva Doblado

Allocation Rules / Reglas de Asignación

Grupo Julio has many different allocation rules. In here we are listing just a few of them for example purposes.

Grupo Julio va a tener varias reglas de asignación diferentes. Abajo tenemos un listado de solamente algunas reglas para ejemplo.

Asignacion Calzado

Seq	Strategy	Location Selection	Eligible UMs
10	First in, first out	Reserva Calzado	

Asignacion Destruccion

Seq	Strategy	Location Selection	Eligible UMs
10	First in, first out	Reserva Destruccion	

Asignacion Devolucion

Seq	Strategy	Location Selection	Eligible UMs
10	First in, first out	Reserva Devolucion	

Asignacion Disponible Col

Seq	Strategy	Location Selection	Eligible UMs
5	First in, first out	Devoluciones	
10	First in, first out	Reserva Colgado TA	
20	First in, first out	Reserva Colgado TP	

Asignacion Disponible Mez

Seq	Strategy	Location Selection	Eligible UMs
30	First in, first out	Reserva Doblado	

10.2.4 Container Creation / Creación de contenedores

Container creation is the process in which SCALE determines the number of containers and each container's contents for every shipment on the wave. A unique container number, commonly referred to as a UCC 128, is assigned to every container as it is created.

La creación de contenedores es el proceso en el que SCALE determina el número de contenedores y el contenido de cada contenedor para cada envío en la ola. Se asigna un número de contenedor único, comúnmente denominado UCC 128, a cada contenedor a medida que se crea.

SCALE first takes all items whose allocated unit of measure is set up as a 'shippable unit' and creates full containers. Shippable units are defined in the item unit of measure configuration. Full containers are containers that are shippable without repacking into another container (box). Pallets, gaylords, and certain cases are generally configured as shippable units.

SCALE primero toma todos los artículos cuya unidad de medida asignada está configurada como una "unidad transportable" y crea contenedores completos. Las unidades que se pueden acoplar se definen en la configuración de la unidad de medida del artículo. Los contenedores llenos son contenedores que se pueden enviar sin volver a empacar en otro contenedor (caja). Los pallets, gaylords y ciertos casos generalmente se configuran como unidades enviables.

SCALE then takes the remaining 'loose' items whose allocated unit of measure is set up as 'not shippable' and groups them together by Packing Class. A Packing Class is defined on the Item Master and then defaulted on the Shipment Detail. Each Packing Class is associated with a container group. A container group is a listing of container types (box sizes) listed from largest container to smallest container. SCALE attempts to cube items into the least number of containers possible. The total weight and volume are calculated for all the items on the shipment with the same packing group. SCALE first tries to cube into the first container of the container group. If capacity still exists, the system tries cubing into the next container type and continues until either capacity in the next priority is reached or there are no additional priorities.

A continuación, SCALE toma los artículos "sueltos" restantes cuya unidad de medida asignada se configura como "no enviable" y los agrupa por clase de embalaje. Una clase de embalaje se define en el maestro de artículos y, a continuación, se establece de forma predeterminada en el detalle de envío. Cada clase de embalaje está asociada a un grupo de contenedores. Un grupo de contenedores es una lista de tipos de contenedores (tamaños de caja) enumerados desde el contenedor más grande hasta el contenedor más pequeño. SCALE intenta agrupar los elementos en el menor número posible de contenedores. El peso total y el volumen se calculan para todos los artículos del envío con el mismo grupo de embalaje. SCALE primero intenta agruparse en el

primer contenedor del grupo de contenedores. Si la capacidad aún existe, el sistema intenta pasar al siguiente tipo de contenedor y continúa hasta que se alcanza la capacidad de la siguiente prioridad o no hay prioridades adicionales.

If there is not enough capacity in the largest container, then SCALE cubes as much as possible into the largest container, calculates the remaining weight and volume, and starts over. SCALE considers the critical dimensions of each item it creates containers. An item is not cubed into a container if any one of its critical dimensions is greater than the corresponding container dimension.

Si no hay suficiente capacidad en el contenedor más grande, entonces SCALE cubica tanto como sea posible en el contenedor más grande, calcula el peso y el volumen restantes, y comienza de nuevo. SCALE considera las dimensiones críticas de cada elemento que crea contenedores. Un artículo no se agrupa en un contenedor si cualquiera de sus dimensiones críticas es mayor que la dimensión del contenedor correspondiente.

If an item doesn't have unit of measure record defined, then SCALE treats the item to have dimension of 0x0x0 and of weight 0 KG. Grupo Julio can build a SCI report that will provide the list of all items that have missing dimensions in the pool and use that to handle the exception.

Si un artículo no tiene definido el registro de unidad de medida, SCALE trata el artículo para que tenga una dimensión de 0 x 0 x 0 y de peso 0 KG. Grupo Julio puede crear un informe SCI que proporcionará la lista de todos los elementos que tienen una dimensión faltante en el grupo y usarla para controlar la excepción.

10.2.5 Load Building / Construcción de cargas

When SCALE executes a wave (that includes load building wave step), the system will then attempt to assign all a carrier's shipments on the wave to a shipping load (using shipment criteria). The system executes this process as follows:

- The system will order all of wave's shipments by carrier, ignoring shipments that do not have a carrier assigned.
- The system will take each shipment and look for any open loads for the carrier/scheduled ship date/route. If the system finds one, the shipment will be added to that load.
- If there are no loads in the system for the carrier/scheduled ship date/route, the system will create a new load for the carrier/scheduled ship date/route and place the shipment on the new load.

Note: In SCALE WM terminology, load means a truck/trailer that can hold all the shipments/orders

Cuando SCALE ejecuta una ola (que incluye el paso de ola de construcción de carga), el sistema intentará asignar todos los envíos de un transportista en la ola

a una carga de envío (utilizando criterios de envío). El sistema ejecuta este proceso de la siguiente manera:

- El sistema ordenará todos los envíos de ola por transportista, ignorando los envíos que no tengan un transportista asignado.
- El sistema tomará cada envío y buscará cualquier carga abierta para el transportista / fecha / ruta de envío programada. Si el sistema encuentra uno, el envío se agregará a esa carga.
- Si no hay cargas en el sistema para el transportista/fecha de envío/ruta programada, el sistema creará una nueva carga para el transportista/fecha/ruta de envío programada y colocará el envío en la nueva carga.

Nota: En la terminología de SCALE WMS, carga significa un camión / remolque que puede contener todos los envíos / pedidos

10.2.6 Work Creation - Shipping Containers / Creación de trabajo - Contenedores de envío

The work creation process performed during the wave is like the work creation process performed during the locating portion of the receiving process. After performing allocation and container creation, SCALE creates a work unit to pick the inventory from a location and transport the inventory to the shipping area based on the configuration in the Work Group, Work Type, Work Criteria, and Work Creation Master. Each location can be assigned a numeric value called Picking Sequence that can be used to sort the picks in an order other than alphabetical by location.

El proceso de creación de trabajo realizado durante la ola es como el proceso de creación de trabajo realizado durante la parte de localización del proceso de recepción. Después de realizar la asignación y la creación de contenedores, SCALE crea una unidad de trabajo para seleccionar el inventario de una ubicación y transporta el inventario al área de envío en función de la configuración del grupo de trabajo, el tipo de trabajo, los criterios de trabajo y el maestro de creación de trabajo. A cada ubicación se le puede asignar un valor numérico llamado Secuencia de surtido que se puede utilizar para ordenar los surtidos en un orden que no sea alfabético por ubicación.

10.2.7 Work Creation – Allocation Request / Creación de trabajo - Solicitaciones de asignación

This work creation takes the results of the allocation – where Grupo Julio is going to pick the product with allocation requests – the pick quantity for each pick is less than a case and a pick path for the end-user to traverse the warehouse to do the actual picking of the product is defined.

Este proceso de creación de trabajo toma los resultados de asignación – donde Grupo Julio va a surtir el producto basado en solicitudes de asignación – la

cantidad a surtir es menos que una caja y el camino de surtir traspasa el almacén para efectivamente surtir el producto definido.

11.0 WAVE MANAGEMENT / GESTIÓN DE OLAS

After building and running the wave, the wave supervisor reviews the results of the wave using the full-screen **Transaction History Insight** and **Work Insight** options. Depending on the results, the user may perform one of two options. These options are identified in the following sections.

Después de construir y ejecutar la ola, el supervisor de la ola revisa los resultados de la ola utilizando las opciones de **pantalla completa Información del historial de transacciones** y **Visor de trabajo**. Dependiendo de los resultados, el usuario puede realizar una de dos opciones. Estas opciones se identifican en las siguientes secciones.

11.1 Cancel Wave / Cancelar una ola

If the results of the entire wave are not satisfactory users may cancel the wave using the Cancel action in the Completed Wave window of the **Wave Insight**.

Si los resultados de toda la ola no son satisfactorios, los usuarios pueden cancelar la ola mediante la acción Cancelar en la ventana ola completada de **Visor de Ola**.




Figure 24 - Cancel a wave Cancelar una ola

The cancel process backs out allocation and deletes work instructions and shipping containers. As allocations are backed out, the corresponding inventory is now available for order fulfillment again. At the point of Cancel, Client personnel can move the canceled shipments onto another wave or move them completely back to the Pool.

El proceso de cancelación retrocede la asignación y elimina las instrucciones de trabajo y los contenedores de envío. A medida que se retiran las asignaciones, el inventario correspondiente ahora está disponible para el cumplimiento de pedidos nuevamente. En el momento de Cancelar, el personal del Cliente puede mover los envíos cancelados a otra ola o moverlos completamente de vuelta a la bandeja de pedidos.




Figure 25 - Return canceled shipments to the pool or another wave / Devolver envíos cancelados al pool u otra ola

11.2 Release Wave / Liberación de Ola

If the results of the wave are satisfactory, Grupo Julio's personnel release the wave. The Release action performs multiple operations:

- Releases the generated work to the warehouse floor (if applicable) by removing the Hold Code from the work units – this allows the work to now be eligible for picking
- Prints Wave Documents and labels as applicable (Pallet/Case Picks, Break Label)

Si los resultados de la ola son satisfactorios, el personal de Grupo Julio libera la ola. La acción Liberar realiza varias operaciones:

- Libera el trabajo generado en el piso del almacén (si corresponde) eliminando el código de retención de las unidades de trabajo, lo que permite que el trabajo ahora sea elegible para el surtido de pedidos
- Imprime documentos y etiquetas de ola según corresponda (Pallet/surtido de cajas, etiqueta de surtido)




Figure 26 - Release a wave / Liberar una ola

11.3 Hold Codes / Códigos de Bloqueo

Hold Codes allow work to be temporarily placed on hold so that no further processing can be done against it. Work created through a wave initially has a Hold Code of *Wave Not Released*. When a wave is released, the Hold Code is removed.

Note: Hold Codes can also be manually removed or added through the Hold option from the **Work Insight**.

Los códigos de bloqueo permiten que el trabajo se ponga temporalmente en espera para que no se pueda realizar ningún procesamiento adicional. El trabajo creado a través de una ola inicialmente tiene un código de retención de *ola no liberada*. Cuando se libera una ola, se elimina el código de bloqueo.

Nota: Los códigos de bloqueo también se pueden eliminar o agregar manualmente a través de la opción Bloquear de **Visor de Trabajos**.

11.4 Print Wave Documents or Labels / Imprimir documentos o etiquetas de Ola
Releasing a wave prints the Wave Documents. This is the normal process Grupo Julio uses to print these documents. If for some reason the Wave Documents ever need to be reprinted at a later point in time, this is always possible by choosing the Reprint Wave Documents option from the **Wave Insight**.

Al soltar una ola se imprimen los documentos de ola. Este es el proceso normal que Grupo Julio utiliza para imprimir estos documentos. Si por alguna razón los documentos de ola alguna vez necesitan ser reimpresos en un momento posterior, esto siempre es posible eligiendo la opción Reimprimir documentos de ola en **Visor de Ola**.




Figure 27 - Reprint wave labels / Reimpresión de etiquetas de onda

11.5 Post Wave Shipment Changes / Cambios en el envío posterior a la ola
If a change is required for an order that has been waved and released (but not picked), the shipment can be canceled by choosing the Cancel option from the **Shipment Insight**. Canceling a shipment de-allocates the inventory for the order, deletes the created shipping

containers and work, and moves the shipment back into the pool. Once an order is partially or completely picked, it can be canceled by the same previous process, but any items that were picked would need to be transferred back to an inventory location using the **Inventory Management** option.

Si se requiere un cambio para un pedido que ha sido rechazado y liberado (pero no surtido), el envío se puede cancelar eligiendo la opción Cancelar de la Información de **envío**. Al cancelar un envío, se desasigna el inventario para el pedido, se eliminan los contenedores de envío y el trabajo creados y se vuelve a mover el envío al grupo de pedidos. Una vez que un pedido se surte parcial o completamente, puede ser cancelado por el mismo proceso anterior, pero cualquier artículo que se haya surtido deberá transferirse de nuevo a una ubicación de inventario utilizando la opción **Gestión de inventario**.

Note: If an order is canceled it cancels all the shipping work tied to the order. Replenishment work will not be canceled (Replenishment work can be manually canceled). Also, while we cancel an order, if any work related to the order is being actively executed by pickers, then order cancellation fails. Canceling of the shipment after the wave is released can only be performed by a warehouse user. After the wave has been released, the Host will not be able to cancel the order (The only time the Host system can make a change is when a shipment is in 'In Pool' status).

Nota: Si se cancela un pedido, se cancelan todos los trabajos de envío vinculados al pedido. El trabajo de reabastecimiento no se cancelará (el trabajo de reabasto se puede cancelar manualmente). Además, mientras cancelamos un pedido, si algún trabajo relacionado con el pedido está siendo ejecutado activamente por los surtidores, entonces la cancelación del pedido falla. La cancelación del envío después de que se libere la ola solo puede ser realizada por un usuario del almacén. Después de que se haya liberado la ola, el ERP no podrá cancelar el pedido (la única vez que el sistema ERP puede realizar un cambio es cuando un envío está en estado 'En grupo').

12.0 WORK MANAGEMENT / GESTION DE TRABAJOS

12.1 Work Viewing / Visualización de Trabajos

Using the fixed station **Work Insight** or **Work Monitoring**, personnel can monitor the progress of work. The **Work Insight** contains views grouping work by condition: Open, In Progress, and Closed. Additionally, this option enables personnel to view the types of work that are open and in progress to determine if additional users are needed to help with receipt putaway, replenishment, or picking work. Personnel can inquire about the specifics of the work unit, such as the 'from' and 'to' location, item(s) and quantity being moved, receipt/shipment id, the user performing the work, etc.

Utilizando la estación fija **Visor de Trabajos** o **Monitoreo de Trabajos**, el personal puede monitorear el progreso del trabajo. **Visor de Trabajos** contiene vistas que agrupan el trabajo por condición: Abierto, En curso y Cerrado. Además, esta opción permite al personal ver los tipos de trabajo que están abiertos y en curso para determinar si se

necesitan usuarios adicionales para ayudar con el trabajo de recepción, reabastecimiento o surtido. El personal puede filtrar sobre los detalles de la unidad de trabajo, como la ubicación "desde" y "hasta", el artículo (s) y la cantidad que se mueve, la identificación de recibo / envío, el usuario que realiza el trabajo, etc.




Figure 28 - Work Insight / Visor de trabajo




Figure 29 - Work Monitoring Group / Grupo de Monitoreo de Trabajo

12.2 Work Priority / Prioridad de trabajo

SCALE allows system directed tasks to be assigned in one of three ways:

- Priority/Location/FIFO
- Location/Priority/FIFO
- FIFO

SCALE permite que las tareas dirigidas al sistema se asignen de una de estas tres maneras:

- Prioridad/Ubicación/FIFO
- Ubicación/Prioridad/FIFO
- FIFO

The above defines the sort order that system-directed tasks will be assigned to users within the warehouse. Within this structure, the “priority” portion from above can be critical. Most tasks will need to be created with the same priority so that they are truly processed by location proximity in ascending order. However, over time Grupo Julio may want to bump up the priority of certain tasks. This is possible via the Work Priority Escalation Criteria configuration. From this configuration, Grupo Julio can define what types of work should be bumped up. This can then be used in conjunction with an interval that is defined by a scheduled job for the work priority

Lo anterior define el orden de clasificación que las tareas dirigidas por el sistema se asignarán a los usuarios dentro del almacén. Dentro de esta estructura, la parte de “prioridad” puede ser crítica. La mayoría de las tareas deberán crearse con la misma prioridad para que se procesen realmente por proximidad de ubicación en orden ascendente. Sin embargo, con el tiempo, Grupo Julio puede querer aumentar la prioridad de ciertas tareas. Esto es posible a través de la configuración de criterios de escalamiento de prioridad de trabajo. A partir de esta configuración, Grupo Julio puede definir qué tipos de trabajo deben aumentarse. Esto se puede utilizar junto con un intervalo definido por un trabajo programado para la prioridad de trabajo.

13.0 PICKING / RECOLECCIÓN

Grupo Julio has a few different work types used for picking inventory to shipping out. The different flows are based on the main 3 item families they have: *Calzado* (Footwear), *Colgado* (Hanging) and *Doblado* (Folded).

Grupo Julio tiene algunos diferentes tipos de trabajo utilizados para surtir inventario para envíos. Los diferentes flujos son basados en las 3 principales familias de artículos que ellos tienen: *Calzado*, *Colgado* y *Doblado*.

13.1 *Calzado* (Footwear)

In this flow, the shipping containers are created during the wave and the works are created using the Container ID as the Work Unit. The Work Creation Master has maximum configurations for number of instructions, weight and volume. Shipping labels will be printed to be used by the users to start the work.

En este flujo, los contenedores de envío son creados durante la ola y los trabajos son creados utilizando el Container ID como la unidad de trabajo. El Work Creation Master tiene configuraciones de máximo de instrucciones, peso y volumen. Se imprimen etiquetas de envío que los usuarios van a utilizar para empezar los trabajos.

The user will enter into the Work Execution option in the Warehouse Mobile screen, select the *Surtido Calzado* work profile and scan the Work Unit. This work profile is configured for Cart Picking, so user can scan 1 or more Work Unit. Once the work units are scanned, user will select 'Begin picks' to effectively start picking the items. After confirming each picking, SCALE will tell the user which spot to be used. Once all the picks are completed, user will perform the putaway to the EMPAQUE-01 location, which is the packing station.

El usuario va a ingresar en la opción Work Execution de la pantalla de Warehouse Mobile, seleccionar el perfil Surtido Calzado y leer la unidad de trabajo. Este perfil está configurado para Cart Picking, entonces el usuario puede escanear 1 o más unidades de trabajo. Una vez que las unidades fueran escaneadas, el usuario va a seleccionar 'Begin picks' para efectivamente empezar a surtir. Después de confirmar cada surtido, SCALE va a indicar al usuario qué Spot utilizar. Una vez que se haga todo el surtido, el usuario va a hacer el putaway a la ubicación EMPAQUE-01, que es la estación de empaque.

While the user is picking, if there is not enough inventory in the location that the user is prompted to pick from, user can perform a *short pick*. User needs permission to perform a short pick. If the picker has permission to short pick, picker will adjust the quantity and then click on the short button. SCALE will ask for a short reason and user must select the reason from the drop down. If picker doesn't have permission to short pick, the picker presses the '*Pass*' button to back out of the work unit (to leave it suspended) and contacts a supervisor. The supervisor intervenes and determines how to handle the out-of-stock situation.

Mientras el usuario está surtiendo, si no hay suficiente inventario en la ubicación que se le pide que elija, el usuario puede realizar una *selección corta*. El usuario necesita permiso para realizar una selección corta. Si el surtidor tiene permiso para selección corta, el surtidor ajustará la cantidad y luego hará clic en el botón corto. SCALE le pedirá una breve razón y el usuario debe seleccionar la razón en el menú desplegable. Si el surtidor no tiene permiso para surtido corto, el surtidor presiona el botón '*Pass*' para retroceder fuera de la unidad de trabajo (para dejarla suspendida) y se comunica con un supervisor. El supervisor interviene y determina cómo manejar la situación de falta de stock.

Config note: *Short Pick* option is controlled using security and Grupo Julio can decide which pickers will have access to *Short Pick* option.

Nota de configuración: La opción Selección corta se controla mediante seguridad y Grupo Julio puede decidir qué Operadores tendrán acceso a la opción *Selección corta*.

13.2 Colgado (Hanging)

This process has an integration (**EX01**) with a Put to Light (PTL) system. During the wave the work is created using the 'Shipment Allocation Work' creation master process. The work creation master has a maximum number of instructions per work unit. The work unit will also be broken based on the USER_DEF3 of the Shipment Alloc Request table. The work instruction will have a P&D location (DROP-COLGADO) configured.

Este proceso tiene una integración (**EX01**) con un sistema Put to Light (PTL). Durante la ola, el trabajo se crea utilizando el proceso maestro de creación para 'Shipment Allocation Work'. El Work Creation Master tiene un número máximo de instrucciones por unidad de trabajo. La unidad de trabajo también se dividirá en función del USER_DEF3 de la tabla Shipment Alloc Request. La instrucción de trabajo tendrá una ubicación de P&D (DROP-COLGADO) configurada.

To perform picking, the user will enter into Work Execution in Warehouse Mobile and select *Surtido de Colgado TA*. The user will enter a Work Unit and start picking. Once the picking is done, the user will putaway to the P&D location (DROP-COLGADO).

Para realizar el picking, el usuario ingresará a Work Execution en Warehouse Mobile y seleccionará *Surtido de Colgado TA*. El usuario ingresará una Unidad de trabajo y comenzará a realizar el picking. Una vez realizado el picking, el usuario va a hacer el putaway en la ubicación de P&D (DROP-COLGADO).

From the P&D location, another user will enter into a custom menu (**EX01**) in Warehouse Mobile (*Sorter Colgado*) and scan an item available in there. This custom screen will ask the user to confirm the sorting process on the PTL. The user will then follow the indications on the PTL system, hanging the number of units of that particular item into the hangers that have the indicating light. Once the user performs this, they will press the confirmation button on the PTL, which will then send information to SCALE to confirm both the picking from the P&D and the putaway to the EMPAQUE-01 location.

Desde la ubicación de P&D, otro usuario ingresará a un menú personalizado (**EX01**) en Warehouse Mobile (*Sorter Colgado*) y escaneará un artículo disponible allí. Esta pantalla personalizada le solicitará al usuario que confirme el proceso de clasificación en el PTL. El usuario seguirá las indicaciones del sistema PTL, colgando la cantidad de unidades de ese artículo en particular en las perchas que tienen la luz indicadora. Una vez que el usuario realiza esto, presionará el botón de confirmación en el PTL, que luego enviará información a SCALE para confirmar tanto la selección del P&D como el almacenamiento en la ubicación EMPAQUE-01.

The above is just a high-level description of the *Colgado* process. The process will be fully described in the **EX01** document.

Lo anterior es solo una descripción de alto nivel del proceso de Colgado. El proceso se describirá en detalle en el documento **EX01**.

13.3 *Doblado* (Folded)

This process will be similar to the *Colgado* process. The wave will use the Shipment Allocation Work to create the work, users will pick the items from the reserve location and putaway to a P&D location. From there another user will start the sorting process, using a custom screen that will perform the communication with the PTL system. The fully detailed process will be described in the EX01 document.

Este proceso será similar al proceso de Colgado. La ola utilizará el Shipment Allocation Work para crear el trabajo, los usuarios van a surtir los artículos de la ubicación de reserva y hacer el putaway en una ubicación de P&D. Desde allí, otro usuario iniciará el proceso de sorting, utilizando una pantalla personalizada que realizará la comunicación con el sistema PTL. El proceso completamente detallado se describirá en el documento **EX01**.

13.4 Task Interleaving / Tareas Cicladas
Grupo Julio will not leverage the task interleaving.

Grupo Julio no va a utilizar tareas cicladas.

14.0 PACKING / EMPAQUE

14.1 Value Added Service (VAS) / Servicio de Valor Agregado (VAS)
Grupo Julio currently does not use VAS, although they have some additional services executed for some clients (Liverpool, Privalia) that could take advantage of this feature.

Grupo Julio actualmente no utiliza VAS, aun que ellos ejecuten servicios adicionales para algunos clientes (Liverpool, Privalia) que podrían tener beneficios por el uso de esta funcionalidad.

14.2 QC Confirmation / Confirmación de control de calidad
Grupo Julio currently does not leverage Outbound QC.

Grupo Julio actualmente no utiliza Control de Calidad para Salidas.

14.3 Close Container / Cierre de Contenedor
Close container action/transaction identifies that the container is packed (sealed), and no other item can be put into it. This also advances the status of the container (and shipment) as per the status flow and determines the next action on the staging/dock area.

La acción/transacción de cerrar contenedor identifica que el contenedor está empaquetado (sellado) y que no se puede colocar ningún otro artículo en él. Esto también avanza el estado del contenedor (y el envío) según el estatus de flujo y determina la siguiente acción en el área de preparación / andén.

The screenshot shows the 'Close container' screen with the following fields:

- Container id:** 00004000000000000046
- Weight:** (empty field)
- Container info:** (empty section)
- User defined:** (empty section)

Figure 30 - Close Container Screen – initiation

The screenshot shows the 'Close container' screen with the following populated fields:

- Container id:** 00004000000000000046
- Weight:** 0.07
- Container info:**
 - Container count:** 1
 - Total containers:** 1
 - Carrier:** UPS
 - Carrier service:** Ground
 - Container type:** Medium
 - Length:** 0.609
 - Width:** 0.609
 - Height:** 0.3045
 - NMFC code:** (empty field)
 - Tracking number:** (empty field)
- User defined:** (empty section)

Figure 31 - Close Container – Container details populated

Config note: Grupo Julio would like to prevent printing some shipping labels, depending on the flow used. This would be achieved using **Document Routing** and configuring the necessary document types to not get printed at the packing stations. Grupo Julio may also use **Workstation** configurations in order to achieve that.

Nota de configuración: Grupo Julio no gustaría de imprimir algunas etiquetas, a depender del tipo de flujo utilizado. Esto se puede alcanzar utilizando el **Document Routing** y configurando el tipo de documento para que no se imprima en la estación de

empaque. Grupo Julio podrá también utilizar la configuración de **Workstation** para alcanzar esto.

14.4 Shipping Container Insight / Visor de Contenedores de Envío

If necessary, the **Shipping Container Insight** can be used to modify the contents of the Shipping Container. The user can change the Container Type, add or remove contents, and create new containers if necessary. The user can update the quantity to pack to 0 for any items needing to be unpacked from a container. Once unpacked, the user can repack into new containers using the Packing screen.

Si es necesario, el **Visor de Contenedores de Envío** se puede utilizar para modificar el contenido del contenedor de envío. El usuario puede cambiar el tipo de contenedor, agregar o quitar contenido y crear nuevos contenedores si es necesario. El usuario puede actualizar la cantidad a empaquetar a 0 para cualquier artículo que necesite ser desembalado de un contenedor. Una vez desembalado, el usuario puede volver a empaquetar en nuevos contenedores utilizando la pantalla Empaque.

If user doesn't have Container ID to Scan but still must perform the close container or QC process, then they can use **Shipping Container Insight** and filter based on the Shipment ID. From the Container insight, user can select the Container ID and then use the *Close Action* to close the container or *Confirm QC* action to perform the QC.

Si el usuario no tiene ID de contenedor para escanear, pero aún debe realizar el proceso de cierre de contenedor o control de calidad, puede usar **Visor de Contenedor de Envío** y filtrar según el ID de envío. Desde la información del contenedor, el usuario puede seleccionar el Container ID y, a continuación, utilizar la *acción Cerrar* para cerrar el contenedor o *Confirmar acción* de control de calidad para realizar el control de calidad.

Shipping container insight

Basic criteria

Container id

Shipment id

Item

Current location

Status

Container type

QC

Warehouse

CD7

Wave number

Internal shipment number

Shipping load

Show only top level

On

Show only manifested

Off

Include closed

Off

Manifest criteria

Advanced criteria

Loads 209

Shipments 399

Containers 3.3k

Locations 1

select columns

Container id	Shipment id	Tracking number	Container type	Status	Item
☒ 00077047890007155192	EXPECUADOR-001		*Default	Load Confirm Pending	
☐ 00077047890007155208	EXPECUADOR-001		*Default	Load Confirm Pending	
☐ 00077047890007130632	EXP-001346+01074844		CAJA M	Load Confirm Pending	
☐ 00077047890007147715	VC-023085858+01086294		30A	Load Confirm Pending	
☐ 00077047890007155116	VC-023097999+01089214		*Default	Staging Pending	
☐ 00077047890007155123	VC-023097999+01089214		*Default	Staging Pending	
☐ DIEGO0909	VC-023096508+01089033		10A	In Packing	
☐ DIEGO0908	VC-023096508+01089033		26A	In Picking	
☐ 00077047890006479763	VC-020745351+00718162		35A	Load Confirm Pending	
☐ 00077047890006479770	VC-020745351+00718162		35A	Load Confirm Pending	
☐ 00077047890006479787	VC-020745351+00718162		35A	Load Confirm Pending	
☐ 00077047890006479794	VC-020745351+00718162		35A	Load Confirm Pending	
☐ 00077047890006479800	VC-020745351+00718162		35A	Load Confirm Pending	
☐ 00077047890006479831	VC-020745351+00718162		35A	Load Confirm Pending	
☐ 00077047890006479848	VC-020745351+00718162		35A	Load Confirm Pending	
☐ 00077047890006479855	VC-020745351+00718162		35A	Load Confirm Pending	

1 - 100 of 3271 records

0 Containers

3 Container contents

0 Open work

14

Figure 32 - Shipping Container Insight

Loads 209

Shipments 399

Containers 3.3k

Locations 1

select columns

Container id	Shipment id	Tracking number	Container type	Status	Item	Description
☐ 00077047890007155192	EXPECUADOR-001		*Default	Load Confirm Pending		
☐ 00077047890007155208	EXPECUADOR-001		*Default	Load Confirm Pending		
☐ 00077047890007130632	EXP-001346+01074844		CAJA M	Load Confirm Pending		
☐ 00077047890007147715	VC-023085858+01086294		30A	Load Confirm Pending		
☐ 00077047890007155116	VC-023097999+01089214		*Default	Staging Pending		
☐ 00077047890007155123	VC-023097999+01089214		*Default	Staging Pending		
☒ DIEGO0909	VC-023096508+01089033		10A	In Packing		
☐ DIEGO0908	VC-023096508+01089033		26A	In Picking		
☐ 00077047890006479763	VC-020745351+00718162		35A	Load Confirm Pending		
☐ 00077047890006479770	VC-020745351+00718162		35A	Load Confirm Pending		
☐ 00077047890006479787	VC-020745351+00718162		35A	Load Confirm Pending		
☐ 00077047890006479794	VC-020745351+00718162		35A	Load Confirm Pending		
☐ 00077047890006479800	VC-020745351+00718162		35A	Load Confirm Pending		
☐ 00077047890006479831	VC-020745351+00718162		35A	Load Confirm Pending		
☐ 00077047890006479848	VC-020745351+00718162		35A	Load Confirm Pending		

Edit

Delete

Edit accessories

Close

Confirm QC

Dock transfer

Manifest

Mark for QC

Nest

Print preview

Print default docs

Print selected docs

Remove from manifest

Remove from nesting

Transfer

Update packed quantity

VAS activity

Open work

Figure 33 - Shipping Container Insight with Close Container Option

Note: To edit container contents, a container must be in a location with a subclass of Packing.

Nota: Para editar el contenido del contenedor, un contenedor debe estar en una ubicación con una subclase de Empaque.

14.5 Hospital Packing Area / Área de Recuperación de Empaque

If necessary, packing exceptions are handled at a physically different pack station than the one used for standard packing process. This is done to eliminate bottleneck in the packing process that could be added due to the analysis and resolutions needed for these problematic picks or packing scenarios.

Si es necesario, las excepciones de Empaque se manejan en una estación de empaque físicamente diferente a la utilizada para el proceso de empaque estándar. Esto se hace para eliminar el cuello de botella en el proceso de empaque que podría agregarse debido al análisis y las resoluciones necesarias para estas recolecciones problemáticas o escenarios de empaque.

Grupo Julio may leverage a manual SOP of updating a shipping container user defined field as 'HOS' indicating that a container is physically at the hospital pack station. Since SCALE tracks one pack location per warehouse, this SOP will provide visibility into which pack station the container is at.

Grupo Julio puede aprovechar un SOP manual de actualización de un campo definido por el usuario del contenedor de envío como 'HOS' que indica que un contenedor está físicamente en la estación de empaque de recuperación. Dado que SCALE rastrea la ubicación de un paquete por almacén, este SOP proporcionará visibilidad en qué estación de empaque se encuentra el contenedor.

Shipping Container Insight screen is used as listed above to modify the contents of the container.

La pantalla **Visor de Contenedor de Envío** se utiliza como se indica anteriormente para modificar el contenido del contenedor.

14.6 Carrier changes / Cambio de transportista

In case it is necessary to change a carrier, Grupo Julio may perform this using the Shipment Insight screen.

En caso de que sea necesario hacer un cambio de transportista, Grupo Julio puede hacerlo utilizando la pantalla de Envío.

Figure 34 - Shipment Insight – Change Carrier in Shipment Before Adding to wave

To change an LTL carrier before loading into truck, the user will use the **Shipment Insight** screen and utilize the *Transfer Shipment* option to change the carrier.

Para cambiar un transportista LTL antes de cargarlo en el camión, el usuario utilizará la pantalla **Visor de Envíos** y utilizará la opción *Transferir Envío* para cambiar el transportista.

When *Transfer Shipment* option is selected, user will be presented with an option to provide the destination load. If the user knows the load number, then they can enter the shipping load number and SCALE will transfer the shipment to that load.

Cuando se selecciona la opción *Transferir envío*, al usuario se le presentará una opción para proporcionar la carga de destino. Si el usuario conoce el número de carga, puede ingresar el número de carga de envío y SCALE transferirá el envío a esa carga.

If the load is not known, then user can select to create a new load and select the carrier for the new load. SCALE will create new load and then transfer the shipment to new load.

Si no se conoce la carga, el usuario puede seleccionar crear una nueva carga y seleccionar el transportista para la nueva carga. SCALE creará una nueva carga y luego transferirá el envío a una nueva carga.




Figure 35 - Shipment Insight – Transfer Shipment Option

The screenshot shows the 'Transfer shipment' form. The title bar includes 'Transfer shipment' and 'PTR_004055805+01086776'. The form is divided into sections: 'Destination load' with a 'Shipping load number' input field; 'Shipment' with fields for 'Shipment id' (PTR_004055805+01086776), 'Warehouse' (CD7), 'Carrier' (COORDINADORA), 'Carrier service' (03-TIENDAS BOGOTÁ), 'Leading status' (Ship Confirm Pending), and 'Trailing status' (Ship Confirm Pending); and 'Load'.

Figure 36 - Transfer Shipment Option – Enter Destination Load Number

Figure 37 - Transfer Shipment Option – Create a new Load

14.7 Packing Exceptions / Excepciones de Empaque

A hospital pack station will be leveraged for exception handling. Grupo Julio will have manual SOPs to handle any packing exception in SCALE.

Se aprovechará una estación de empaque de recuperación para el manejo de excepciones. Grupo Julio tendrá SOP manuales para manejar cualquier excepción de empaque en SCALE.

15.0 DOCK MANAGEMENT / GESTION DE MUELLES (ANDÉNES)

Dock management represents several processes, all of which concern tracking shipments after they have arrived in the shipping dock area of the warehouse. These processes include the consolidation of items/containers at the packing area location, the placing of containers on the shipping dock at staging locations, and the loading of containers onto the truck, referred to in the system as dock door locations.

La gestión del muelle representa varios procesos, todos los cuales se refieren al seguimiento de los envíos después de que hayan llegado al área del muelle de envío del almacén. Estos procesos incluyen la consolidación de artículos / contenedores en la ubicación del área de empaque, la colocación de contenedores en el muelle de envío en lugares de preparación y la carga de contenedores en el camión, denominados en el sistema ubicaciones de puertas de andén.

These different types of dock locations are specific inventory-tracked areas on or near the shipping dock where a shipment's containers can be assigned to. Each dock management

process can be independently switched on/off, thereby allowing a warehouse to use any or all this functionality.

Estos diferentes tipos de ubicaciones de andén son áreas específicas rastreadas por inventario en o cerca del andén de envío donde se pueden asignar los contenedores de un envío. Cada proceso de gestión de andenes se puede encender / apagar de forma independiente, lo que permite que un almacén utilice cualquiera o todas estas funcionalidades.

Dock management will be used at Grupo Julio for all orders. Grupo Julio does not have defined dock doors for either type of orders.

La gestión del andén se utilizará en Grupo Julio para todos los pedidos. Grupo Julio no tiene puertas de andén definidas para ninguno de los dos tipos de pedidos.

The general outbound flow for Grupo Julio is to move the inventory to the Packing location, from there create next move to transfer the inventory to a Stage location and from there create the next move of the containers to the Shipping Dock locations.

El flujo general de salida de Grupo Julio es mover el inventario hacia la ubicación de Empaque, desde ahí crear el próximo movimiento para transferir para una ubicación de Stage y desde ahí crear el próximo movimiento de los contenedores para los muelles de salida.

The following dock management flow shows the base configuration in use by Grupo Julio. More dock management flows can be created to accommodate future requirements.

El siguiente flujos de gestión del muelle tiene la configuración base en uso por Grupo Julio. Se puede crear configuraciones adicionales en caso de requerimientos futuros.

Status	Location Subclass	Default Loc	Create Next Move
In Packing	Packing	EMPAQUE-01	No
Staging Pending	Packing	EMPAQUE-01	YES
Loading Pending	Staging	STG-001	YES
Ship Confirm Pending	Dock Door	EMBDock-01	NO

15.1 Dock Door Assignment / asignación de puerta de muelle (Andén)

Shipping loads are created using the load building wave step. When the carrier shows at the warehouse, the shipping supervisor instructs the driver to go to a specific dock door. In SCALE the user will go to shipping load insight screen and search for the shipping load and will edit the shipping load to assign a dock door. Once the dock door is assigned, SCALE will generate the loading work as indicated in the Dock Management Flow configuration.

Las cargas de envío se crean utilizando el paso de ola de construcción de carga. Cuando el transportista se presenta en el almacén, el supervisor de envío le indica al conductor que vaya a una puerta de andén específica. En SCALE, el usuario irá a la pantalla de información de carga de envío y buscará la carga de envío y editará la carga de envío para asignar una puerta de andén. Una vez asignada la puerta del andén, SCALE generará el trabajo de carga como se indica en la configuración del flujo de gestión del muelle.

Another option used by Grupo Julio is to transfer the shipment into another load and assign a different Shipping Dock Door to this new load.

Otra opción utilizada por Grupo Julio sería transferir el envío a otra carga y asignar un nuevo muelle de salida a esta nueva carga.

Config Note: The option 'Create dock work on assigning load to dock door' in Shipping Preference must be checked.

Nota de configuración: La opción 'Crear trabajo de andén para asignar carga a la puerta del andén' en Preferencia de envío debe estar marcada.




Figure 38 - Shipping Load Insight

16.0 LOAD CONFIRMATION / CONFIRMACION DE CARGA


16.1 Processing / Procesamiento

Grupo Julio's personnel may use the **Shipping Load Insight** screen to monitor the status of shipments and loads. Once all shipments for a Load are in *Ship Confirm Pending* status, the Load can be confirmed. To Confirm the Load, a user selects the Load and uses the Confirm Load action in the **Shipping Load Insight** options. This relieves the inventory from the Shipping Dock locations in SCALE. At this point, the shipments are available for upload to the host system the next time the interface job runs. In addition, the shipment can no longer be modified in SCALE.

El personal de Grupo Julio puede usar la pantalla **Visor de Carga** para monitorear el estado de los envíos y cargas. Una vez que todos los envíos de una carga están en estado *Ship Confirm Pending*, la carga se puede confirmar. Para confirmar la carga, un usuario selecciona la carga y utiliza la acción Confirmar carga en las opciones **de Visor de Carga**. Esto alivia el inventario de las ubicaciones del muelle de envío en SCALE. En este punto, los envíos están disponibles para cargarse en el sistema ERP la próxima vez que se ejecute el trabajo de interfaz. Además, el envío ya no se puede modificar en SCALE.

Shipments that are not ready for confirmation will be removed and added to new shipping loads as required by split shipment processing. Since split shipment functionality will be leveraged in the initial Go-live phase, the **Shipping Preferences** is set to prompt and allow split for a status range from Ship Confirmation to Ship Confirmation.

Los envíos que no estén listos para la confirmación se eliminarán y se agregarán a las nuevas cargas de envío según lo requiera el procesamiento de envíos divididos. Dado que la funcionalidad de envío dividido se aprovechará en la fase inicial de puesta en marcha, las **Preferencias** de envío están configuradas para solicitar y permitir la división para un rango de estado desde Confirmación de envío hasta Confirmación de envío.



Icon	Shipping load	Carrier	Pro number	Scheduled ship date	Trailing status	Leading status	Total containers	To
☐	1901195	LIFTIT URBANO		8/4/2023	Packing Pending	Packing Pending	0	0
☐	1901194	TCC CARGA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901193	LYD		8/4/2023	Packing Pending	Packing Pending	0	0
☐	1901190	LYD		8/4/2023	Packing Pending	Packing Pending	0	0
☒	1901192	LYD		8/9/2023	Load Confirm Pending	Load Confirm Pending	3	18.51
☐	1901086	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901084	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901082	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901075	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901073	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901072	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901071	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901067	TCC CARGA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901061	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901060	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0
☐	1901057	COORDINADORA		8/3/2023	Packing Pending	Packing Pending	0	0

Figure 39 - Load confirm using Shipping Load insight

Additionally, personnel may print documents before, or after the load is confirmed using the **Shipping Load Insight** options.

- Packing List (DOC02)

Además, el personal puede imprimir documentos antes o después de que se confirme la carga mediante las opciones **de Visor de Carga**.

- Lista de embalaje **(DOC02)**

Once a load has been confirmed, all statuses (load, shipments, details, containers) are moved to Closed, and inventory is relieved from the Shipping Dock (is officially out of the building). This generates the shipment upload interface files for the Host system.

Una vez que se ha confirmado una carga, todos los estados (carga, envíos, detalles, contenedores) se mueven a Cerrado, y el inventario se libera del muelle de envío (está oficialmente fuera del almacén). Esto genera los archivos de interfaz de carga de envío para el sistema ERP.

IX. INVENTORY CONTROL

17.0 INVENTORY MANAGEMENT

17.1 Adjustments

Inventory adjustments either increase or decrease the on-hand quantity of an item in a location. The adjustment types are configurable and are created to indicate reason codes such as Damaged, Scrap, etc. Each adjustment type can be set up to have minimum and maximum adjustment quantities. Security is maintained to control which users have access to which adjustment types. Adjustment types can be configured to not upload to the Host.

All adjustments are entered in the **Inventory Management** option. This option can be initiated blindly from the main menu or **Warehouse Mobile Inventory Management**. It can also be initiated by selecting a location/item combination in the **Inventory Insight**. The user proceeds by entering the quantity to adjust, where the quantity is specified as a negative value for negative adjustments. After confirming, SCALE adjusts the inventory in the location and creates a history log of the inventory transaction.

Figure 40 - Inventory Adjustment Screen

Note: Inventory cannot be adjusted in the receiving dock location. Only located items can be adjusted using Inventory Management.

Below there is a list of a few Adjustment Types currently in use by Client. This is not the final list, though.

Name	Class	Quantities	Create Work	Interface
Ajuste Inventario Inicial	Adjustment	-50 / +99999999	N	Y

Name	Class	Quantities	Create Work	Interface
Ajuste Conteo Ciclico (+)	Adjustment	0 / +9999999	N	Y
Ajuste por Online (-)	Adjustment	-9999999 / 0	N	Y
Cambio de Estado	Status Change		N	Y
Transferencia a Tda Movil	Transfer	0 / +99999	N	N
Transferencia con Trabajo	Transfer	0 / +99999	Y	N

17.2 Transfers

Inventory transfers move the on-hand quantity of an item from one location to another within the four walls of the warehouse. The transfer types are configurable and are created to indicate reason codes such as Consolidation, Back to Stock, etc. Each transfer type can be set up to have minimum and maximum transfer quantities. Security is maintained to control which users have access to which transfer types.

The Inventory Transfer option is initiated blindly from the main menu or **Warehouse Mobile Inventory Management**. This can also be initiated by selecting a location/item combination in the *Inventory Insight*, in which case the “from location” and item automatically default. In the scenario where Inventory Management is blindly initiated, the user is forced to specify the “from location”, item and quantity being transferred.

As part of inventory transfer, users can also create work. This way a supervisor can decide what inventory needs to be moved and then a picker on the floor will get the work to physically move the product. Inventory transfer with work must be created on the insight screen. The work execution can happen on the RF device.

The screenshot displays the 'Inventory transfer' form with the following fields and values:

- Adjustment type:** Transfer
- License plate:** ASDASDADD
- From location:** 2A002
- To location:** (empty)
- Item:** KEL-JM-001-L
- Description:** Keller JM Item 01 T
- Lot:** 2019T130
- Expiration date:** 11/30/2019
- Quantity:** 0
- Company:** KEL - Johns Manville
- Status:** Available
- U/M:** EA (1)

The 'Transfer' button in the top right corner is highlighted in red.

Figure 41 - Inventory Transfer with work




Figure 42 - Inventory transfer work execution

17.3 Status Change

Inventory is received into SCALE with a default status of Available. However, Client may choose to have different inventory statuses to represent contrasting conditions of inventory such as New, Refurbished, damaged, Held etc. The Warehouse personnel can use an Inventory Status Change to update inventory status. These status change types are configurable, and security is maintained to control which users have access to which status change types.

The **Inventory Management** option can be initiated blindly from the main menu wherein the user specifies the location and item. It can also be initiated by selecting a location/item combination in the **Inventory Insight**, in which case the location and item automatically default. The user then specifies the new inventory status. At confirmation, SCALE updates the inventory status for the item and location combination. SCALE also creates a history log of the inventory transaction.

Note: Single location cannot hold the same item with a quantity in status Available and another quantity in status Damaged if the location is not License plate tracked or if it does not have different inventory attributes.

18.0 CYCLE COUNT

18.1 Generating Cycle Counts

18.1.1 Plan Based Cycle Counting

SCALE utilizes *Cycle Count* Plans for everyday cycle counting. Client personnel define the Cycle Count Plans in the **Cycle Count Plan Insight**. A Cycle Count Plan is used to define a range of items and/or locations for which to generate cycle count work. For an example of location criteria, Client can exclude a location that was counted within the last 30 days. For an example of item criteria, Client can use the Item categories (Client Code, etc.). Once the plan has been created, SCALE creates work to count a specified number of locations within the criteria of the Cycle Count Plan. Each location determined for cycle count is generated as a separate work unit in SCALE.

Some Plan based counts that Client may use are:

- All locations counted every twelve months. (Not a single cycle count master for the entire DC, rather multiple ensuring all locations are covered)
- Zone Counting
 - Picking
 - Reserve
- Movement Class (A, B and C)
 - Primary Focus on A, B and C Movement Classes
 - A movement items will be counted 3 times a year
 - B movement items will be counted 2 times a year
 - Class C based on Client's decision.
- Count for Empty Locations

Plans	Requests	Reviewed	Open	Closed
1	1	0	1	0

Plan	Master name	Created date	Completed date	Open	Closed	Errors	Released
29	A-1-1-C-2	3/2/2021 1:22:09 PM		1	0	0	☒

1	Requests
0	Transactions
1	Open work

Figure 43 - Cycle Count Plan Insight

18.1.2 Activity Based Cycle Counting

Activity-based cycle counting is the concept of triggering the generation of a cycle count request after a warehouse activity (i.e., Short Picking). The triggering of these requests is tied to the location being processed. After the transaction is executed, the location is reviewed to see if cycle count work should be generated.

SCALE can create activity-based cycle count work for a location for the following instances:

- Short picking inventory during pick work execution
- Driving the inventory for a location below a certain threshold, for example, 0 quantity (empty)

Figure 44 - Cycle Count Threshold config window

18.2 Executing Cycle Counts

18.2.1 Work Execution

For Client the cycle count execution is set to *Standard* count for active and reserve locations. To confirm the cycle count, users sign onto a warehouse mobile device, chooses the *Work* option, and then specify the *Cycle Count Work Profile*. The user is then prompted to scan a location for SCALE to assign a Work Unit in closest proximity. Work can also be user-directed, if the user knows exactly which locations need to be counted. If User directed, then the user needs to scan the location that they intend to count. Once done, SCALE assigns the work to the user and shows the location to be counted on the work execution screen and the item present in that location. User then must specify the quantity present in the location.




Figure 45 - Cycle Count Work execution

Config Note: Cycle Count Preferences are set up to “Verify Bad Count”.

Config Note: The current cycle count preferences allow users to automatically perform reconcile on bad counts to the tolerance 9999. This should be reviewed with operational and inventory teams, as usually only supervisors can perform these adjustments by their own.

If the quantity entered by the user is the same as the system quantity, then the system accepts that quantity and displays the cycle count screen where the user can count other items in the location (Multi-item location). If the location is a single item, then the user needs to click on the Done to indicate the cycle count work execution is complete. If no discrepancy in count the cycle count request is updated to close.

If the quantity entered by the user for the first time doesn't match the system quantity, SCALE displays verify count screen and ask the user to confirm the quantity again. If the user enters verify count, they need to enter two consecutive counts of the same value to complete the count.

Upon entering the information, if there is a discrepancy in the count then SCALE determines whether to post the inventory adjustment or update the cycle count request to status Pending Review. For Client the Cycle Count Tolerances will be set to 0 (all discrepancies must be reconciled). So, SCALE updates the cycle count

request to pending review, and reconciliation needs to be completed for cycle count request to be updated to closed status.

18.2.2 Cycle Count Reconciliations

For cycle count transactions that fall outside of a user's tolerance, SCALE updates the status of the Cycle Count work to Pending Review.

To reconcile a cycle count, a supervisor uses *Reconcile* option from the **Cycle Count Request Insight** screen.

From the **Cycle Count Request Insight**, the supervisor selects the appropriate cycle count in the status Pending Review. On each of the counts requiring review, the supervisor uses the Reconcile action to complete the cycle count adjustment. Once in the reconcile screen, the supervisor enters the correct On-Hand quantity for the specific item in the location.




Figure 46 - Cycle Count Reconcile using Insight screen

Cycle count reconciliation

51

Reconcile quantity

Set on hand quantity to: UM: EA (1)

Count number: 51 Plan number: 29

Item info

Item: 75091-001-05

Company:

Description: ELEANOR PHONE CARD POCKET

Lot: Location: A-1-1-C-2

License plate: Warehouse: TB_UKDC

Inventory attributes:

Figure 47 - Cycle Count Reconciliation insight screen

The supervisor confirms the on-hand quantity, and then SCALE updates the inventory in the location, records an inventory transaction, and closes the cycle count request.

Cycle Count reconciliation can also be performed using the warehouse mobile option.

Warehouse Mobile

- Assign printer
- Close container
- Close putaway group
- Cycle count reconciliation**
- Immediate dock transfer
- Inventory management
- Location inquiry
- Receiving
- Remove cart container
- Work execution
- Shipping container nesting

Figure 48 - Cycle Count Reconciliation insight screen




Figure 49 - Cycle Count Reconciliation insight screen

19.0 REPLENISHMENT

Replenishment is setup using Replenishment Master records. A replenishment master record helps define how a replenishment request is generated. It specifies the parameters for replenishing product based on either location need or demand generated for a wave/order pool. The sequence records for a replenishment rule can be edited. Each sequence rule identifies how the system will perform replenishment (strategy).

Config Note: Grupo Julio does not use replenishment in their operation.

20.0 WORK ORDERS

Work orders manage how a finished item will be assembled. All work order related information, such as components and instructions, can be stored on a bill of material record or manually entered when the work order is created.

Config Note: Grupo Julio does not use Bill of Materials in their operation.

X. LABOR MANAGEMENT

Client uses Labor Management to track user productivity throughout the warehouse. The system generates this labor data when a worker performs one of many warehouse actions, such as work execution (both full-screen and Warehouse Mobile), packing, and receiving. Labor management can provide with such information as “how efficient is this employee at picking Eaches?” or “how many containers can this employee pick an hour. It also provides how well the labor plan measures up to what was expected. This data can be used to plan the warehouse operations.

21.0 KEY FEATURES

Following key features of labor management functionality are available:

21.1 Using Labor Management Data

The system includes few options to view labor data on both individuals and teams: Labor Activity Insight, Labor Monitoring, and an optional Operational SCI component. Manual Labor Entry Screen can be used to manually enter labor data records that are not “tracked” by the application in typical warehouse processing. For example, custodial staff may log their time used in cleaning the warehouse, labeling this time with a custom work type used only for these types of tasks.

21.2 Generating Labor Management Data Records

When an employee executes a warehouse action (such as confirming a work instruction), the system generates a request record. This request is processed by the Labor Management service (which runs continuously, looking for labor requests). A labor management detail record then is generated by this service to represent the action that the user performed. These detail records can be viewed either in the Labor Activity Insight or on a report

21.3 Labor Groups

A labor group represents a collection of warehouse users that perform related work duties, such as picking products for a certain company’s shipments. The labor group records in SCALE define such employee information as to how many people (full time and temporary) who work at the warehouse, as well as what quantity units of measure they typically process.

Labor Group - Edit Existing

File Actions Help

Labor Group: Batch case pick Labor

Description: Batch case pick Labor

Resources Estimation Planning & Monitoring User Defined Data

Estimated Time Per Transaction (in minutes): 0.75

Calculate Time Based On

☐ Unit of Measure ☒ Quantity

Quantity Units of Measure

☐ Select All

☒ Case
☐ Each
☐ Inner Pack
☐ Pallet

Figure 50 - Labor Group

21.4 Labor Plans

Labor plans identify how the system will calculate the estimated labor data during the run wave process. An actual plan is a record that determines which labor group(s) to calculate values for in the wave, and in what sequence order to process them. Note that the labor plan execution wave step must be a part of the flow to use this value. Reports can be developed to view this data.

Labor Plan - Edit Existing

File Actions View Help

Labor Plan: PTS Plan

Description: PTS Plan

Detail Records User Defined Data

Sequence Number	Labor Group
10	PTS Labor

☐ Inactive

OK Cancel Apply

Figure 51 - Labor Plan

The system uses the Shipment Labor planning criteria record to determine what shipment(s) the labor plan execution wave step will process when calculating estimated

labor data for a certain labor group. It is associated with a labor group record. For example, suppose labor group needs to process only shipments that contain items from a certain work zone, a shipment labor planning criteria record is created that has a rule defined that indicates that any shipment line(s) that contain items that originate from a specific work zone should be processed by this group.

The screenshot shows a software window titled "Shipment Labor Planning Criteria - Edit Existing". It has a menu bar with "File", "Actions", and "Help". The main area contains several input fields: "Record Type" with value "SHPLABPLNCRT", "Filter Name" with value "MTL", "Description" with value "MTL", and "Table Name" with a dropdown menu showing "Shipment Detail". Below these is a "Filter data" section with a "Filter Criteria" tab. Inside this tab, there are radio buttons for "And" and "Or", and three dropdown menus for "Attribute", "Operand", and "Value". The "Attribute" dropdown is currently selected and shows "SHIPMENT_DETAIL.warehouse". The "Value" dropdown shows "N'8001'". To the left of the criteria list are "Up" and "Down" buttons. To the right are buttons for "Add Rule", "Delete Selected Rule", "Delete Last Rule", "Insert Left Parenthesis", "Insert Right Parenthesis", and "Delete Parenthesis".

Figure 52 - Shipment Labor planning criteria

21.5 Direct/Indirect Labor

Direct Labor describes an activity performed by a worker that provides direct value to the warehouse. For example, such activities as performing actions in SCALE, or such physical activities as loading shipments onto a truck.

Indirect Labor describes a basic maintenance activity performed by a worker that is required for the business to operate but does not directly impact the customer. For example, activities such as cleaning the warehouse. Indirect labor cannot be tracked from RF. The following are a few suggested work types that Client may track for Indirect Labor using the **Manual Labor Entry Screen**.

- Box Building
- Mopping
- Cleaning
- Bathroom Break

21.6 View Labor Activity

Labor Activity can be viewed using **Labor Activity Insight Screen**

<

Figure 53 - Labor Activity Insight

21.7 Reporting

Using the optional Operational SCI, or SSRS, new reports can be developed. For example, below is a custom report indicating case and pallet picks performed per hour. Note, that this is not an existing report and there is dependency on the use of SCI framework. This will require a dedicated discussion for SCI reporting.




Figure 54 - Sample Labor Management OSCI Report

XI. PERFORMANCE MANAGEMENT SUMMARY

22.0 REPORTING REQUIREMENTS

23.0 EVENT MANAGEMENT REQUIREMENTS

24.0 HISTORICAL REPORTING – ANALYSIS

XII. SYSTEM EXTENSIONS

PTL Integration Extensions

Extension	Description
EX01	Put to Light Sort Integration Extension to integrate with a PTL (Put to Light) system. Existing extension in 2015. Will be ported to Active SCALE. The old extensions that this extension will replace are: EX01, EX01-A, EX01-B, EX01-C, AI0011, AI0013, AI0019, AI0020, AI0038, AI0039 and AI0040. Base Alternative: None.

Interface Integration Extensions

Extension	Description
EX03	Inventory Reserve for E-Commerce Extension to set/reset inventory attributes, used to reserve inventory for specific order types (Online, for example). Existing extension in 2015. Will be ported to Active SCALE. The old extensions that this extension will replace are: EX03, EX03-A and EX03-B. Base Alternative: Check-in the items and then allocate from specific location.

Warehouse Mobile Extensions

Extension	Description
EX04	Add Inventory RF Screen Existing extension in 2015. Not in use. Will not be ported to Active SCALE. The extensions that this extension would replace are: EX04 and EX04 A. Base Alternative: N/A
EX05	Receiving Workflow without Quantity Prompt Extension to default the quantity being checked-in to 1 (one). Existing extension in 2015. Will be ported to Active SCALE. The old extensions that this extension will replace are: EX05 and EX07. Base Alternative: Enter the required quantity (1) before checking in.

Extension	Description
EX07	Putaway Grouping by Item Location Extension to group the putaway work based on Putaway Group ID/Item/To Location. Existing extension in 2015. Will be ported to Active SCALE as part of the EX05. Base Alternative: This extension is only needed as a side effect of EX05.
EX09	Cycle Count One by One Extension to allow counting one by one during cycle count. Existing extension in 2015. Will be ported to Active SCALE. Base Alternative: Perform regular counting.

Performance Improvement Extensions

Extension	Description
EX02	Cross Dock for Multi Item Container Extension to allow cross docking for multi-item containers. Existing extension in 2015. Still under discussion if it should be ported or not to Active SCALE. Base Alternative: Check in the items and then allocate from specific location.
EX06	Immediate Needs Locating Rule by Receiving Preference Extension to use a different locating rule based on the receiving preference used, only for immediate needs. Existing extension in 2015. The required configuration is not in place on Grupo Julio production's environment, which means it is not being used. Grupo Julio will execute some tests to make sure the extension is not in use. Base Alternative: Use a single locating rule.
EX08	Custom Immediate Needs Viewer This extension was never developed by Manhattan Associates. A draft document was provided by Logística de México. Most of the requirements from this document are now supported by base SCALE. Base Alternative: Use the base Immediate Needs Insight screen and handle any possible exceptional scenario by SOP.

Action Items that will NOT be migrated in this project.

The below list shows all the Action Items that will **NOT** be migrated as part of this project. These Action Items were reviewed by Manhattan Associates' technical team and should not be necessary any longer.

Action Item	Description
AI0003	Load Confirmation Slowness Analysis
AI0004	Error on Load Confirmation
AI0005	Null reference exception on dock door transfer
AI0006	Debug patch for load confirmation issue
AI0007	Dock Transfer with open staging work issue
AI0008	Fix for Date issue while upload
AI0009	No staging work created issue fix
AI0010	Fix for partial Imm needs update issue
AI0012	Distributed shipment wave cancellation issue
AI0014	Fix for session issue
AI0016	Mezzanine new container and printing issue fix
AI0017	Mezzanine new container issue fix
AI0018	Colgado close work issue
AI0024	InternalShipAllocNum issue fix
AI0026	Deactivate work issue fix
AI0028	Confirm imm Work till DropLoc issue
AI0029	Debug patch for EX05 issue
AI0035	Receipt interface upload issue fix
AI0037	Work confirmation during load confirm issue fix
AI0041	Fix for EX09 Cycle count issue
AI0042	Fix for EX09 Cycle count work assignment issue

XIII. OPEN ISSUES

~~EPIC Company - 16/Jul/2024~~

- ~~• Grupo Julio currently has a company called EPIC configured in SCALE. This company is not used by Grupo Julio.~~
- ~~• Grupo Julio would like to remove this company from configuration.~~

~~Receiving with Putaway Groups - 9/Aug/2024~~

- ~~• This option is not available in Warehouse Mobile in version 24.1.2278 that is available at this moment. It is currently being implemented by Manhattan Associates, although we cannot provide an expected date at this point.~~

~~EX02 - Cross Dock for Multi Item Container - 17/Jul/2024~~

- ~~• Grupo Julio has never used the original extension (developed in 2016).~~
- ~~• Manhattan Associates recommends NOT porting this extension during this project.~~

~~EX04 - Add Inventory RF Screen - 17/Jul/2024~~

- ~~• Grupo Julio does not use this extension anymore. It was replaced by EX09.~~
- ~~• Manhattan Associates recommends NOT porting this extension.~~

~~EX08 - Custom Immediate Needs Viewer - 15/Aug/2024~~

- ~~• This extension was never developed by Manhattan Associates.~~
- ~~• Logística de México has provided a draft document of what would be this extension. Based on that document, the extension should allow users to multi-select lines to change priority and/or delete records. This is now supported by base Immediate Needs Insight screen.~~
- ~~• The only custom functionality that the extension would implement that is not supported in base is to completely eliminate the records once they are eliminated on the screen. Base would send them back to the pool.~~
- ~~• Manhattan Associates recommends NOT porting this extension.~~

~~EX06 - Immediate Needs Locating Rule by Receiving Preference - 28/Aug/2024~~

- ~~• This extension is currently not in use by Grupo Julio.~~
- ~~• Manhattan Associates recommends NOT porting this extension during this project.~~

XIV. RESOLVED ISSUES

~~EPIC Company - 18/Jul/2024~~

- ~~• Grupo Julio has decided to remove this company from configuration.~~

~~EX02 - Cross Dock for Multi Item Container - 20/Aug/2024~~

- Grupo Julio has decided to not migrate this extension at this moment. In the future, in case Grupo Julio decides to implement it, the extension will be reevaluated, based on the original mod spec and on current requirements from Grupo Julio.
- The original mod spec will be shared with Grupo Julio for their reference. The original source code of the extension will be kept by Manhattan Associates.

EX04 - Add Inventory RF Screen – 18/Jul/2024

- Grupo Julio has decided to not migrate this extension, as it was replaced by EX09.

EX08 – Custom Immediate Needs Viewer – 21/Aug/2024

- There is no documentation about this extension.
- In a meeting with Grupo Julio and LDM it was mentioned that this extension was supposed to allow users to multi-select lines to delete Immediate Needs.
- This functionality is now a base option in SCALE.
- Manhattan Associates recommends NOT porting this extension.

EX06 – Immediate Needs Locating Rule by Receiving Preference – 3/Sep/2024

- As discussed, and tested with Grupo Julio, this extension is not being used.
- This extension will not be migrated as part of the initial project.
- In the future, in case Grupo Julio decides to have such behavior, this can be discussed, and new requirements can be gathered.

XV. FUTURE FUNCTIONALITY

Future functionality is listed here based on Client's future operational needs. The list below could be an immediate future phase or a long-term functionality activation as part of subsequent phases.

VAS – 17/Jul/2024

- Manhattan's recommendation would be to use VAS for processes that should be executed during packing, as adding tags, wrapping instructions, etc. By using VAS Grupo Julio would have better tracking of the activities executed.
- The use of VAS would be especially beneficial for new/temporary users, as they don't have the tribal knowledge to perform the required tasks.
- Grupo Julio has decided to perform tests using VAS during the test phase, with support from Logística de México.
- In case Grupo Julio decides to implement the base VAS, this document will need to be updated, reflecting this new flow. This change will require additional efforts from Manhattan Associates, that are outside the current migration scope, and therefore such efforts will be billable.

Inbound QC – 20/Aug/2024

- Grupo Julio would like to perform some tests using base Inbound QC to evaluate changing their current inbound process.
- Grupo Julio will test this feature, with support from Logística de México, during their test phase.
- In case Grupo Julio decides to implement the base Inbound QC, this document will need to be updated, reflecting this new inbound flow. This change will require additional efforts from Manhattan Associates, that are outside the current migration scope, and therefore such efforts will be billable.

Labor Management reports – 28/Aug/2024

- Grupo Julio already has the Labor Management configured, although the current configuration needs to be reviewed.
- Grupo Julio will review, during testing phase of later after the project, the configurations in place to make sure the values for work execution time is accurate.
- Grupo Julio will also develop the Labor Management reports, using SCI, based on their requirements.
- LDM may support Grupo Julio to develop these reports.

XVI. REVISION HISTORY

Date	Changed By	Version	Notes
8/8/2024	Luciano Peres	1.0	First draft
8/19/2024	Luciano Peres	1.1	Added outbound section
8/26/2024	Luciano Peres	1.2	Changes based on client's feedback
8/28/2024	Luciano Peres	1.3	Changes based on client's feedback
8/29/2024	Luciano Peres	1.4	Changes based on client's feedback
9/3/2024	Luciano Peres	1.5	Last changes to prepare document for sign-off

Functional Flow Sign-Off

As part of our project methodology, Manhattan Associates requires a written acknowledgement of the Functional Flow document at the end of the Design Phase.

By signing this letter Grupo Julio indicates their understanding that the operations and extensions specified in this Solution Design Document (Grupo Julio – Manhattan Active SCALE Implementation Solution Design Document – v1.5 – Final – 2024-09-03) will support the operational procedures outlined during the functional design phase.

Please sign below to indicate your acknowledgement and email scanned document to elopez@manh.com . Please contact Ed Lopez in the event you have any questions.

Sincerely,

Ed Lopez
Project Manager, Professional Services

Operations Signature

Printed Name / Title

Date

IT Signature

Printed Name / Title

Date