# UT-GOAL Manual

Koen Hindriks, Rien Korstanje, Wouter Pasman, Birna van Riemsdijk, Lennard de Rijk, Peter Evers, Michiel Hegemans, and Vincent Koeman

Delft University of Technology, The Netherlands

April 5, 2016

### 1 Introduction

This manual describes the UNREAL TOURNAMENT 2004/3 (UT) EIS interface.

The manual is organized as follows. Section 2 discusses how to install the environment and how to run it. In Section 3 the initialization parameters that can be set in a <code>.mas2g</code> file are discussed. Section 4 introduces the *visualizer* that provides (i) a 3D map which displays all bots as well as the flags, (ii) options for managing the UT server, and (iii) options for managing bots. In Section 5 the UnrealGoal bot is described, a software layer between GoAL agents and UT bots that implements low-level behaviour (including e.g. a path planner). Section 6 documents the actions that the interface provides and can be performed by a GoAL agent. Finally, Section 7 documents the percepts that a GOAL agent receives when connected to the UT environment.

#### 1.1 Differences UT2004 and UT3 environment

The environments are different on some points. The UT3 environment provide the bot with game mechanics like deployable weapons, new weapons and powerups. Sections with the UT2004 tag are UT2004 only, sections with the UT3 tag are UT3 only. Most of the percepts and actions are the same, but with different names for the items, weapons, armor and powerups. These names are provided in an extra table with UT3 specific names. Unreal Tournament 3, and therefore the environment is not available for Mac/OSX and Linux.

# 2 Setting up the Environment

This section explains how to startup a dedicated server to which the bots of the UnrealGoal will connect.

#### 2.1 Installation

To install the unreal environment, you can run the installer. Please ensure that Java and Unreal Tournament have been installed. For UT3 make sure you install the UT3Patch4 and the UT3TitanPack otherwise the server will crash.

# 2.2 Startup Scripts UT2004

For your convenience a number of scripts have been provided (e.g.CTFServer UG-Chrome). These starts the UT server with a specific map, web admin enabled and translocators disabled and can be found in the /System folder of UT2004.

You can adopt these script to suit your own needs. For more command line parameters you can consult http://wiki.unrealadmin.org/Commandline\_Parameters\_(UT2004).

#### 2.3 Startup Scripts UT3

The run scripts for an UT3 server can be found in the Unreal Tournament 3 directory.

You can adopt these script to suit your own needs. For more command line parameters you can consult http://wiki.unrealadmin.org/UT3\_Command\_line\_options.

#### 2.4 Dedicated Server UT2004

To setup your own dedicated UT2004 server you can use the UnrealOS execution environment (UCC) from the command prompt. The ucc is located in the Unreal Tournament 2004\¬System directory.

The following command starts a game of capture the flag on the map CTF-UG-Chrome that ends after 999999 minutes.

Windows: ucc server CTF-UG-Chrome?game=GameBots2004.BotCTFGame?timelimit=999999

Unix, OSX: ucc-bin server CTF-UG-Chrome?game=GameBots2004.BotCTFGame?timelimit=999999

#### 2.5 Dedicated Server UT3

To setup your own dedicated UT3 server you can use the UT3.EXE SERVER from the command prompt. The UT3.EXE binary is located in the Program Files (x86)\Unreal Tournament 3 directory.

The following command starts a game of capture the flag on the GOAL testmap that ends after 99999 minutes.

ut3.exe server CTF-GOALTest?game=GameBotsUT3.GBCTFGame?bIsDedicated=True?bIsLan Match=True?bUsesStats=False?TimeLimit=99999

#### 2.6 Web Admin UT2004

A dedicated server can be managed using the web admin. To enable it, locate [UWeb.WebServer] in the UT2004.ini and set bEnabled=False to bEnabled=True. To set a password and user name append ?AdminName=Bot?AdminPassword=Goal to the command that starts the dedicated server. When enabled the web admin can be found at http://localhost/ServerAdmin/.

For more information on managing a dedicated server please consult the UnrealAdmin wiki http://wiki.unrealadmin.org/Server\_Setup\_(UT2004).

# 2.7 Disabling Translocators UT2004

The translocator is a device that players and bots in UT can use to move across the map quickly. The UnrealGoal bot is unable to use this device. To keep things fair you can disable the translocator by appending \?Translocator=False to the command that starts the dedicated server.

#### 2.8 Running on non-Windows OSs

UT3 is only available for the Windows operating system. Therefore users of Linux or OSX have to run Windows with UT3 elsewhere. There are a number of options:

- Run UT3 on a separate windows machine, e.g. a machine on the Drebbelweg.
- Run UT3 in VirtualBox (https://www.virtualbox.org); you can then run your agents (e.g., GOAL) either on your native OS or also in the virtual box.

 Make your system dual-boot (e.g. Bootcamp for OSX: https://support.apple.com/ nl-nl/HT201468) and run Windows on your machine from a separate partition.

As TU Delft student, you can get a free Windows license through http://www.ma3d.com/productverification.php.

If UT runs on a different operating system than where you run your agents, then you will have to set up the init parameters for botServer, controlServer, and visualizer as discussed in the section 3).

Running the server only (without the visuals of UT.exe) is sufficient for connecting and running the agents. UT3.exe may be slow but good enough for testing and debugging.

# 3 Connecting GOAL to Unreal Tournament

This section explains how to connect a GOAL multi-agent systems to UT by starting the UnrealGoal environment from GOAL. The UnrealGoal environment is a special .jar file that facilitates connecting GOAL to UT. In order to connect to UT, a dedicated UT server needs to be running and Pogamut Gamebots must have been installed. (See the installation instructions for this.)

The UnrealGoal environment can be launched by means of a MAS file from Goal. The general structure and set-up of such files is discussed in more detail in the Goal Programming Guide. Here we only discuss the initialization parameters that are specific for the UT environment.

Several parameters for initializing the UT environment can be set when connecting GOAL to UT. For the UT environment six parameters are available. If a parameter is not provided, the environment will use a default value for the parameter. The following is an example for the UT environment which sets all parameters:

```
botServer = "ut://127.0.0.1:3000",
controlServer = "ut://127.0.0.1:3001",
visualizer = "rmi://127.0.0.1:1099",
logLevel = "ALL",
bots = [
            ["name", "BotA1"],
            ["skill", 1],
            ["skin", "BotA"],
            ["team", "red"],
            ["logLevel", "OFF"]
        ],[
             ["name", "BotB2"],
            ["skill", 1],
            ["skin", "BotB"],
            ["team", "red"],
            ["logLevel", "OFF"]
        ],[
            ["name", "BotC3"],
            ["skill", 7],
```

```
["skin", "BotC"],
             ["team", "blue"],
             ["logLevel", "OFF"],
             ["startRotation", rotation(0,0,0)],
             ["startLocation", location(696.12,5900.18,-741.0)]
        ]
],
nativebots = [
        Γ
             ["name", "Native1"],
             ["skill", 5],
             ["team", "blue"]
        ],[
             ["name", "Native2"],
             ["skill", 5],
             ["team", "red"]
        ]
٦
```

The meaning of each of the parameters is as follows:

- botServer: IP address of host running the UT server with the GameBots modifications. The bots will be created on this server. *Default value*: local host port 3000, meaning that if no address is provided the environment will connect to a server on the the local host port 3000.
- controlServer: IP address of host running the UT server with the GameBots modifications. This is used for the control connection to server to allow adding bots. *Default value:* local host port 3001, meaning that if no address is provided the environment will connect to a server on the the local host port 3001.
- visualizer: IP address of the host that is running the visualizer. If the visualizer is running on the same host as Goal the IP address of the local host can be used. The port should always be 1099. By connecting to the Visualizer, the Visualizer can add bots to the environment. *Default value*: none, meaning that if no address for the Visualizer is provided, the environment will not connect to the Visualizer.
- logLevel: Dicates the level of detail of the log information that the environment bot will output to the console in the Goal IDE. Accepted values are OFF(none), SEVERE (least), WARNING, INFO, CONFIG, FINE, FINER, FINEST and ALL (most). Default value: WARNING.
- bots: Parameters for the bots. For each bot a list containing tuples of a key and a value. *Default value*: the empty list, meaning that no bots will be launched; bots may however also be launched by means of the Visualizer (see Section 4). The keys and values follow:

<sup>-</sup> name: The name of a bot. *Default value*: UnrealGOALBot.

- skill: The accuracy of the bot. Any value between 1 (worst) and 7 (best). The default is 5.
- skin: The skin used by all bots launched from this mas. Default value: BotB but can be any one of:

NightMaleA, NightMaleB, NightFemaleA, NightFemaleB, MercMaleA, MercMaleB, MercMaleC, MercMaleD, MercFemaleA, MercFemaleB, MercFemaleC, EgyptMaleA, EgyptMaleB, EgyptFemaleA, EgyptFemaleB, AlienMaleA, AlienMaleB, AlienFemaleA, AlienFemaleB, BotA, BotB, BotC, BotD, Hellion\_Kane, Hellion\_Garrett, Hellion\_Gitty, JuggMaleA, JuggMaleB, JuggFemaleA, JuggFemaleB, AbaddonM, Ophelia, JakobM, Skaarj2, Skaarj3, Skaarj4, XanMO3, XanMO2, XanFO2, EnigmaM

- team: either red or blue. Default value: red.
- logLevel: Dictates the level of detail of the log information that each bot will output to the console in the Goal IDE. Accepted values are OFF(none), SE-VERE (least), WARNING, INFO, CONFIG, FINE, FINER, FINEST and ALL (most). Default value: WARNING.
- startLocation: The starting location of the bot provided as a location(x,y,z). When this parameter is not provided bots will spawn using the UT spawn points.
- startRotation: The starting rotation of the bot provided as a rotation(pitch,yaw,roll). The values of of pitch yaw and roll range from -32768 to 32767. Only the yaw value will be used by the bot. When this parameter is not provided the starting rotation is not defined.
- nativebots: similar to the bots parameter. These bots are launched as native UT bots. Only name, skill and team are used, the other parameters are ignored. Notice that these bots are not killed when you kill the MAS.

## 4 Visualizer

The visualizer is a tool that can be used to visualize and manipulate the UnrealGoal environment. It can be started independently from the Environment and provides a 3D visualization of navpoints, players, bots and flags currently present in the UT server. Bots can be placed, added and removed to the UnrealGoal environment. The visualizer can also be used to place items or add them to a bots inventory.

#### 4.1 Installation

Use the Unreal Environment installer to install the visualizer and start it via the Unreal Visualizer short cut.

#### 4.2 Map Screen

In figure 1 you can see a simple map. The players are denoted by spheres, which are colored according to their team. Their names are also drawn above. A red arrow indicates in which direction they are looking. The blue disk and grey lines represent navigational points present

in the map, these are used by automated players such as bots to move around the area. If you are playing a Capture the Flag gametype you will be able to see the flags, denoted by a sphere on a stick and once again colored according to their team.

The camera can be moved using the standard UnrealEd camera controls. To move forward/backwards hold the left mouse button and move up/down. To pan the camera hold the right mouse button down. To elevate the camera up/down hold both buttons down and move up/down, move left/right to strafe the camera. Pressing the middle mouse button will reset the camera view.




Figure 1: An example of a map screen

## 4.3 Server

The server menu can be found on the top of the visualizer by clicking Server. This section deals with the server administrative functionality.

#### Connection

Server->Connection will open a dialog showing the current state of the connection. When the visualizer is disconnected an address to the UT server can be provided. Pressing connect will then start the connection to the server. Should at anytime the connection to the server be lost, such as when changing a map, the Visualizer will automatically try to reconnect.

#### Pause / Resume

Server->Pause pauses the Unreal Server. Pausing the server means that nothing in UT will move anymore. To resume just press this same option again. Note that this will not pause individual bots that are running in GOAL.

#### Game Speed

Server->Game Speed allows you to change the gamespeed. A lower number means that all movement in the game will be slower, a higher number means faster movement. Although UT2004 allows for a higher gamespeed then the dialog might suggest, we have capped it to 10 to ensure that any secondary systems driving the game do not get synchronization problems on most modern pc's. Note however that it is best to leave this set to 1 to ensure normal gameplay.

#### Change Map

Server->Change Map will open a dialog showing a list of maps from which you can choose. Pick the one you want to switch to and press Ok to change the map. The server will restart and load the new map. It may take a few seconds before the visualizer notices the disconnect after which it will try to reconnect. Note that all native bots will be removed and all other bots will be disconnected.

#### Add Native Bot

The Server->Add Native Bot item will show the dialog to add an native Bot to the game as illustrated in figure 2. All fields except level are optional. The name field allows you to set a custom name for your bot, the level field determines how accurate bot is, 1 for a total nuub and 7 for a warzone hero. Select one of the teams to assign this bot to. And finally a location where to spawn this bot, if none is selected a proper spawn location for the team the bot plays in will be used.




Figure 2: Dialog to add an native bot.

#### Add UnrealGoal Bot

The Server->Add UnrealGoal bot will be disabled until the Visualizer has been connected to an UT server and an environment has connected to the visualizer. As seen in figure 3 this menu is very similar to that of Add Native Bot. All fields except level and environment are optional. Unlike the native bots, level here only indicates how accurate the bot is. In case there are multiple environments, you can select one. When Add Bot is pressed, the visualizer will connect to the chosen environment and instruct it to launch another bot with the given settings.




Figure 3: Dialog to add UnrealGoal bot.

# List Players

The Server->List players item will show a list of players currently in the server. The buttons kick and respawn will respectively kick or respawn the player. Please note that actual human players can not be kicked from the server. Also humans and native bots can only respawn on random navpoints.

#### 4.4 Context Menus

The context menu is accessible by left clicking on a player or way point. Depending on which is selected different options are available.

#### Respawn

When a bot is selected the respawn menu item is available (see Figure 4). Selecting it will respawn the bot at a random PlayerStart way point associated with their team. When a way point was selected, the menu item offers a list of bots and players to respawn on that way point. Note that native bots and players can only be spawned randomly and will only spawn at PlayerStart way point.




Figure 4: The context menu for a bot.

### Change team of a Bot

When a bot is selected, using the change team menu item will change the team of the bot. Note that again this does not work for players and native bots.

#### Spawn Item

Spawn item is available whenever a way point is selected. This menu item offers a list of items that can be spawned. This will allow you to put extra weapons, health, shields or adrenaline into a level. Pickups have a respawn timer just like any other object in the world, so a newly added large shield pickup will spawn a shield every 55 seconds after it has been picked up. An example of this dialogue can be found in Figure 5.

#### Add Inventory

Add Inventory is available when ever a bot is selected. This menu item offers a list of items that can be added to the bots inventory such as weapons, ammunition, shields, adrenaline and health. This allows you to setup a bot without needing the bot to collect everything. Note that all weapons added in this way will not have any ammo. Ammunition has to be added in the same way as the weapon.

#### Kick

This menu item allows you to kick the selected bot or player from the game.




Figure 5: The context menu to spawn a new actor/item into the world.

# 5 UnrealGoal Bot

The UnrealGoal environment is a layer in between the GOAL agents and the UT bots that are visible in the UT environment. UnrealGoal bots implement the low-level behavior of the bots such as shooting weapons and navigating the world. This section describes how the UnrealGoal bots internally work. The aim is to create a greater understanding of the workings that can't be gained from merely reading the percepts and action specifications.

#### 5.1 Limitations

The UnrealGoal bot has many limitations over a human player, the major limitations are:

- Maps Currently UnrealGoal bot is unable to do several types of movement that the native bots and human players can do.
  - Elevator Jumping. This means that the bot won't be able to time his jumps such that when he reaches the top of the elevator he gets an extra boost.
  - Precise Double Jumping. By correctly timing a second jump while mid air, bots and players can give themselves a boost and jump extra far. the UnrealGoal bot is unable to do such exact timing. This means that certain areas will be out of reach.
  - To remedy this the map needs to be modified using the Unreal Editor and all LiftExit nodes that aren't roughly at the same level as the lifts maximum have to be removed.

**Translocators** The translocator is a device that can teleport a player some distance and generally allow rapid movement across large maps. The bot is unable to unable to use this weapon which provides an advantage to players and native bots that can use it.

• Disabling the translocator removes the advantage from other bots and players.

Currently three maps for UT2004 have been fixed to allow full navigation. CTF-UG-Chrome, CTF-UG-Grendelkeep and CTF-UG-AbsoluteZero. For more information about bot pathing refer to: http://wiki.beyondunreal.com/Legacy:Topics\_On\_Mapping.

There are three maps for UT3: 'CTF-GOAL-Hydrosis', 'CTF-GOAL-Reflection', and 'CTF-GOAL-Searchlight'. And a testmap CTF-GOALTest, a simple small map with all the items, powerups and weapons useful for testing.

#### 5.2 The behavior

To abstract the low level details the Unreal Bot provides a behavior. This behavior takes input on who to shoot, where to look and where to go. This input is provided in the form of actions from GOAL. These are described below. The behavior is encoded as logic routine that evaluates approximately every 100 milliseconds. In each evaluation the following steps are taken:

- Execute all outstanding actions.
- Determine a target to shoot at based on the input from the last shoot action.
- Determine a weapon to shoot with based on the input from the prefer action.
- Determine a target to look at based on the input from the last look action.
- Determine a location to go to based on the input from the last navigate action.
- If we have a target to shoot at, shoot it with the preferred weapon.
- If we have location to go to, run to this location, look at the first applicable of the target we are shooting, the target we should look at or the path ahead.
- If we are standing still, look at the first applicable of the target we are shooting, the target we should look at or turn in circles.
- Prepare a new batch of percepts for the Environment.

Because the bot has its own thread actions are queued up and executed when the bot is ready. As a result there may be a 0-100ms delay between the execution of an action in GOAL and the bot executing the action. Likewise all percepts will be from 0-100ms in the past. This delay is small and should not adversely affect the performance of a GOAL program. However this delay should be taken into account in some cases. For example executing dropWeapon until a weapon is perceived to have been dropped may leave the bot with a big pile of weapons in front of him.

# Actions

In this section, the design and specification of the actions that a GOAL agent can perform while controlling an Unreal bot in UT2004 or UT3 is described. The actions described here are provided by an UT-GOAL interface. An overview of the actions can be found in Section 6.3.

#### **Behavior Actions** 6.1

The behavior actions are actions that govern how the bot looks, moves and shoots. The actions all take place over an extended duration of time.

#### Navigate action

Description This action makes a best effort attempt to navigate the

navigate(<Destination>) Syntax

Parameters <Destination> : A location presented either as a loca-

tion(x,y,z) or as the UnrealId of a player, navpoint, or item.

Effects 0. Sets the destination the bot will run to.

> 1. The bot switches to the navigation navigation(navigating,Destination) ,

> Plans a path to this destination. If is not path the navigation state becomes navigation(noPath, Desination)

Then it starts moving along this path.

bot gets stuck on the way the navigation state becomes navigation(stuck, Destination)

4. While traveling, opponents will be shot at according to

the last shoot action.

5. Once the destination has been reached, the navigation

state changes to navigation(reached, Destination). 1. A player is considered reached when the bot comes with

in 100 units of the player or when the player is no longer

visible; his last known location. 2. If the bot gets stuck this doesn't mean a destination is actually unreachable. It is for example possible to miss a

jump twice. 3. The UnrealId's used must have been received in a per-

cept. Id's received from other bots might not be known by

this bot.

#### Stop action

Description

Halts the bot on the spot.

Syntax

Effects

Notes

0. Clears the destination the bot will run to.

The bot switches the navigation state to navigation(waiting, none).

2. The bot looks around as ordered by the last look action.

3. If an opponent becomes visible that matches the last shoot action the bot will shoot at it.

#### Shoot action

Description Sets the priority of each opponent.

Syntax shoot(<TargetLabel>)

shoot([<TargetLabel>])

Parameters <TargetLabel>: A single target label.

[<TargetLabel>]: A list of target labels in order of prior-

ity.

A target label can be: none, nearestEnemy, nearestFriendly, nearestFriendlyWithLinkGun, enemyFlagCarrier, friendlyFlagCarrier, PlayerID or location(X,Y,Z). The bot takes the first target label and checks if the target is visible. If the target is visible, it will be shot at. Otherwise the bot will try the next target label. When all target labels have been tried and none matched any visible players the bot will not target any

opponent.

Effects 1. Sets target labels that decide which visible opponent the

bot shoots at.

Notes 1. A full overview of who is targeted by which target label

can be found below.

Target label	Targets	
none	No one.	
nearestEnemy	The nearest enemy player the bot can see.	
nearestFriendly	The nearest friendly player the bot can see.	
nearestFriendlyWithLinkG	GunThe nearest friendly player the bot can see	
	that is holding a link gun.	
enemyFlagCarrier	The bot from the opponent team that is cur-	
	rently holding the flag.	
friendlyFlagCarrier	The bot from the team that is currently hold-	
	ing the flag.	
PlayerID	The bot identified by the UnrealID. Valid Id's	
	can be extracted from the See other bot and	
	Flag percept.	
location(X,Y,Z)	A location in the world.	

### Stop shooting action

Description Stops the bot from shooting anyone.

Syntax stopShooting

Effects 1. The bot stops shooting at once. Identical to calling

 $\mathrm{shoot}([]).$ 

# Prefer weapon action

Description Sets the priority for the use of each weapon.

Syntax prefer(<Weapon>)

prefer([<Weapon>])

 $\verb|[<Weapon>]: A list of weapon(WeaponLabel, Firemode) in$ 

the order of priority.

A WeaponLabel can be any of the following:

UT2004	UT3
shield_gun	impact_hammer
assault_rifle	enforcer
bio_rifle	bio_rifle
shock_rifle	shock_rifle
minigun	stinger_minigun
link_gun	link_gun
flak_cannon	flak_cannon
rocket_launcher	rocket_launcher
lightning_gun	avril
sniper_rifle	sniper_rifle
redeemer	redeemer

The FireMode is either primary or secondary.

Effects

- 1. Set the preference used to select a weapon.
- 2. Select the first weapon from the list that can be used (e.g. the bot has the weapon and it is loaded).
- 3. Once the bot changes weapons it won't be able to shoot for about half a second.

Notes

- 1. Using prefer([]) will cause the bot to use its default weapon preferences.
- 2. When the bot has none of its preferred weapons, it will use its default weapon preference.
- 3. The default preferences are:

UT2004	UT3
weapon(shock_rifle, secondary)	weapon(shock_rifle, secondary)
<pre>weapon(rocket_launcher, primary)</pre>	weapon(rocket_launcher, primary)
weapon(flak_cannon, primary)	weapon(stinger_minigun, primary)
weapon(sniper_rifle, primary)	weapon(flak_cannon, primary)
weapon(lightning_gun, primary)	weapon(link_gun, primary)
weapon(minigun, primary)	weapon(sniper_rifle, primary)
weapon(link_gun, primary)	weapon(bio_rifle, primary)
<pre>weapon(bio_rifle, secondary)</pre>	weapon(bio_rifle, primary)
<pre>weapon(assault_rifle, primary)</pre>	weapon(enforcer, primary)
weapon(shield_gun, secondary)	weapon(impact_hammer, primary)

- 4. Deployable weapons will always be equiped as soon as the bot picks them up, they can't be switched until it is deployed.
- 5. When shooting the bot will use the weapon it is holding in an intelligent fashion. This includes the use of shock combos and assisting with the link gun. A skill level of 6 or 7 is required to set up shock combos reliably.
- 6. When using a weapon that causes splash damage the bot will hold fire when the splash damage would kill it. Ensure your bot is not using a weapon with splash damage when the target is nearby!

#### Look action

Description Sets the priority of bots and locations to look at. Use this

action to keep an eye on the flag or snipe down an alley.

Syntax look(<TargetLabel>)

look([<TargetLabel>])

Parameters <TargetLabel>: A single target label.

[<TargetLabel>]: A list of target labels in order of prior-

ity.

A target label can be: none, nearestEnemy, nearestFriendly, nearestFriendlyWithLinkGun, enemyFlagCarrier, friendlyFlagCarrier, PlayerID or location(X,Y,Z). The bot takes the first target label and checks if the target is visible. If the target is visible, it will be looked at. Otherwise the bot will try the next target label. When all target labels have been tried and none matched any visible players the bot will either look in the

direction it is traveling or turn around on the spot.

Effects 1. If the bot is not actively shooting some one and the target is visible the bot will look at the given target.

Target label	Targets	
none	No one.	
nearestEnemy	The nearest enemy player the bot can see.	
nearestFriendly	The nearest friendly player the bot can see.	
nearestFriendlyWithLinkG	kGunThe nearest friendly player the bot can see	
	that is holding a link gun.	
enemyFlagCarrier	The bot from the opponent team that is cur-	
	rently holding the flag.	
friendlyFlagCarrier	The bot from the team that is currently hold-	
	ing the flag.	
PlayerID	The bot identified by the UnrealID. Valid ID's	
	can be extracted from the See other bot and	
	Flag percept.	
location(X,Y,Z)	A location in the world.	

#### 6.2 Instant actions

The instant actions are actions that can be carried out in a single instant - and with the exception of respawn - do not disrupt any ongoing behavior.

#### Respawn action

Description Respawns the bot.

Syntax respawn

Effect 1. The bot dies and is returned to a random starting posi-

tion.

2. The navigation state is switched to naviga-

tion(waiting,none), i.e. the bot stands still.

Notes 1. The respawn action does not need to be performed if

a bot is fragged. In that case, the bot is automatically

respawned by UT.

2. The respawn action was originally thought up as a way out for the hopelessly stuck bot, but can also be used tac-

tically in a CTF game.

3. In UT2004 the bot starts again with 100 health, 0 armour, no active combo, a Shield Gun and Assault Rifle (including 100 rounds of ammo). Adrenaline is not lost.

4. In UT3 the bot starts again with 100 health, 0 armour, no powerup, an Enforcer (including 100 rounds of ammo)

and an Impact Hammer.

## Combo action UT2004

Description The bot slowly consumes 100 adrenaline pills and gets a

power up.

Precondition The bot has 100 pills. Syntax combo(<Combo>)

Parameters <Combo>: Any of the following: berserk, booster, invisibil-

ity, speed. Effects: speed - Makes the bot run super fast; booster - Bot gains health at a rate of 5 points per second up to 199, then it gives the bot shield at a rate of 5 per second up to 150; invisible - Bot becomes nearly invisible. Other bots only have small chance at spotting an invisible

bot; berserk - Makes you fire at a twice the rate.

Effect 1. The bot activates the power up.

2. The adrenaline slowly drains.

3. Once the adrenaline reaches 0, the effect no longer ap-

plies.

Notes 1. When invisible with the flag, the flag is still visible. This

means you can still be shot at.

2. Be careful when using speed, the navigation can have

trouble keeping up.

3. One adrenaline pill gives 2 adrenaline. Adrenaline stays

if the bot gets killed.

#### Drop weapon action UT2004

Description Drops the weapon it is currently holding, possibly for an-

other bot to use.

Precondition Bot is holding a weapon other than the shield gun.

Syntax dropWeapon

Effect 1. The weapon the bot is currently holding is dropped and

lands a few feet away in the direction the bot is looking.

#### Path action

Description The bot computes a path from a to b.

Syntax path(<From>,<To>)

Parameters  $\langle From \rangle$ : A location presented either as a location(x,y,z) or

as the UnrealId of a navpoint, player, or item.

 $\langle To \rangle$ : A location presented either as a location(x,y,z) or

as the UnrealId of a player, navpoint, or item.

Effect 1. The bot computes the path.

2. The bot emits a Path percept.

Notes 1. The UnrealId's used must have been received in a per-

cept. Id's received from other bots might not be known by

this bot.

2. When a player is not visible, the path will lead to the

last location this bot remembers.

#### Chat action UT2004

Description The bot chats on the specified channel (useful for debug-

ging).

Syntax chat(<Scope>,<Message>)

Parameters <Scope > : Scope to chat on, can be global or team.

<Message> : Message to send, use GOAL string. Example:

'Hello world!'

Effect 1. Bot chats on specified channel.

Notes 1. Useful if you want to read what the bot is doing while

you are in game.

#### Skip action

Description The bot does nothing.

Syntax skip

Notes Useful when you want the bot to continue what it was do-

ing.

#### Deploy action UT3

Description If the bot is holding a deployable weapon it will be dropped.

Syntax deploy

Notes The shoot action will not work when a bot is holding a de-

ployable weapon so check if your bot is holding a deployable

weapon!

#### 6.3 Overview

Action Name	Syntax
Navigate action	navigate( <destination>)</destination>
Stop action	stop
Shoot action	<pre>shoot(<targetlabel>)</targetlabel></pre>
	<pre>shoot([<targetlabel>])</targetlabel></pre>
Stop shooting action	stopShooting
Prefer weapon action	<pre>prefer(<weapon>)</weapon></pre>
	<pre>prefer([<weapon>])</weapon></pre>
Look at action	look( <targetlabel>)</targetlabel>
	look([ <targetlabel>])</targetlabel>
Respawn action	respawn
Use power up action	combo( <combo>)</combo>
Drop weapon action	dropWeapon
UT2004	
Path action	<pre>path(<from>,<to>)</to></from></pre>
Chat action UT2004	<pre>chat(<scope>,<message>)</message></scope></pre>
Skip action	skip
Deploy action	deploy

# 7 Percepts

This section describes the percept design that provides a specification for the implementation of the UT-GOAL interface component that handles the transfer of percepts to GOAL.

To limit the percept load, not all percepts are provided at each iteration of the cycle.

- **Send once**: "Send once" percepts are provided only once when an agent is connected for the first time to the UT environment. Handle these percepts in the **init** module of the agent.
- On change: "On change" percepts provide new, up-to-date information that overrides previously perceived information. These percepts are received whenever some change is perceived that invalidates old perceptual information. The new percept provides the most current and up-to-date information.
- On change with negation: "On change with negation" percepts negate previously observed information and, if available, provide an update. For example, if the agent perceived flag(blue,...,location(581.0,4936.31,-742.1))) but now sees the blue flag's position has changed it will get two percepts:

```
- percept(not(flag(blue,...,location(581.0,4936.31,-742.1)))), and
```

- percept(flag(blue,...,location(590.37,4816.16,-742.1)))

where the last percept provides the new, up-to-date information. These percepts thus are provided when a change occurs. In all cases of these percepts, the old percept percept(old) is negated and the agent perceives percept(not(old)) which indicates the old fact is no longer true. In case a new relevant observation is available, another percept will be available that provides this information.

#### 7.1 **Self Percepts**

All the following percepts relate to the bot's state in the game. Its name, physical state and inventory.

#### Self percept

Description Information about the bot's identity and team.

Type Send once

Syntax self(<UnrealID>, <NickName>, <Team>)

Parameters <UnrealID>: Unique identifier string for this bot assigned

by Unreal.

<NickName>: Name of the bot as it appears in the game. <Team>: Either one of the following strings red, blue, or

#### Orientation percept

Description Information about the bot's orientation in the world.

Type Send on change

Syntax orientation(<Location>, <Rotation>, <Velocity>) Parameters  $\langle Location \rangle$ : the position in the world as location(x,y,z).

> <Rotation>: the rotation of the bot as rota-

tion(pitch,yaw,roll).

<Velocity>: the velocity of the bot as velocity(vx,vy,vz)

in ut units per second.

#### Status Percept

Description Information about the bot's current physical state.

Type Send on change

Syntax status(<Health>, <Armour>, <Adrenaline>, <Combo>) Parameters <Health>: An integer between 0 and 199, indicating the

health left in this bot.

<adrenaline>: An integer between 0 and 100 indicating</a> how much adrenaline this bot has. Not used in UT3 <Combo>: Either booster, berserk, invisibility, speed or none, indicating the active combo. Not used in UT3

<Armour>:

UT2004	An integer between 0 and 150, indicating the amount of
	armour this bot has.
UT3	There are different types of armour in UT3, the shieldbelt
	will provide 100 points of protection, the vest 50 points, the
	tighpads 30 points and the helmet 20 points of protection.

Notes

- 1. A bot initially starts with 100 health, 0 armour, 0 adrenaline and no active combo or powerup.
- 2. When a bot dies or respawns he starts with 100 health, 0 armor and no active combo. Adrenaline is not lost.
- 3. See the 'armor' percept for more details on the UT3 armor parts

# Score percept

Description Information about the number of kills, deaths, and suicides

this bot accumulated.

Type Send on change

Syntax score(<TotalKills>, <TotalDeaths>, <TotalSuicides>)
Parameters <TotalKills>: Number of people the bot fragged during

this game.

<TotalDeaths>: Number of times the bot died during this

game.

<TotalSuicides>: Number of times the bot got himself

killed.

Notes 1. Using respawn and being fragged by an opponent both

count as a death. Being killed by the your own weapon

counts as a suicide.

### Current Weapon percept

Notes

Description Information on which weapon the bot is currently holding.

Type Send on change

Syntax currentWeapon(<WeaponType>,<FireMode>)
Parameters <WeaponType>: none or any of the following:

TITTOOOA	TITTO
UT2004	UT3
shield_gun	impact_hammer
assault_rifle	enforcer
bio_rifle	bio_rifle
shock_rifle	shock_rifle
minigun	stinger_minigun
link_gun	link_gun
flak_cannon	flak_cannon
rocket_launcher	rocket_launcher
lightning_gun	avril
sniper_rifle	sniper_rifle
redeemer	redeemer
	slow_volume

<FireMode>: either none, primary or secondary, indicating
if the weapon is used and in which fire mode.

1. Not all weapons may be present on each map.

2. While holding the slow\_volume weapon the bot can not change to another weapon!

#### Inventory Weapon percept

Description Information on which weapons the bot currently has in its

inventory and their status.

Type Send on change, with negation.

Syntax weapon(<WeaponType>, <Ammo>, <AltAmmo>)
Parameters <WeaponType>: none or any of the following:

UT2004	UT3
shield_gun	impact_hammer
assault_rifle	enforcer
bio_rifle	bio_rifle
shock_rifle	shock_rifle
minigun	stinger_minigun
link_gun	link_gun
flak_cannon	flak_cannon
rocket_launcher	rocket_launcher
lightning_gun	avril
sniper_rifle	sniper_rifle
redeemer	redeemer

<a href="#"><Ammo>: An integer between 0 and specific maximum for the WeaponType.</a>

<altammo>: An integer between 0 and specific maximum for the WeaponType.

Notes

- 1. Not all weapons may be present on each map.
- 2. Depending on the WeaponType, Ammo and AltAmmo may refer to the same reservoir of ammunition. For UT3 this is always the same, for more information please consult the Unreal Documentation.
- 3. The shield\_gun primary has infinite ammo which is always 1.
- 4. The shield\_gun secondary will recharge when not used.
- 5. The impact\_hammer ammo is always 0.

#### UDamage percept UT2004

Description Information about the duration of the udamage effect.

Type Send on change Syntax udamage(<Ttime>)

Parameters <Time>: Time in seconds rounded to 2 decimals.

### Powerup percept UT3

Description Information about the current powerup of the bot.

Type Send on change

Syntax powerup(<Type>, <Duration>)

Parameters <Type>: none or any of the following udamage, berserk,

invulnerability.

<Time>: Time in seconds rounded to 2 decimals.

### Armor percept in UT3

Description Information about the armor parts of the bot.

Type Send on change

Syntax armor(<Helmet>, <Vest>, <Thighpad>, <Shieldbelt>)
Parameters <Helmet>: Armor rating of the helmet. Maximum is 20

points of protection, removing 50% of damage or completely

blocking a single headshot.

<Vest>: Armor rating of the vest with a maximum of 50

points for protection, removing 75% of damage.

<Thighpad>: Armor rating of the thighpad with a maximum of 30 points for protection, removing 50% of damage.
<Shieldbelt>:Armor rating of the shieldbelt with a maximum of 100 points for protection, removing 100% of dam-

age.

# 7.2 Action Percepts

#### Fragged percept

Notes

Description This percept is provided when one bot is violently frag-

mented by another.

Type Always

Syntax fragged(<Time>,<KillerID>,<VictimID>,<WeaponType>)

Parameters <Time>: The UT time of the Frag, in milliseconds.

<KillerID>: The UnrealID of killer or none.
<VictimID>: The UnrealID of the victim.

<WeaponType>: Weapon type used for the killing shot.

 When the killer and victim id are equal, the bot com-

mitted suicide.

2. When the killer id is none, the bot used respawn.

#### Navigation state percept

Description This percept is provided when the navigation state of the

bot changes.

Type On change

Syntax navigation(<State>,<Destination>)

Parameters <state>: Either navigating, stuck, noPath, reached or

waiting, indicating the state of the navigation.

<Destination>: The current destination of the bot or none

when the bot is not navigating.

Notes 1. For more information see the navigate action.

#### Path percept

Description This percept is provided when a

path(<Location>, <Location>) action successfully

completes.

Type On change

Syntax path(<StartId>, <EndId>, <Length>, [<Location>])
Parameters <Start>: Start location of the path used in the path action.

<End> : End of location of the path used in the path.
<Length> : The Length of the path in UT units.

[<Location>] : A list of UnrealIDs that represent a path

from the starting location to the end.

Notes 1. The first and last node in the path equal the <From>

and <To> arguments of the Path action only iff both were navpoints. Otherwise it will be the closest navpoint.

Notes 2. Likewise the distance of the path is the distance between

the starting navpoint and the destination navpoint.

#### Logic Iteration percept

Description This percept indicates the number of logic evaluations of

the bot.

Type On change

Syntax logic(<Iterations>)

 $get_{-time}$ .

### 7.3 Map percepts

The following percepts provide information about what the bot knows about the map and the game. Navigations points, pick up points, etc. but also the map name, game played, current score and victory conditions.

#### Navpoint percept

Description Information about point in the map. Together these form

a directed graph that spans the entire map.

Type Send once.

Syntax navPoint(<UnrealID>, <Position>, [<NeigsUnrealID>])

Parameters <UnrealID>: The the unique ID for this navpoint.

<Position>: The location of this navpoint on the map as

a location(x,y,z).

[<NeigsUnrealID>]: A list of ID's for the neighbouring

navpoints that are reachable from this navpoint.

# Item Pickup percept

Description Information indicating at which navpoint weapons can be

found.

Type Send once.

Syntax pickup(<UnrealID>, <Label>, <ItemType> )

Parameters <UnrealID>: The UnrealID of the navigation point this

pickup spot is placed on.

<Label>: The category of the pick up, useful for prioritiz-

ing.

<ItemType>: The actual item type of the item located on

the pickup.

Notes 1. Depending on the game setting "weapon stay", there

may not always be a weapon present on a pick up point.

2. If "weapon stay" is enabled, a weapon can only be picked up if one of the same type is not present in the bots inventor.

3. A full overview of which category Label belongs to which

item type.

<label></label>	<pre><itemtype> UT2004</itemtype></pre>	<pre><itemtype> UT3</itemtype></pre>
weapon	shield_gun, assault_rifle,	impact_hammer, enforcer,
	bio_rifle, shock_rifle,	bio_rifle, shock_rifle,
	minigun, link_gun, flak_cannon,	stinger, link_gun, flak_cannon,
	rocket_launcher, lightning_gun,	rocket_launcher, avril,
	sniper_rifle, redeemer	sniper_rifle, redeemer
ammo	assault_rifle, bio_rifle,	enforcer, bio_rifle, shock_rifle,
	shock_rifle, minigun, link_gun,	stinger, link_gun, flak_cannon,
	flak_cannon, rocket_launcher,	rocket_launcher, avril,
	lightning_gun, sniper_rifle,	sniper_rifle, redeemer
	redeemer	
health	health, mini_health, super_health	medium_vial, medium_health,
		super_health
armor	small_armor, super_armor	armor_shield_belt, armor_vest,
		armor_helmet, armor_thighpads
adrenaline	adrenaline	none
deployable	none	slow_volume
other	udamage	weapon_locker, jump_boots,
		invulnerability, berserk, udamage,
		invisibility

### Flag base percept

Description Information about the location of the flag base. This will

be the place to be for all bots.

Type Send once.

Syntax base(<Team>, <UnrealID>)

Parameters <Team>: The team this flagbase belongs to.

<UnrealID>: The UnrealID of the navpoint this flagbase is

placed upon.

Notes 1. Defend well.

2. The flag may not always be present.

#### Game info percept

Description Information about the type of game being played, the map

and the score required for winning the game.

Type Send on change.

Syntax game(<Gametype>, <Map>, <GoalScore>,<TimeLimit>) Parameters <Gametype>: A String representing the game. For CTF

typically 'BotCTFGame'.

<Map>: A string with the name of the map being played on. <GoalScore>: The first team to reach the GoalScore wins the game. For CTF this is the number of times the flag must be captured. If the goal score is zero, the game can't be won by reaching the goalscore first. If there is a time limit, the team with the highest score at the end of the

game wins.

<TimeLimit>: The remaining duration of the game from the moment this percept is received. When the time is up and the GoalScore is in a tie, the game will go into overtime. If the time limit is zero, the game won't end until the goal

score is reached.

Note If both the GoalScore and TimeLimit are zero, the game

can't be won.

#### Team score percept

Description Percept that provides information about the current state

of the game.

Type On change

Syntax teamScore(<TeamScore>, <OpponentTeamScore>) Parameters <TeamScore> score of the team this bot is on.

<OpponentTeamScore> score of the opponent team.

Notes 1. For CTF the score is the number of times the flag has

been captured.

2. Once either team reaches the goal score from the Game-

info percept, the game is over.

#### Flag status percept

Description Percept that provides information about the current state

of the flag.

Type On change with negation.

Syntax flagState(<Team>, <FlagState>)

<Team>: Colour of the flag, matches the colour of the team

that has to protect this flag.

<FlagState>: State of the flag. Either home, held or

dropped.

Notes 1. See also the See flag percept.

#### 7.4See Percepts

The following percepts cover what the bot can see.

#### See item percept

Description Provides information about an item the bot sees in the

world.

Type On change, with negation.

Syntax item(<UnrealID>, <Label>, <ItemType>, <Position>)

Parameters <UnrealID>: The UnrealID of this item.

<Label>: The category of the pick up, useful for prioritiz-

ing.

<ItemType>: The actual item type of the item located on

the pickup.

 $\operatorname{Position}$ : the UnrealID where the item is located, or the x,y,z coordinates of the item as a location(x,y,z) if the

item is not at a navpoint (e.g., it was dropped).

Notes 1. A full over view of which category Label belongs to which

item type.

<label></label>	UT2004 <itemtype></itemtype>	UT3 <itemtype></itemtype>
weapon	shield_gun, assault_rifle,	impact_hammer, enforcer,
	bio_rifle, shock_rifle,	bio_rifle, shock_rifle,
	minigun, link_gun, flak_cannon,	stinger, link_gun, flak_cannon,
	rocket_launcher, lightning_gun,	rocket_launcher, avril,
	sniper_rifle, redeemer	sniper_rifle, redeemer
ammo	assault_rifle, bio_rifle,	enforcer, bio_rifle, shock_rifle,
	shock_rifle, minigun, link_gun,	stinger, link_gun, flak_cannon,
	flak_cannon, rocket_launcher,	rocket_launcher, avril,
	lightning_gun, sniper_rifle,	sniper_rifle, redeemer
	redeemer	
health	health, mini_health, super_health	medium_vial, medium_health,
		super_health
armor	small_armor, super_armor	armor_shield_belt, armor_vest,
		armor_helmet, armor_thighpads
adrenaline	adrenaline	none
deployable	none	slow_volume
other	udamage	weapon_locker, jump_boots,
		invulnerability, berserk, udamage,
		invisibility

### See flag percept

Description Percept provided when the flag becomes visible to the bot.

Type On change, with negation.

Syntax flag(<Team>, <HolderUnrealID>, <Position>)

Parameters <Team>: Colour of the flag, matches the colour of the team

that has to protect this flag.

<HolderUnrealID>: The Unreal ID of the bot that holds

flag, none when the flag is not held.

<Position>: The x,y,z coordinates of the flag as a loca-

tion(x,y,z).

Notes 1. See also the flagStatus percept.

#### See other bot percept

Description Percept provided when another bot becomes visible to this

bot.

Type On change with negation.

Syntax bot(<UnrealID>, <Name>, <Team>, <Position>, <Weapon>, <FireMode>)

Parameters <UnrealID>: Unique identifier string for this bot assigned

by Unreal.

<Name>: The name of this bot.
<Team>: The team of this bot.

<Position>: The x,y,z coordinates of the bots position in

UT units, described as location(x,y,z)

<Weapon>: The weapon the bot is holding. none or any of

the following:

UT2004	UT3
shield_gun	impact_hammer
assault_rifle	enforcer
bio_rifle	bio_rifle
shock_rifle	shock_rifle
minigun	stinger_minigun
link_gun	link_gun
flak_cannon	flak_cannon
rocket_launcher	rocket_launcher
lightning_gun	avril
sniper_rifle	sniper_rifle
redeemer	redeemer

<Shooting>: Either primary, secondary or none to indicate if the bot is shooting and in which firemode.

#### See Pickup percept

Description Currently visible navpoint that has a ready-to-pick-up item.

Type On change with negation. Syntax pickup(<UnrealID>)

Parameters <UnrealID>: The unique ID for the navpoint this pickup is

located on.

# See Slow Volume percept

Description Information about a slow volume the bot can see.

Type On change with negation.
Syntax slowVolume([<UnrealId>])

Parameters <UnrealID>: The list of unique ID's for Navpoints laying

in the slow volume.

Notes 1. The slowVolume percept is provided when the bot can

see a deployed slow volume, use this percept to avoid it.

### 8 Know Issues & Workarounds

A list of known issues and their workaround.

#### 8.1 Window Focus in Windows 7

A known issue exists where when using Alt-Tab to switch to the UT2004 window it is possible that the window does not grab the mouse clicks. This can be resolved by holding down Alt-Tab and clicking on the UT2004 preview window with the mouse.

# 8.2 Non standard characters in Windows computer names prevent environment startup

Windows allows non-standard characters in computer names. This prevents Pogamut from starting agents which in turn prevents environment startup. To solve this you can change your computer name to one that uses only standard characters. Standard character include the letters(A-Z, a-z), digits(0-9), and hypens(-).

# 8.3 Environment will fail to launch bots when not enough spawn points are available

The current implementation of Pogamut waits until all bots are spawned. When bots are unable to spawn due to a lack of space, the whole launch of the environment fails. This typically occurs in CTF-Joust which has 2 spawn points per team. If you want to play on this map, use fewer players.

#### 8.4 Max 15 player and bots in a 16 slot server

By default an UT server starts with 16 player slots. Only 15 of these can actually be used. You can change the maximum number of available slots by changing MaxPlayers=16 under [Engine.GameInfo] in UT2004.ini.

### 8.5 Non-English UT crashes Pogmut parser

When a bot dies in a non-English version of UT the GOAL bot crashes. You can change the language to english by setting Language=int under [Engine.Engine] in UT2004.ini. On OSX UT2004.ini is located Library/Application/Support/Unreal Tournament 2004/System/.

#### 8.6 Master server connection failed

The UT server may occasionally complain that it could not connect to the master server. This can be fixed by either fixing your firewall settings or by disabling the connection to the master server. This can be done by setting <code>DoUplink=False</code> and <code>UplinkToGamespy=False</code> under <code>[IpDrv.MasterServerUplink]</code> in <code>UT2004.ini</code>

#### 8.7 Slow startup of agents

If you use an extra network adapter (e.g., when you run from Virtual Box), the function InetAddress.getLocalHost().getCanonicalHostName() that is called to determine a unique bot id can take several seconds. A workaround is to temporary turn off the virtual adapter.