INSIDE STUDIO SP · VST3 · AU

BAREBASS

SIMPLE BASS SYNTH

Step-by-step manual

Version 0.3.0 · Windows and macOS · VST3 and AU · free



insidestudiosp.com.br/barebass · contato@insidestudiosp.com.br

What is BAREBASS

BAREBASS is a **simple bass synth** with one voice: it plays one note at a time (the last one you press). It has two oscillators and a SUB, a 12 or 24 dB low-pass filter with envelope, and **unHUNF**.

- **unHUNF** (removes the low-end "hunf"): lets the sub hit at the start of the note, then takes it away. The bass stays tight and doesn't muddy up with the kick.
- **Phase-locked:** on every note the wave restarts from the same point, so every note hits the same.
- **Live display:** shows the wave, the filter and the envelope of each note as you play.

Before you start

ITEM	DETAILS
Format	VST3 instrument (Windows and Mac) and AU (Mac).
Systems	64-bit Windows 10 or 11; macOS 11 Big Sur or newer (Apple Silicon or Intel).
DAWs	Any DAW that loads VST3 or AU: Ableton Live, FL Studio, Logic, Cubase, Bitwig, Reaper, Studio One…
Price	**Free**, with license activation.
License	Valid on **1 computer**.

Download and activation


1. Go to **insidestudiosp.com.br/barebass**, enter your e-mail and choose Windows or Mac.
2. You'll receive your **license token** and the installer link. Keep the token.
3. Run the installer. The plugin goes to the system's default plugin folder.
4. Open your DAW (rescan if needed) and load BAREBASS on a MIDI track. The first time, enter your **e-mail** and **token**.

LICENSE. To view the license or move to another computer: `≡` menu › `Licença…` (license) › **Desativar este computador** (deactivate this computer), then activate on the new one.

NOT ACTIVATED? The synth opens but stays silent.

STEP 1

1 Pick a preset



NOTE (the note playing now), PRESET ▾ and the ≡ menu.

Click `PRESET ▾` and choose:

PRESET	SOUND
INIT	Neutral starting point: filter open, no envelope and no unHUNF. The plugin opens on it.
ROLLING	Rolling psy bass: SAW + SQR one octave down, closed filter with a short envelope and unHUNF at 50%. The basis for the other presets.
PLUCK	Shorter and snappier.
DEEP SUB	More sub and a more open filter, light unHUNF.
ACID 12	12 dB filter with high resonance, LEGATO and GLIDE.
SQUARE GROWL	Two detuned squares.

The `≡` menu has `Como funciona` (how it works: a summary of every control), `Licença…` and the version.

STEP 2

2 Build the tone (OSC 1, OSC 2 and SUB)



CONTROL	RANGE / DEFAULT	WHAT IT DOES
Title LED	on/off · **ON**	Turns OSC 1, OSC 2 or SUB on and off.
Wave (OSC)	SIN, TRI, SAW, SQR · OSC 1 **SAW**, OSC 2 **SQR**	Oscillator waveform.
Wave (SUB)	SIN, SQR · **SIN**	Sub waveform.
OCTAVE	OSC −2 to +2 (**0**) · SUB −2 to 0 (**−1**)	Octave relative to the played note.
FINE	−50 to +50 cents · **0**	Slight detune to fatten the sound.
LEVEL	0–100% · **80%**	Level of each one.

STEP 3

3 Sculpt with FILTER and FILTER ENV




CONTROL	RANGE / DEFAULT	WHAT IT DOES
SLOPE	12 dB or 24 dB · **24 dB**	Low-pass slope. 12 dB is more open and "acid".
CUTOFF	20 Hz – 18 kHz · **18 kHz**	Where the filter cuts.
RESONANCE	0–100% · **0%**	Boost at the cutoff point.
ENV	−100% to +100% · **0%**	How much the envelope opens (+) or closes (−) the filter on each note.
ATTACK	0 – 2000 ms · **0 ms**	Envelope rise. At 0 the attack is dry, with the wave's click.
DECAY	1 – 3000 ms · **92 ms**	Envelope fall. Short = tight, punchy bass.
SUSTAIN	0–100% · **100%**	Level the envelope holds while the note is held.
RELEASE	1 – 3000 ms · **40 ms**	How long the sound takes to fade after you let go of the note.

PSY BASS. Low CUTOFF (e.g. 180 Hz), high ENV (e.g. +72%), short DECAY (e.g. 92 ms) and SUSTAIN at 0%: that's the ROLLING preset recipe.

STEP 4

4 Clean up the low end with unHUNF



After the filter, unHUNF lets the sub (10 to 50 Hz) **hit in full at the start of the note** and then takes it away. The higher the knob, the faster and deeper.

- **unHUNF**: 0–100% · **0%** = off.
- **SUB DECAY**: how long the low end takes to drop (from 300 ms at the start of the knob to 15 ms at max).
- **GR**: how much unHUNF is taking off the sub right now.
- The graph shows the low end over the first 500 ms of the note; the dashed line is the sub without unHUNF.

It only touches the **level** of the low end: the sub's pitch stays exact from start to end of the note. On a 1/16 note at 143 BPM, the low end below 50 Hz drops about 6 dB with the knob at 50% and about 30 dB at 100%.

STEP 5


5 MASTER: mode, glide and velocity



CONTROL	RANGE / DEFAULT	WHAT IT DOES
MONO / LEGATO	**MONO**	MONO retriggers the envelope on every note; LEGATO doesn't retrigger when notes overlap.
VOLUME	−36 to +6 dB · **−3 dB**	Output level.
GLIDE	0–500 ms · **0 ms**	Slides from one note to the next.
VELO	0–100% · **60%**	How much note velocity changes the level and the ENV opening. At 0% every note comes out the same.

STEP 6

6 Read the display



DISPLAY	WHAT IT SHOWS
WAVE · NOW	Two cycles of the wave playing now: **PRE-FILTER** (orange, before the filter), **OUTPUT** (green, what comes out) and **SUB** (dashed lilac). At the top, the note's frequency and where the filter is right now.
FILTER	The filter curve (12 or 24 dB). **NOW** = where it is right now; **ENV SWEEP** (dashed) = how far the envelope opens it.
FILTER ENV	The envelope shape (A, S and R at the top, DECAY in the title), with a dot moving along the played note.

KNOBS. Drag up and down (hold **Shift** for fine adjustment), use the mouse wheel or **double-click** to return to the default. Drag the bottom-right corner to resize the window.

FAQ and troubleshooting

SITUATION	WHAT TO DO
No sound	Check that the license is active (≡ menu › Licença…) and that OSC 1, OSC 2 or SUB is on (title LED).
I play chords and only one note sounds	That's normal: BAREBASS has one voice and plays the last note you press.
The bass muddies up with the kick	Raise **unHUNF** (start at 50%). Use it together with ALIGN to keep kick and bass in phase.
Sound too dull	Raise CUTOFF or ENV.
Soft notes come out too quiet	Lower **VELO** (at 0% every note comes out the same).
The envelope doesn't retrigger on legato notes	It's in LEGATO. To make every note hit again, use MONO.
I changed computers	On the old one: ≡ menu › Licença… › Desativar este computador. Then activate on the new one.

30-second summary

1. Download from insidestudiosp.com.br/barebass and activate with e-mail + token.
2. Pick the **ROLLING** preset to start.
3. Set the waves and octaves on the OSCs and the SUB.
4. CUTOFF, ENV and DECAY to shape the bass.
5. **unHUNF** to clear the mud from the low end.
6. VOLUME, GLIDE and VELO on the MASTER.

SUPPORT. Questions, suggestions or issues: **contato@insidestudiosp.com.br** · **insidestudiosp.com.br**