INSIDE STUDIO SP · VST3 · AU

GROOVADOR

SYNTHESIZED PERCUSSION

Step-by-step manual

Version 0.2.0 · Windows and macOS · VST3 and AU



insidestudiosp.com.br/groovador · contato@insidestudiosp.com.br

What is GROOVADOR

GROOVADOR is a **synthesized percussion drum machine**, with no kick, and a style-based groove generator. It builds the rim, snare, clap, hats, shaker and percussion pattern on top of your kick, in sync with your DAW.

- **8 instruments**: RIM, SNARE, CLAP, HAT FECH. (closed hat), HAT ABERTO (open hat), SHAKER, PERC 1 and PERC 2, each with 5 sound models and 10 knobs.
- **Groove generator** by style: PSY FULL, PSY PROG, TECHNO, HOUSE, TRIBAL and BREAK.
- **Timbre variation**: every so often the instruments switch to a B timbre, so the groove never sits still.
- **ARRASTAR MIDI** (drag MIDI): takes the groove into your DAW, one file per piece.

Before you start

ITEM	DETAILS
Format	VST3 instrument (Windows and Mac) and AU (Mac).
Systems	64-bit Windows 10 or 11; macOS 11 Big Sur or newer (Apple Silicon or Intel).
DAWs	Any DAW that loads VST3 or AU: Ableton Live, FL Studio, Logic, Cubase, Bitwig, Reaper, Studio One…
Presets	72 factory presets (12 per style) plus your own presets.
License	Valid on 2 computers. Internet only to activate: after that it runs up to 45 days offline and renews by itself.

Installation and activation

1. Download the installer from the link in your purchase e-mail (Windows or Mac).
2. Run the installer. The plugin goes to the system's default plugin folder.
3. Open your DAW and, if needed, have it scan for new plugins (rescan).
4. Load GROOVADOR on a MIDI track (as an instrument). The first time, enter your **e-mail** and **license token**.

> **LICENSE.** To view the license or move to another computer: click the **preset name** › `Licença…` (license) › deactivate on the old computer and activate on the new one.

> **NOT ACTIVATED?** The instrument opens but stays silent.

STEP 1

1 Pick a preset



DAW TEMPO, SYNC light, PADRÃO (pattern) number, preset name, ◀ ▶, + and the output meter.

- `◀` `▶` step through presets; `+` saves the current sound as a new preset.
- Click the **preset name** to open the list: the 72 factory presets sorted by style (PSY FULL, PSY PROG, TECHNO, HOUSE, TRIBAL, BREAK) and your own under USER.
- Same menu: save, rename and delete user presets, `Tamanho da janela` (window size) and `Licença…`.

Each factory preset is a style with its own kit and groove. User presets store everything: values and grid.

> **PRESETS DON'T CHANGE:** the locks, mute/solo and the TOCAR mode.

STEP 2

2 Choose how it plays (TOCAR)


TOCAR (PLAY)	HOW IT WORKS
COM PLAY (with play; default)	The groove runs in sync with the DAW when you hit play. The top of the grid shows "SYNC COM O DAW" (synced to DAW) or "AGUARDANDO PLAY" (waiting for play).
PADS	The grid stops and each MIDI note plays one instrument, like a drum sampler.

Notes in PADS mode

C1	D1	E1	F1	G1	A1	B1	C2
RIM	SNARE	CLAP	HAT FECH.	HAT ABERTO	SHAKER	PERC 1	PERC 2

STEP 3


3 Generate the groove (GERADOR DE GROOVE)



CONTROL	OPTIONS / DEFAULT	WHAT IT DOES
ESTILO (style)	PSY FULL, PSY PROG, TECHNO, HOUSE, TRIBAL, BREAK · **PSY FULL**	Where each instrument usually hits in that style.
COMPASSO (meter)	4/4 or 3/4 · **4/4**	Time signature.
TAMANHO (length)	1, 2 or 4 bars · **2**	Grid length (96 steps max).
RATE	1/16, 1/16T, 1/8 · **1/16**	Length of each step.
DENSIDADE (density)	0–100% · **60%**	How much of the style comes in: higher = more hits.
SWING	0–75% · **10%**	Delays every other step (groove).
GHOST	0–100% · **35%**	Soft hits in the gaps.
ROLL	0–100% · **20%**	2 or 3 hits inside one step.
HUMANO (human)	0–100% · **20%**	Slightly shifts the strength and timing of each hit.

Bar 1 is randomized and the following bars repeat it with a few changes, like a real drummer.


Randomize, undo and MIDI



BUTTON	WHAT IT DOES
GERAR GROOVE (generate groove)	Randomizes everything: rhythm, timbres, fills and velocity. Skips the parts whose lock is closed.
RITMO · TIMBRES · FILLS · VELOCITY	Each die randomizes only that part (RITMO = rhythm). The **lock** keeps GERAR GROOVE from touching it.
DESF. (undo)	Undoes the last randomization (up to 32 steps back).
ARRASTAR MIDI	Drag into your DAW: you get **one file per piece** that has notes (e.g. "GROOVADOR - preset - SNARE.mid"), each on that piece's pad note. In Ableton, hold **Ctrl** (Windows) or **Cmd** (Mac) as you drop so each piece lands on its own track.

STEP 4

4 Edit the grid (GROOVE)



One row per instrument (in the order of the INSTRUMENTOS list) and one column per step.

ACTION	RESULT
Click a step	Turns the hit on or off.
Drag up/down on a hit	Changes its strength (velocity).
Right-click (or Ctrl+click)	Cycles: strong → ghost → roll ×2 → roll ×3 → maybe (plays 50% of the time).

The coloured strip below the grid shows, bar by bar, who is on timbre **A** and who is on **B**. Below it: length, meter, rate and FILL.

STEP 5

5 Set up the instruments



- **Click the name** of an instrument to hear it and open its sound in the SOM (sound) panel.
- `M` = mute · `S` = solo.
- The row's **die**: randomizes a new sound for that instrument only.
- The **A**/**B** tag shows whether the instrument is on timbre A or B right now.
- HAT FECH. chokes HAT ABERTO, just like a real drum machine.

STEP 6

6 Shape the sound (SOM)



The display shows the selected instrument's waveform. Pick the **model**:

MODEL	SOUND (AND WHAT BODY DOES)
ANALÓG. (analog)	Sine with pitch env and filtered noise. BODY = 2nd membrane mode.
808	Saturated sine. BODY = saturation.
FM	Bongo, zap. BODY = modulator ratio.
METAL	6 squares at the 808 hat ratios. BODY spreads the ratios.
RUÍDO (noise)	Clap and shaker. BODY = 1 to 4 claps (the clap).

The **die** next to the models randomizes a new sound for the instrument.

KNOB	RANGE	WHAT IT DOES
TUNE	−24 to +24 st	Tuning.
DECAY	10 ms – 2 s	Sound length.
TONE	200 Hz – 16 kHz	Noise filter cutoff (high-pass on hats and shaker, band-pass on the others).
SNAP	0–100%	Attack click and pitch env speed.
BODY	0–100%	Depends on the model (table above).
NOISE	0–100%	How much noise comes in.
PITCH ENV	−24 to +24 st	Pitch drop (or rise) on the attack.
DRIVE	0–100%	The instrument's own saturation.
PAN	L100 to R100	Stereo position.
LEVEL	−30 to +6 dB	Instrument volume.

KNOBS. Drag up and down; **double-click** returns to the default value.

STEP 7

7 Vary the timbres (VARIAÇÃO DE TIMBRE)



Each instrument has a **B timbre** (different pitch, decay, tone, snap, body and pitch env). The TIMBRES die randomizes a new B.

CONTROL	OPTIONS / DEFAULT	WHAT IT DOES
MUDA A CADA (change every)	½, 1, 2, 4, 8 bars · **1**	How often the switch happens.
MODO (mode)	A ↔ B, **CONVERSA**, DERIVA	**A ↔ B** switches them all together; **CONVERSA** (conversation) puts half of the selected ones on B while the other half stays on A, then they swap; **DERIVA** (drift) changes gradually.
QUANTO (amount)	0–100% · **45%**	How different B is from A.
QUEM VARIA (who varies)	on/off per instrument	Which instruments take part in the variation (default: SNARE, HAT F., PERC 1 and PERC 2).
FILL A CADA (fill every)	—, 4 or 8 bars · **8**	Replaces the 2nd half of the cycle's last bar with a fill.

STEP 8

8 Effects and output



BLOCK	CONTROLS AND DEFAULTS
DRIVE	TIPO (type) TAPE, TUBE or FOLD; DRIVE (**20%**) and TONE (**80%**).
DELAY PING-PONG	ON (**off**); TIME 1/16 to 3/8 in tempo (**3/16**); FEEDBACK 0–95% (**40%**); MIX (**18%**).
REVERB	ON (**on**); SIZE (**45%**); MIX (**14%**).
SAÍDA (output)	VOLUME −36 to +6 dB (**−6 dB**).

FAQ and troubleshooting

SITUATION	WHAT TO DO
I hit play and there's no sound	Check that TOCAR is on **COM PLAY** and that the license is active (preset name › Licença...). Also make sure no instrument is soloed.
I play notes and nothing happens	Notes only trigger the instruments in **PADS** mode (C1 to C2).
It got too busy	Lower DENSIDADE, GHOST and ROLL and hit RITMO again.
It sounds "robotic"	Raise HUMANO and SWING.
I like the rhythm, I want other sounds	Close the RITMO lock and hit TIMBRES or GERAR GROOVE.
The sound changes by itself	That's VARIAÇÃO DE TIMBRE. Turn instruments off in QUEM VARIA or lower QUANTO.
I randomized and lost what I liked	**DESF.** button.
I want one track per piece in Ableton	ARRASTAR MIDI holding Ctrl (Windows) or Cmd (Mac) as you drop.
There's no kick	On purpose: GROOVADOR builds the percussion around your kick.

30-second summary

1. GROOVADOR on a MIDI track, activate the license.
2. Pick a preset or an ESTILO.
3. **GERAR GROOVE** until you like it; lock what you want to keep.
4. Tweak the grid by hand and the sound in the SOM panel.
5. VARIAÇÃO DE TIMBRE and FILL to keep the groove moving.
6. **ARRASTAR MIDI** to take it into your DAW.

> **SUPPORT.** Questions, suggestions or issues: **contato@insidestudiosp.com.br** · **insidestudiosp.com.br**