INSIDE STUDIO SP · VST3 · AU

RESENHA

CALL & RESPONSE · HUB

Step-by-step manual

Version 0.7.0 · Windows and macOS · VST3 and AU



insidestudiosp.com.br/resenha · contato@insidestudiosp.com.br

What is RESENHA

RESENHA is a **call & response** instrument. Four slots (A, B, C and D) take turns on a phrase generated in key: one asks, another answers, like a conversation between leads. Everything plays in sync with your DAW.

- **Phrase generator:** writes the melody in the scale and root you pick, with rhythm, gate and contour.
- **Timbre switching:** every few notes (or every ½ / 1 bar) the turn passes to the next slot, and the answer can repeat, vary or mirror the call.
- **INTERNO (internal) or PLUGIN slots (HUB):** each slot uses RESENHA's own sound (FM or VA engines) or loads one of your synths, such as Serum, Sylenth1, Vital or Diva.
- **ARRASTAR MIDI (drag MIDI):** drops the conversation into your DAW as a .mid file, one channel per slot.

Before you start

ITEM	DETAILS
Format	VST3 instrument (Windows and Mac) and AU (Mac).
Systems	64-bit Windows 10 or 11; macOS 11 Big Sur or newer (Apple Silicon or Intel).
DAWs	Any DAW that loads VST3 or AU: Ableton Live, FL Studio, Logic, Cubase, Bitwig, Reaper, Studio One…
Presets	120 factory presets in 10 categories, plus your own presets and imported banks.
License	Valid on 2 computers. Internet only to activate: after that it runs up to 45 days offline and renews by itself.

Installation and activation


1. Download the installer from the link in your purchase e-mail (Windows or Mac).
2. Run the installer. The plugin goes to the system's default plugin folder.
3. Open your DAW and, if needed, have it scan for new plugins (rescan).
4. Load RESENHA on a MIDI track (as an instrument). The first time, enter your **e-mail** and **license token**.

LICENSE. To view the license or move to another computer: click the **preset name** › `Licença…` (license) › deactivate on the old computer and activate on the new one.

NOT ACTIVATED? The instrument opens but stays silent.

STEP 1

1 Pick a preset



Top of the window: BPM and clock status, preset name, ◀ ▶, + and the output meter.

- ◀ ▶ step through presets; `+` saves the current sound as a new preset.
- Click the **preset name** to open the list: the categories PSY CLÁSSICO, FULL ON, DARK, GOA, PROG, HI-TECH, MINIMAL, FX, CONVERSA FM and LEAD FALANTE (12 presets each) and your own presets under USER.
- Same menu: save, rename and delete user presets, `Importar banco de presets…` (import preset bank; **.rsnbank** files), `Tamanho da janela` (window size, 75% to 200%) and `Licença…`.

Each preset holds the 4 timbres, the generator, timbre switching, effects and the phrase. The plugin opens on the **"Boca Aberta"** preset.

> **PRESETS DON'T CHANGE:** the locks, the TOCAR mode and the PLUGIN slot settings. So you can switch presets live without losing your setup.

STEP 2


2 Choose how it plays (TOCAR)

TOCAR (PLAY)	HOW IT WORKS
COM NOTA (with note; default)	The phrase only plays while a note is held in the clip or on the keyboard, transposed by it. **C3 (note 60) = the phrase as written.** The top shows "SEGURE UMA NOTA" (hold a note) while waiting.
SEMPRE (always)	The phrase plays with the DAW's transport. The note only transposes.
NOTAS (notes)	The sequencer turns off and RESENHA plays the clip's notes like a regular synth. The MIDI channel picks the slot: channels 1 to 4 = A to D (other channels play A). Each slot plays one note at a time, with its own GLIDE.

> **TIP (NOTAS).** Drag the conversation into a clip with ARRASTAR MIDI (it already comes out with one channel per slot), set TOCAR to NOTAS and edit the notes in your DAW.

STEP 3

3 Build the phrase (GERADOR DE FRASE)



CONTROL	RANGE / DEFAULT	WHAT IT DOES
ESCALA (scale)	CHROMATIC, MAJOR, MINOR, DORIAN, PHRYGIAN… · **PHRYGIAN**	Scale of the phrase's notes.
TÔNICA (root)	C to B · **C#**	Root note of the scale.
COMPASSOS (bars)	1, 2 or 4 · **2**	Phrase length (64 steps max).
RATE	1/32, 1/16T, 1/16, 1/8T, 1/8 · **1/16**	Length of each step.
OITAVAS (octaves)	1 to 3 · **2**	How many octaves the melody can span.
DENSIDADE (density)	0–100% · **70%**	How many steps have a note (the rest are rests).
GATE	5–100% · **45%**	Note length: short = staccato, long = legato.
VAR. GATE	0–100% · **30%**	How much the gate varies from note to note.
SWING	0–75% · **0%**	Delays every other step (groove).

CONTORNO DAS NOTAS (note contour)

CONTOUR	SHAPE OF THE MELODY
MOTIVO (motif)	Repeats a short figure with variations.
CORRIDA (run)	Climbs like a staircase (stepwise or arpeggiated) and starts again at the bottom.
QUEDA (fall)	Goes down.
ONDA (wave)	Goes up and comes back.
PEDAL	Alternates a fixed note (the root) with a moving line.
RETA (flat)	Every note on the root. Rhythm, gate, PAPO and timbre switching carry on; the written melody is kept and comes back when you pick another contour. GERAR CONVERSA never picks RETA.

STEP 4

4 Set up the conversation (TROCA DE TIMBRE)




CONTROL	OPTIONS / DEFAULT	WHAT IT DOES
VOZES NA CONVERSA (voices)	1 to 4 · **3**	How many slots join the conversation (A, B, C, D).
TROCA A CADA (switch every)	1, 2, 3, 4, 6, 8 notes, ½C or 1C · **4**	After how many notes (or ½ / 1 bar) the turn passes to the next slot.
ORDEM (order)	A→B→C, PING-PONG, SORTEIO (random)	Who speaks after whom.
RESPOSTA (answer)	LIVRE, **ECO**, VARIA, INVERTE	LIVRE (free) plays what is written; ECO (echo) repeats the call; VARIA (vary) repeats it changing a few notes; INVERTE (invert) mirrors it (what went up goes down).
ALTURA DA RESPOSTA (answer pitch)	MESMA (same), **+OITAVA**, +5ª, −OITAVA	At what pitch the answer comes in (OITAVA = octave).
PAPO (chat)	0–100% · **0%**	How much the switching feels like a real conversation: lines of different lengths, breathing room or answers overlapping, answers off the grid, legato on neighbouring notes. 0% = rigid grid.

Even lines ask (play as written) and odd lines answer. Outside LIVRE, the answer resolves on the root: the call is left hanging and the answer closes it.

STEP 5


5 Read the CONVERSA (conversation)



- At the top: phrase length, RATE and the scale.
- Each note shows in the **colour of the slot** speaking; answers have a light outline.
- The curve at the end of a line is the **BEND** (the dive of the last note).
- The **FALA** (line) lane shows who speaks in each section and the answer type (e.g. "B ECO").
- Below, a sentence sums up the conversation (e.g. "a resposta faz ECO (+OITAVA) · ordem SORTEIO" = the answer echoes, order random).

STEP 6

6 Randomize, undo and take it to the DAW



BUTTON	WHAT IT DOES
GERAR CONVERSA (generate conversation)	Randomizes everything at once: notes, rhythm, gate, timbres and the conversation. Skips the parts whose lock is closed.
NOTAS · RITMO · GATE (notes · rhythm · gate)	Each die randomizes only that part. The **lock** next to it keeps GERAR CONVERSA from touching it.
TIMBRES (timbres)	Randomizes the slots' sounds. Respects each slot card's lock; the button's lock locks or unlocks all 4 at once. On a PLUGIN slot, it picks a preset from that plugin (when the plugin exposes its preset list).
DESF. (undo)	Undoes the last randomization (keeps up to 32 steps back).
ARRASTAR MIDI	Click and drag onto a DAW track: the phrase becomes a **.mid** file, one channel per slot (A = 1 … D = 4).

> **QUICK WORKFLOW.** Hit GERAR CONVERSA until you like it. Found a good rhythm? Close the RITMO lock and keep randomizing just the notes and timbres.

Each slot card also has a **die** (randomizes only that slot) and a **lock** (protects the slot from the TIMBRES randomizer).

STEP 7

7 Shape each slot's sound (INTERNO)



Slot A card in VA

In `INTERNO` (internal) mode the sound comes from RESENHA itself. At the top of the card: the waveform and the **ENGINE**:

- **VA**: virtual analog, like the psy leads and arps made on subtractive synths. SAW, SQUARE, PULSE 25 and PULSE 12 waves, up to 8 detuned voices spread in stereo, a 2nd oscillator and a 24 dB filter.
- **FM**: 2 operators (modulator with feedback → carrier), for metallic tones. SINE, TRI, SAW, SQUARE waves.

The 1st row of knobs changes name with the ENGINE:

FM	VA	WHAT IT DOES
RATIO	**OSC 2**	FM: modulator ratio (0.50 to 13.0). VA: 2nd oscillator interval.
FM	**OSC 2 LVL**	FM: modulation amount. VA: OSC 2 level.
FEEDBACK	**DETUNE**	FM: feedback. VA: detune between voices.
FM DEC	**ENV DEC**	Attack envelope time (5 ms to 2 s).
UNISON	**VOICES**	FM: detuned copies in stereo. VA: 1 to 8 voices.

INTERNO × PLUGIN. The switches at the top of the card change where the slot's sound comes from. The PLUGIN slot is covered in Step 8.

The slot's other knobs

KNOB	RANGE	WHAT IT DOES
FILTER	LP, BP, VOWEL, HP	Filter type. **VOWEL** = two formants: CUTOFF picks the vowel (u-o-a-e-i) and the lead "talks".
CUTOFF	150 Hz – 18 kHz	Filter cutoff (in VOWEL, the vowel).
RESO	0–100%	Resonance.
F.ENV	0–100%	How much the filter opens on the attack (in VOWEL, opens the "mouth").
MOVE	0–100%	Tempo-synced LFO that moves the FM and the filter/vowel.
RATE	1/16 to 2 BARS	MOVE period.
DECAY	30 ms – 3 s	Note length.
P.ENV	−24 to +24 st	Pitch on the attack (the "zap"), falling over the FM DEC / ENV DEC time.
GLIDE	0–500 ms	Glide from the same slot's previous note.
BEND	−24 to +24 st	The dive: the last note of each line bends over its whole length (starts slow and speeds up). 0 = straight.
PAN	L100 to R100	Stereo position.

Each slot is monophonic (one note at a time); tails from different slots overlap.

8

STEP 8

Use your own synths (PLUGIN slot)

1. On the slot card, click `PLUGIN`. **ESCOLHER PLUGIN** (choose plugin) opens with your installed instruments (VST3 on Windows; AU and VST3 on Mac), with search by name or maker and starred favourites.
2. The first time, click `BUSCAR PLUGINS DE NOVO` (rescan plugins). The scan reads instruments only, outside the DAW: any plugin that hangs, crashes or won't open is skipped. `PULAR ESTE PLUGIN` (skip this plugin) moves on right away.
3. Pick the synth. The card shows name, maker, preset and CPU, with `ABRIR` (open; plugin window), `TROCAR` (swap) and `BYP` (mutes the slot, leaving silence on its turn).

PLUGIN slot settings

CONTROL	RANGE / DEFAULT	WHAT IT DOES
OITAVA (octave)	−3 to +3 · **0**	Shifts the notes the slot receives up or down.
VELOC.	1–127 · **100**	Note velocity (accents go out at 127).
BEND	−100% to +100% · **0**	MIDI pitch bend on the note that closes the line.
NÍVEL (level)	−36 to +6 dB · **0 dB**	Slot volume.
4 LIGAR knobs (link)	—	Click `+ LIGAR` and move a control in the plugin window ("MEXA NO PLUGIN" appears): the knob now drives that control and can be automated in the DAW.

- On a PLUGIN slot, RESENHA sends only the conversation as MIDI; the sound and presets belong to your plugin.
- The conversation stays between C1 and B3 (C3 = note 60). To move a slot up or down, use its OITAVA.
- The DAW project saves the plugin, its sound and each slot's settings. If the plugin isn't installed on the machine, the slot warns you and the sound isn't lost when you save.
- RESENHA presets don't change the slots' plugins.

STEP 9

9 Effects and output



BLOCK	CONTROLS AND DEFAULTS
DRIVE	TIPO (type) TAPE, TUBE or FOLD; DRIVE (**20%**) and TONE (**70%**).
DELAY PING-PONG	On/off switch (**on**); TIME 1/16 to 3/8 in tempo (**3/16**); FEEDBACK 0–95% (**45%**); MIX (**25%**).
REVERB	On/off switch (**on**); SIZE (**55%**); MIX (**18%**).
SAÍDA (output)	VOLUME −36 to +6 dB (**−6 dB**); **DUCK** (**0%**): the sound dips on every beat and comes back within half a beat, like kick sidechain.

FAQ and troubleshooting

SITUATION	WHAT TO DO
I hit play and there's no sound	In **COM NOTA** mode the phrase only plays while a note is held: put a long note (e.g. C3) in the clip or switch to **SEMPRE**. Also check that the license is active (preset name › Licença…).
The phrase is in the wrong key	Adjust ESCALA and TÔNICA. In COM NOTA, remember the held note transposes: C3 = as written.
I want to edit the notes in the DAW	ARRASTAR MIDI into a clip and set TOCAR to **NOTAS**. Channels 1 to 4 pick slots A to D.
My synth isn't in the list	Click BUSCAR PLUGINS DE NOVO. The scan only lists instruments (effects are left out) and skips anything that hangs or won't open; those go to the blocked list with the reason.
The PLUGIN slot is too high or too low	Use the slot's OITAVA (−3 to +3).
I randomized and lost what I liked	**DESF.** button. To protect a part, close its lock.
It sounds "stiff", like a sequence	Raise **PAPO** and use TROCA A CADA ½C or 1C.
It clashes with the kick	Raise **DUCK**.
Window too big or too small	Preset name › Tamanho da janela (75% to 200%).
A new-version notice showed up	Click **ATUALIZAR** (update): it downloads and installs the new version (Windows and Mac).

30-second summary

1. RESENHA on a MIDI track, activate the license.
2. Pick a preset (click the name).
3. TOCAR: COM NOTA (hold C3), SEMPRE or NOTAS.
4. ESCALA, TÔNICA and CONTORNO to fit your track.
5. **GERAR CONVERSA** until you like it; lock what you want to keep.
6. Want your own synth? **PLUGIN** slot.
7. **ARRASTAR MIDI** to take the phrase into your DAW.

SUPPORT. Questions, suggestions or issues: **contato@insidestudiosp.com.br** · **insidestudiosp.com.br**