INSIDE STUDIO SP · VST3 · AU

KNOB SERIES

TEN ONE-BIG-KNOB PEDALS

Step-by-step manual

10 plugins · Windows and macOS · VST3 and AU



insidestudiosp.com.br · contato@insidestudiosp.com.br

What is the KNOB SERIES

Ten pedals with one big knob, all locked to the tempo. Sidechain, trance gate, filter, auto-pan, stutter, delay, reverse, tape stop, pitch and bitcrush. On every one: TRIGGER from the DAW, from MIDI or from audio, plus RATE, SHAPE and MIX.

PLUGIN	WHAT IT'S FOR
FOLE	Tempo-synced sidechain: the volume ducks and comes back in time.
PICADOR	16-step trance gate.
MARÉ	Low-pass filter that opens and closes in time.
VAIVÉM	Tempo-synced auto-pan.
REPIQUE	Stutter / beat repeat.
ECO	Tempo-synced tape delay. The dry signal passes untouched and MIX sets only the repeats.
AVESSO	Slices of the bar played backwards.
FREIO	Tape stop / tape start.
ESCADA	Pitch sequencer: the sound changes note on every step.
MASTIGA	Rhythmic bitcrush.

Before you start

ITEM	DETAILS
Formats	VST3 (Windows and Mac) and AU (Mac).
Systems	Windows 10 or 11, 64-bit · macOS 11 Big Sur or newer (Apple Silicon or Intel).
DAWs	Any DAW that loads VST3 or AU: Ableton Live, FL Studio, Logic, Cubase, Bitwig, Reaper, Studio One…

Install and activate

Installation

1. Download the installer from the link in your purchase e-mail (Windows or Mac).
2. **Windows:** run the .exe installer and follow the screens. The plugins go to `C:\Program Files\Common Files\VST3`.
   Mac: open the .dmg, double-click the .pkg installer and follow the screens (VST3 and AU in `/Library/Audio/Plug-Ins`).
3. Close and reopen your DAW. If the plugin doesn't show up, have the DAW rescan its plugins (in Logic: Logic Pro › Settings › Plug-in Manager › "Reset & Rescan Selection").

> **SECURITY WARNING.** The installers are new, so Windows or macOS may show a warning. Windows: "More info" › "Run anyway". Mac: System Settings › Privacy & Security › "Open Anyway". Always download from the link in the e-mail or from the website.

Activation

1. Open any plugin from the pack in your DAW. The activation screen appears.
2. Enter your **purchase e-mail** and your **token** (`ISP-XXXX-…`) and click **ATIVAR** (activate). Internet is only needed at this moment.
3. **Activating one plugin unlocks all 10 plugins in the pack** on that computer.

> **LICENSE.** Valid on up to **2 computers**. Once activated, it works offline for up to **45 days** and renews by itself when the computer goes online. To switch computers: right-click an empty area of the pedal › `Licença…` (license) › **Desativar este computador** (deactivate this computer), then activate on the new one.

> **WITHOUT ACTIVATION**, the plugin opens but passes the sound straight through, unprocessed.

The controls (same on all 10)

The big knob goes from **0** (none) to **10** (full). The lamps around it light up to the current value and breathe along with the effect.



CONTROL	WHAT IT DOES
Knob	The amount of effect (what it does on each pedal is on the next pages). Drag up/down; **Shift** = fine adjust; **double-click** resets to default; the mouse wheel turns it too.
TRIGGER	3-position switch. **INT**: follows the DAW timeline (when stopped, keeps running at the last BPM). **MIDI**: every incoming note restarts the movement. **ÁUDIO** (audio): every sidechain hit restarts it; with no sidechain connected, it uses its own input. Click INT, MIDI or ÁUDIO (or the lever, to step to the next one).
RATE	Time division, 7 positions (each pedal has its own). Right-click opens the list.
SHAPE	Shape of the movement, drawn on the display with a cursor at the point the sound is at. Click the right half of the display for the next shape and the left half to go back; right-click opens the list.
MIX	Blend with the original sound. On ECO the dry signal stays whole and MIX sets only the repeats.

The **LED** next to TRIGGER blinks on every beat (INT) or on every note/hit (MIDI/ÁUDIO).

Sidechain and MIDI in Ableton Live

- **ÁUDIO:** on the pedal, under *Sidechain*, pick the track that will trigger it (the kick, for example).
- **MIDI:** on a MIDI track, under *MIDI To*, pick the pedal's track and, below it, the pedal.

In other DAWs the path has different names: look for "sidechain" for audio, and for routing a track's MIDI output to the plugin.

> **LICENSE.** Right-click an empty area of the pedal (outside the controls) › `Licença…`.



FOLE

Tempo-synced sidechain: the volume ducks and comes back in time.

Knob	Sidechain depth (10 = the sound disappears on the hit). Default: 6.
SHAPE	CLÁSSICO (classic), SUAVE (smooth), BOMBA (pump), CORTE (cut), RAMPA (ramp), INVERSO (inverse)
RATE	1/16 · 1/8 · **1/4** · 1/2 · 1 COMP · 2 COMP · 4 COMP (COMP = bar; default in bold)

TIP. On bass or pads, set TRIGGER to ÁUDIO with the kick in the sidechain: every kick hit triggers the duck, even through fills and variations.



PICADOR

16-step trance gate.

Knob	Up to 6: how much it cuts. From 6 to 10: the gate also gets shorter. Default: 6.
SHAPE	TRANCE 1, TRANCE 2, RETO (straight), GALOPE (gallop), CONTRATEMPO (offbeat), TRESILLO, QUEBRADO (broken)
RATE	1/32 · 1/16T · **1/16** · 1/8T · 1/8 · 1/4 · 1/2 (default in bold)

TIP. On pads and long chords, change the SHAPE to change the gate rhythm without touching anything else.



MARÉ

Low-pass filter that opens and closes in time.

Knob	How far the low-pass sweeps down (to ~30 Hz), with resonance. Default: 6.5.
SHAPE	SENO (sine), TRIÂNGULO (triangle), SOBE (up), DESCE (down), QUADRADO (square), ALEATÓRIO (random)
RATE	1/16 · 1/8 · 1/4 · 1/2 · 1 COMP · **2 COMP** · 4 COMP (default in bold)

> **TIP.** SOBE with a long RATE (2 or 4 COMP) opens the filter gradually, great for build-ups.



VAIVÉM

Tempo-synced auto-pan.

Knob	Auto-pan width. Default: 8.
SHAPE	SENO, TRIÂNGULO, QUADRADO, SOBE, ALEATÓRIO
RATE	1/16 · 1/8T · 1/8 · 1/4 · **1/2** · 1 COMP · 2 COMP (default in bold)

> **TIP.** QUADRADO on hats and percussion makes the sound jump from side to side in time.



REPIQUE

Stutter / beat repeat.

Knob	How much of the end of the bar turns into repeats (10 = the whole bar). RATE is the slice size. Default: 4.
SHAPE	ROLL (ever-smaller slices), REPETE (repeat), DECAI (decay), TRAVA (lock: repeats the start of the bar)
RATE	1/32 · 1/16T · **1/16** · 1/8T · 1/8 · 1/4 · 1/2 (default in bold)

> **TIP.** ROLL with the knob low creates a "drum roll" only at the end of the bar, great for fills.



ECO

Tempo-synced tape delay. The dry signal passes untouched and MIX sets only the repeats.

Knob	Feedback (0 = a single repeat; on DUB it saturates and never stops). Default: 5.5.
SHAPE	SIMPLES (simple), PING-PONG, FITA (tape), DUB, ESPALHADO (spread)
RATE	1/16 · 1/8T · 1/8 · **3/16** · 1/4 · 3/8 · 1/2 (default in bold)

> **TIP.** TRIGGER on MIDI or ÁUDIO turns it into a "dub throw": only what plays right after the note or hit goes into the delay.



AVESSO

Slices of the bar played backwards.

Knob	How many slices of the bar play backwards (0 = none, 10 = all). Default: 5.
SHAPE	ALTERNADO (alternating), FIM DO COMP. (end of bar), INÍCIO (start), ALEATÓRIO (which slices flip first)
RATE	1/16 · 1/8T · **1/8** · 1/4T · 1/4 · 1/2 · 1 COMP (default in bold)

> **TIP.** FIM DO COMP. with the knob low flips only the last slice: a short reverse right before the next bar.



FREIO

Tape stop / tape start.

Knob	How much of the cycle the slowdown takes (up to half). Default: 3.
SHAPE	PARADA (stop), PARTIDA (start), PARA E VOLTA (stop and return), MEIA VELOCIDADE (half speed)
RATE	1/8 · 1/4 · 1/2 · **1 COMP** · 2 COMP · 4 COMP · 8 COMP (default in bold)

> **TIP.** With TRIGGER on MIDI, every note restarts the movement: write a note where the slowdown should start.



ESCADA

Pitch sequencer: the sound changes note on every step.

Knob	Size of the pitch jumps, always within the scale/chord. Default: 7.
SHAPE	SOBE, DESCE, SOBE E DESCE (up and down), OITAVAS (octaves), ARPEJO MAIOR (major arpeggio), ARPEJO MENOR (minor arpeggio), QUINTAS (fifths), ALEATÓRIO
RATE	1/32 · 1/16 · 1/8T · **1/8** · 1/4 · 1/2 · 1 COMP (default in bold)

> **TIP.** On a sustained chord, ARPEJO MAIOR or ARPEJO MENOR turns the sound into a tempo-synced arpeggio.



MASTIGA

Rhythmic bitcrush.

Knob	How hard it bites: drive, bits (down to 3) and rate (down to /32) at the peak of the shape. Default: 8.5.
SHAPE	QUADRADO, SENO, SOBE, DESCE, DEGRAUS (steps), PULSO (pulse), ALEATÓRIO
RATE	1/32 · 1/16 · **1/8** · 1/4 · 1/2 · 1 COMP · 2 COMP (default in bold)

> **TIP.** Use MIX to blend the "chewed-up" sound with the original and keep the body.

FAQ and troubleshooting

SITUATION	WHAT TO DO
The plugin doesn't show up in the DAW	Close and reopen the DAW and have it rescan plugins. In Logic: Plug-in Manager › "Reset & Rescan Selection". Make sure you ran the installer for your system.
The sound doesn't change	Check that the pack is activated (right-click an empty area of the pedal › Licença…). Without activation, the sound passes straight through.
I switched computers	Right-click an empty area of the pedal › Licença… › Desativar este computador on the old one, then activate on the new one with the same e-mail and token. Valid on up to 2 computers.
I'm offline	Once activated, it works for up to 45 days without internet and renews by itself when the connection is back.
I lost my token	Write to contato@insidestudiosp.com.br with the e-mail used for the purchase.
TRIGGER on MIDI or ÁUDIO does nothing	Check the routing: the sidechain must point to the triggering track, and the MIDI track must send to the pedal (MIDI To). With no sidechain, ÁUDIO uses its own input.
I want to hear the original sound	Turn the knob or MIX to 0, or bypass the plugin in the DAW.

SUPPORT. Questions, suggestions or problems: **contato@insidestudiosp.com.br** · **insidestudiosp.com.br**