Troubleshooting Guide

Installation and starting

“Windows protected your PC” (SmartScreen) Click **More info → Run anyway**. Windows shows this for new software from smaller publishers.

Antivirus blocks or deletes the file Restore the file from quarantine and add it as an exception, or download the ZIP again. The software contains no network components other than the licence check.

The portable version is slow to open the first time It unpacks itself on first start. Later starts are faster. Run it from a local disk rather than a slow USB stick when possible.

“The application could not start”

1. Restart the computer and try again.
2. Make sure the data folder is not on a full or read-only disk.
3. Send the log file to support. Installed edition: `C:\Users\<you>\AppData\Roaming\Mobile Shop Manager Pro\logs\main.log`. Portable edition: `MobileShopManagerPro-Data\app\logs\main.log`. The log contains no customer or sales data.

“This database was created by a newer version of the application” You opened newer data with an older program. Install the latest version.

Sales and stock

A phone does not appear on the New Sale screen Only phones with status **In Stock** can be sold. Check its status in **Mobile Inventory**.

“IMEI … already exists” That IMEI is already in Mobile Inventory or in available Used Stock. Search for it with **Ctrl + K**.

“Select a customer to sell on credit” A walk-in sale must be paid in full. Choose or add a customer to leave a balance.

I made a mistake on a completed sale Sales are never deleted. Open **Sales History**, click the void icon, and give a reason. Stock returns, the customer's balance is reversed and the invoice stays in history marked **VOID**. Then enter the sale again correctly.

A sold phone cannot be deleted or its IMEI changed This protects your financial history. Void the sale first if the sale itself was a mistake.

Profit looks too low or too high Profit = selling price − purchase price − discount (and excludes tax). Check the purchase price of the items. Credit payments do not add profit; profit is counted once, on the day of the sale.

Printing and invoices

Nothing happens when I click Print Check that a printer is installed in Windows. Use **Save as PDF** as an alternative.

Thermal receipts are cut off or too small Choose the **Thermal receipt** layout on the invoice, and in the Windows print dialog select your receipt printer and an 80 mm paper size with margins set to none.

WhatsApp does not open WhatsApp Desktop or a browser must be available. The customer's phone needs a country code — edit the customer and choose it.

Backup and restore

"This file is not a Mobile Shop Manager Pro backup" Choose a `.msmbackup` file created by the app.

"The backup file is damaged" The file is incomplete or corrupted (for example, a failed USB copy). Use another backup.

I restored the wrong backup Every restore first creates a **Safety** backup of what you had. Find it in **Backup history** and restore it.

Automatic backups are not appearing Check **Backup & Restore → Automatic backup** is not Off, and that the backup folder still exists (for example, the USB drive is connected).

Licence

See the **Licence Activation** guide for every licence message and its fix.

Password

I forgot the app password There is no recovery, by design: the password is stored only on your computer in hashed form. Contact support with your purchase details for guidance; restoring a backup made *before* the password was set also removes it.

Still stuck?

Contact support (see the Support Information page) and include: the app version (**Settings → About**), your Windows version, what you clicked, and the exact message shown.