

Don't see what you're looking for? Log in for the full Help Center experience

Broadcasting substatuses

Updated 18 days ago

Overview

These substatuses apply to transactions in the [Broadcasting](#) primary status. They provide visibility into each step as Fireblocks submits your signed transaction to the blockchain network.

Broadcasting substatuses and the `broadcastingStatusInfo` object are available through the [Get Transaction by ID](#) API endpoint. To monitor broadcasting progress, poll the endpoint directly.

Note

Broadcasting substatuses are available through the API only. Webhook notifications do not include Broadcasting substatuses at this time.

Substatus flow

QUEUED_FOR_BROADCAST → SENDING_TO_NODE → TRANSIENT_NODE_ERROR_RETRY → RETRY_LIMIT_EXCEEDED

When a step succeeds, the transaction advances to its next state. Not every transaction passes through all substatuses: a transaction that broadcasts successfully moves forward from `SENDING_TO_NODE` without entering the retry or limit-exceeded states.

QUEUED_FOR_BROADCAST

The `QUEUED_FOR_BROADCAST` substatus indicates the transaction has been received by the Fireblocks broadcasting infra and is queued to be picked up for the first RPC call to the blockchain node. This is a short-lived transient state that requires no action.

API response example

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center

/

```
{
  "status": "BROADCASTING",
  "subStatus": "QUEUED_FOR_BROADCAST",
  "txHash": "0x000...000",
  "operation": "TRANSFER",
  "nonce": "34"
}
```

SENDING_TO_NODE

The `SENDING_TO_NODE` substatus indicates Fireblocks is making its first RPC call to the blockchain node. No action is required.

If the node responds successfully, the transaction advances to its next state. A non-terminal error moves the substatus to `TRANSIENT_NODE_ERROR_RETRY`. A terminal error moves the transaction to [Failed](#) with an appropriate substatus.

API response example

```
{
  "id": "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx",
  "assetId": "USDC_ETH_TEST5_6ZNT",
  "status": "BROADCASTING",
  "subStatus": "SENDING_TO_NODE",
  "txHash": "0x000...000",
  "operation": "TRANSFER",
  "nonce": "35"
}
```

TRANSIENT_NODE_ERROR_RETRY

The `TRANSIENT_NODE_ERROR_RETRY` substatus indicates the blockchain node rejected the transaction with a non-terminal error and Fireblocks is actively retrying. The `broadcastingStatusInfo` object provides the error type, error code, and an estimated window for how long retries continue.

Check the `errorCode` in `broadcastingStatusInfo` to understand the cause and take action before retries are exhausted. Use `estimatedRetryDeadline` (epoch milliseconds) to determine approximately how long Fireblocks continues retrying before stopping.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

```
{
  "id": "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx",
  "assetId": "USDC_ETH_TEST5_6ZNT",
  "status": "BROADCASTING",
  "subStatus": "TRANSIENT_NODE_ERROR_RETRY",
  "txHash": "0x000...000",
  "operation": "TRANSFER",
  "nonce": "35",
  "broadcastingStatusInfo": {
    "estimatedRetryDeadline": 1776079929836,
    "errorType": "NODE_ERROR",
    "errorCode": "INSUFFICIENT_FUNDS"
  }
}
```

RETRY_LIMIT_EXCEEDED

The `RETRY_LIMIT_EXCEEDED` substatus indicates Fireblocks exhausted all retry attempts and stopped submitting the transaction to the network. The `broadcastingStatusInfo` object contains the final error details from the last attempt. The `estimatedRetryDeadline` field is absent at this substatus because retries are no longer occurring.

This substatus is uncommon under normal conditions. The transaction does not progress on its own. Submit a [Boost \(RBF\) transaction](#) using the same nonce with corrected parameters (e.g., resolved funding or an adjusted fee). Fireblocks automatically handles the status tracking of both the original and replacement transactions.

API response example

```
{
  "id": "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx",
  "assetId": "USDC_ETH_TEST5_6ZNT",
  "status": "BROADCASTING",
  "subStatus": "RETRY_LIMIT_EXCEEDED",
  "txHash": "0x000...000",
  "operation": "TRANSFER",
```

Don't see what you're looking for? Log in for the full Help Center experience

```
}  
}
```

broadcastingStatusInfo field reference

The `broadcastingStatusInfo` object is present only on the `TRANSIENT_NODE_ERROR_RETRY` and `RETRY_LIMIT_EXCEEDED` substatures.

Field	Type	Present on	Description
<code>estimatedRetryDeadline</code>	number (epoch ms)	<code>TRANSIENT_NODE_ERROR_RETRY</code> only	Estimated time of the final retry attempt. Not present on <code>RETRY_LIMIT_EXCEEDED</code> .
<code>errorType</code>	string	Both	Error category. Possible values: <code>NODE_ERROR</code> , <code>NETWORK_ERROR</code> .
<code>errorCode</code>	string	Both	Mapped error code from the node. Examples: <code>INSUFFICIENT_FUNDS</code> , <code>NONCE_TOO_LOW</code> .

Was this article helpful?

Yes

No

ON THIS PAGE

- Overview
- Substatus flow
- broadcastingStatusInfo field reference**

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

-  Cancelled substatuses
-  Rejected substatuses
-  Failed substatuses
-  Completed substatuses



[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

[info@fireblocks.com](#)



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)