

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

Enabling & Disabling MPC-BAM

Updated 2 months ago

Early Access feature

This feature is currently in Early Access. If you are interested in joining the Early Access phase, [contact your Fireblocks Customer Success Manager](#).

Overview

This guide walks you through enabling MPC-BAM for an API user via the Fireblocks Console.

Before you begin


Verify the following:

- **Early Availability access granted:** [Contact your Customer Success Manager](#) to enable Fast MPC for your workspace, or [use the Fireblocks Labs page in the Console](#) to request enablement.
- **API user paired with co-signer:** The API user must be paired with an API co-signer (SGX, AWS Nitro, or GCP).
- **Co-signer version 2026.03.02:** Verify your co-signer version meets this minimum requirement. If your co-signer's version is below the requirement, you won't be able to enable MPC-BAM until you upgrade.

Enabling MPC-BAM for an API user

1. In the Fireblocks Console, go to **Developer center** > **Co-signers**.
2. Find (and expand, if necessary) the co-signer with the API user you want to configure.
3. Find the API user in the Paired API users list, then select **More actions** (...) > **Enable fast signing**.

Don't see what you're looking for? Log in for the full Help Center experience




4. Review the MPC-BAM explanation on the confirmation dialog, then select **Enable**.

After confirming, MPC-BAM keys are automatically provisioned in the background. You'll see a "Processing" status indicator next to the API user. Key provisioning typically completes within a few minutes.

During provisioning, your API user continues to use MPC-CMP for signing. There is no downtime.

Verifying MPC-BAM is active

Once key provisioning completes, a lightning bolt icon (⚡) appears next to the API user's name. This icon indicates that the API user now uses MPC-BAM for all ECDSA SECP256K1 signing operations.



Disabling MPC-BAM usage

You can disable MPC-BAM at any time and revert to MPC-CMP. Repeat the process you performed to enable MPC-BAM, but instead select **Disable fast signing** from the **More**

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center

/

Bitcoin external signer
ID 555BM96Xp6
Enclave type: SGX | Version: x1y2z3 | Online

Paired API users (2) [+ Pair API user](#)

Name	Role	Groups	Callback handler
API user Y	Admin	All signers	https://www.chr/123456789...
API user Z	Admin	-	+

Bitcoin external signer
ID 555BM96Xp6
Enclave type: AWS Nitro | Version: x1y2z3 | Last...

- Configure callback handler
- Disable fast signing
- Unpair
- History

When disabled, the API user immediately reverts to MPC-CMP signing. Your MPC-BAM keys are retained but not used.

Troubleshooting

Fast signing option not available

Possible causes:

- Early Availability access not granted for your workspace
- API user not paired with an API co-signer
- Co-signer version below 2026.03.02 (you'll see "Upgrade co-signer to enable fast signing" indicator)

Solution:

- Contact your Customer Success Manager to verify Early Availability access
- Upgrade your co-signer to version 2026.03.02 or higher
- Ensure the API user is properly paired with the co-signer

Key provisioning is stuck in "Processing"

Possible causes:

- Co-signer is offline or temporarily unavailable
- Network connectivity issues

Solution:

- Check that the co-signer status shows "Online" in the Console
- Wait a few minutes and refresh the page

Don't see what you're looking for? Log in for the full Help Center experience

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Before you begin

Enabling MPC-BAM for an API user

Verifying MPC-BAM is active

Disabling MPC-BAM usage

Troubleshooting

Related Articles

 Fast MPC & MPC-BAM Overview