
**CONTROLLER GUIDE | STEP 1 OF 9**

# Prepare one controller VM




Give this picture to your server team. These are starting allocations for 20 servers.

You need a prepared Linux server first. Ask your server team to confirm the items in the picture. The app installer does not install Docker or Python.

Use RHEL 9 or Ubuntu 26.04. Keep SELinux enabled. Reserve UID/GID 10001 for the dedicated application account.


The rest of this guide uses one installer command and the browser. Native OS and DC testing are still to be completed.



© 2026 Airtel Payments Bank. All rights reserved.

**CONTROLLER GUIDE | STEP 2 OF 9**

# Make three connections available




These are destination TCP ports. Allow return traffic and restrict access to approved networks.

Ask the network team for a fixed IP, a stable name, correct time and trusted HTTPS. The installer needs approved image/package download access; this is not an offline installer.


The installer does not open host firewall ports. Keep backend, database and cluster ports private. An approved load balancer can provide different public URLs.



© 2026 Airtel Payments Bank. All rights reserved.

**CONTROLLER GUIDE | STEP 3 OF 9**

# Run the controller installer




Installation illustration. Your server address and progress messages will differ.

Ask your release/server team for prthak-controller-0.16.0.tar.gz. They must verify its signature, copy it privately and extract it into a protected root-owned folder using independently approved release trust.

Open Terminal in that extracted folder. Paste the command below. If sudo asks for your Linux password, type it and press Enter; the password does not appear on screen.

Paste this command and press Enter

```
sudo ./scripts/install-controller.sh --gui-setup
```

Wait for installation to finish. Keep the HTTPS setup URL that it prints. Do not create or edit an .env file.


© 2026 Airtel Payments Bank. All rights reserved.

**CONTROLLER GUIDE | STEP 4 OF 9**

# Sign in and change the password





Illustration of the current login fields. This is not a live installation screenshot.

Open the exact HTTPS URL printed by the installer. Your server team must confirm the certificate identity before you enter credentials.

A fresh installation uses admin / admin. Replace the password with 12 to 256 characters before entering the workspace. Existing installations keep their existing users.


The built-in admin cannot be deleted, disabled, renamed or demoted. Its password can be changed or reset.



© 2026 Airtel Payments Bank. All rights reserved.

**CONTROLLER GUIDE | STEP 5 OF 9**

# Finish the platform settings




SYNTHETIC PREVIEW · Current v0.16 synthetic preview. An installed controller enables its supported setup actions.

Click Platform settings → Setup. Use Site & cluster settings for this node, then HTTPS certificates to prepare the permanent application name and approved certificate.


Use the Storage tab for the data location. Default: /var/lib/prthak. Mount storage first; moving active data uses the reviewed GUI operation.

Leave workers on AUTO. Start with one standalone node. It runs the controller/router with SQLite; PostgreSQL HA is a separate three-voter setup stage.


© 2026 Airtel Payments Bank. All rights reserved.

**CONTROLLER GUIDE | STEP 6 OF 9**

# Choose who may use the app




Local accounts and configured organisation sign-in use the same three roles.

Click Users & access. As Super Admin, add the named people who will use Prṛthak and select their role.

You may start with local accounts. Configure optional SAML here, or Microsoft Entra through Platform settings → Setup. SSO needs your identity team and explicitly provisioned users.


Users change their own local password through the top-right account menu. Only Super Admin manages other users and roles.



© 2026 Airtel Payments Bank. All rights reserved.

**CONTROLLER GUIDE | STEP 7 OF 9**

# Set the update interval




SYNTHETIC PREVIEW · Current synthetic preview. Desired settings are separate from an agent receipt showing they were applied.

Click Platform settings → Agent polling. Start with 30 seconds for policy control and 900 seconds for the full inventory fallback.

Preview affected servers, save the settings, then check their applied polling status. Later you can change the whole fleet or selected groups/tags here.


Agents pull new policies automatically. Polling includes timing variation and network work; a saved setting is not a guaranteed completion time.



© 2026 Airtel Payments Bank. All rights reserved.

**CONTROLLER GUIDE | STEP 8 OF 9**

# Confirm the dashboard is ready




SYNTHETIC PREVIEW · Current synthetic preview. A fresh installation should show your own records, not these example servers.

Check: trusted HTTPS opens, your new password works, and controller readiness is healthy. Keep the printed URL and the new password in your approved records.

Next: create your real locations in Locations, then follow the separate Agent installation guide. Servers appear after installation and their first authenticated report.

Create a backup schedule in Platform settings → Backups. Back up private trust/identity material separately as required by the recovery procedure.


An empty server list is normal before agents connect. Do not add example records to make the dashboard look populated.



© 2026 Airtel Payments Bank. All rights reserved.

**CONTROLLER GUIDE | STEP 9 OF 9**

# If something does not work




Take the error message to your server team. Do not disable security checks to make an install continue.

No dashboard? Ask the server team to check installation completion, Docker, the address, HTTPS trust and TCP 8787 access.

Need help preparing Linux? Share the prerequisite page and the official Docker RHEL/Ubuntu instructions linked in the browser guide. The one app command assumes that preparation is complete.

This guide explains the current code and GUI. Your native RHEL/Ubuntu validation, actual 20-server pilot and DC/DR tests remain separate deployment work.



© 2026 Airtel Payments Bank. All rights reserved.